



**Program Directory for
IBM Db2 Query Management Facility for z/OS
National Language Version**

V13.01.00

Program Number 5698-QMF

HSQDD10, HFQMD10, HQDCC10, HHPCC10, JYQDD10, JSQDD1Q and NLVs

for use with
z/OS

Document Date: May 2022

G113-5527-00

Note

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 72.

© Copyright International Business Machines Corporation 1982, 2022.

© Rocket Software Incorporated 2018. All rights reserved

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

1.0 Introduction	1
1.1 QMF for z/OS - NLV Description	2
1.2 QMF for z/OS - NLV FMIDs	3
2.0 Program Materials	4
2.1 Basic Machine-Readable Material	4
2.2 Optional Machine-Readable Material	16
2.3 Program Publications	16
2.3.1 Optional Program Publications	17
2.4 Program Source Materials	17
2.5 Publications Useful During Installation	17
3.0 Program Support	18
3.1 Program Services	18
3.2 Preventive Service Planning	18
3.3 Statement of Support Procedures	19
4.0 Program and Service Level Information	21
4.1 Program Level Information	21
4.2 Service Level Information	21
5.0 Installation Requirements and Considerations	22
5.1 Driving System Requirements	22
5.1.1 Machine Requirements	22
5.1.2 Programming Requirements	22
5.2 Target System Requirements	23
5.2.1 Machine Requirements	23
5.2.2 Programming Requirements	23
5.2.2.1 Installation Requisites	23
5.2.2.2 Operational Requisites	24
5.2.2.3 Toleration/Coexistence Requisites	25
5.2.2.4 Incompatibility (Negative) Requisites	25
5.2.3 DASD Storage Requirements	25
5.3 FMIDs Deleted	42
5.4 Special Considerations	43
6.0 Installation Instructions	44
6.1 Installing QMF for z/OS - NLV	44
6.1.1 SMP/E Considerations for Installing QMF for z/OS - NLV	44
6.1.2 SMP/E Options Subentry Values	44
6.1.3 SMP/E CALLLIBS and SIDE DECK PROCESSING	44
6.1.4 Sample Jobs	45

6.1.4.1	Sample Jobs for QMF for z/OS - NLV	45
6.1.4.2	Sample Jobs for National Language Version for QMF Korean	49
6.1.4.3	Sample Jobs for National Language Version for QMF Brazilian Portuguese	50
6.1.4.4	Sample Jobs for National Language Version for QMF Spanish	51
6.1.4.5	Sample Jobs for National Language Version for QMF Swedish	52
6.1.4.6	Sample Jobs for National Language Version for QMF Swiss French	53
6.1.4.7	Sample Jobs for National Language Version for QMF Swiss German	54
6.1.4.8	Sample Jobs for National Language Version for QMF Canadian French	55
6.1.4.9	Sample Jobs for National Language Version for QMF Uppercase English	56
6.1.4.10	Sample Jobs for National Language Version for QMF Danish	57
6.1.4.11	Sample Jobs for National Language Version for QMF French	58
6.1.4.12	Sample Jobs for National Language Version for QMF German	59
6.1.4.13	Sample Jobs for National Language Version for QMF Italian	60
6.1.4.14	Sample Jobs for National Language Version for QMF Japanese	61
6.1.5	Allocate SMP/E CSI (Optional)	62
6.1.6	Initialize CSI zones (Optional)	62
6.1.7	Perform SMP/E RECEIVE	62
6.1.8	Allocate SMP/E Target and Distribution Libraries	63
6.1.9	Create DDDEF Entries	64
6.1.10	Perform SMP/E APPLY	65
6.1.11	Perform SMP/E ACCEPT	67
6.1.12	Run REPORT CROSSZONE	69
6.2	Activating QMF for z/OS - NLV	70
6.2.1	Product Customization	71
7.0	Notices	72
7.1	Trademarks	72
Reader's Comments		73

Figures

1.	Program File Content for QMF TSO/CICS Base	4
2.	Program File Content for QMF Z Client	5
3.	Program File Content for QMF HPO	5
4.	Program File Content for QMF Data Service	6
5.	Program File Content for QMF applications	7
6.	Program File Content for QMF for z/OS OTC	7
7.	Program File Content for QMF Korean	8
8.	Program File Content for QMF Brazilian Portuguese	8
9.	Program File Content for QMF Spanish	9
10.	Program File Content for QMF Swedish	9

11.	Program File Content for QMF Swiss French	10
12.	Program File Content for QMF Swiss German	11
13.	Program File Content for QMF Canadian French	11
14.	Program File Content for QMF Uppercase English	12
15.	Program File Content for QMF Danish	12
16.	Program File Content for QMF French	13
17.	Program File Content for QMF German	14
18.	Program File Content for QMF Italian	14
19.	Program File Content for QMF Japanese	15
20.	Basic Material: Unlicensed	16
21.	Publications Useful During Installation	17
22.	PSP Upgrade and Subset ID	18
23.	Component IDs	19
24.	Driving System Software Requirements	23
25.	Target System Mandatory Installation Requisites	23
26.	Target System Mandatory Operational Requisites	24
27.	Total DASD Space Required by Db2 QMF for z/OS	25
28.	Total DASD Space Required by any National Language Version	25
29.	QMF National Language Identifiers	27
30.	Storage Requirements for QMF for TSO/CICS Target Libraries	27
31.	Storage Requirements for QMF Z Client Target Libraries	28
32.	Storage Requirements for QMF HPO Target Libraries	28
33.	Storage Requirements for QMF applications Target Libraries	29
34.	Storage Requirements for QMF Data Service Target Libraries	29
35.	Storage Requirements for QMF for z/OS - NLV - NLV Target Libraries	30
36.	Storage Requirements for QMF for TSO/CICS Distribution Libraries	35
37.	Storage Requirements for QMF Z Client Distribution Libraries	35
38.	Storage Requirements for QMF HPO Distribution Libraries	36
39.	Storage Requirements for QMF applications Distribution Libraries	36
40.	Storage Requirements for QMF Data Service Distribution Libraries	36
41.	Storage Requirements for QMF for z/OS - NLV - NLV Distribution Libraries	37
42.	Storage Requirements for QMF for z/OS - NLV Non-SMP/E Data Sets	42
43.	SMP/E Options Subentry Values	44
44.	Sample Installation Jobs	45
45.	Sample Installation Jobs for QMF Korean	49
46.	Sample Installation Jobs for QMF Brazilian Portuguese	50
47.	Sample Installation Jobs for QMF Spanish	51
48.	Sample Installation Jobs for QMF Swedish	52
49.	Sample Installation Jobs for QMF Swiss French	53
50.	Sample Installation Jobs for QMF Swiss German	54
51.	Sample Installation Jobs for QMF Canadian French	55
52.	Sample Installation Jobs for QMF Uppercase English	56
53.	Sample Installation Jobs for QMF Danish	57
54.	Sample Installation Jobs for QMF French	58
55.	Sample Installation Jobs for QMF German	59
56.	Sample Installation Jobs for QMF Italian	60

57. Sample Installation Jobs for QMF Japanese	61
58. NLV Activating Jobs	70

1.0 Introduction

This program directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of IBM Db2 Query Management Facility for z/OS. This publication refers to IBM Db2 Query Management Facility for z/OS as QMF for z/OS - NLV.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 4 identifies the basic program materials and documentation for QMF for z/OS - NLV.
- 3.0, “Program Support” on page 18 describes the IBM support available for QMF for z/OS - NLV.
- 4.0, “Program and Service Level Information” on page 21 lists the APARs (program level) and PTFs (service level) that have been incorporated into QMF for z/OS - NLV.
- 5.0, “Installation Requirements and Considerations” on page 22 identifies the resources and considerations that are required for installing and using QMF for z/OS - NLV.
- 6.0, “Installation Instructions” on page 44 provides detailed installation instructions for QMF for z/OS - NLV. It also describes the procedures for activating the functions of QMF for z/OS - NLV, or refers to appropriate publications.

Before installing QMF for z/OS - NLV, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this program directory; after which, keep the documents for your reference. Section 3.2, “Preventive Service Planning” on page 18 tells you how to find any updates to the information and procedures in this program directory.

QMF for z/OS - NLV is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The program directory that is provided in softcopy format on the CBPDO is identical to the hardcopy format if one was included with your order. All service and HOLDDATA for QMF for z/OS - NLV are included on the CBPDO.

Do not use this program directory if you install QMF for z/OS - NLV with a ServerPac. When you use this offering, use the jobs and documentation supplied with the offering. The offering will point you to specific sections of this program directory as needed.

1.1 QMF for z/OS - NLV Description

QMF for z/OS is a comprehensive business analytics solution that provides interactive dashboards, graphical reports, self-service BI, batch reports, and analytics through web, workstation, and mobile interfaces. It supports most structured and unstructured data sources, and is optimized for IBM z Systems sources such as IBM Db2 for z/OS and VSAM.

QMF for z/OS consists of the following capabilities:

- QMF for TSO and CICS
- QMF Z Client
- QMF High Performance Option (HPO)
- QMF applications
- QMF Data Service
- QMF for z/OS OTC

New **QMF for TSO and CICS** enhancements are:

- The CURRENT LOCK TIMEOUT special register can be set from within a QMF SQL query. This special register specifies the number of seconds to elapse before a resource timeout is detected.
- By using new keyword parameters options ALL or NONE on the folder keyword of the LIST command, users can view QMF objects needing to be organized by FOLDER that may help users organize QMF objects.
- The DESCRIBE Panel has been updated to show all folder names currently assigned to the QMF objects.
- The DESCRIBE command is executed from an active list of QMF objects.

New **QMF Z Client** enhancements are:

- Support for new global variables for Column default and null indicator. New Global variables supported are DSQCP_TEDFLT, DSQCP_TEDFLT_DBCS, DSQCP_TENULL and DSQCP_TENULL_DBCS. DSQCP_TEDFLT and DSQCP_TEDFLT_DBCS are used to specify default value for a column. DSQCP_TENULL and DSQCP_TENULL_DBCS to use to indicate null value in a column

1.2 QMF for z/OS - NLV FMIDs

QMF for z/OS - NLV consists of the following FMIDs:

HSQDD10 (QMF TSO/CICS Base)
HFQMD10 (QMF Z Client)
HHPCC10 (QMF HPO)
HQDCC10 (QMF Data Service)
JYQDD10 (QMF applications)
JSQDD1Q (QMF for z/OS OTC)

JSQDD5A (QMF Korean)
JSQDD5B (QMF Brazilian Portuguese)
JSQDD5C (QMF Spanish)
JSQDD5D (QMF Swedish)
JSQDD5E (QMF Swiss French)
JSQDD5F (QMF Swiss German)
JSQDD5G (QMF Canadian French)
JSQDD51 (QMF Uppercase English)
JSQDD55 (QMF Danish)
JSQDD56 (QMF French)
JSQDD57 (QMF German)
JSQDD58 (QMF Italian)
JSQDD59 (QMF Japanese)

Notes:

- To install the QMF for TSO and CICS product, install FMIDs HSQDD10 (QMF TSO/CICS Base) and JSQDD1Q (QMF for z/OS OTC).
- To install the features QMF Analytics for TSO and the QMF Enhanced Editor for QMF for TSO and CICS, install FMID JYQDD10 (QMF applications). QMF for TSO and CICS FMID HSQDD10 is a prerequisite.
- To install QMF HPO, install the FMID HHPCC10 (QMF HPO). Please note that QMF HPO 12.1 FMID (HHPCC10) is provided with this QMF 13 feature.
- To install QMF Data Service, install the FMID HQDCC10 (QMF Data Service). Please note that QMF Data Service 12.1 (FMID HQDCC10) is provided with this QMF 13 feature.
- The installation of any QMF National Language FMID, requires the prerequisite QMF for TSO and CICS FMID HSQDD10.
- To install the QMF distributed components, read the Memo to Users document on the LCD4-8602 CD provided with this product, to access the IBM Web Membership (IWM) site, to download the distributed components.

2.0 Program Materials

An IBM program is identified by a program number. The program number for QMF for z/OS - NLV is 5698-QMF.

Basic Machine-Readable Materials are materials that are supplied under the base license and are required for the use of the product.

The program announcement material describes the features supported by QMF for z/OS - NLV. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is physical media or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 44 for more information about how to install the program.

You can find information about the physical media for the basic machine-readable materials for QMF for z/OS - NLV in the *CBPDO Memo To Users Extension*.

Figure 1 describes the program file content for QMF for z/OS - NLV. You can refer to the *CBPDO Memo To Users Extension* to see where the files reside on the tape.

Notes:

1. The data set attributes in this table must be used in the JCL of jobs that read the data sets. However, because the data sets are in IEBCOPY unloaded format, their actual attributes might be different.
2. If any RELFILEs are identified as PDSEs, ensure that SMPTLIB data sets are allocated as PDSEs.

Figure 1 (Page 1 of 2). Program File Content for QMF TSO/CICS Base

Name	ORG	RECFM	RECL	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.HSQDD10.F1	PDS	FB	80	8800
IBM.HSQDD10.F2	PDS	FB	80	8800
IBM.HSQDD10.F3	PDS	F	400	400
IBM.HSQDD10.F4	PDS	FB	80	8800
IBM.HSQDD10.F5	PDS	FB	80	8800

Figure 1 (Page 2 of 2). Program File Content for QMF TSO/CICS Base

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.HSQDD10.F6	PDS	FB	80	8800
IBM.HSQDD10.F7	PDS	F	400	400
IBM.HSQDD10.F8	PDS	FB	80	8800
IBM.HSQDD10.F9	PDS	U	0	6144
IBM.HSQDD10.F10	PDS	FB	80	8800
IBM.HSQDD10.F11	PDS	VB	32622	32626
IBM.HSQDD10.F12	PDS	FB	80	8800
IBM.HSQDD10.F13	PDS	FB	80	8800
IBM.HSQDD10.F14	PDS	FB	80	8800

Figure 2. Program File Content for QMF Z Client

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.HFQMD10.F1	PDS	FB	80	8800
IBM.HFQMD10.F2	PDS	FB	80	8800
IBM.HFQMD10.F3	PDS	VB	0	6144
IBM.HFQMD10.F4	PDSE	U	0	6144
IBM.HFQMD10.F5	PDS	FB	80	8800
IBM.HFQMD10.F6	PDS	FB	80	8800

Figure 3 (Page 1 of 2). Program File Content for QMF HPO

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.HHPCC10.F1	PDS	FB	80	8800

Figure 3 (Page 2 of 2). Program File Content for QMF HPO

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.HHPCC10.F2	PDS	FB	80	8800
IBM.HHPCC10.F3	PDS	FB	80	8800
IBM.HHPCC10.F4	PDS	FB	80	8800
IBM.HHPCC10.F5	PDS	FB	80	8800
IBM.HHPCC10.F6	PDS	FB	80	8800
IBM.HHPCC10.F7	PDS	U	0	6144
IBM.HHPCC10.F8	PDS	FB	80	8800
IBM.HHPCC10.F9	PDS	FB	80	8800

Figure 4 (Page 1 of 2). Program File Content for QMF Data Service

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.HQDCC10.F1	PDS	FB	80	8800
IBM.HQDCC10.F2	PDS	FB	80	8800
IBM.HQDCC10.F3	PDS	FB	80	8800
IBM.HQDCC10.F4	PDS	FB	80	8800
IBM.HQDCC10.F5	PDS	FB	80	8800
IBM.HQDCC10.F6	PDSE	U	0	6144
IBM.HQDCC10.F7	PDS	FB	2048	30720
IBM.HQDCC10.F8	PDS	FB	80	8800
IBM.HQDCC10.F9	PDS	FB	80	8800
IBM.HQDCC10.F10	PDS	FB	80	8800
IBM.HQDCC10.F11	PDSE	U	0	6144
IBM.HQDCC10.F12	PDS	FB	80	8800
IBM.HQDCC10.F13	PDS	FB	80	8800
IBM.HQDCC10.F14	PDS	FB	2048	30720
IBM.HQDCC10.F15	PDS	FB	80	8800

Figure 4 (Page 2 of 2). Program File Content for QMF Data Service

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.HQDCC10.F16	PDS	FB	80	8800
IBM.HQDCC10.F17	PDS	FB	80	8800
IBM.HQDCC10.F18	PDS	FB	80	8800
IBM.HQDCC10.F19	PDS	FB	80	8800
IBM.HQDCC10.F20	PDS	FB	80	8800
IBM.HQDCC10.F21	PDS	FB	80	8800

Figure 5. Program File Content for QMF applications

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JYQDD10.F1	PDS	FB	80	8800
IBM.JYQDD10.F2	PDS	FB	80	8800
IBM.JYQDD10.F3	PDS	FB	80	8800
IBM.JYQDD10.F4	PDS	U	0	6144
IBM.JYQDD10.F5	PDS	FB	80	8800
IBM.JYQDD10.F6	PDS	U	0	6144
IBM.JYQDD10.F7	PDS	FB	80	8800
IBM.JYQDD10.F8	PDS	FB	80	8800

Figure 6. Program File Content for QMF for z/OS OTC

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD1Q.F1	PDS	U	0	6144

Figure 7. Program File Content for QMF Korean

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5A.F1	PDS	FB	80	8800
IBM.JSQDD5A.F2	PDS	FB	80	8800
IBM.JSQDD5A.F3	PDS	FB	80	8800
IBM.JSQDD5A.F4	PDS	FB	80	8800
IBM.JSQDD5A.F5	PDS	F	400	400
IBM.JSQDD5A.F6	PDS	FB	80	8800
IBM.JSQDD5A.F7	PDS	U	0	6144
IBM.JSQDD5A.F8	PDS	FB	80	8800
IBM.JSQDD5A.F9	PDS	V	32622	32626
IBM.JSQDD5A.F10	PDS	FB	80	8800
IBM.JSQDD5A.F11	PDS	FB	80	8800
IBM.JSQDD5A.F12	PDS	FB	80	8800

Figure 8 (Page 1 of 2). Program File Content for QMF Brazilian Portuguese

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5B.F1	PDS	FB	80	8800
IBM.JSQDD5B.F2	PDS	FB	80	8800
IBM.JSQDD5B.F3	PDS	FB	80	8800
IBM.JSQDD5B.F4	PDS	FB	80	8800
IBM.JSQDD5B.F5	PDS	F	400	400
IBM.JSQDD5B.F6	PDS	FB	80	8800
IBM.JSQDD5B.F7	PDS	U	0	6144
IBM.JSQDD5B.F8	PDS	FB	80	8800
IBM.JSQDD5B.F9	PDS	V	32622	32626
IBM.JSQDD5B.F10	PDS	FB	80	8800

Figure 8 (Page 2 of 2). Program File Content for QMF Brazilian Portuguese

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD5B.F11	PDS	FB	80	8800
IBM.JSQDD5B.F12	PDS	FB	80	8800

Figure 9. Program File Content for QMF Spanish

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5C.F1	PDS	FB	80	8800
IBM.JSQDD5C.F2	PDS	FB	80	8800
IBM.JSQDD5C.F3	PDS	FB	80	8800
IBM.JSQDD5C.F4	PDS	FB	80	8800
IBM.JSQDD5C.F5	PDS	F	400	400
IBM.JSQDD5C.F6	PDS	FB	80	8800
IBM.JSQDD5C.F7	PDS	U	0	6144
IBM.JSQDD5C.F8	PDS	FB	80	8800
IBM.JSQDD5C.F9	PDS	V	32622	32626
IBM.JSQDD5C.F10	PDS	FB	80	8800
IBM.JSQDD5C.F11	PDS	FB	80	8800
IBM.JSQDD5C.F12	PDS	FB	80	8800

Figure 10 (Page 1 of 2). Program File Content for QMF Swedish

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5D.F1	PDS	FB	80	8800
IBM.JSQDD5D.F2	PDS	FB	80	8800

Figure 10 (Page 2 of 2). Program File Content for QMF Swedish

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD5D.F3	PDS	FB	80	8800
IBM.JSQDD5D.F4	PDS	FB	80	8800
IBM.JSQDD5D.F5	PDS	F	400	400
IBM.JSQDD5D.F6	PDS	FB	80	8800
IBM.JSQDD5D.F7	PDS	U	0	6144
IBM.JSQDD5D.F8	PDS	FB	80	8800
IBM.JSQDD5D.F9	PDS	V	32622	32626
IBM.JSQDD5D.F10	PDS	FB	80	8800
IBM.JSQDD5D.F11	PDS	FB	80	8800
IBM.JSQDD5D.F12	PDS	FB	80	8800

Figure 11. Program File Content for QMF Swiss French

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5E.F1	PDS	FB	80	8800
IBM.JSQDD5E.F2	PDS	FB	80	8800
IBM.JSQDD5E.F3	PDS	FB	80	8800
IBM.JSQDD5E.F4	PDS	FB	80	8800
IBM.JSQDD5E.F5	PDS	F	400	400
IBM.JSQDD5E.F6	PDS	FB	80	8800
IBM.JSQDD5E.F7	PDS	U	0	6144
IBM.JSQDD5E.F8	PDS	FB	80	8800
IBM.JSQDD5E.F9	PDS	V	32622	32626
IBM.JSQDD5E.F10	PDS	FB	80	8800
IBM.JSQDD5E.F11	PDS	FB	80	8800
IBM.JSQDD5E.F12	PDS	FB	80	8800

Figure 12. Program File Content for QMF Swiss German

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5F.F1	PDS	FB	80	8800
IBM.JSQDD5F.F2	PDS	FB	80	8800
IBM.JSQDD5F.F3	PDS	FB	80	8800
IBM.JSQDD5F.F4	PDS	FB	80	8800
IBM.JSQDD5F.F5	PDS	F	400	400
IBM.JSQDD5F.F6	PDS	FB	80	8800
IBM.JSQDD5F.F7	PDS	U	0	6144
IBM.JSQDD5FF8	PDS	FB	80	8800
IBM.JSQDD5F.F9	PDS	V	32622	32626
IBM.JSQDD5F.F10	PDS	FB	80	8800
IBM.JSQDD5F.F11	PDS	FB	80	8800
IBM.JSQDD5F.F12	PDS	FB	80	8800

Figure 13 (Page 1 of 2). Program File Content for QMF Canadian French

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5G.F1	PDS	FB	80	8800
IBM.JSQDD5G.F2	PDS	FB	80	8800
IBM.JSQDD5G.F3	PDS	FB	80	8800
IBM.JSQDD5G.F4	PDS	FB	80	8800
IBM.JSQDD5G.F5	PDS	F	400	400
IBM.JSQDD5G.F6	PDS	FB	80	8800
IBM.JSQDD5G.F7	PDS	U	0	6144
IBM.JSQDD5G.F8	PDS	FB	80	8800
IBM.JSQDD5G.F9	PDS	V	32622	32626
IBM.JSQDD5G.F10	PDS	FB	80	8800

Figure 13 (Page 2 of 2). Program File Content for QMF Canadian French

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD5G.F11	PDS	FB	80	8800
IBM.JSQDD5G.F12	PDS	FB	80	8800

Figure 14. Program File Content for QMF Uppercase English

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD51.F1	PDS	FB	80	8800
IBM.JSQDD51.F2	PDS	FB	80	8800
IBM.JSQDD51.F3	PDS	FB	80	8800
IBM.JSQDD51.F4	PDS	FB	80	8800
IBM.JSQDD51.F5	PDS	F	400	400
IBM.JSQDD51.F6	PDS	FB	80	8800
IBM.JSQDD51.F7	PDS	U	0	6144
IBM.JSQDD51.F8	PDS	FB	80	8800
IBM.JSQDD51.F9	PDS	V	32622	32626
IBM.JSQDD51.F10	PDS	FB	80	8800
IBM.JSQDD51.F11	PDS	FB	80	8800
IBM.JSQDD51.F12	PDS	FB	80	8800

Figure 15 (Page 1 of 2). Program File Content for QMF Danish

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD55.F1	PDS	FB	80	8800
IBM.JSQDD55.F2	PDS	FB	80	8800

Figure 15 (Page 2 of 2). Program File Content for QMF Danish

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD55.F3	PDS	FB	80	8800
IBM.JSQDD55.F4	PDS	FB	80	8800
IBM.JSQDD55.F5	PDS	F	400	400
IBM.JSQDD55.F6	PDS	FB	80	8800
IBM.JSQDD55.F7	PDS	U	0	6144
IBM.JSQDD55.F8	PDS	FB	80	8800
IBM.JSQDD55.F9	PDS	V	32622	32626
IBM.JSQDD55.F10	PDS	FB	80	8800
IBM.JSQDD55.F11	PDS	FB	80	8800
IBM.JSQDD55.F12	PDS	FB	80	8800

Figure 16. Program File Content for QMF French

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD56.F1	PDS	FB	80	8800
IBM.JSQDD56.F2	PDS	FB	80	8800
IBM.JSQDD56.F3	PDS	FB	80	8800
IBM.JSQDD56.F4	PDS	FB	80	8800
IBM.JSQDD56.F5	PDS	F	400	400
IBM.JSQDD56.F6	PDS	FB	80	8800
IBM.JSQDD56.F7	PDS	U	0	6144
IBM.JSQDD56.F8	PDS	FB	80	8800
IBM.JSQDD56.F9	PDS	V	32622	32626
IBM.JSQDD56.F10	PDS	FB	80	8800
IBM.JSQDD56.F11	PDS	FB	80	8800
IBM.JSQDD56.F12	PDS	FB	80	8800

Figure 17. Program File Content for QMF German

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD57.F1	PDS	FB	80	8800
IBM.JSQDD57.F2	PDS	FB	80	8800
IBM.JSQDD57.F3	PDS	FB	80	8800
IBM.JSQDD57.F4	PDS	FB	80	8800
IBM.JSQDD57.F5	PDS	F	400	400
IBM.JSQDD57.F6	PDS	FB	80	8800
IBM.JSQDD57.F7	PDS	U	0	6144
IBM.JSQDD57.F8	PDS	FB	80	8800
IBM.JSQDD57.F9	PDS	V	32622	32626
IBM.JSQDD57.F10	PDS	FB	80	8800
IBM.JSQDD57.F11	PDS	FB	80	8800
IBM.JSQDD57.F12	PDS	FB	80	8800

Figure 18 (Page 1 of 2). Program File Content for QMF Italian

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD58.F1	PDS	FB	80	8800
IBM.JSQDD58.F2	PDS	FB	80	8800
IBM.JSQDD58.F3	PDS	FB	80	8800
IBM.JSQDD58.F4	PDS	FB	80	8800
IBM.JSQDD58.F5	PDS	F	400	400
IBM.JSQDD58.F6	PDS	FB	80	8800
IBM.JSQDD58.F7	PDS	U	0	6144
IBM.JSQDD58.F8	PDS	FB	80	8800
IBM.JSQDD58.F9	PDS	V	32622	32626
IBM.JSQDD58.F10	PDS	FB	80	8800

Figure 18 (Page 2 of 2). Program File Content for QMF Italian

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD58.F11	PDS	FB	80	8800
IBM.JSQDD58.F12	PDS	FB	80	8800

Figure 19. Program File Content for QMF Japanese

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD59.F1	PDS	FB	80	8800
IBM.JSQDD59.F2	PDS	FB	80	8800
IBM.JSQDD59.F3	PDS	FB	80	8800
IBM.JSQDD59.F4	PDS	FB	80	8800
IBM.JSQDD59.F5	PDS	F	400	400
IBM.JSQDD59.F6	PDS	FB	80	8800
IBM.JSQDD59.F7	PDS	U	0	6144
IBM.JSQDD59.F8	PDS	FB	80	8800
IBM.JSQDD59.F9	PDS	V	32622	32626
IBM.JSQDD59.F10	PDS	FB	80	8800
IBM.JSQDD59.F11	PDS	FB	80	8800
IBM.JSQDD59.F12	PDS	FB	80	8800

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for QMF for z/OS - NLV.

2.3 Program Publications

The following sections identify the basic publications for QMF for z/OS - NLV.

Figure 20 identifies the basic unlicensed publications for QMF for z/OS - NLV. Those publications that are in softcopy format can be obtained from the IBM Knowledge Center website at:

<https://www.ibm.com/resources/publications>

Some publications are available in other languages.

<i>Figure 20. Basic Material: Unlicensed</i>		
Publication Title	Form Number	Media Format
Db2 QMF NLV License Information	GC27-9106	Internet
Introducing Db2 QMF	SC28-2792	Internet
Installing and Managing Db2 QMF for TSO and CICS	SC28-2788	Internet
Developing Db2 QMF applications	SC28-2793	Internet
Using Db2 QMF	SC28-2794	Internet
Db2 QMF Reference	SC28-2795	Internet
Db2 QMF Messages and Codes	SC28-2796	Internet
DB2 QMF High Performance Option User's Guide for TSO and CICS	SC28-3269	Internet
Installing and Managing Db2 QMF for Workstation and Db2 QMF for WebSphere	SC28-2789	Internet
Getting Started with Db2 QMF for Workstation and Db2 QMF for WebSphere	SC28-2797	Internet
Db2 QMF Data Service Studio Getting Started Guide	SC28-3264	Internet
Db2 QMF Data Service Studio User's Guide	SC28-3267	Internet
Db2 QMF Data Service Solutions Guide	SC28-3266	Internet
Db2 QMF Data Service Customization Guide	SC28-3265	Internet
Getting Started with Db2 IBM QMF Vision	SC28-3268	Internet
Getting Started with QMF Z Client	SC28-3263	Internet
Installing and Managing Db2 QMF Server	SC28-2798	Internet

2.3.1 Optional Program Publications

No optional publications are provided for QMF for z/OS - NLV.

2.4 Program Source Materials

No program source materials or viewable program listings are provided for QMF for z/OS - NLV.

2.5 Publications Useful During Installation

You might want to use the publications listed in Figure 21 during the installation of QMF for z/OS - NLV.

<i>Figure 21. Publications Useful During Installation</i>	
Publication Title	Form Number
<i>IBM SMP/E for z/OS User's Guide</i>	SA23-2277
<i>IBM SMP/E for z/OS Commands</i>	SA23-2275
<i>IBM SMP/E for z/OS Reference</i>	SA23-2276
<i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i>	GA32-0883

Note: These publications can be found in IBM Documentation at <https://www.ibm.com/docs/en/zos/2.5.0?topic=zos-smpe>

3.0 Program Support

This section describes the IBM support available for QMF for z/OS - NLV.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before you install QMF for z/OS - NLV, make sure that you have reviewed the current Preventive Service Planning (PSP) information. Review the PSP Bucket for General Information, Installation Documentation, and the Cross Product Dependencies sections. For the Recommended Service section, instead of reviewing the PSP Bucket, it is recommended you use the IBM.PRODUCTINSTALL-REQUIREDSERVICE fix category in SMP/E to ensure you have all the recommended service installed. Use the **FIXCAT(IBM.ProductInstall-RequiredService)** operand on the **APPLY CHECK** command. See 6.1.10, "Perform SMP/E APPLY" on page 65 for a sample **APPLY** command.

If you obtained QMF for z/OS - NLV as part of a CBPDO, HOLDDATA is included.

If the CBPDO for QMF for z/OS - NLV is older than two weeks by the time you install the product materials, you can obtain the latest PSP Bucket information by going to the following website:

<https://esupport.ibm.com/customercare/psearch/search?domain=psp>

You can also use S/390 SoftwareXcel or contact the IBM Support Center to obtain the latest PSP Bucket information.

For program support, access the Software Support Website at <https://www.ibm.com/mysupport/>.

PSP Buckets are identified by UPGRADEs, which specify product levels; and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for QMF for z/OS - NLV are included in Figure 22.

Figure 22 (Page 1 of 2). PSP Upgrade and Subset ID

UPGRADE	SUBSET	Description
5698QMF	HSQDD10	QMF TSO/CICS Base
	HFQMD10	QMF Z Client
	HHPCC10	QMF HPO
	HQDCC10	QMF Data Service

Figure 22 (Page 2 of 2). PSP Upgrade and Subset ID

UPGRADE	SUBSET	Description
	JYQDD10	QMF applications
	JSQDD1Q	QMF for z/OS OTC
	JSQDD5A	QMF Korean
	JSQDD5B	QMF Brazilian Portugues
	JSQDD5C	QMF Spanish
	JSQDD5D	QMF Swedish
	JSQDD5E	QMF Swiss French
	JSQDD5F	QMF Swiss German
	JSQDD5G	QMF Canadian French
	JSQDD51	QMF Uppercase English
	JSQDD55	QMF Danish
	JSQDD56	QMF French
	JSQDD57	QMF German
	JSQDD58	QMF Italian
	JSQDD59	QMF Japanese

3.3 Statement of Support Procedures

Report any problems which you feel might be an error in the product materials to your IBM Support Center. You may be asked to gather and submit additional diagnostics to assist the IBM Support Center in their analysis.

Figure 23 identifies the component IDs (COMPID) for QMF for z/OS - NLV.

Figure 23 (Page 1 of 2). Component IDs

FMID	COMPID	Component Name	RETAIN Release
HSQDD10	566872101	QMF TSO/CICS Base	D10
HFQMD10	566872105	QMF Z Client	D10
HHPCC10	5668HPO00	QMF HPO	C10
HQDCC10	566872103	QMF Data Service	C10
JYQDD10	5668QCA00	QMF applications	D10
JSQDD1Q	566872101	QMF for z/OS OTC	D1Q
JSQDD5A	566872101	QMF Korean	D5A

Figure 23 (Page 2 of 2). Component IDs

FMID	COMPID	Component Name	RETAIN Release
JSQDD5B	566872101	QMF Brazilian Portuguese	D5B
JSQDD5C	566872101	QMF Spanish	D5C
JSQDD5D	566872101	QMF Swedish	D5D
JSQDD5E	566872101	QMF Swiss French	D5E
JSQDD5F	566872101	QMF Swiss German	D5F
JSQDD5G	566872101	QMF Canadian French	D5G
JSQDD51	566872101	QMF Uppercase English	D51
JSQDD55	566872101	QMF Danish	D55
JSQDD56	566872101	QMF French	D56
JSQDD57	566872101	QMF German	D57
JSQDD58	566872101	QMF Italian	D58
JSQDD59	566872101	QMF Japanese	D59

4.0 Program and Service Level Information

This section identifies the program and relevant service levels of QMF for z/OS - NLV. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

4.1 Program Level Information

APAR fixes against this release of QMF for z/OS - NLV have been incorporated into this product package. For a list of included fixes, examine the ++VER statement in the product's SMPMCS.

4.2 Service Level Information

PTFs containing APAR fixes against this release of QMF for z/OS - NLV have been incorporated into this product package. For a list of included PTFs, examine the ++VER statement in the product's SMPMCS.

Frequently check the QMF for z/OS - NLV PSP Bucket for HIPER and SPECIAL attention PTFs against all FMIDs that you must install. You can also receive the latest HOLDDATA, then add the **FIXCAT(IBM.PRODUCTINSTALL-REQUIRESERVICE)** operand on your **APPLY CHECK** command. This will allow you to review the recommended and critical service that should be installed with your FMIDs.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating QMF for z/OS - NLV. The following terminology is used:

- *Driving system*: the system on which SMP/E is executed to install the program.
The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.
- *Target system*: the system on which the program is configured and run.
The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

- When you install a new level of a product that is already installed, the new level of the product will replace the old one. By installing the new level onto a separate target system, you can test the new level and keep the old one in production at the same time.
- When you install a product that shares libraries or load modules with other products, the installation can disrupt the other products. By installing the product onto a separate target system, you can assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install QMF for z/OS - NLV.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

Figure 24. Driving System Software Requirements				
Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	V02.03.00	N/A	No

Note: SMP/E is a requirement for Installation and is an element of z/OS but can also be ordered as a separate product, 5655-G44, minimally V03.06.00.

Note: Installation might require migration to new z/OS releases to insure serviceability. See <https://www.ibm.com/support/lifecycle/>.

5.2 Target System Requirements

This section describes the environment of the target system required to install and use QMF for z/OS - NLV.

QMF for z/OS - NLV installs in the DBS (P115) SREL.

5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites

Installation requisites identify products that are required and *must* be present on the system or products that are not required but *should* be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product.

Figure 25 (Page 1 of 2). Target System Mandatory Installation Requisites				
Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	02.03.00	N/A	No
Any one of the following:				
5650-DB2	Db2 for z/OS	12.01.00	N/A	No

Figure 25 (Page 2 of 2). Target System Mandatory Installation Requisites

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5770-AF3	Db2 for z/OS VUE	12.01.00	N/A	No
5698-DB2	Db2 for z/OS	13.01.00	N/A	No
5698-DBV	Db2 for z/OS VUE	13.01.00	N/A	No

Note: Installation might require migration to new z/OS releases to be service supported. See <https://www.ibm.com/support/lifecycle/>.

Conditional installation requisites identify products that are *not* required for successful installation of this product but can resolve such things as certain warning messages at installation time.

QMF for z/OS - NLV has no conditional installation requisites.

5.2.2.2 Operational Requisites

Operational requisites are products that are required and *must* be present on the system or products that are not required but *should* be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions.

Figure 26. Target System Mandatory Operational Requisites

Program Number	Product Name and Minimum VRM/Service Level
Any one of the following:	
5650-DB2	Db2 for z/OS V12.01.00
5770-AF3	Db2 for z/OS VUE V12.01.00
5698-DB2	Db2 for z/OS V13.01.00
5698-DBV	Db2 for z/OS VUE V13.01.00
Any one of the following (for QMF under CICS only):	
5655-Y04	CICS Transaction Server for z/OS V05.05.00
5655-Y04	CICS Transaction Server for z/OS V05.06.00

Note: Installation might require migration to new z/OS releases to be service supported. See <https://www.ibm.com/support/lifecycle/>.

Conditional operational requisites identify products that are *not* required for this product to operate its basic functions but are required at run time for this product to operate specific functions.

QMF for z/OS - NLV has no conditional operational requisites.

5.2.2.3 Toleration/Coexistence Requisites

Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

QMF for z/OS - NLV has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites

Negative requisites identify products that must *not* be installed on the same system as this product.

QMF for z/OS - NLV has no negative requisites.

5.2.3 DASD Storage Requirements

QMF for z/OS - NLV libraries can reside on all supported DASD types.

The following tables list the total space required for each type of library.

<i>Figure 27. Total DASD Space Required by Db2 QMF for z/OS</i>	
Library Type	Total Space Required in 3390 Trks
Target	7336
Distribution	6488

<i>Figure 28. Total DASD Space Required by any National Language Version</i>	
Library Type	Total Space Required in 3390 Trks
Target	281
Distribution	328

Notes:

1. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.
2. Abbreviations used for data set types are shown as follows.

- U** Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
- S** Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- E** Existing shared data set, used by this product and other products. This data set is *not* allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.8, "Allocate SMP/E Target and Distribution Libraries" on page 63.

3. All target and distribution libraries listed have the following attributes:
 - The default name of the data set can be changed.
 - The default block size of the data set can be changed.
 - The data set can be merged with another data set that has equivalent characteristics.
 - The data set can be either a PDS or a PDSE.
4. All target libraries listed have the following attributes:
 - These data sets can be SMS-managed, but they are not required to be SMS-managed.
 - These data sets are not required to reside on the IPL volume.
 - The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.
5. All target libraries that are listed and contain load modules have the following attributes:
 - These data sets can be in the LPA, but they are not required to be in the LPA.
 - These data sets can be in the LNKLIST.
 - These data sets are not required to be APF-authorized.

If you are installing a National Language in this document, please refer to the following table which associates a lettered language identifier to each National Language. The language identifier is the last character shown in the Storage Requirement figures for the Target, Distribution and Non-SMP/E data set names.

This language identifier does not apply to the QMF for TSO/CICS base.

Figure 29. QMF National Language Identifiers

Language	Language Identifier	FMID
QMF Korean	H	JSQDD5A
QMF Brazilian Portuguese	P	JSQDD5B
QMF Spanish	S	JSQDD5C
QMF Swedish	V	JSQDD5D
QMF Swiss French	Y	JSQDD5E
QMF Swiss German	Z	JSQDD5F
QMF Canadian French	C	JSQDD5G
QMF Uppercase English	U	JSQDD51
QMF Danish	Q	JSQDD55
QMF French	F	JSQDD56
QMF German	D	JSQDD57
QMF Italian	I	JSQDD58
QMF Japanese	K	JSQDD59

The following figures describe the target and distribution libraries required to install QMF for z/OS - NLV. The storage requirements of QMF for z/OS - NLV must be added to the storage required by other programs that have data in the same library.

Note: Use the data in these tables to determine which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 30 (Page 1 of 2). Storage Requirements for QMF for TSO/CICS Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C O R D S	L E N G T H	No. of 3390 Trks	No. of DIR Blks
SDSQBASE	SAMP	Any	U	PDS	FB	80	9	5
SDSQCHRT	DATA	Any	U	PDS	FB	400	2	5
SDSQCLTE	CLIST	Any	U	PDS	FB	80	34	5
SDSQDBRM	MAC	Any	U	PDS	FB	80	10	5
SDSQEXCE	EXEC	Any	U	PDS	FB	80	21	5
SDSQEXIT	LMOD	Any	U	PDS	U	0	4	5

Figure 30 (Page 2 of 2). Storage Requirements for QMF for TSO/CICS Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQLOAD	LMOD	Any	U	PDS	U	0	1626	30
SDSQMAPE	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBE	MSGENU	Any	U	PDS	FB	80	6	5
SDSQPLBE	PNLENU	Any	U	PDS	FB	80	22	10
SDSQPVRE	DATA	Any	U	PDS	V	32622	200	5
SDSQSAPE	MAC	Any	U	PDS	FB	80	51	15
SDSQSLBE	MAC	Any	U	PDS	FB	80	6	5
SDSQTLBE	TBL	Any	U	PDS	FB	80	17	5
SDSQUSRE	MAC	Any	U	PDS	FB	80	26	5

Figure 31. Storage Requirements for QMF Z Client Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SFQMBASE	SAMP	Any	U	PDS	FB	80	2	5
SFQMEXEC	EXEC	Any	U	PDS	FB	80	1	2
SFQMLANG	DATA	Any	U	PDS	VB	256	13	2
SFQMLOAD	PROGRAM	Any	U	PDSE	U	0	570	n/a
SFQMPPARM	PPARM	Any	U	PDS	FB	80	1	2
SFQMSKEL	SKEL	Any	U	PDS	FB	80	1	2

Figure 32 (Page 1 of 2). Storage Requirements for QMF HPO Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SRAACLST	CLIST	Any	U	PDS	FB	80	20	5
SRAADB RM	MAC	Any	U	PDS	FB	80	40	5
SRAAEXEC	EXEC	Any	U	PDS	FB	80	5	5

Figure 32 (Page 2 of 2). Storage Requirements for QMF HPO Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SRAAISPM	MSGENU	Any	U	PDS	FB	80	25	20
SRAAISPP	PNLENU	Any	U	PDS	FB	80	160	90
SRAALOAD	MOD	Any	U	PDS	U	0	400	25
SRAASAMP	SAMP	Any	U	PDS	FB	80	30	10
SRAASKEL	DATA	Any	U	PDS	FB	80	120	5

Figure 33. Storage Requirements for QMF applications Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDYQCFG	DATA	Any	U	PDS	FB	80	5	5

Figure 34 (Page 1 of 2). Storage Requirements for QMF Data Service Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SCQDBASE	SAMP	Any	U	PDS	FB	80	15	5
SCQDCLOD	MOD	Any	U	PDSE	U	0	10	n/a
SCQDCNTL	DATA	Any	U	PDS	FB	80	30	10
SCQDDBRM	MAC	Any	U	PDS	FB	80	50	5
SCQDEXEC	EXEC	Any	U	PDS	FB	80	60	5
SCQDLOAD	MOD	Any	U	PDSE	U	0	3000	n/a
SCQDMAP	DATA	Any	U	PDS	FB	2048	20	10
SCQDMENU	MSGENU	Any	U	PDS	FB	80	10	5
SCQDOBJX	DATA	Any	U	PDS	FB	80	35	5
SCQDPENU	PNLENU	Any	U	PDS	FB	80	50	25
SCQDRPC	MOD	Any	U	PDSE	U	0	60	n/a
SCQDSAMP	DATA	Any	U	PDS	FB	80	30	15

Figure 34 (Page 2 of 2). Storage Requirements for QMF Data Service Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SCQDSLIB	SKL	Any	U	PDS	FB	80	5	5
SCQDSMAP	DATA	Any	U	PDS	FB	2048	1050	30
SCQDTENU	TBL	Any	U	PDS	FB	80	5	5
SCQDXATH	DATA	Any	U	PDS	FB	80	15	10
SCQDXCMD	DATA	Any	U	PDS	FB	80	10	5
SCQDXEXC	DATA	Any	U	PDS	FB	80	12	5
SCQDXSQL	DATA	Any	U	PDS	FB	80	15	5
SCQDXTOD	DATA	Any	U	PDS	FB	80	5	5
SCQDXVTB	DATA	Any	U	PDS	FB	80	5	5

Figure 35 (Page 1 of 5). Storage Requirements for QMF for z/OS - NLV - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQCLTH	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCH	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPH	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBH	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBH	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRH	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMH	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPH	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBH	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRH	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTP	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCP	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPP	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBP	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBP	PANEL	Any	U	PDS	FB	80	22	5

Figure 35 (Page 2 of 5). Storage Requirements for QMF for z/OS - NLV - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQPVRP	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMP	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPP	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBP	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRP	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTS	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCS	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPS	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBS	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBS	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRS	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMS	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPS	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBS	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRS	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTV	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCV	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPV	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBV	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBV	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRV	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMV	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPV	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBV	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRV	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTY	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCY	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPY	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBY	MSG	Any	U	PDS	FB	80	7	5

Figure 35 (Page 3 of 5). Storage Requirements for QMF for z/OS - NLV - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQPLBY	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRY	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMY	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPY	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBY	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRY	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTZ	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCZ	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPZ	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBZ	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBZ	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRZ	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMZ	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPZ	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBZ	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRZ	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTC	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCC	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPC	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBC	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBC	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRC	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMC	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPC	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBC	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRC	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTU	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCU	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPU	DATA	Any	U	PDS	FB	400	5	5

Figure 35 (Page 4 of 5). Storage Requirements for QMF for z/OS - NLV - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQMLBU	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBU	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRU	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMU	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPU	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBU	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRU	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTQ	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCQ	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPQ	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBQ	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBQ	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRQ	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMQ	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPQ	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBQ	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRQ	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTF	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCF	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPF	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBF	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBF	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRF	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMF	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPF	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBF	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRF	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTD	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCD	EXEC	Any	U	PDS	FB	80	14	5

Figure 35 (Page 5 of 5). Storage Requirements for QMF for z/OS - NLV - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQMAPD	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBD	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBD	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRD	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMD	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPD	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBD	TBL	Any	U	PDS	FB	80	5	10
SDSQUSRD	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTI	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCI	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPI	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBI	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBI	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRI	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMI	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPI	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBI	TBL	Any	U	PDS	FB	80	11	5
SDSQUSR1	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTK	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCK	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPK	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBK	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBK	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRK	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMK	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPK	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBK	TBL	Any	U	PDS	FB	80	5	10
SDSQUSRK	SAMPLE	Any	U	PDS	FB	80	26	5

Figure 36. Storage Requirements for QMF for TSO/CICS Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQBASE	U	PDS	FB	80	9	5
ADSQCHRT	U	PDS	FB	400	2	5
ADSQCLTE	U	PDS	FB	80	34	5
ADSQDBRM	U	PDS	FB	80	10	5
ADSQEXCE	U	PDS	FB	80	14	5
ADSQLOAD	U	PDS	U	0	7	5
ADSQMAPE	U	PDS	FB	400	5	5
ADSQMLBE	U	PDS	FB	80	6	5
ADSQOBJ	U	PDS	U	0	1005	200
ADSQPLBE	U	PDS	FB	80	19	10
ADSQPVRE	U	PDS	V	32622	150	5
ADSQSAPE	U	PDS	FB	80	51	15
ADSQSLBE	U	PDS	FB	80	6	5
ADSQTLBE	U	PDS	FB	80	17	5
ADSQUSRE	U	PDS	FB	80	26	5

Figure 37. Storage Requirements for QMF Z Client Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
AFQMBASE	U	PDS	FB	80	2	5
AFQMEXEC	U	PDS	FB	80	1	2
AFQMLANG	U	PDS	VB	256	13	2
AFQMLoad	U	PDSE	U	0	570	n/a
AFQM Parm	U	PDS	FB	80	1	2
AFQMSKEL	U	PDS	FB	80	1	2

Figure 38. Storage Requirements for QMF HPO Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ARAACLST	U	PDS	FB	80	20	5
ARAADBRM	U	PDS	FB	80	40	5
ARAAEXEC	U	PDS	FB	80	5	5
ARAAISPM	U	PDS	FB	80	25	20
ARAAISPP	U	PDS	FB	80	160	90
ARAALOAD	U	PDS	U	0	250	15
ARAASAMP	U	PDS	FB	80	20	10
ARAASKEL	U	PDS	FB	80	120	5

Figure 39. Storage Requirements for QMF applications Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADYQCFG	U	PDS	FB	80	5	5

Figure 40 (Page 1 of 2). Storage Requirements for QMF Data Service Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ACQDBASE	U	PDS	FB	80	15	5
ACQDCNTL	U	PDS	FB	80	30	10
ACQDDBRM	U	PDS	FB	80	50	5
ACQDEXEC	U	PDS	FB	80	60	5
ACQDLOAD	U	PDSE	U	0	3000	N/A
ACQDMAP	U	PDS	FB	2048	20	10
ACQDMENU	U	PDS	FB	80	10	5
ACQDOBJX	U	PDS	FB	80	35	5
ACQDPENU	U	PDS	FB	80	50	25

Figure 40 (Page 2 of 2). Storage Requirements for QMF Data Service Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ACQDRPC	U	PDSE	U	0	60	N/A
ACQDSAMP	U	PDS	FB	80	30	15
ACQDSLIB	U	PDS	FB	80	5	5
ACQDSMAP	U	PDS	FB	2048	1050	30
ACQDTENU	U	PDS	FB	80	5	5
ACQDXATH	U	PDS	FB	80	15	10
ACQDXCMD	U	PDS	FB	80	10	5
ACQDXEXC	U	PDS	FB	80	12	5
ACQDXSQL	U	PDS	FB	80	15	5
ACQDXTOD	U	PDS	FB	80	5	5
ACQDXVTB	U	PDS	FB	80	5	5

Figure 41 (Page 1 of 6). Storage Requirements for QMF for z/OS - NLV - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQCLTH	U	PDS	FB	80	16	5
ADSQEXCH	U	PDS	FB	80	16	5
ADSQMAPH	U	PDS	FB	400	5	5
ADSQMLBH	U	PDS	FB	80	16	5
ADSQPLBH	U	PDS	FB	80	26	5
ADSQPVRH	U	PDS	V	32622	150	5
ADSQSAMH	U	PDS	FB	80	16	5
ADQSAPH	U	PDS	FB	80	51	15
ADSQTLBH	U	PDS	FB	80	16	5
ADSQUSRH	U	PDS	FB	80	16	5
ADSQCLTP	U	PDS	FB	80	16	5
ADSQEXCP	U	PDS	FB	80	16	5
ADSQMAPP	U	PDS	FB	400	5	5

Figure 41 (Page 2 of 6). Storage Requirements for QMF for z/OS - NLV - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQMLBP	U	PDS	FB	80	16	5
ADSQPLBP	U	PDS	FB	80	26	5
ADSQPVRP	U	PDS	V	32622	150	5
ADSQSAMP	U	PDS	FB	80	16	5
ADSQSAPP	U	PDS	FB	80	51	15
ADSQTLBP	U	PDS	FB	80	16	5
ADSQUSRP	U	PDS	FB	80	16	5
ADSQCLTS	U	PDS	FB	80	16	5
ADSQEXCS	U	PDS	FB	80	16	5
ADSQMAPS	U	PDS	FB	400	5	5
ADSQMLBS	U	PDS	FB	80	16	5
ADSQPLBS	U	PDS	FB	80	26	5
ADSQPVRS	U	PDS	V	32622	150	5
ADSQSAMS	U	PDS	FB	80	16	5
ADSQSAPS	U	PDS	FB	80	51	15
ADSQTLBS	U	PDS	FB	80	16	5
ADSQUSRS	U	PDS	FB	80	16	5
ADSQCLTV	U	PDS	FB	80	16	5
ADSQEXCV	U	PDS	FB	80	16	5
ADSQMAPV	U	PDS	FB	400	5	5
ADSQMLBV	U	PDS	FB	80	16	5
ADSQPLBV	U	PDS	FB	80	26	5
ADSQPVRV	U	PDS	V	32622	150	5
ADSQSAMV	U	PDS	FB	80	16	5
ADSQSAPV	U	PDS	FB	80	51	15
ADSQTLBV	U	PDS	FB	80	16	5
ADSQUSRV	U	PDS	FB	80	16	5
ADSQCLTY	U	PDS	FB	80	16	5
ADSQEXCY	U	PDS	FB	80	16	5

Figure 41 (Page 3 of 6). Storage Requirements for QMF for z/OS - NLV - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQMAPY	U	PDS	FB	400	5	5
ADSQMLBY	U	PDS	FB	80	16	5
ADSQPLBY	U	PDS	FB	80	26	5
ADSQPVR	U	PDS	V	32622	150	5
ADSQSAMY	U	PDS	FB	80	16	5
ADSQSAPY	U	PDS	FB	80	51	15
ADSQTLBY	U	PDS	FB	80	16	5
ADSQUSRY	U	PDS	FB	80	16	5
ADSQCLTZ	U	PDS	FB	80	16	5
ADSQEXCZ	U	PDS	FB	80	16	5
ADSQMAPZ	U	PDS	FB	400	5	5
ADSQMLBZ	U	PDS	FB	80	16	5
ADSQPLBZ	U	PDS	FB	80	26	5
ADSQPVRZ	U	PDS	V	32622	150	5
ADSQSAMZ	U	PDS	FB	80	16	5
ADSQSAPZ	U	PDS	FB	80	51	15
ADSQTLBZ	U	PDS	FB	80	16	5
ADSQUSRZ	U	PDS	FB	80	26	5
ADSQCLTC	U	PDS	FB	80	16	5
ADSQEXCC	U	PDS	FB	80	16	5
ADSQMAPC	U	PDS	FB	400	5	5
ADSQMLBC	U	PDS	FB	80	16	5
ADSQPLBC	U	PDS	FB	80	26	5
ADSQPVRC	U	PDS	V	32622	150	5
ADSQSAMC	U	PDS	FB	80	16	5
ADSQSAPC	U	PDS	FB	80	51	15
ADSQTLBC	U	PDS	FB	80	16	5
ADSQUSRC	U	PDS	FB	80	26	5
ADSQCLTU	U	PDS	FB	80	16	5

Figure 41 (Page 4 of 6). Storage Requirements for QMF for z/OS - NLV - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQEXCU	U	PDS	FB	80	16	5
ADSQMAPU	U	PDS	FB	400	5	5
ADSQMLBU	U	PDS	FB	80	16	5
ADSQPLBU	U	PDS	FB	80	26	5
ADSQPVRU	U	PDS	V	32622	150	5
ADSQSAMU	U	PDS	FB	80	16	5
ADSQSAPU	U	PDS	FB	80	51	15
ADSQTLBU	U	PDS	FB	80	16	5
ADSQUSRU	U	PDS	FB	80	26	5
ADSQCLTQ	U	PDS	FB	80	16	5
ADSQEXCQ	U	PDS	FB	80	16	5
ADSQMAPQ	U	PDS	FB	400	5	5
ADSQMLBQ	U	PDS	FB	80	16	5
ADSQPLBQ	U	PDS	FB	80	26	5
ADSQPVRQ	U	PDS	V	32622	150	5
ADSQSAMQ	U	PDS	FB	80	16	5
ADSQSAPQ	U	PDS	FB	80	51	15
ADSQTLBQ	U	PDS	FB	80	16	5
ADSQUSRQ	U	PDS	FB	80	26	5
ADSQCLTF	U	PDS	FB	80	16	5
ADSQEXCF	U	PDS	FB	80	16	5
ADSQMAPF	U	PDS	FB	400	5	5
ADSQMLBF	U	PDS	FB	80	16	5
ADSQPLBF	U	PDS	FB	80	26	5
ADSQPVRF	U	PDS	V	32622	150	5
ADSQSAMF	U	PDS	FB	80	16	5
ADSQSAPF	U	PDS	FB	80	51	15
ADSQTLBF	U	PDS	FB	80	16	5
ADSQUSRF	U	PDS	FB	80	26	5

Figure 41 (Page 5 of 6). Storage Requirements for QMF for z/OS - NLV - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQCLTD	U	PDS	FB	80	16	5
ADSQEXCD	U	PDS	FB	80	16	5
ADSQMAPD	U	PDS	FB	400	5	5
ADSQMLBD	U	PDS	FB	80	16	5
ADSQPLBD	U	PDS	FB	80	26	5
ADSQPVRD	U	PDS	V	32622	150	5
ADSQSAMD	U	PDS	FB	80	16	5
ADSQSAPD	U	PDS	FB	80	51	15
ADSQTLBD	U	PDS	FB	80	16	5
ADSQUSRD	U	PDS	FB	80	26	5
ADSQCLTI	U	PDS	FB	80	16	5
ADSQEXCI	U	PDS	FB	80	16	5
ADSQMAPI	U	PDS	FB	400	5	5
ADSQMLBI	U	PDS	FB	80	16	5
ADSQPLBI	U	PDS	FB	80	26	5
ADSQPVRI	U	PDS	V	32622	150	5
ADSQSAMI	U	PDS	FB	80	16	5
ADSQSAPI	U	PDS	FB	80	51	15
ADSQTLBI	U	PDS	FB	80	16	5
ADSQUSRI	U	PDS	FB	80	26	5
ADSQCLTK	U	PDS	FB	80	16	5
ADSQEXCK	U	PDS	FB	80	16	5
ADSQMAPK	U	PDS	FB	400	5	5
ADSQMLBK	U	PDS	FB	80	16	5
ADSQPLBK	U	PDS	FB	80	26	5
ADSQPVRK	U	PDS	V	32622	150	5
ADSQSAMK	U	PDS	FB	80	16	5
ADSQSAPK	U	PDS	FB	80	51	15
ADSQTLBK	U	PDS	FB	80	16	5

Figure 41 (Page 6 of 6). Storage Requirements for QMF for z/OS - NLV - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQUSRK	U	PDS	FB	80	26	5

Figure 42. Storage Requirements for QMF for z/OS - NLV Non-SMP/E Data Sets

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
DSQPNLE	U	VSAM	VS	32756	135	n/a
DSQPNLH	U	VSAM	VS	32756	135	n/a
DSQPNLP	U	VSAM	VS	32756	135	n/a
DSQPNLS	U	VSAM	VS	32756	135	n/a
DSQPNLV	U	VSAM	VS	32756	135	n/a
DSQPNLY	U	VSAM	VS	32756	135	n/a
DSQPNLZ	U	VSAM	VS	32756	135	n/a
DSQPNLC	U	VSAM	VS	32756	135	n/a
DSQPNLU	U	VSAM	VS	32756	135	n/a
DSQPNLQ	U	VSAM	VS	32756	135	n/a
DSQPNLF	U	VSAM	VS	32756	135	n/a
DSQPNLD	U	VSAM	VS	32756	135	n/a
DSQPNLI	U	VSAM	VS	32756	135	n/a
DSQPNLK	U	VSAM	VS	32756	135	n/a

5.3 FMIDs Deleted

Installing QMF for z/OS - NLV might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install QMF for z/OS - NLV into separate SMP/E target and distribution zones.

Note: These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, use the SMP/E REJECT NOFMID DELETEFMID command. See the SMP/E Commands book for details.

5.4 Special Considerations

- Db2 QMF TSO and CICS Clients' Special Requirements:
 - Operates on any z Systems hardware configuration that supports the required software.
 - Runs on any processor that is supported by the operating system. Some operations, however, will not work with columns that contain decimal floating point data if the processor on which QMF is running does not support decimal floating point instructions.
 - Accesses all of the DASD devices that are supported by z/OS and Db2 for z/OS, as well as all display devices supported by Graphical Data Display Manager (GDDM).
 - To implement a national language feature that uses a double-byte character set (DBCS), you need a workstation that supports DBCS. Ensure that this device is supported by GDDM.
 - When you plan your region size, consider the storage required to load modules during initialization and the virtual storage requirements for report operations.
 - Restriction: For TSO only, consider the amount of space required to run applications other than Db2 QMF.
- Db2 QMF Data Service Special Requirements:
 - Operates on any z Systems hardware configuration that supports the required software
 - Runs on any processor that is supported by the operating system
- Db2 QMF Data Service Studio Special Requirements:
 - Any hardware configuration that supports the required Microsoft software
 - Approximately 1 GB of disk space (single language installation)
 - Minimum of 1 GB of RAM
 - Network connectivity

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of QMF for z/OS - NLV.

Please note the following points:

- If you want to install QMF for z/OS - NLV into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.
- You can use the SMP/E dialogs instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing QMF for z/OS - NLV

6.1.1 SMP/E Considerations for Installing QMF for z/OS - NLV

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of QMF for z/OS - NLV.

6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 43. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

Figure 43. SMP/E Options Subentry Values

Subentry	Value	Comment
DSSPACE	(500,500,500)	3390 DASD tracks
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

6.1.3 SMP/E CALLLIBS and SIDE DECK PROCESSING

QMF for z/OS - NLV uses the CALLLIBS function provided in SMP/E to resolve external references during installation. When QMF for z/OS - NLV is installed, ensure that DDDEFs exist for the following libraries:

- CSSLIB
- SADMMOD
- SCCNOBJ

- SCEELKED
- SCEESPC
- SCSQLOAD
- SDFHLOAD
- SISPLLOAD

QMF for z/OS - NLV also uses Side Deck processing during link-edits. When QMF for z/OS - NLV is installed, ensure that the DDDEFs exist for the following libraries:

- SDSNLOAD

6.1.4 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install QMF for z/OS - NLV:

6.1.4.1 Sample Jobs for QMF for z/OS - NLV

<i>Figure 44 (Page 1 of 2). Sample Installation Jobs</i>			
Job Name	Job Type	Description	RELFILE
FQMALA	ALLOCATE	Sample job to allocate and initialize a new SMP/E CSI data set for QMF Z Client	IBM.HFQMD10.F1
FQMALB	ALLOCATE	Sample job to allocate new SMP/E data sets for QMF Z Client	IBM.HFQMD10.F1
FQMRECV	RECEIVE	Sample RECEIVE job for QMF Z Client	IBM.HFQMD10.F1
FQMALLOC	ALLOCATE	Sample job to allocate target and distribution libraries for QMF Z Client	IBM.HFQMD10.F1
FQMDDEF	DDDEF	Sample job to define SMP/E DDDEFs for QMF Z Client	IBM.HFQMD10.F1
FQMAPPLY	APPLY	Sample APPLY job for QMF Z Client	IBM.HFQMD10.F1
FQMACCPT	ACCEPT	Sample ACCEPT job for QMF Z Client	IBM.HFQMD10.F1
DSQALA	SMP/E	Sample job to allocate and initialize a new SMP/E CSI data set (Optional)	IBM.HSQDD10.F2
DSQALB	SMP/E	Sample job to allocate SMP/E data sets (Optional)	IBM.HSQDD10.F2
DSQRECV1	RECEIVE	Sample RECEIVE job for QMF TSO/CICS Base	IBM.HSQDD10.F2
DSQRECV2	RECEIVE	Sample RECEIVE job for QMF HPO	IBM.HSQDD10.F2
DSQRECV3	RECEIVE	Sample RECEIVE job for QMF applications	IBM.HSQDD10.F2
CQDRECV4	RECEIVE	Sample RECEIVE job for QMF Data Service	IBM.HQDCC10.F2
DSQRECVQ	RECEIVE	Sample RECEIVE job for QMF for z/OS OTC	IBM.HSQDD10.F2

Figure 44 (Page 2 of 2). Sample Installation Jobs

Job Name	Job Type	Description	RELFILE
DSQALLOC	ALLOCATE	Sample job to allocate target and distribution libraries for QMF (TSO/CICS, OTC, HPO and QMF applications)	IBM.HSQDD10.F2
CQDALOC4	ALLOCATE	Sample job to allocate target and distribution libraries for QMF Data Service	IBM.HQDCC10.F2
DSQDDEF	DDDEF	Sample job to define SMP/E DDDEFs for QMF (TSO/CICS, OTC, HPO and QMF applications)	IBM.HSQDD10.F2
CQDDDEF4	DDDEF	Sample job to define SMP/E DDDEFs for QMF Data Service	IBM.HQDCC10.F2
DSQAPPLY	APPLY	Sample APPLY job for QMF (TSO/CICS, HPO and QMF applications)	IBM.HSQDD10.F2
CQDAPLY4	APPLY	Sample APPLY job for QMF Data Service	IBM.HQDCC10.F2
DSQAPLYQ	APPLY	Sample APPLY job for QMF (OTC)	IBM.HSQDD10.F2
DSQACCEP	ACCEPT	Sample ACCEPT job for QMF (TSO/CICS, HPO and QMF applications)	IBM.HSQDD10.F2
CQDACCE4	ACCEPT	Sample ACCEPT job for QMF Data Service	IBM.HQDCC10.F2
DSQACCEQ	ACCEPT	Sample ACCEPT job for QMF (OTC)	IBM.HSQDD10.F2

You can access the sample installation jobs by performing an SMP/E RECEIVE (refer to 6.1.7, "Perform SMP/E RECEIVE" on page 62) then copy the jobs from the RELFILES to a work data set for editing and submission. See Figure 44 on page 45 to find the appropriate refile data set.

You can also copy the sample installation jobs from the product files by submitting the following job. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//*****
//* Make the //TAPEIN DD statement below active if you install*
//* from a CBPDO tape by uncommenting the DD statement below. *
//*****
//*TAPEIN DD DSN=IBM.HSQDD10.F2,UNIT=tunit,
//* VOL=SER=volser,LABEL=(x,SL),
//* DISP=(OLD,KEEP)
//*TAPEIN2 DD DSN=IBM.HQDCC10.F2,UNIT=tunit,
//* VOL=SER=volser,LABEL=(x,SL),
//* DISP=(OLD,KEEP)
//*TAPEIN3 DD DSN=IBM.HFQMD10.F1,UNIT=tunit,
//* VOL=SER=volser,LABEL=(x,SL),
//* DISP=(OLD,KEEP)
```

```

/*****
/* Make the //TAPEIN DD statement below active if you install*
/* from a product tape received outside the CBPDO process *
/* (using the optional SMP/E RECEIVE job) by uncommenting *
/* the DD statement below. *
/*****
/*TAPEIN DD DSN=IBM.HSQDD10.F2,UNIT=tunit,
/* VOL=SER=volser,LABEL=(3,SL),
/* DISP=(OLD,KEEP)
/*TAPEIN2 DD DSN=IBM.HQDCC10.F2.,UNIT=tunit,
/* VOL=SER=volser,LABEL=(3,SL),
/* DISP=(OLD,KEEP)
/*TAPEIN3 DD DSN=IBM.HFQMD10.F1,UNIT=tunit,
/* VOL=SER=volser,LABEL=(2,SL),
/* DISP=(OLD,KEEP)
/*****
/* Make the //FILEIN DD statement below active for *
/* downloaded DASD files. *
/*****
/*FILEIN DD DSN=IBM.HSQDD10.F2,UNIT=SYSALLDA,DISP=SHR,
/* VOL=SER=filevol
/*FILEIN2 DD DSN=IBM.HQDCC10.F2.,UNIT=SYSALLDA,DISP=SHR,
/* VOL=SER=filevol
/*FILEIN3 DD DSN=IBM.HFQMD10.F1.,UNIT=SYSALLDA,DISP=SHR,
/* VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,
// SPACE=(TRK,(20,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
COPY INDD=yyyyIN,OUTDD=OUT
COPY INDD=zzzzIN,OUTDD=OUT
/*

```

See the following information to update the statements in the previous sample:

TAPEIN/TAPEIN2/TAPEIN3:

tunit is the unit value that matches the product package.

volser is the volume serial that matches the product package.

x is the tape file number that indicates the location of the data set name on the tape.

See the documentation that is provided by CBPDO for the location of IBM.HSQDD10.F2, IBM.HQDCC10.F2 and IBM.HFQMD10.F1 on the tape.

FILEIN/FILEIN2/FILEIN3:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT:

jcl-library-name is the name of the output data set where the sample jobs are stored.

dasdvol is the volume serial of the DASD device where the output data set resides.

SYSIN:

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

yyyyIN is either TAPEIN2 or FILEIN2 depending on your input DD statement.

zzzzIN is either TAPEIN3 or FILEIN3 depending on your input DD statement.

6.1.4.2 Sample Jobs for National Language Version for QMF Korean

<i>Figure 45. Sample Installation Jobs for QMF Korean</i>			
Job Name	Job Type	Description	RELFILE
DSQHRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5A.F2
DSQHALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5A.F2
DSQHDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5A.F2
DSQHAPLY	APPLY	Sample APPLY job	IBM.JSQDD5A.F2
DSQHACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5A.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 45 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD5A.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.3 Sample Jobs for National Language Version for QMF Brazilian Portuguese

Figure 46. Sample Installation Jobs for QMF Brazilian Portuguese

Job Name	Job Type	Description	RELFILE
DSQPRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5B.F2
DSQPALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5B.F2
DSQPDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5B.F2
DSQPAPLY	APPLY	Sample APPLY job	IBM.JSQDD5B.F2
DSQPACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5B.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 46 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD5B.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.4 Sample Jobs for National Language Version for QMF Spanish

<i>Figure 47. Sample Installation Jobs for QMF Spanish</i>			
Job Name	Job Type	Description	RELFILE
DSQSRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5C.F2
DSQSALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5C.F2
DSQSDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5C.F2
DSQSAPLY	APPLY	Sample APPLY job	IBM.JSQDD5C.F2
DSQSACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5C.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 47 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD5C.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.5 Sample Jobs for National Language Version for QMF Swedish

Figure 48. Sample Installation Jobs for QMF Swedish

Job Name	Job Type	Description	RELFILE
DSQVRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5D.F2
DSQVALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5D.F2
DSQVDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5D.F2
DSQVAPLY	APPLY	Sample APPLY job	IBM.JSQDD5D.F2
DSQVACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5D.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 48 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD5D.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.6 Sample Jobs for National Language Version for QMF Swiss French

<i>Figure 49. Sample Installation Jobs for QMF Swiss French</i>			
Job Name	Job Type	Description	RELFILE
DSQYRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5E.F2
DSQYALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5E.F2
DSQYDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5E.F2
DSQYAPLY	APPLY	Sample APPLY job	IBM.JSQDD5E.F2
DSQYACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5E.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 49 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD5E.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.7 Sample Jobs for National Language Version for QMF Swiss German

Figure 50. Sample Installation Jobs for QMF Swiss German

Job Name	Job Type	Description	RELFILE
DSQZRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5F.F2
DSQZALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5F.F2
DSQZDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5F.F2
DSQZAPLY	APPLY	Sample APPLY job	IBM.JSQDD5F.F2
DSQZACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5F.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 50 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD5F.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.8 Sample Jobs for National Language Version for QMF Canadian French

Figure 51. Sample Installation Jobs for QMF Canadian French

Job Name	Job Type	Description	RELFILE
DSQCRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5G.F2
DSQCALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5G.F2
DSQCDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5G.F2
DSQCAPLY	APPLY	Sample APPLY job	IBM.JSQDD5G.F2
DSQACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5G.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 51 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD5G.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.9 Sample Jobs for National Language Version for QMF Uppercase English

Figure 52. Sample Installation Jobs for QMF Uppercase English

Job Name	Job Type	Description	RELFILE
DSQURECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD51.F2
DSQUALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD51.F2
DSQUDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD51.F2
DSQUAPLY	APPLY	Sample APPLY job	IBM.JSQDD51.F2
DSQUACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD51.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 52 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD51.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.10 Sample Jobs for National Language Version for QMF Danish

<i>Figure 53. Sample Installation Jobs for QMF Danish</i>			
Job Name	Job Type	Description	RELFILE
DSQQRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD55.F2
DSQQALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD55.F2
DSQQDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD55.F2
DSQQAPLY	APPLY	Sample APPLY job	IBM.JSQDD55.F2
DSQQACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD55.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 53 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD55.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.11 Sample Jobs for National Language Version for QMF French

Figure 54. Sample Installation Jobs for QMF French

Job Name	Job Type	Description	RELFILE
DSQFRCV	RECEIVE	Sample RECEIVE job	IBM.JSQDD56.F2
DSQFALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD56.F2
DSQFDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD56.F2
DSQFAPLY	APPLY	Sample APPLY job	IBM.JSQDD56.F2
DSQFACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD56.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 54 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD56.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.12 Sample Jobs for National Language Version for QMF German

<i>Figure 55. Sample Installation Jobs for QMF German</i>			
Job Name	Job Type	Description	RELFILE
DSQDRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD57.F2
DSQDALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD57.F2
DSQDDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD57.F2
DSQDAPLY	APPLY	Sample APPLY job	IBM.JSQDD57.F2
DSQDACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD57.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 55 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD57.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.13 Sample Jobs for National Language Version for QMF Italian

Figure 56. Sample Installation Jobs for QMF Italian

Job Name	Job Type	Description	RELFILE
DSQIRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD58.F2
DSQIALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD58.F2
DSQIDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD58.F2
DSQIAPLY	APPLY	Sample APPLY job	IBM.JSQDD58.F2
DSQIACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD58.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 56 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD58.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.4.14 Sample Jobs for National Language Version for QMF Japanese

<i>Figure 57. Sample Installation Jobs for QMF Japanese</i>			
Job Name	Job Type	Description	RELFILE
DSQKRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD59.F2
DSQKALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD59.F2
DSQKDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD59.F2
DSQKAPLY	APPLY	Sample APPLY job	IBM.JSQDD59.F2
DSQKACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD59.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 57 for the relfile data set.

You may also choose to copy the jobs from the product files by submitting the job below. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.JSQDD59.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

6.1.5 Allocate SMP/E CSI (Optional)

If you are using an existing CSI, do not execute this job.

If you are allocating a new SMP/E data set for this install, edit and submit sample job DSQALA to allocate the SMP/E data set for QMF for z/OS - NLV. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.6 Initialize CSI zones (Optional)

If you are using an existing CSI, do not execute this job.

Edit and submit sample job DSQALB to initialize SMP/E zones for QMF for z/OS - NLV. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.7 Perform SMP/E RECEIVE

If you have obtained QMF for z/OS - NLV as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the QMF for z/OS - NLV FMIDs, service, and HOLDDATA that are included on the CBPDO package. For more information, see the documentation that is included in the CBPDO.

1. You can also choose to edit and submit sample job DSQRECV1 to perform the SMP/E RECEIVE for QMF TSO/CICS Base. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

2. You can also choose to edit and submit sample job FQMRECV to perform the SMP/E RECEIVE for QMF Z Client. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

3. You can also choose to edit and submit sample job DSQRECV2 to perform the SMP/E RECEIVE for QMF HPO. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

4. You can also choose to edit and submit sample job DSQRECV3 to perform the SMP/E RECEIVE for QMF applications. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

5. You can also choose to edit and submit sample job CQDRECV4 to perform the SMP/E RECEIVE for QMF Data Service. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6. You can also choose to edit and submit sample job DSQRECVQ to perform the SMP/E RECEIVE for QMF for z/OS OTC. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

7. You may also edit and submit a sample job below to perform the SMP/E RECEIVE for the National Language Version you have selected.

- DSQHRECV - National Language Version for QMF Korean
- DSQPRECV - National Language Version for QMF Brazilian Portuguese
- DSQSRECV - National Language Version for QMF Spanish
- DSQVRECV - National Language Version for QMF Swedish
- DSQYRECV - National Language Version for QMF Swiss French
- DSQZRECV - National Language Version for QMF Swiss German
- DSQCRCV - National Language Version for QMF Canadian French
- DSQURECV - National Language Version for QMF Uppercase English
- DSQQRECV - National Language Version for QMF Danish
- DSQFRECV - National Language Version for QMF French
- DSQDRECV - National Language Version for QMF German
- DSQIRECV - National Language Version for QMF Italian
- DSQKRECV - National Language Version for QMF Japanese

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.8 Allocate SMP/E Target and Distribution Libraries

1. Edit and submit sample job DSQALLOC to allocate the SMP/E target and distribution libraries for QMF for z/OS - NLV. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

2. Edit and submit sample job FQMALLOC to allocate the SMP/E target and distribution libraries for QMF Z Client. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

3. Edit and submit sample job CQDALOC4 to allocate the SMP/E target and distribution libraries for QMF Data Service. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

4. You may also edit and submit a sample job below to allocate the SMP/E target and distribution libraries of the National Language Version you have selected.

- DSQHALOC - National Language Version for QMF Korean
- DSQPALOC - National Language Version for QMF Brazilian Portuguese
- DSQSALOC - National Language Version for QMF Spanish
- DSQVALOC - National Language Version for QMF Swedish
- DSQYALOC - National Language Version for QMF Swiss French
- DSQZALOC - National Language Version for QMF Swiss German
- DSQCALOC - National Language Version for QMF Canadian French
- DSQUALOC - National Language Version for QMF Uppercase English

- DSQQALOC - National Language Version for QMF Danish
- DSQFALOC - National Language Version for QMF French
- DSQDALOC - National Language Version for QMF German
- DSQIALOC - National Language Version for QMF Italian
- DSQKALOC - National Language Version for QMF Japanese

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.9 Create DDDEF Entries

1. Edit and submit sample job DSQDDEF to create DDDEF entries for the SMP/E target and distribution libraries for QMF for z/OS - NLV. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

2. Edit and submit sample job FQMDDEF to create DDDEF entries for the SMP/E target and distribution libraries for QMF Z Client. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

3. Edit and submit sample job CQDDDEF4 to create DDDEF entries for the SMP/E target and distribution libraries for QMF Data Service. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

4. You may also edit and submit a sample job below to create DDDEF entries for the SMP/E target and distribution libraries of the National Language Version you have selected.

- DSQHDDEF - National Language Version for QMF Korean
- DSQPDDEF - National Language Version for QMF Brazilian Portuguese
- DSQSDDEF - National Language Version for QMF Spanish
- DSQVDDEF - National Language Version for QMF Swedish
- DSQYDDEF - National Language Version for QMF Swiss French
- DSQZDDEF - National Language Version for QMF Swiss German
- DSQCDDEF - National Language Version for QMF Canadian French
- DSQUDEF - National Language Version for QMF Uppercase English
- DSQQDDEF - National Language Version for QMF Danish
- DSQFDDEF - National Language Version for QMF French
- DSQDDDEF - National Language Version for QMF German
- DSQIDDEF - National Language Version for QMF Italian
- DSQKDDEF - National Language Version for QMF Japanese

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.10 Perform SMP/E APPLY

1. Ensure that you have the latest HOLDDATA; then edit and submit sample job DSQAPPLY to perform an SMP/E APPLY CHECK for QMF TSO/CICS Base, HPO and QMF applications. Consult the instructions in the sample job for more information.

The latest HOLDDATA is available through several different portals, including <http://service.software.ibm.com/holddata/390holddata.html>. The latest HOLDDATA may identify HIPER and FIXCAT APARs for the FMIDs you will be installing. An APPLY CHECK will help you determine if any HIPER or FIXCAT APARs are applicable to the FMIDs you are installing. If there are any applicable HIPER or FIXCAT APARs, the APPLY CHECK will also identify fixing PTFs that will resolve the APARs, if a fixing PTF is available.

You should install the FMIDs regardless of the status of unresolved HIPER or FIXCAT APARs. However, do not deploy the software until the unresolved HIPER and FIXCAT APARs have been analyzed to determine their applicability. That is, before deploying the software either ensure fixing PTFs are applied to resolve all HIPER or FIXCAT APARs, or ensure the problems reported by all HIPER or FIXCAT APARs are not applicable to your environment.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. The SMP/E root cause analysis identifies the cause only of *errors* and not of *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here are sample APPLY commands:

- a. To ensure that all recommended and critical service is installed with the FMIDs, receive the latest HOLDDATA and use the APPLY CHECK command as follows

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND .
```

Some HIPER APARs might not have fixing PTFs available yet. You should analyze the symptom flags for the unresolved HIPER APARs to determine if the reported problem is applicable to your environment and if you should bypass the specific ERROR HOLDS in order to continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixing PTFs available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

- b. To install the FMIDs without regard for unresolved HIPER APARs, you can add the BYPASS(HOLDCLASS(HIPER)) operand to the APPLY CHECK command. This will allow you to install FMIDs even though one or more unresolved HIPER APARs exist. After the FMIDs are installed, use the SMP/E REPORT ERRSYSMODS command to identify unresolved HIPER APARs and any fixing PTFs.

```

APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER),HOLDFIXCAT) .
..any other parameters documented in the program directory

```

This method is quicker, but requires subsequent review of the Exception SYSMOD report produced by the REPORT ERRSYSMODS command to investigate any unresolved HIPERs. If you have received the latest HOLDDATA, you can also choose to use the REPORT MISSINGFIX command and specify Fix Category IBM.PRODUCTINSTALL-REQUIREDSERVICE to investigate missing recommended service.

If you bypass HOLDS during the installation of the FMIDs because fixing PTFs are not yet available, you can be notified when the fixing PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 or 4 if this job runs correctly.

You may receive any of the following messages which do not affect product installation: GIM23903I, GIM23903W, GIM23913W, IEW2454W.

2. After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 or 4 if this job runs correctly.

You may receive any of the following messages which do not affect product installation: GIM23903I, GIM23903W, GIM23913W, IEW2454W.

3. You can also choose to edit and submit sample job FQMAPPLY to perform the SMP/E APPLY CHECK for QMF Z Client. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

4. You can also choose to edit and submit sample job CQDAPPLY4 to perform the SMP/E APPLY CHECK for QMF Data Service. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 or 4 if this job runs correctly. You may receive the following message for DFHEI1 in the CQDHLI module which does not affect product installation: IEW2456E. This means CICS is not setup for this installation.

After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Expected Return Codes and Messages: You will receive a return code of 0 or 4 if this job runs correctly. You may also receive the following message for DFHEI1 in the CQDHLI module which does not affect product installation: IEW2456E. This means CICS is not setup for this installation.

5. You can also choose to edit and submit sample job DSQAPLYQ to perform the SMP/E APPLY CHECK for QMF for z/OS OTC. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6. You may also edit and submit a sample job below to perform the SMP/E APPLY CHECK of the National Language Version you have selected.

- DSQHAPLY - National Language Version for QMF Korean
- DSQPAPLY - National Language Version for QMF Brazilian Portuguese
- DSQSAPLY - National Language Version for QMF Spanish
- DSQVAPLY - National Language Version for QMF Swedish
- DSQYAPLY - National Language Version for QMF Swiss French
- DSQZAPLY - National Language Version for QMF Swiss German
- DSQCAPLY - National Language Version for QMF Canadian French
- DSQUAPLY - National Language Version for QMF Uppercase English
- DSQQAPLY - National Language Version for QMF Danish
- DSQFAPLY - National Language Version for QMF French
- DSQDAPLY - National Language Version for QMF German
- DSQIAPLY - National Language Version for QMF Italian
- DSQKAPLY - National Language Version for QMF Japanese

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 if this job runs correctly.

After the APPLY CHECK completes successfully remove the CHECK and run the job again to perform the APPLY.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 if this job runs correctly.

6.1.11 Perform SMP/E ACCEPT

1. Edit and submit sample job DSQACCEP to perform an SMP/E ACCEPT CHECK for QMF TSO/CICS Base, HPO and QMF applications. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. The SMP/E root cause analysis identifies the cause of *errors* but not *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E Commands book for details.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 or 4 if this job runs correctly.

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 or 4 if this job runs correctly.

2. You can also choose to edit and submit sample job FQMACCPT to perform the SMP/E ACCEPT CHECK for QMF Z Client. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

3. You can also choose to edit and submit sample job CQDACCE4 to perform the SMP/E ACCEPT CHECK for QMF Data Service. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 or 4 if this job runs correctly. You may receive the following message for DFHEI1 in the CQDHLLI module which does not affect product installation: IEW2456E. This means CICS is not setup for this installation.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Expected Return Codes and Messages: You will receive a return code of 0 or 4 if this job runs correctly. You may receive the following message for DFHEI1 in the CQDHLLI module which does not affect product installation: IEW2456E. This means CICS is not setup for this installation.

4. You can also choose to edit and submit sample job DSQACCEQ to perform the SMP/E ACCEPT CHECK for QMF for z/OS OTC. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

5. You may also edit and submit a sample job below to perform the SMP/E ACCEPT CHECK of the National Language Version you have selected.

- DSQHACEP - National Language Version for QMF Korean
- DSQPACEP - National Language Version for QMF Brazilian Portuguese
- DSQSACEP - National Language Version for QMF Spanish
- DSQVACEP - National Language Version for QMF Swedish
- DSQYACEP - National Language Version for QMF Swiss French
- DSQZACEP - National Language Version for QMF Swiss German
- DSQCACEP - National Language Version for QMF Canadian French
- DSQUACEP - National Language Version for QMF Uppercase English
- DSQQACEP - National Language Version for QMF Danish
- DSQFACEP - National Language Version for QMF French
- DSQDACEP - National Language Version for QMF German
- DSQIACEP - National Language Version for QMF Italian
- DSQKACEP - National Language Version for QMF Japanese

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 if this job runs correctly.

After the ACCEPT CHECK completes successfully remove the CHECK and run the job again to perform the ACCEPT.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 if this job runs correctly.

6.1.12 Run REPORT CROSSZONE

The SMP/E REPORT CROSSZONE command identifies requisites for products that are installed in separate zones. This command also creates APPLY and ACCEPT commands in the SMPPUNCH data set. You can use the APPLY and ACCEPT commands to install those cross-zone requisites that the SMP/E REPORT CROSSZONE command identifies.

After you install QMF for z/OS - NLV, it is recommended that you run REPORT CROSSZONE against the new or updated target and distribution zones. REPORT CROSSZONE requires a global zone with ZONEINDEX entries that describe all the target and distribution libraries to be reported on.

For more information about REPORT CROSSZONE, see the SMP/E manuals.

6.2 Activating QMF for z/OS - NLV

Once the SMP/E installation is completed for QMF for z/OS - NLV, the QMF VSAM panel library, DSQPNLE, must be populated. The VSAM data set DSQPNLE was created when QMF SMP/E job, DSQALLOC (allocate QMF target and distribution libraries), was run in section 6.1.8 "Allocate SMP/E Target and Distribution Libraries" of this Program Directory.

Edit the job SDSQSAPE(DSQ1EPNL). Modify the job card and the variable QMFTPRES to the QMF target library prefix. Submit the job and verify that it runs successfully. This job will copy member DSQPNLE from the SDSQPVRE target library to the VSAM panel data set.

Run the corresponding job for each QMF National Language Version being accessed.

<i>Figure 58. NLV Activating Jobs</i>		
Language	Job	Description
QMF Korean	SDSQSAPH(DSQ1HPNL)	Copy SDSQPVRH(DSQPNLH) to the VSAM panel data set DSQPNLH
QMF Brazilian Portuguese	SDSQSAPP(DSQ1PPNL)	Copy SDSQPVRP(DSQPNLP) to the VSAM panel data set DSQPNLP
QMF Spanish	SDSQSAPS(DSQ1SPNL)	Copy SDSQPVRS(DSQPNLS) to the VSAM panel data set DSQPNLS
QMF Swedish	SDSQSAPV(DSQ1VPNL)	Copy SDSQPVRV(DSQPNLV) to the VSAM panel data set DSQPNLV
QMF Swiss French	SDSQSAPY(DSQ1YPNL)	Copy SDSQPVRV(DSQPNLY) to the VSAM panel data set DSQPNLY
QMF Swiss German	SDSQSAPZ(DSQ1ZPNL)	Copy SDSQPVRZ(DSQPNLZ) to the VSAM panel data set DSQPNLZ
QMF Canadian French	SDSQSAPC(DSQ1CPNL)	Copy SDSQPVRC(DSQPNLC) to the VSAM panel data set DSQPNLC
QMF Uppercase English	SDSQSAPU(DSQ1UPNL)	Copy SDSQPVRU(DSQPNLU) to the VSAM panel data set DSQPNLU
QMF Danish	SDSQSAPQ(DSQ1QPNL)	Copy SDSQPVRQ(DSQPNLQ) to the VSAM panel data set DSQPNLQ
QMF French	SDSQSAPF(DSQ1FPNL)	Copy SDSQPVRF(DSQPNLF) to the VSAM panel data set DSQPNLF
QMF German	SDSQSAPD(DSQ1DPNL)	Copy SDSQPVRD(DSQPNLD) to the VSAM panel data set DSQPNLD
QMF Italian	SDSQSAPI(DSQ1IPNL)	Copy SDSQPVRF(DSQPNLI) to the VSAM panel data set DSQPNLI
QMF Japanese	SDSQSAPK(DSQ1KPNL)	Copy SDSQPVRD(DSQPNLK) to the VSAM panel data set DSQPNLI

6.2.1 Product Customization

The publication *Getting Started with QMF Z Client*, SC28-3263, contains the step-by-step procedures to customize and use QMF Z Client.

The publication *Installing and Managing Db2 QMF for TSO and CICS*, SC28-2788, contains the step-by-step procedures to customize and use QMF for TSO/CICS and QMF applications.

The publication *Db2 High Performance Option User's Guide for TSO and CICS*, SC28-3269, contains the necessary information to customize and use QMF HPO.

The publication *IBM Db2 QMF Data Service Customization Guide*, SC28-3265, contains the necessary information to customize and use QMF Data Service.

7.0 Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan, Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan

7.1 Trademarks

IBM, the IBM logo, and [ibm.com](https://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on <https://www.ibm.com/trademark>.

Reader's Comments

Program Directory for IBM Db2 Query Management Facility for z/OS, May 2022

We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Send your comments by emailing us at ibmdocs@us.ibm.com, and include the following information:

Your name and address

Your email address

Your telephone or fax number

The publication title and order number

The topic and page number related to your comment

The text of your comment

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit.

Thank you for your participation.



Printed in USA

G113-5527-00

