

CICS Transaction Server for z/OS



Installation Guide

Version 3 Release 1

CICS Transaction Server for z/OS



Installation Guide

Version 3 Release 1

Note!

Before using this information and the product it supports, be sure to read the general information under "Notices" on page 493.

Ninth edition (July 2010)

This edition applies to Version 3 Release 1 of CICS Transaction Server for z/OS, program number 5655-M15, and to all subsequent versions, releases, and modifications until otherwise indicated in new editions. Make sure you are using the correct edition for the level of the product.

© Copyright IBM Corporation 1989, 2010.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Preface	xv
What this book is about.	xv
Who is this book for?.	xv
What you need to know to understand this book.	xv
How to use this book	xvi
for planning	xvi
for installation	xvi
Notes on terminology	xvi
CICS system connectivity.	xvii
Summary of changes.	xix
Changes for CICS Transaction Server for z/OS, Version 3 Release 1	xix
Changes for CICS Transaction Server for z/OS Version 2 Release 3	xix
Changes for CICS Transaction Server for z/OS Version 2 Release 2	xx
Changes for CICS Transaction Server for z/OS, Version 2 Release 1	xx
Changes for CICS Transaction Server for OS/390 Version 1 Release 3.	xxi
CICSplex SM installation and setup	xxi
Changes for CICS Transaction Server for OS/390 Version 1 Release 2.	xxi
Changes for CICS Transaction Server for OS/390 Version 1 Release 1.	xxi

Part 1. Planning for Installation 1

Chapter 1. Introduction	3
Overview of CICS TS	3
Packaging	3
CICS TS elements and features	4
Exclusive and non-exclusive elements and features.	4
What you receive with CICS TS	4
Documentation	5
Summary of elements in CICS TS	6
The CICS Clients and The CICS Transaction Gateway.	7
Installing CICS TS	7
Chapter 2. Installing CICS TS	9
Requirements for CICS TS	9
Hardware requirements for installing CICS TS	9
Software requirements for installing CICS TS.	10
DASD storage requirements for CICS TS	11
Installing CBPDO	11
using the SMP/E RECEIVE, APPLY, and ACCEPT commands	11
using the DFHISTAR process	12
Installing ServerPac	13
What you need to install the ServerPac.	14
Summary of the ServerPac installation steps	14
The next step	15
Chapter 3. Installing CICS TS using DFHISTAR	17
Edit the DFHISTAR Job.	17
Specify the CICS Transaction Server Temporary Installation Libraries	20
Specify the JOB Parameters for Installation Jobs	20
Specify the Scope of the Installation	21
Specify the Type of JES to be Used	21
Specify the Utilities to be used	21

Specify the Prefix of CICS Transaction Server Jobs	22
Specify the Indexes of CICS Transaction Server Data Sets	22
Specify the CICS TS HFS Directories and Data Sets	23
Specify extra qualifiers	24
Specify Block Sizes	24
Specify the Disk Unit for Work Data Sets	24
Specify SMS Option for DASD Allocations	24
Specify Disk Volumes	25
Allocate the Space for CICS Transaction Server Disk Volumes	28
Specify Attributes of the Temporary SMP/E Work Data Sets	28
Specify Attributes of the Permanent SMP/E Data Sets	29
Specify SMP/E Zone Attributes	30
Specify the High-level Qualifiers for SMP/E Data Sets	33
Specify the distribution tape device type	33
Specify Attributes of the CICS Transaction Server system Data Sets	33
Specify Attributes of any additional target Libraries	34
Specify the Data Set Name of the SISLOAD Library	35
Specify the Data Set Name of the CSSLIB Library	35
Specify the Data Set Name of the SCEECPP Library	35
Specify the Data Set Name of the SCEELKED Library	36
Specify the Data Set Name of the SCEELKEX Library	36
Specify the Data Set Name of the SCEEOBJ Library	36
Specify the Data Set Name of the SCEESAMP Library	36
Specify the Data Set Name of the SCLBSID Library	36
Specify the Data Set Name of the SCSQLOAD Library	36
Specify the Data Set Name of the SCSQANLE Library	37
Specify the Data Set Name of the SCSQCICS Library	37
Specify the Data Set Name of the SCSQAUTH Library	37
Specify the Name of the Java directory	37
Specify the Data Set Name of the SDSNLOAD Library	37
Specify the Data Set Name of the SEZARPCL and SEZACMTX libraries	37
Specify the Data Set Name of the SCEECICS & SCEERUN libraries	38
Specify the Data Set Name of the SCEERUN2 & SCEELIB libraries	38
Specify the Data Set Name of the SCEEBND2 library	38
Specify Log stream and Log stream Structure Attributes.	38
Create RACF Profiles for the CICS Transaction Server Data Sets	39
Run the DFHISTAR Job	39
Check the Output from the DFHISTAR Job	40
Check that You Are Ready to Run the Installation Jobs	41
Run the installation Jobs	42
Run Times of the Installation Jobs	42
The DFHIHFS0 Job	43
The DFHIHFS1 Job	43
The DFHISMKD Job	44
The DFHINST1 Job	44
The DFHINST2 Job	44
The DFHINST3 Job	45
The DFHINST4 Job	46
The DFHINST5 Job	46
The DFHINST6 Job	46
The DFHIJVMJ Job	47
Check the Output from the Installation Jobs	47
What next?	48
Copy the CICS Transaction Server Procedures into a Procedure Library.	48
Create Extra Sets of CICS Transaction Server Target Libraries (Optional)	50
Load the CICS Transaction Server Source Material (Optional)	52

Load Other Optional Features	53
Activating CICS Transaction Server	53
Checklist for the CICS Transaction Server for z/OS Installation	53
Chapter 4. Post-installation requirements	55
Implementing changes in your z/OS environment for CICS	55
APF-authorizing CICS SDFHAUTH library	56
Authorizing CICS region userids to RACF	56
Adding SDFHLINK to the MVS LNKLIST	57
Defining CICS as an MVS subsystem	57
Defining and installing the CICS Type 3 SVC	57
Reviewing the high-performance option	58
Defining CICS regions as applications to VTAM	58
Defining log streams	58
MVS ASR exit	59
Planning for CICSplex SM	60
Planning for CICSplex SM migration	60
Parallel Sysplex considerations	60
Chapter 5. Installing the CICS Information Center	61
Requirements	61
Installing the information center on a workstation	61
Installing the information center on a server	62
Installing the CICS plug-in in an Eclipse IDE or help system	63

Part 2. Setting up the MVS environment for CICS 65

Chapter 6. Authorizing the hlq.SDFHAUTH library	67
Chapter 7. Authorizing CICS regions to access MVS resources	69
Protecting CICS load module data sets	69
Authorizing access to data set services modules	70
Authorizing access to a CICS region's VTAM ACB	70
Authorizing the region userid to access category 1 transactions	71
Authorizing access to an SMSVSAM server	71
Authorizing access to MVS log streams	72
Authorizations for users of IXCMIAPU	72
Authorizations for CICS regions	73
Authorizing CICS region userids to z/OS UNIX System Services	74
Activating RACF resource classes	75
Chapter 8. Defining the default CICS userid to RACF	77
Chapter 9. Installing CICS-required modules in the MVS linklist	79
CICS-supplied modules required in the MVS linklist	79
CICS shared data tables modules for the MVS linklist	80
Modules of other MVS products in the MVS linklist	81
Chapter 10. Defining CICS as an MVS subsystem	83
The IEASYSxx MVS initialization member	83
The IEFSSNaa MVS subsystem initialization member	84
The SYS1.PARMLIB(BPXPRMxx) parameters	84
The console message-handling facility	86
The DFHSSIyy message-formatting initialization member	87
Default message-formatting initialization parameters	88
Activating message formatting	89

#

Modules needed to use the console message-handling facilities	89
Coexistence considerations	90
EXCI pipe allocation	91
The DFHSSlyy initialization member	91
The EXCI pipe allocation limit	91
Default EXCI pipe allocation limit initialization parameter	91
Chapter 11. Installing the CICS Type 3 SVC	93
Defining the CICS SVCs to your MVS	93
Using more than one version of the CICS Type 3 SVC	94
MRO between different CICS releases with a changed SVC number	95
Chapter 12. Selecting the high-performance option	97
Defining DFHHP SVC to MVS	97
Loading module DFHHP SVC	97
Removing existing DFHHP SVC modules from the MVS nucleus	98
Chapter 13. Defining CICS regions as applications to VTAM	99
Defining specific CICS APPL statements to VTAM	99
VTAM APPL parameters for CICS regions	99
VTAM version and release level indicator	101
Message DFH3C473 on opening the VTAM ACB	101
Cross-domain considerations	101
VTAM LU alias facility	102
Chapter 14. Installing CICS modules in the MVS link pack area	107
Preparing to install CICS modules in the MVS link pack area	107
Benefits of using the MVS link pack area	107
What is meant by the MVS link pack area?	108
Which modules must be in the MVS link pack area	108
Which modules can be in the MVS link pack area?	109
Service considerations	110
How to use modules in the MVS link pack area	111
Space requirements for CICS modules in the MVS link pack area	111
Defining the CICS LPA library to your MVS	111
Installing CICS modules in the LPA	112
Selecting modules for the MVS link pack area	112
The CICS-supplied SMP/E USERMOD, DFHUMOD	113
Changing a CICS-supplied USERMOD	113
Preparing the USERMOD	113
Receiving and applying the USERMOD	113
Controlling the use of modules from the MVS link pack area	114
Modules in the MVS link pack area from hlq.SDFHAUTH	114
Modules in the MVS link pack area from hlq.SDFHLOAD	114
Sample DFHCSDUP job to specify USELPACOPY(YES)	118
Chapter 15. Defining CICS IPCS exit control data to MVS	121
The DFHIPCSP CICS exit control data	121
Chapter 16. MVS Program properties table entries	123
RACF password checking	123
Non-swappable CICS regions	123
MVS protection key for CICS	124
Chapter 17. MVS performance definitions	125
Implementing MVS workload management	125

Matching CICS performance parameters to service policies	126
Chapter 18. MVS automatic restart management definitions	127
Implementing MVS automatic restart management	127
Chapter 19. MVS cross-system MRO definitions	129
Sysplex overview	129
MVS XCF considerations for MRO	129
Chapter 20. PR/SM policy for handling MVS failures	131
XCF PR/SM policy	131
Chapter 21. MVS ASREXIT - SYMREC Authorization Exit.	133
Chapter 22. Definitions required for VSAM RLS support	135
Defining the master coupling facility lock structure	135
Defining coupling facility cache structures and cache sets	135
Defining cache sets.	136
Defining SMS storage classes for RLS access	136
Altering data set attributes for RLS access	136
Defining sharing control data sets	137
Authorizing CICS userids for VSAM RLS support	138
Adding new parameters to SYS1.PARMLIB(IGDSMSxx)	138
Establishing new procedures for VSAM RLS support	138
Activating the coupling facility structures	139
Chapter 23. Console messages.	141
Chapter 24. Defining the logger environment for CICS journaling	143
Requirements planning and checklist	143
Setting up the environment for CICS log manager	148
Coupling facility or DASD-only?	150
Coupling facility log streams	151
Defining coupling facility structures	152
Planning considerations for the number of log structures	155
Log structure naming conventions	156
Defining coupling facility log streams	156
Sizing considerations for coupling facility log streams	158
Coupling facility requirements in an RLS environment	165
Staging data sets for coupling facility log streams.	166
DASD-only log streams	167
Defining DASD-only log streams	168
Sizing considerations for DASD-only log streams	169
Converting a DASD-only log stream to use a coupling facility	172
Analyzing SMF Type 88 records	173
Managing secondary storage	174
Managing log data sets	174
Log tail management	175
Chapter 25. Enabling Unicode data conversion by z/OS	177
Selecting conversion images	177
Chapter 26. Applying service to CICS Transaction Server for z/OS	179
Load library secondary extents	179
The CICS TS-supplied SMP/E procedure.	179
APAR fixes	180

I
I

PTFs	180
CICS service considerations	181
CICSplex SM service considerations	181
Servicing the CICS messages data set	182

Part 3. Getting ready to run CICS 183

Chapter 27. Tailoring the CICS-supplied skeleton jobs	185
The CICS installation libraries	185
What you should do	186
Running DFHISTAR	186

Chapter 28. Creating the CICS data sets	189
Naming conventions	190
Creating data sets common to all CICS regions, DFHCOMDS job.	191
Creating several copies of the DFHCSD and SYSIN data sets	191
Creating data sets unique to each CICS region, DFHDEFDS job	192
Creating the CICS messages data set, DFHCMACI job	193
Defining the DFHCMACD file and associated CICS resources	193
Defining the sample applications data sets	194
The CUA text level application.	194
The FILEA sample application programs	195
The CICS Application Programming Primer sample application	195

Chapter 29. Defining DL/I support.	197
PDIRs.	197
Adding remote DL/I support.	198
Defining a PSB directory	198
Coding CICS system initialization parameters for remote DL/I support	198
Global user exits for DL/I.	199

Chapter 30. Adding CICS support for programming languages	201
Installing Language Environment support.	201
Installing CICS support for Language Environment	202
Language Environment support for COBOL	203
Language Environment support for C and C++.	203
Language Environment support for PL/I	204
Language Environment support for CICS JVM programs	204

Chapter 31. Verifying your Java components installation	205
Verifying Java components checklist	205
Java Virtual Machine sample definition files	207
JVM profiles	207
JVM properties files.	208
Java 2 security policy for EJBs	209
Authorizing the hlq.SDFJAUTH library	210
The hlq.SDFJLPA library	210
Amending parameters in SYS1.PARMLIB(BPXPRMxx).	210

Chapter 32. Installing MRO and ISC support	211
Installing MRO support	211
Defining CICS as an MVS subsystem	212
Installing the modules DFHIRP and DFHC SVC in the LPA	212
Installing required hardware and software for XCF/MRO	212
Defining MVS images as systems in an XCF sysplex	212
Enabling MRO for CICS startup	213

Adding ISC support	213
Running a CICS region with ISC	213
Chapter 33. Enabling TCP/IP in a CICS region	215
Using TCP/IP in a CICS region	215
Chapter 34. Enabling REXX for CICS	217
Step 1--Modify your RDO definitions to add required entries	217
Step 2--Create the RFS filepools	217
Step 3--BIND the CICS SQL program to your DB2 plan	218
Step 4--Add DD statements to your CICS startup job	218
Step 5--Modify member CICSTART	218
Step 6--Format the RFS filepools	218
Step 7--Verifying the installation	219
Step 8--Accessing the supplied softcopy documentation	219
Customization information for REXX	219
Changing supplied CICS transaction codes	220
RFS filepool definitions	221
TD queues needed for IMPORT and EXPORT commands	221
SQL definitions used for authorizing transactions to use DB2	221
Special exec data sets used by the REXX Development System	222
Special USER ids and their usage	222
Other considerations	223
Online HELP facility	223

Part 4. CICS verification. 225

Chapter 35. Running the installation verification procedures	227
Preparation for running the IVPs	227
Create the CICS data sets for the IVP jobs	227
Install the CICS SVC for the IVP jobs	227
Define and activate the CICS applids	228
Authorize the IVP userid	228
Review security requirements for the IVP jobs	229
Define log streams	230
Specify system initialization parameters for the IVP jobs	231
Resources for the CICS messages facility, CMAC	232
The CICS startup procedure, DFHSTART	232
DD statements for CICS data sets	233
Verify batch job, DFHIVPBT.	234
Sample job log for the DFHIVPBT job	235
Output from the DFHIVPBT job	238
Verify interactive job, DFHIVPOL	241
Defining a terminal for the online IVP	242
Defining the CICS APPLID to VTAM	244
Defining an MVS console	244
Defining a TSO user as a console device.	245
Running the DFHIVPOL job.	246
Logging on at a VTAM terminal	249
Using CICS-supplied transactions through a terminal	250
Using the CEDA transaction	252
Invoking and executing sample programs.	253
Using transactions from a console device.	253
Terminating CICS	255
Verifying shared data tables support	255
Example verification of shared data tables	256

Verifying the CICS-DBCTL interface	262
The IMS installation requirements for the DFHIVPDB job	262
The DFHIVPDB job steps	262
Testing the CICS-DB2 environment	267
Run DB2 jobs DSNTEJ5C and DSNTEJ5P	267
Starting a DB2 organization or project application.	267
Running the EJB "Hello World" sample	268

Part 5. CICSplex SM installation and setup 269

Chapter 36. CICSplex SM setup checklist and worksheets	271
Installation checklist	272
MVS installation and setup checklist	272
System worksheet	275
CAS worksheet	276
CMAS worksheet	277
Local MAS worksheet	279

Chapter 37. Setting up the MVS environment	281
Noting IEASYSxx values	281
Updating IEASYSxx (CAS)	282
Updating IEASYSxx (CMAS)	282
Authorizing libraries.	283
Updating the MVS linklist.	284
Preparing to use the CICSplex SM API	284
Installing the REXX function package	285
Using CICSplex SM modules in the MVS link pack area	286
Space requirements	286
Installing CICSplex SM modules into the LPA	287
Applying maintenance to LPA modules.	288

Chapter 38. VTAM requirements	289
Defining VTAM requirements (CAS).	289
Step 1: (Optional) Creating a mode table	289
Step 2: Creating a VTAM application definition (CAS)	291
Step 3: Defining cross-domain resources (CAS)	292
Step 4: Updating the configuration list (CAS)	292
Step 5: Activating the major nodes (CAS).	293
Defining VTAM requirements (CMAS)	293
Step 1: Creating a VTAM application definition (CMAS)	294
Step 2: Defining cross-domain resources (CMAS)	295
Step 3: Updating the configuration list (CMAS).	296
Step 4: Activating the major nodes (CMAS)	296

Chapter 39. Generating post-installation members	297
---	------------

Chapter 40. Creating and managing CICSplex SM data sets	299
CAS-related data sets	299
Creating the CICSplex SM data repository	299
Populating the CICSplex SM data repository	302
Converting the CICSplex SM data repository	302
Expanding the CICSplex SM data repository	304
Taking backups of the CICSplex SM data repository	304
Defining a forward recovery log for the data repository	304

Chapter 41. Upgrading the CSD and macro definitions	307
--	------------

Creating CICS resource definition tables for CMASs.	307
Updating the CSD files using DFHCSDUP (CMAS)	307
Journalmodel considerations in a CICS TS z/OS CMAS	308
Considerations when upgrading the CSD release (CMAS)	309
Considerations when sharing the CSD (CMAS)	309
Updating CICS resource definition tables for MASs	310
Updating CSD files using DFHCSDUP (MVS MAS)	311
Considerations when upgrading the CSD release (MVS MAS)	312
Considerations when sharing the CSD (MVS MAS)	312
Chapter 42. Preparing user access to CICSplex SM	313
Chapter 43. Setting up a coordinating address space (CAS)	315
Preparing to start a CAS	315
START command for a CAS	316
Identifying and connecting to a CAS	318
Setting the CAS system communication information	318
Preparing to stop a CAS	318
Stopping a CAS	318
Chapter 44. Setting up a CICSplex SM address space (CMAS)	321
Before you begin.	321
CICSplex SM auxiliary storage usage	321
Preparing to transmit generic alerts to NetView	322
Preparing to start a CMAS	323
Editing CICSplex SM system parameters	325
CMAS-related CICS SIT parameters	326
Controlling tasks in a CMAS	328
Controlling CICS storage in a CMAS	329
START command for a CMAS.	330
Setting the VTAM APPLID for a CMAS	330
Shutting down a CMAS	330
Using the SHUtdown command	331
Using the COSD transaction	331
Restarting a CMAS	331
Chapter 45. Setting up a CICS managed application system (MAS).	333
Before you begin.	333
Using CICS global user exits and user-replaceable modules.	333
Controlling the use of modules from the LPA	334
Preparing to start an MVS MAS	334
Activating DB2 connections during CICS startup	335
MQSeries connections	336
MVS MAS-related CICS SIT parameters	336
Preparing the MAS for history recording	338
Stopping and restarting management of a CICS system	339
Stopping management of a CICS system.	339
Restarting management of a CICS system	339
Terminating a MAS	340
Controlling the number of long running tasks in a MAS.	340
Chapter 46. Setting up a CICSplex SM Web User Interface server	341
Preparing a CICS system to act as the Web User Interface server	341
Configure CICS Web support	342
Review CICS system initialization parameters	343
Specify language and codepage	344

#

|
|
|
|
|

	Prepare codepage conversion table	345
	Generate the Program Load Table (PLT)	345
	Create the Web User Interface server repository (EYUWREP)	346
	Specify the customizable view and menu help data set.	346
	Specify the Web User Interface server initialization parameters.	347
	Required parameters	347
	Optional parameters	348
	Update CICS CSD definitions	355
	Transient data queue definitions	356
#	Temporary storage models	356
	Specify the JCL DD statements	356
	Security considerations	357
	CICS security considerations	357
	Secure Sockets Layer support.	358
	Authorizing access to MVS data sets	358
	Additional tasks	359
	Submit start-up JCL	359
	Check browser connection	359
	Obtain view and menu definitions	359
	Shutdown the Web User Interface server.	359
	Chapter 47. Configuring the Starter Set	361
	The Starter Set samples libraries.	361
	JCL in CICSTS31.CPSM.SEYUJCL for creating the Starter Set	361
	JCL in CICSTS31.CPSM.SEYUJCL for running the Starter Set.	362
	Definitions in CICSTS31.CPSM.SEYUDEF for the Starter Set environment	362
	The Starter Set naming convention	363
	Creating the Starter Set environment	364
	Selecting the Starter Set configuration	364
	Defining the Starter Set environment	365
	Starting the Starter Set components	366
	Deleting the Starter Set	368
	Using the Starter Set as a model.	368
	Chapter 48. Applying service to CICSplex SM	371
	CICS Transaction Server for z/OS-supplied SMP/E procedure	371
	Applying PTFs to CICSplexes running CICS Transaction Server for z/OS, Version 3 Release 1 and later	371
	Chapter 49. Using the EYUINST EXEC to tailor skeleton jobs	373
	Sample JCL editing considerations	373
	EYUINST EXEC parameters	375
	Sample JCL execution considerations	382
	Chapter 50. CICSplex SM system parameters	383
	Chapter 51. CMAS journaling	397
	Chapter 52. Preparing to use the IPCS tools	401
	Updating BLSCECT	401
	Updating library allocations	402
	SDUMP options	402

Part 6. CICSplex SM verification 405

	Chapter 53. CICSplex SM installation verification procedures	407
--	---	------------

If the IVPs do not work as described	407
The stages of IVP1 and IVP2	407
The IVP samples libraries	408
Chapter 54. Installation verification procedure 1 (IVP1)	411
Setting up the CICSplex SM environment on system A	411
Starting up and verifying CICSplex SM components on system A	413
1: Start the CAS EYUCAS1A	413
2: Start the CMAS EYUCMS1A	414
3: Define a CICSplex to CICSplex SM	415
4: Run the batched repository update facility on system A	418
5: Start the MAS EYUMAS1A	419
Testing CICSplex SM functions	420
Test the operations functions on system A	420
Chapter 55. Installation verification procedure 2 (IVP2)	425
Setting up the CICSplex SM environment on system B	426
Starting up and verifying CICSplex SM components on system B	427
1: Create CAS definitions	428
2: Start the CAS EYUCAS1B	432
3: Checking CAS-to-CAS connections	433
4: Start the CMAS EYUCMS1B	434
5: Run the batched repository update facility on system B	435
6: Enable EYUCMS1B to manage EYUPLX01	436
7: Start the MAS EYUMAS1B	439
Testing CICSplex SM functions	440
Test the operations functions on system B	440
Customizing the installation verification procedures	443

Part 7. Appendixes 445

Appendix. CICS modules eligible for the MVS link pack area	447
CICS modules required in the MVS link pack area	447
CICS modules eligible for the MVS link pack area	447
Information about modules eligible for the MVS link pack area	447
Priority	448
Size	448
Option/Note	448

Glossary of SMP/E terms used in this book. 465

Bibliography	467
The CICS Transaction Server for z/OS library	467
The entitlement set	467
PDF-only books	467
Other CICS books	469
Books from related libraries	469
Systems Network Architecture (SNA)	469
Advanced communications function for VTAM (ACF/VTAM)	469
NetView Version 3.1	470
NetView MultiSystem Manager Version 2.2	470
DATABASE 2 (DB2)	470
eNetwork Communications Server for OS/2 Warp, Version 5	470
Virtual Storage Access Method (VSAM)	470
Resource Access Control Facility (RACF).	470
System Modification Program Extended (SMP/E)	470

Sysplex planning	471
DFSMS/MVS	471
MVS	471
Determining if a publication is current	471
Accessibility	473
Index	475
Notices	493
Trademarks.	494
Sending your comments to IBM	495

Preface

What this book is about

This book describes CICS® Transaction Server for z/OS®, Version 3 Release 1 (CICS TS). It takes you through the necessary planning and helps you install CICS Transaction Server for z/OS, Version 3 Release 1. It contains guidance about tailoring CICS for use in your systems environment. It:

- Describes the content of CICS TS and the two delivery methods—ServerPac and CBPDO
- Explains the method of installing CICS TS (with either ServerPac or CBPDO), and provides references to the required sources of information. In this book, “installing” means loading the code into the libraries in preparation for the migration and customizing tasks.
- Lists the hardware and software you must have to run the CICS TS product elements and exploit the function provided by CICS TS.
- Covers installation, and verification of that installation, for both CICS and CICSplex® SM.
- Tells you about installing the workstation-based components of CICS TS.

The book assumes that you are upgrading to CICS TS levels of all the product elements in the Server.

Planning the migration to CICS TS requires that you understand the function provided by the CICS TS product set. You can learn about the function in the various product libraries of the individual elements that comprise the product set.

Always check the product libraries (for example, in the *CICS Transaction Server for z/OS Migration from CICS TS Version 2.3*) for changes that might affect CICS TS elements.

Who is this book for?

This book is intended for experienced CICS system programmers who are planning to migrate to CICS TS.

This book is also for system programmers who are responsible for installing and tailoring CICS and CICSplex SM.

By “experienced”, we mean that a system programmer’s experience includes installing and managing CICS and some or all of the other elements in the CICS TS product set.

What you need to know to understand this book

To fully understand the installation information in this book, you should have experience of the IBM® MVS™ operating system, and the System Modification Program/Extended (SMP/E) licensed program needed to maintain CICS and CICSplex SM. To use the installation verification procedures, you should be familiar with the JCL and cataloged procedures for MVS. It also helps if you are familiar with CICS and CICSplex SM concepts.

How to use this book

for planning

Read through the sections of this book that tell you about:

- The products and hardware you need to support the function that comes with CICS TS.
- The pointers to migration and installation information that is in the product libraries that you receive with CICS TS.

Once you have identified the actions you need to take to complete your migration, write a plan describing the steps your installation will take. Include your estimate of how much time each step requires and who will do it.

for installation

CICS and CICSplex SM are available only as elements of the CICS Transaction Server, through either the ServerPac or CBPDO method of delivery. For information about these two methods of delivery of the CICS Transaction Server, see Chapter 2, “Installing CICS TS,” on page 9.

To install the CICS Transaction Server using the CBPDO method, you should use the *CICS Transaction Server for z/OS Program Directory*, together with the instructions contained in the Memo to Users Extension, to load the software from the tape DASD. For the ServerPac method, you follow the supplied set of ISPF dialogs and the accompanying documentation.

After you have loaded the CICS Transaction Server elements to DASD, you should then use this book to tailor CICS to your environment; that is to:

- Integrate CICS with MVS and ACF/VTAM
- Apply service to CICS (if required)
- Create the CICS data sets
- Install DB2[®] support (if required)
- Install MRO and ISC support (if required)
- Run the installation verification procedures (if required).

Notes:

1. “CICS modules eligible for the MVS link pack area,” on page 447 gives details of the CICS modules that are needed in, and eligible for, the MVS link pack area.
2. If you installed CICS from CBPDO, you do not need to run the DFHISTAR job again to specify the post-installation parameters. However, if you wish to create several copies of the post-installation jobs (for example to create several copies of the DFHDEFDS job to define CICS data sets unique to several CICS regions), you can edit and run the DFHISTAR job as many times as required.

Some of the information in this book is also of interest if you have installed CICS Transaction Server using the ServerPac method of delivery.

In particular, you should edit and run the DFHISTAR job, specifying the keyword POST, to define parameters needed to tailor your CICS environment.

Notes on terminology

CICS is used throughout this book to mean the CICS element of the IBM CICS Transaction Server for z/OS, Version 3 Release 1.

CICSplex SM refers to CICSplex System Manager, an element of CICS Transaction server.

CICS TS Version 2 region is used to refer to a CICS region running under CICS TS Version 2, in contrast, for example, to a CICS/ESA 4.1 region.

MVS is used throughout this book to mean the operating system MVS, or the Base Control Program (BCP) element of z/OS.

RACF[®] is used throughout this book to mean the MVS Resource Access Control Facility (RACF) or any other external security manager that provides equivalent function.

The term **CICS TS 3.1 region** is used to refer to a CICS region running under CICS TS Version 3 Release 1, in contrast, for example, to a CICS/ESA 4.1 region.

\$ In the programming examples in this book, the dollar symbol (\$,) is used as a national currency symbol and is assumed to be assigned the EBCDIC code point X'5B'. In some countries a different currency symbol, for example the pound symbol (£), or the yen symbol (¥), is assigned the same EBCDIC code point. In these countries, the appropriate currency symbol should be used instead of the dollar symbol.

hlq Throughout this book, the term *hlq* is used to denote the high-level qualifier of the CICS TS data sets; for example, CICSTS31.CICS for CICS data sets and CICSTS31.CPSM for CICSplex SM data sets. The CICSTS31 part of the high-level qualifier is defined by the LINDEX parameter in the DFHISTAR installation job.

IMS[™] library names

The IMS libraries referred to in this chapter are identified by IMS.libnam (for example, IMS.SDFSRESL). If you are using your own naming conventions, change the IMS prefix to match those naming conventions.

#

CICS system connectivity

This release of CICSplex SM can be used to control CICS systems that are directly connected to it.

For this release of CICSplex SM, the connectable CICS systems are:

- CICS Transaction Server for z/OS 3.1
- CICS Transaction Server for z/OS 2.3
- CICS Transaction Server for z/OS 2.2
- CICS Transaction Server for OS/390[®] 1.3

You can use this release of CICSplex SM to control systems running supported releases of CICS that are connected to, and managed by, your previous release of CICSplex SM. However, if you have any directly-connectable release levels of CICS, as listed above, that are connected to a previous release of CICSplex SM, you are strongly recommended to migrate them to the current release of CICSplex SM, to take full advantage of the enhanced management services. See the *CICS Transaction Server for z/OS Migration from CICS TS Version 2.3* for information on how to do this.

Table 1 shows which supported CICS systems can be directly connected to which releases of CICSplex SM.

Table 1. Directly-connectable CICS systems by CICSplex SM release

CICS system	CICSplex SM component of CICS TS 3.1	CICSplex SM component of CICS TS 2.3	CICSplex SM component of CICS TS 2.2	CICSplex SM component of CICS TS 1.3
CICS TS 3.1	Yes	No	No	No
CICS TS 2.3	Yes	Yes	No	No
CICS TS 2.2	Yes	Yes	Yes	No
CICS TS 1.3	Yes	Yes	Yes	Yes
TXSeries 4.3.0.4	No	Yes	Yes	No
TXSeries 5.0	No	Yes	Yes	No

Summary of changes

This book is based on the Installation Guide for CICS Transaction Server for z/OS, Version 2 Release 3, GC34-6224-00. Changes from that edition are marked by vertical bars in the left margin.

This part lists briefly the changes that have been made for the following recent releases:

Changes for CICS Transaction Server for z/OS, Version 3 Release 1

The more significant changes for this edition are:

- Technical changes :
 - A new topic, Chapter 25, “Enabling Unicode data conversion by z/OS,” on page 177
 - There are changes to Chapter 5, “Installing the CICS Information Center,” on page 61
 - In CICSplex SM, support for the CICS NT remote MAS is removed, and the corresponding topic in the section about CICSplex SM verification is deleted.
 - References to HFS directories now show the optional */pathprefix*, see, for example, “Specify the CICS TS HFS Directories and Data Sets” on page 23
- Structural changes :
 - Chapter 3, “Installing CICS TS using DFHISTAR,” on page 17 is a collection of topics which used to appear in the the *CICS Transaction Server for z/OS Program Directory*
 - Chapter 46, “Setting up a CICSplex SM Web User Interface server,” on page 341 is a topic which used to appear in the the *CICSplex System Manager Web User Interface Guide*

Changes for CICS Transaction Server for z/OS Version 2 Release 3

The more significant changes for this edition are:

- Technical changes :
 - In CICSplex SM, support for the CICS OS/2 remote MAS is removed, and the corresponding topic in the section about CICSplex SM verification is deleted.
 - New or revised topics include:
 - “Java Virtual Machine sample definition files” on page 207
 - “Authorizing the hlq.SDFJAUTH library” on page 210
 - “Populating the CICSplex SM data repository” on page 302
 - “CMAS-related CICS SIT parameters” on page 326
 - “Preparing the MAS for history recording” on page 338
- Structural changes :
 - Chapter 5, “Installing the CICS Information Center,” on page 61 has been moved from the back of the book. It is now in Part 1, “Planning for Installation,” on page 1.

Changes for CICS Transaction Server for z/OS Version 2 Release 2

The more significant changes for this edition are:

- Technical changes :
 - In support of the new CICSplex SM remote MAS agent for Windows®, two chapters have been added:
 - Setting up a CICSplex SM remote MAS agent for Windows
 - Installation verification procedure 6 (IVP6)
 - Chapter 50, “CICSplex SM system parameters,” on page 383 has been updated with several new security-related parameters.
- Chapter 44, “Setting up a CICSplex SM address space (CMAS),” on page 321 has been expanded with the addition of the new sections “Controlling tasks in a CMAS” on page 328 and “Controlling CICS storage in a CMAS” on page 329.
- Structural changes :
 - A new chapter Chapter 34, “Enabling REXX for CICS,” on page 217 contains information about REXX that previously appeared in the *CICS Transaction Server for z/OS Program Directory*.
 - The former Appendix A, dealing with “Disk space needed for CICS”, has been removed. This information is available from the *CICS Transaction Server for z/OS Program Directory*. As a consequence, the former Appendix B is now Appendix A.

Changes for CICS Transaction Server for z/OS, Version 2 Release 1

The more significant changes for this edition are:

- This book has a new PART Part 1, “Planning for Installation,” on page 1, which replaces the *Planning for Installation* manual of earlier releases.
- Information has been added to Chapter 7, “Authorizing CICS regions to access MVS resources,” on page 69 describing “Authorizations for users of IXCMIAPU” on page 72.
- In Chapter 24, “Defining the logger environment for CICS journaling,” on page 143, suggested values for HIGHOFFLOAD and LOWOFFLOAD have been revised, and new sections “Requirements planning and checklist” on page 143 and “Analyzing SMF Type 88 records” on page 173 have been added.
- Chapter 29, “Defining DL/I support,” on page 197 is significantly changed.
- Chapter 30, “Adding CICS support for programming languages,” on page 201 is new.
- Chapter 31, “Verifying your Java components installation,” on page 205, replaces the previous “Java™ support” chapter.
- Chapter 33, “Enabling TCP/IP in a CICS region,” on page 215 is new.
- CICSplex SM for this release of CICS Transaction Server does not support CICS systems running under VSE/ESA. The chapters: “Setting up a CICS/VSE remote managed application system (MAS)” and “Installation verification procedure 3 (IVP3)”, (of the previous release) are removed.

For most items in each of the lists above, there is a reference to the part of the book where there is more detail.

Changes for CICS Transaction Server for OS/390 Version 1 Release 3

- Post-installation, addition to chapter on authorizing CICS regions
- VTAM® definitions required for CICS: PERSIST=MULTI
- Defining an MVS console
- Java support

CICSplex SM installation and setup

To support the inclusion of CICSplex SM as an element of CICS Transaction Server for OS/390, Version 1 Release 3, and the consequent revised installation processes, a new part, Part 5, “CICSplex SM installation and setup,” on page 269 has been added to explain how to install the CICSplex SM element. This information was previously available in the *CICSplex SM Setup* book at the previous release. It contains the following chapters

- Chapter 36, “CICSplex SM setup checklist and worksheets,” on page 271.
- Chapter 43, “Setting up a coordinating address space (CAS),” on page 315.
- Chapter 44, “Setting up a CICSplex SM address space (CMAS),” on page 321.
- Chapter 45, “Setting up a CICS managed application system (MAS),” on page 333.
- Chapter 47, “Configuring the Starter Set,” on page 361.
- Chapter 48, “Applying service to CICSplex SM,” on page 371.
- Chapter 53, “CICSplex SM installation verification procedures,” on page 407.
- Chapter 55, “Installation verification procedure 2 (IVP2),” on page 425.
- Chapter 49, “Using the EYUINST EXEC to tailor skeleton jobs,” on page 373.
- Chapter 50, “CICSplex SM system parameters,” on page 383.
- Chapter 51, “CMAS journaling,” on page 397.
- Chapter 52, “Preparing to use the IPCS tools,” on page 401.

Changes for CICS Transaction Server for OS/390 Version 1 Release 2

The major changes to CICS that affect CICS Transaction Server for OS/390, Version 1 Release 2 are:

- Chapter 24, “Defining the logger environment for CICS journaling,” on page 143 has been rewritten, to include information about DASD-only log streams.
- The chapter discussing the installation of DB2 support has been removed. Information about CICS DB2 is available in the *CICS DB2 Guide*.
- A new section Chapter 7, “Authorizing CICS regions to access MVS resources,” on page 69 to explain how to authorize CICS region userids to z/OS UNIX® System Services.

Changes for CICS Transaction Server for OS/390 Version 1 Release 1

The major changes to CICS Transaction Server for OS/390 Release 1 that affect this book are:

- Support for the MVS logger
- The removal of journal control
- Support for VSAM RLS.

Other changes made to this book include:

- The removal of information relating to XRF, including information for the DFHALTDS and DFHIVPAL jobs

- The removal of information relating to the CICSplex IVPs.

Part 1. Planning for Installation

This part discusses planning considerations prior to Installation. It contains the following chapters

- Chapter 1, "Introduction," on page 3
- Chapter 2, "Installing CICS TS," on page 9
- Chapter 3, "Installing CICS TS using DFHISTAR," on page 17
- Chapter 4, "Post-installation requirements," on page 55
- Chapter 5, "Installing the CICS Information Center," on page 61

Chapter 1. Introduction

Generally, large online CICS applications run on an MVS operating system together with a collection of other supporting software products, some provided by IBM and others by independent software vendors (ISVs). Functional additions include distributed CICS software on alternative platforms, enabling you to distribute transaction processing, with CICS on the MVS host acting as a large database server. IBM recognizes that customers traditionally run these products at various release levels—a piecemeal or mix-and-match approach.

CICS TS, together with other z/OS Software Servers, is designed to make it easier to install and operate the mix of software you need to run your business.

Overview of CICS TS

With CICS Transaction Server for z/OS (CICS TS), IBM continues to integrate CICS with a set of other supporting software, offering you a single product in place of several products. You order an entire set of software, integrated into one licensed product, instead of having to order new levels of some products but not others.

CICS TS is a member of the z/OS family of MVS-based software servers, and is separately orderable as a single part number.

Within CICS TS, the levels of all products reflect the level of the CICS TS product itself. Even the word “product” has new meaning; for this reason the products that make up the base of CICS TS are called **elements**. CICS TS marks a significant change from the former piecemeal approach to the way you order and install CICS and its related software.

Getting all the elements in CICS TS installed and running is the subject of this book. Because the elements and features of CICS TS are integrated into a single package with compatible service levels, it is expected that you will migrate all elements and features of CICS TS at the same time.

Packaging

The packaging of CICS TS into a number of elements is similar to the packaging of z/OS. For its operating system environment, CICS TS requires z/OS, Version 1 Release 4. As you prepare to install CICS TS, keep in mind that you gain the benefits of a comprehensively tested environment when you install CICS TS.

In summary, the concept of CICS TS is to integrate a range of transaction server functions into a single product that delivers the function previously provided by a number of individual IBM software products. CICS TS consists of several base elements. The intent is that IBM ships, and you run, all elements at the single release level that IBM has subjected to comprehensive system testing.

Migrating from one release of CICS TS to the next is relatively simple, and the transition from your current systems to CICS TS should also be straightforward.

CICS TS elements and features

CICS TS consists of base elements that deliver essential transaction server functions. When you order CICS TS, you receive all the base elements, described in Table 2 on page 6.

Two methods of installing CICS TS come free with your license:

1. A system replace method called ServerPac
2. The Custom-Built Product Delivery Option (CBPDO).

Exclusive and non-exclusive elements and features

Some elements and features contain new function that is available only within CICS TS. This book labels such an element or feature **exclusive**: new function is exclusive to CICS TS. If an element or feature is **exclusive**, you receive new function only through CICS TS. That is, while prior levels continue to be available, future functional enhancements occur only within CICS TS.

Other elements, however, exist both within CICS TS and also as separately orderable products. These are **non-exclusive**.

IBM's direction is to make functional enhancements only within CICS TS.

What you receive with CICS TS

Because the elements of CICS TS are integrated into a single package, you are expected to install the entire product.

You can install CICS TS using one of several IBM packages. Two of these packages are available at no additional charge when you license CICS TS: (1) ServerPac, the system replace deliverable, or (2) CBPDO.

There is no stand-alone product tape for CICS TS, and there is no Custom Built Installation Process Offering (CBIPO).

Because of the overall ease of installing, **IBM recommends** that you choose ServerPac, if possible.

- **If you order the ServerPac offering, you receive:**
 - A series of tapes, each in IEBCOPY dump-by-dataset format (not a physical volume dump) containing a complete generated CICS TS system. This consists of distribution and target libraries, consolidated software inventory (CSI) and other SMP/E libraries already generated. CICS TS elements and their service are integrated into distribution and target libraries.
IBM has IPLed the system and executed all installation verification programs (IVPs) prior to shipment.
 - A CustomPac dialog, accessed through ISPF, that produces jobs that unload the tape to DASD. Through the dialog, you can name the data sets and place them in the catalogs you specify. The following accompanying documentation tells you how to use the dialog:
 - *ServerPac: Installing Your Order* (customized for each customer order)
 - *ServerPac: Using the Installation Dialog*, SA22-7815
 - All unintegrated service, available on a service tape.
 - Sample jobs to assist with the installation of CICS TS product and service.

Through the dialog, you can:

- Name the data sets and place them on the volumes and in the catalogs you choose
- Save configuration data for the next install, easing your move to the next release of CICS TS
- Run tailored post-installation verification jobs.
- **If you order CBPDO**, you receive one logically stacked SMP/E RELFILE tape that contains all the base elements. Depending on your customer profile, you receive uninstalled service. You also receive:
 - Sample jobs to help you install CICS TS and service.
 - *Custom-Built Offerings Plan/Install*, SC23-0352; the CBPDO Memo to Users Extension; CICS TS *Program Directory*, GC33-1200, and program materials that describe your CBPDO order.

Figure 1 illustrates the content differences between the ServerPac method and the CBPDO method of installing CICS TS.




Figure 1. Contents of the ServerPac and the CBPDO Delivery

Documentation

Regardless of whether you use ServerPac or CBPDO, you receive:

- The CICS TS Program Directory and other installation information for the elements, in hardcopy and softcopy.
- Essential hardcopy books to help you with installation.
- All the publications for CICS Transaction Server for z/OS in softcopy as part of the CICS Information Center. This is supplied on a CD-ROM. Installation instructions for the CICS Information Center can be found in Chapter 5, “Installing the CICS Information Center,” on page 61.

For details of all the publications available, see “Bibliography” on page 467.

Summary of elements in CICS TS

This section lists all the elements and features in CICS Transaction Server for z/OS. Most of the elements are products that have been available for some time; you may already be running some of them.

Table 2 lists all elements that are in the CICS TS base. The table tells you:

Name

The short name of the element used in this book.

Excl.

Whether the element is exclusive. In the **Excl.** column, **Yes** indicates an exclusive element, and **No** indicates a non-exclusive element that is also available as a stand-alone product.

Function Level

The latest CICS TS release in which the element changed (that is, was added to CICS TS or had new function added). For non-exclusive elements, this column also gives the release level of the stand-alone product.

Note: To ensure compatibility with previous releases, the CICS base element maintains its own level (identification) number. Each time new function is added to CICS and shipped with the CICS Transaction Server product, the CICS level number is incremented. The CICS level number no longer implies a specific version and release number, because CICS is no longer a separate product.

The CICS level number in CICS TS is 0640. This number is returned in the **RELEASE** parameter of the **INQUIRE SYSTEM** command. The 0640 number also appears in other forms such as 6.4.0 in offline utilities such as statistics and dump formatters to identify the level of utility being used, and as the suffix in module names such as DFHPD640.

Comments

Some general information about the element.

Table 2. List of base elements shipped in CICS TS

Name of element	Excl.	Function level	Comments
CICS	Yes	CICS TS V3 R1	CICS includes: <ul style="list-style-type: none"> • ONC RPC support • CICS Web interface • CICS DB2 attachment facility • CICS/DDM

Table 2. List of base elements shipped in CICS TS (continued)

Name of element	Excl.	Function level	Comments
CICSplex SM	Yes	CICS TS V3 R1	Updated to support new levels of function in CICS. CICSplex SM becomes an exclusive element in CICS TS Release 3. IBM CICSplex System Manager for MVS/ESA Version 1 Release 3 continues to be available for customers that are not yet ready to migrate to CICS TS (for example, customer with CICS/ESA Version 4 Release 1 or earlier).
Application Migration Aid	No	CICS TS V1 R1	First available in 1990, this element is still available stand-alone as IBM Customer Information Control System (CICS) program offering, CICS Application Migration Aid, program number 5695-061.
REXX for CICS	No	CICS TS V1 R2 (REXX for CICS/ESA V1R1)	Separately available as REXX for CICS, program number 5655-B54.

The CICS Clients and The CICS Transaction Gateway

CICS Transaction Server for z/OS does not include the CICS Universal Clients or
 # the CICS Transaction Gateway. To use the CICS Universal Client V5 or the CICS
 # Transaction Gateway V5, licenses for these products are required.

Installing CICS TS

Chapter 2, "Installing CICS TS," on page 9 tells you about installing the CBPDO delivery version of CICS TS.

Chapter 2. Installing CICS TS

IBM offers the following methods for installing CICS TS:

- ServerPac
- CBPDO, using the SMP/E RECEIVE, APPLY, and ACCEPT commands
- CBPDO, using the DFHISTAR process
- IBM customized packages.

The first three of these are entitled offerings, and are the subject of this book, but IBM customized packages are fee-based and are not discussed except for the following summary information. Depending on the country in which you order, you can purchase one of the following customized packages:

- A SystemPac[®], which tailors CICS TS to your environment, such as DASD layout and naming conventions, based on information provided to IBM.
- SoftwareXcel Installation Express (SIE), which tailors CICS TS to your specification and provides services that perform the actual install for you.
- Other fee-based services and customized offerings.

Both the ServerPac and CBPDO methods of delivering CICS TS come with a set of documentation that you use when you install the product. To help you plan ahead, this chapter gives you a preview of some of this information, such as the information contained in the *Program Directory*, which is shipped regardless of the delivery method you choose.

Note: The *Program Directory* is available in hardcopy only with the product—it cannot be ordered separately. A softcopy version is available on the CICS TS CD-ROM product kit, and also on the Transaction Processing and Data Collection Kit, SK2T-0730. The *Program Directory* is also available on the CBPDO and ServerPac tapes.

This chapter also helps you with other planning steps you must take:

- Ensuring you have the required hardware and software to install and run CICS TS; see “Requirements for CICS TS.”
- Ensuring you have enough DASD storage space for CICS TS; see “DASD storage requirements for CICS TS” on page 11.
- Outlining the install steps for CBPDO; see “Installing CBPDO” on page 11

Requirements for CICS TS

A major part of your planning effort involves looking at the software and hardware required for the system that you are installing.

Hardware requirements for installing CICS TS

Whether you choose the CBPDO method or the ServerPac method, the hardware requirement is the same.

Hardware requirements are more fully described in the *CICS Transaction Server for z/OS Release Guide*

You need a hardware configuration that runs the required levels of MVS, provided the configuration has a terminal and a tape device capable of reading one of the following types of tape on which CICS TS is supplied:

- 6250 bpi 9-track reels

- 3480 cartridges
- 4MM DAT cartridges

Software requirements for installing CICS TS

The system software requirements for installing CICS TS using the ServerPac method or the CBPDO method is the same except for the addition of SMP/E for CBPDO.

Software requirements are more fully described in the *CICS Transaction Server for z/OS Release Guide*

The products shown in Table 3 must be installed on the system you use to install both the ServerPac and the CBPDO.

Table 3. Program products required on the installing system for ServerPac and CBPDO

Program Product	Minimum Level
z/OS (5694-A01)	<p>Version 1 Release 4.</p> <p>z/OS includes the following elements that are required for installing CICS TS:</p> <ul style="list-style-type: none"> • Interactive System Productivity Facility (ISPF) • Time Sharing Option/Extended (TSO/E) • DFSMS/MVS • Language Environment® • Two components of eNetwork Communications Server: SNA and IP (previously VTAM and TCP/IP). • z/OS UNIX system services (see “HFS and PDSE requirements” for more information). <p>If you are installing CICS TS using the CBPDO method, you also need:</p> <ul style="list-style-type: none"> • System Modification Program/Extended (SMP/E) • High Level Assembler/MVS & VM & VSE.

Service note:: See the *CICS Transaction Server for z/OS Program Directory* for information about the service which should be applied on z/OS Version 1 Release 4 to ensure that CICS TS installs correctly.

HFS and PDSE requirements

Some components of CICS TS are installed in PDSE data sets and HFS files. CICS TS for z/OS, Version 3.1 requires PDSE data set support for installation to complete successfully. DFSMS/MVS, which is supplied as an element of z/OS, provides this support for PDSE data sets. The components concerned are part of the CICS support for Java programs and for IIOB inbound to Java applications. For FMID JCI640D, which contains the HFS-dependent code, the OMVS address space must be active in full-function mode, otherwise the install of this function fails.

In the set of installation jobs, there are some new initial jobs to create the HFS files and the directories shown in Figure 2 on page 11. You run these jobs before any of the normal DFHINST n jobs. Note that the user ID running these jobs requires superuser authority.




Figure 2. The HFS directory structure for CICS java and IIOF files

Notes:

1. If you normally maintain additional SMP/E target zone libraries for the purpose of applying service, you can also create additional directories at the /cicsts31 level to create the HFS equivalent. See the DFHIHFS job for more information.
2. The pathprefix in Figure 2 is optional.

DASD storage requirements for CICS TS

The amount of storage required for all the **target** and **distribution** data sets is detailed in the space table in the *CICS Transaction Server for z/OS: Program Directory*.

Installing CBPDO

You install all the elements from the CICS TS CBPDO using a single installation process. The CBPDO *Memo to Users Extension* contains information about the CBPDO you ordered, and the features and service it includes. It also contains CBPDO installation information.

The first planning task is to read the *Memo to Users Extension* thoroughly before starting any of the install tasks. If you are a new user of CBPDO, you should also read the IBM publication, *MVS Custom-Built Offerings Planning and Installation*, SC23-0352.

The *CICS Transaction Server for z/OS: Program Directory* gives a sample IEBCOPY job that you can customize to copy RELFILE(2) from the CICS TS CBPDO tape. Modify the LABEL=3 parameter to reference the file number of RELFILE(2) as supplied on the CBPDO tape. When you have copied RELFILE(2) to DASD, you generate a single set of install jobs using the CICS TS job generator, DFHISTAR. This generates the following set of customized install jobs, based on the parameters you specify to DFHISTAR:

- DFHIHFS0, DFHIHFS1, DFHIHFSa, and DFHISMKD, the HFS-related jobs
- DFHINST1 through DFHINST6

using the SMP/E RECEIVE, APPLY, and ACCEPT commands

The *CICS Transaction Server for z/OS: Program Directory* describes this process and tells you when to return to the *CICS Transaction Server for z/OS Installation Guide* to continue..

using the DFHISTAR process

“Edit the DFHISTAR Job” on page 17 describes all the parameters that you can specify to customize the install jobs, and explains the jobs that are generated.

One of the most significant parameters you are asked to specify is the high-level qualifier for the data sets into which the jobs install the product. CICS TS comprises a number of elements that are installed in a single process by the DFHINST n jobs. To ensure the element libraries are easily identified, DFHISTAR adds an element qualifier to the data set names. Using the default high-level qualifier CICSTS31, the names generated by DFHISTAR take the following form:

CICS	CICSTS31.CICS. <i>ddname</i>
CICSplex SM	CICSTS31.CPSM. <i>ddname</i>
Application Migration Aid	CICSTS31.AMA. <i>ddname</i>
REXX for CICS	CICSTS31.REXX. <i>ddname</i>

To enable you to customize the HFS-related jobs, the following parameters are provided in the DFHISTAR job:

HFSDSN

The data set name of the HFS to be mounted at directory */pathprefix/usr/lpp/*
cicsts. Pathprefix is variable, and optional, The other parts of this directory
name structure are fixed. The default data set name is
OMVS.USR.LPP.CICSTS.

This parameter is used by job DFHIHFS0.

HFSDSN

The data set name of the HFS to be mounted at directory */pathprefix/usr/lpp/*
cicsts/ussdir, where *ussdir* is a variable you specify in the **ussdir** parameter in
DFHISTAR. If you omit the **ussdir** parameter it defaults to the value of the
TINDEX parameter in lowercase, which in turn defaults to CICSTS31, so if both
defaults are taken, the full directory path resolves to */pathprefix/usr/lpp/cicsts/*
cicsts31.

The default data set name is OMVS.USR.LPP.CICSTS.CICSTS31.

This parameter is used by job DFHIHFS1.

HFSDSN

The data set name of the HFS to be mounted at directory */pathprefix/usr/lpp/*
cicsts/ussdira, where *ussdira* is a variable you also specify in DFHISTAR. If
you omit the **ussdira** parameter it defaults to the value (in lower case) of
AINDEX, which in turn defaults to CICSTS31.A. The default data set name is
OMVS.USR.LPP.CICSTS.CICSTS31.A.

This parameter is used by job DFHIHFSA.

Running the install jobs

Run the install jobs as follows:

1. Run the HFS-related jobs to create the HFS directories down to the */cicsts31* level:

DFHIHFS0 (required once only)

This job creates the HFS specified on the HFSDSN parameter and also the **/cicsts** directory at */pathprefix/usr/lpp*.

This job is required once only, the first time you install CICS TS, and can be skipped in subsequent releases.

Note: When you install a new release of z/OS, directories down to the `/pathprefix/usr/lpp` level are replaced, effectively losing the `/cicsts` and lower directories. Issue the make directory command (`mkdir /pathprefix/usr/lpp/cicsts`) to recreate mount point `/pathprefix/usr/lpp/cicsts` for the HFS defined in DFHIHFS0 (OMVS.USR.LPP.CICSTS). The mount command should already be in the PARMLIB member BPXPRMxx, copied from the DFHBPXP0 member of SDFHINST.

DFHIHFS1 (required)

This job creates, at `/pathprefix/usr/lpp/cicsts`, the HFS specified on the HFS1DSN parameter and also the directory specified on the parameter (default name `/cicsts31`).

DFHIHFSa (optional)

This job creates, at `/usr/lpp/cicsts`, the alternate HFS specified on the HFSADSN parameter and also the directory specified on the `ussdira` parameter (default name `/cicsts31.a`).

2. Run DFHISMKD to create the directories and HFS under `/pathprefix/usr/lpp/cicsts/cicsts31`, required for FMID JCI640D, to contain the Java and IIOF classes, samples, and so on, that have to reside in HFS.
3. Run the DFHINST1 through DFHINST4 jobs as described in the *Program Directory*
4. Run the CBPDO-supplied SMP/E RECEIVE job, RCVPDO, located in the CBPDO RIMLIB dataset (this replaces the DFHINST5 job described in the *Program Directory*).
5. Run the DFHINST6 job.

Note: This job must run in the same MVS image in which you ran the DFHISMKD job to create the HFS directories. DFHINST6 uses the CICS TS HFS directories and data sets, and these are accessible only in the MVS in which you created them.

There is more detailed information about all these jobs in the CICS TS *CICS Transaction Server for z/OS Program Directory*, and also in the comments at the start of each job.

On completion of the installation jobs, you have all the elements installed. Note that there is no provision within the DFHISTAR job generator, or in the generated jobs, to exclude an element from the install process. When you run the jobs, SMP/E installs all the elements included on the CICS TS CBPDO tape.

By default, SMP/E installs CICS TS in new SMP/E global, target, and distribution zones. The DFHINST3 job creates a new CSI data set for each zone. If you want to vary this default SMP/E configuration, see the *CICS Transaction Server for z/OS Program Directory* for information about the parameters that control the SMP/E zones and the disposition of the CSI data sets.

Installing ServerPac

A CICS TS ServerPac consists of a number of tapes, the exact number depending on whether other products are included with the CICS TS Serverpac, and also on the type of tape requested. For example, a ServerPac order can comprise the following:

- A tape that contains related-installation material (RIM) files.

- Three tapes that contain the CICS TS product, consisting of all the SMP/E CSI data sets, and the target and distribution libraries.
- A service tape.

If you already have printed copies of the ServerPac manuals that you need to install the ServerPac, use these to guide you through the installation process. If you don't have copies, download and print the manuals from the first ServerPac tape. There is a sample job, in member PRTDOC, on the RIM tape, that you can use to print the manuals.

What you need to install the ServerPac

You need the following resources to install the CICS TS ServerPac:

- A tape drive for reading the tapes.
- A TSO session for running the CustomPac dialog.
- A copy of the *ServerPac: Using the Installation Dialog* manual, SA22-7815.
- The *ServerPac: Installing Your Order*, customized for each customer order
- The CustomPac dialog supplied with ServerPac.

First-time user of the CustomPac dialog for ServerPac

If you are installing a ServerPac for the first time, start by installing the CustomPac dialog, as described in the *ServerPac: Using the Installation Dialog* manual in “Chapter 2. Installing and Starting the Dialogs”.

When you have installed the dialog, invoke the dialog as directed in the *ServerPac: Using the Installation Dialog* manual under the INVOCATION topic.

Existing user of the CustomPac dialog for ServerPac

If you have installed a ServerPac version of CICS TS for a previous order, use the dialog already installed. Invoke the CustomPac dialog, either from the ISPF primary options menu, or by invoking the ServerPac CLIST.

As an existing user of the CustomPac dialog, you can begin at the step described in the *ServerPac: Using the Installation Dialog* manual, in “Chapter 2. Receive a New Order”.

Summary of the ServerPac installation steps

When you invoke the CustomPac dialog, you are presented with the primary option menu, from which you can:

- Receive the order (option **R**)
- Install the order (option **I**).

Note: The primary menu also enables you to display information about orders.

The following tasks are described, with illustrations of the various panels, in the *ServerPac: Using the Installation Dialog* manual:

Receive the order

This step is described in section “6.0 Receive an Order”.

The “Order Receive” panels enable you enter your CICS TS order information, and complete the job card information needed to generate the order-receive job. The final phase of this step presents you with the generated JCL in an edit session, from which you can submit the job to receive the installation material (RIM) files to your DASD.

Install orders

This step is described in section “7.0 Installation Menu”.

The “Installation Menu” panels enable you to:

- Configure the order control information tables.
- Define values for the installation variables used in skeleton batch jobs.
- Define the names of the SMP/E zones into which you want to install CICS TS.
- Modify data set profiles and DASD allocation for the order.
- Define catalog data set names and the aliases associated with them.
- Define system-specific aliases (where applicable)
- Select and submit the installation jobs
- Save the installation work configuration for use with future CICS TS orders
- Update the order inventory status.

The next step

After you have completed the basic installation process using one of these methods, the next step is to test the two main elements, CICS and CICSplex SM. In general, this means running the CICS installation verification procedures (IVPs) and the CICSplex SM starter set.

These post-installation steps are discussed in the Chapter 4, “Post-installation requirements,” on page 55 chapter.

Chapter 3. Installing CICS TS using DFHISTAR

IBM offers the DFHISTAR process for those who prefer to use it for installation. This topic covers the following subjects:

- “Edit the DFHISTAR Job”
- “Create RACF Profiles for the CICS Transaction Server Data Sets” on page 39
- “Run the DFHISTAR Job” on page 39
- “Check that You Are Ready to Run the Installation Jobs” on page 41
- “Run the installation Jobs” on page 42
- “Check the Output from the Installation Jobs” on page 47
- “What next?” on page 48
- “Activating CICS Transaction Server” on page 53
- “Checklist for the CICS Transaction Server for z/OS Installation” on page 53

Edit the DFHISTAR Job

Edit the DFHISTAR job, to assign values to installation parameters for your environment. The DFHISTAR job is in the TDFHINST library when you copy RELFILE(2) from the distribution tape. You can either edit the DFHISTAR job directly, or copy the DFHISTAR job (to preserve the IBM-supplied values) and edit your copy.

Remember that the product is installed using **cataloged** data sets.

This topic describes the process of editing the parameters in the DFHISTAR job. It contains the following sub-topics in an order that corresponds to the order of parameters in the DFHISTAR job:

- “Specify the CICS Transaction Server Temporary Installation Libraries” on page 20
- “Specify the JOB Parameters for Installation Jobs” on page 20
- “Specify the Scope of the Installation” on page 21
- “Specify the Type of JES to be Used” on page 21
- “Specify the Utilities to be used” on page 21
- “Specify the Prefix of CICS Transaction Server Jobs” on page 22
- “Specify the Indexes of CICS Transaction Server Data Sets” on page 22
- “Specify the CICS TS HFS Directories and Data Sets” on page 23
- “Specify extra qualifiers” on page 24
- “Specify Block Sizes” on page 24
- “Specify the Disk Unit for Work Data Sets” on page 24
- “Specify SMS Option for DASD Allocations” on page 24
- “Specify Disk Volumes” on page 25
- “Allocate the Space for CICS Transaction Server Disk Volumes” on page 28
- “Specify Attributes of the Temporary SMP/E Work Data Sets” on page 28
- “Specify Attributes of the Permanent SMP/E Data Sets” on page 29
- “Specify SMP/E Zone Attributes” on page 30
- “Specify the High-level Qualifiers for SMP/E Data Sets” on page 33
- “Specify the distribution tape device type” on page 33
- “Specify Attributes of the CICS Transaction Server system Data Sets” on page 33
- “Specify Attributes of any additional target Libraries” on page 34

- “Specify the Data Set Name of the SISpload Library” on page 35
- “Specify the Data Set Name of the CSSLIB Library” on page 35
- “Specify the Data Set Name of the SCEECPP Library” on page 35
- “Specify the Data Set Name of the SCEELKED Library” on page 36
- “Specify the Data Set Name of the SCEELKEX Library” on page 36
- “Specify the Data Set Name of the SCEEOBJ Library” on page 36
- “Specify the Data Set Name of the SCEESAMP Library” on page 36
- “Specify the Data Set Name of the SCLBSID Library” on page 36
- “Specify the Data Set Name of the SCSQLOAD Library” on page 36
- “Specify the Data Set Name of the SCSQANLE Library” on page 37
- “Specify the Data Set Name of the SCSQCICS Library” on page 37
- “Specify the Data Set Name of the SCSQAUTH Library” on page 37
- “Specify the Name of the Java directory” on page 37
- “Specify the Data Set Name of the SDSNLOAD Library” on page 37
- “Specify the Data Set Name of the SEZARPCL and SEZACMTX libraries” on page 37
- “Specify the Data Set Name of the SCEECICS & SCEERUN libraries” on page 38
- “Specify the Data Set Name of the SCEERUN2 & SCEELIB libraries” on page 38
- “Specify the Data Set Name of the SCEEBND2 library” on page 38
- “Specify Log stream and Log stream Structure Attributes.” on page 38

To help you look up details about a particular parameter, Table 4 lists the DFHISTAR parameters, in alphabetical order, with their predefined values. (The parameters in the DFHISTAR job itself are listed in associated groups.)

The default values of the parameters are the same as the IBM-supplied values.

You can use the IBM-supplied values, define your own values, or let the CICS Transaction Server installation process determine default values for you.

Note: You can enter your values for parameters of the DFHISTAR job in lowercase; except for the HFS-related parameters (USSDIR, USSDIRA, and JAVADIR), the values are translated into uppercase when you run the DFHISTAR job.

Table 4. Alphabetical list of parameters for the DFHISTAR job

Parameter	CICS-supplied value	Your value ?	See page
ADDTVOL	CICS31 SYSALLDA		34
AINDEX	CICSTS31.A		34
ALINDEX	SYS1.CICSTS31.A		34
ASMPPTS	CICSTS31.A.SMPPTS		34
ASMPMTS	CICSTS31.A.SMPMTS		34
ASMPSCDS	CICSTS31.A.SMPSCDS		34
ASMPSTS	CICSTS31.A.SMPSTS		34
AZONE	AZONE		34
AZONECSI	CICSTS31.A.AZONE		34
AZONELOG	CICSTS31.A.AZONE.SMPLOG		34
BLKFB80	0		24
BLKISPF	3200		24
BLKU	32760		24

Table 4. Alphabetical list of parameters for the DFHISTAR job (continued)

Parameter	CICS-supplied value	Your value ?	See page
CMACVOL	CICS31		25
CSSLIB	SYS1.CSSLIB		35
DEFVOL	CICS31 SYSALLDA		25
DINDEX	CICSTS31		22
DISTVOL	CICS31 SYSALLDA		25
DSINFO	CICSTS31 CICS31 SYSALLDA .		33
DZONE	DZONE		30
DZONECSI	CICSTS31.DZONE NEW CICS31 SYSALLDA		30
DZONELOG	CICSTS31.DZONE.SMPLOG NEW		30
GINDEX	CICSTS31		22
GZONE	NEW CICSOPT		30
GZONECSI	CICSTS31.GZONE NEW CICS31 SYSALLDA		30
GZONELOG	CICSTS31.GZONE.SMPLOG NEW		30
HFS0DSN	OMVS.USR.LPP.CICSTS		23
HFS1DSN	OMVS.USR.LPP.CICSTS.CICSTS31		23
HFSADSN	OMVS.USR.LPP.CICSTS.CICSTS31..A		23
JAVADIR	java142s/J1.4		37
JES	JES2		21
JOB	(No valid value)		20
LIB	CICSTS31.XDFHINST		20
LINDEX	SYS1.CICSTS31		22
LOGGER-INFO	001 500 4096 64000 2048 MVSX XXXXXXXX XXXXXXXX		38
OPTVOL	CICS31 SYSALLDA		25
PREFIX	DFH		22
SCEECICS	SYS1.SCEECICS		38
SCEECPP	SYS1.SCEECPP		35
SCEELIB	SYS1.SCEELIB		38
SCEEBND2	SYS1.SCEEBND2		38
SCEERUN	SYS1.SCEERUN		38
SCEERUN2	SYS1.SCEERUN2		38
SCEELKED	SYS1.SCEELKED		36
SCEELKEX	SYS1.SCEELKEX		36
SCEEOBJ	SYS1.SCEEOBJ		36
SCLBSID	SYS1.SCLBSID		36
SCSQLOAD	SYS1.SCSQLOAD		36
SCOPE	ALL		21
SDSNLOAD	SYS1.SDSNLOAD		37
SCSQLOAD	SYS1.SCSQLOAD		36
SCSQANLE	SYS1.SCSQANLE		37
SCSQCICS	SYS1.SCSQCICS		37
SCSQAUTH	SYS1.SCSQAUTH		37
SEZACMTX	SYS1.SEZACMTX		37
SEZARPCL	SYS1.SEZARPCL		37
SISPLOAD	SYS1.SISPLOAD		35
SMPLTS	CICSTS31.SMPLTS		29
SMPMTS	CICSTS31.SMPMTS		29
SMPPTS	CICSTS31.SMPPTS		29
SMPSCDS	CICSTS31.SMPSCDS		29
SMPSTS	CICSTS31.SMPSTS		29
SMPVOL	CICS31 SYSALLDA		25
SMPWORK	SYSALLDA		28

Table 4. Alphabetical list of parameters for the DFHISTAR job (continued)

Parameter	CICS-supplied value	Your value ?	See page
SMS	NO		24
TAPEUNIT	3480		33
TARGVOL	CICS31 SYSALLDA		25
TEMPLIB	CICSTS31.TDFHINST		20
TINDEX	CICSTS31		22
TZONE	TZONE		30
TZONECSI	CICSTS31.TZONE NEW CICS31 SYSALLDA		30
TZONELOG	CICSTS31.TZONE.SMPLOG NEW		30
USSDIR	.		23
USSDIRA	.		34
UTILITIES	ASMA90 IEWL GIMSMP IEBCOPY		21
WORKUNIT	SYSALLDA		24
XTRAQUAL	...		24

Specify the CICS Transaction Server Temporary Installation Libraries

Specify the data set names you want to use for the two temporary libraries that will be used to install CICS Transaction Server. If you do not want to use the default names, record your values for the TEMPLIB and LIB parameters.

TEMPLIB library_name

This specifies the name of the temporary installation library that contains the skeleton installation jobs. Specify the name of the data set into which you copied RELFILE(2) from the distribution tape (in the topic *Copy RELFILE(2) from the Distribution Tape* in the *Program Directory*).

Also specify this name on the SYSPROC DD statement of the DFHISTAR job.

LIB library_name

Specifies the name of the installation output library to which the jobs generated by the DFHISTAR job are added.

Specify the JOB Parameters for Installation Jobs

Decide what parameters you want to use on the JOB statements of the CICS Transaction Server installation jobs, and specify them on the JOB parameter:

JOB accounting_information

Specifies the JOB statement and accounting information that you want substituted into the jobs generated by the DFHISTAR job. For example:

```
JOB //XXXXXXX JOB 1,userid,MSGCLASS=A,MSGLEVEL=(1,1),
JOB //          CLASS=A,NOTIFY=userid
JOB /*JOBPARM SYSAFF=node1
JOB /*ROUTE PRINT node2.userid
```

Notes:

1. Do not change XXXXXXXX given in the sample JOB statement in the DFHISTAR job. This is the 8-character job name that is substituted by the DFHISTAR job. For example, for the installation job DFHIVPBT, the DFHISTAR job changes XXXXXXXX to DFHIVPBT.
2. Normal JCL rules for coding JOB statements apply to the JOB parameter.
3. If you want to add a TIME parameter to the CICS Transaction Server installation jobs, sample run times are given in "Run Times of the Installation Jobs" on page 42.

4. Delete (or comment out) extra lines of the JOB statement that you do not need.
5. Normal JCL rules apply when coding the JOB statement (for example, all lines except the last line must end in a comma).

Specify the Scope of the Installation

Specify the scope of the CICS Transaction Server installation on the SCOPE parameter:

SCOPE ALLIBASEIPOST

Specifies whether you want to generate all the CICS Transaction Server installation and post-installation jobs, or only the post-installation jobs. When installing CICS Transaction Server from the distribution tape, you would normally specify SCOPE ALL (the default). You would normally code the other options, if necessary, during some post-installation tasks, as described in Chapter 4, “Post-installation requirements,” on page 55.

ALL

Specifies that you want to generate all the CICS Transaction Server installation jobs and all the post-installation jobs.

BASE

Specifies that you want to generate only the installation jobs (DFHINST1 through DFHINST6, DFHIHFS0, DFHIHFS1, and DFHISMKD) that you use to install CICS Transaction Server from the distribution tape.

POST

Specifies that you want to generate only the post-installation jobs, that you can use to create the CICS Transaction Server data sets, and run the IVPs.

Specify the Type of JES to be Used

Specify the type of job entry subsystem (JES) that you intend to use to install CICS Transaction Server on the JES parameter: This enables the DFHISTAR job to generate jobs with statements suitable for JES2 or JES3.

JES JES2|JES3|3

Specifies the release of JES that you are using. If you are using JES2, specify *JES2* or *2*. If you are using JES3, specify *JES3* or *3*.

Specify the Utilities to be used

Specify the utilities to be used to install CICS Transaction Server on the UTILITIES parameter:

UTILITIES *asmprog binder smpeprog copyutil*

Specifies the names of utility programs to be used when installing CICS Transaction Server elements and programs that it uses.

asmprog

is the program name of the assembler. Specify ASMA90, for High Level Assembler/MVS & VM & VSE, which is required.

binder

is the program name of the OS/390 binder. Ensure that program IEWL references the OS/390 program management binder.

smpeprog

is the program name of the SMP/E program. The IBM-supplied name is GIMSMP.

copyutil

is the program name of the data set copy utility program. The IBM-supplied name is IEBCOPY.

Note: The High Level Assembler must be either in the LINKLST concatenation **or** you must add a STEPLIB DD statement that points to the library containing the High Level Assembler in any jobs that invoke SMP/E.

Specify the Prefix of CICS Transaction Server Jobs

Specify the prefix, as one through six characters, to be added to the jobs generated by the DFHISTAR job. This prefix overwrites the first characters of the job name. For example, PREFIX USERID changes the job name DFHINST1 to USERIDT1.

PREFIX prefix

One through six characters.

Specify the Indexes of CICS Transaction Server Data Sets

Specify the high-level indexes for the CICS Transaction Server distribution, target, and SMP/E libraries allocated by the installation process.

DINDEX library_prefix

Assigns a high-level index to the CICS Transaction Server SMP/E distribution libraries (except for the SDFHLINK and SDFHLPA target libraries) allocated by the installation process.

The *library_prefix* value must not be longer than 26 characters, and the leading character must be alphabetic. If you specify more than one level of index, the names must be separated by a period (for example, DINDEX CICSTS31.TEST).

GINDEX library_prefix

Assigns a high-level index to the CICS Transaction Server SMP/E global libraries (except for the SDFHLINK and SDFHLPA target libraries) allocated by the installation process.

The *library_prefix* value must not be longer than 26 characters, and the leading character must be alphabetic. If you specify more than one level of index, the names must be separated by a period (for example, GINDEX CICSTS31.TEST).

LINDEX library_prefix

Assigns a high-level index to the SDFHLPA, SDFHLINK, SDFJLPA, SEYULINK and SEYULPA libraries allocated by the installation process. The *library_prefix* value must be defined in the MVS Master Catalog.

The *library_prefix* value must not be longer than 26 characters, and the leading character must be alphabetic. If you specify more than one level of index, the names must be separated by a period (for example, LINDEX SYS1.CICSTS31.CICS.TEST).

TINDEX library_prefix

Assigns a high-level index to the CICS Transaction Server SMP/E target libraries (except for the SDFHLINK, SDFHLPA, SDFJLPA, SEYULINK, and SEYULPA target libraries) allocated by the installation process.

Notes:

1. The high-level index for the SDFHLINK and SDFHLPA libraries is defined by the LINDEX parameter.
2. The high-level index for the data sets created by the jobs DFHCOMDS and DFHDEFDS is defined by the *dsindex* operand of the DSINFO parameter.

The *library_prefix* value must not be longer than 26 characters, and the leading character must be alphabetic. If you specify more than one level of index, the names must be separated by a period (for example, TINDEX CICSTS31.TEST).

Specify the CICS TS HFS Directories and Data Sets

The DFHISTAR job has parameters that enable you to customize the UNIX system services HFS directories.

Note: When discussing HFS Directory names, this topic and the *Program Directory* use different methods to show fixed and variable names, as follows:

Table 5.

This topic uses:	the Program Directory uses:	to show:
<i>/variable</i>	/@variable@	a variable value
/constant	/constant	a fixed value

pathprefix

The name of an optional prefix to the CICS TS directory **/usr/lpp/cicsts**. For example:

/example/usr/lpp/cicsts

ussdir

The name of the CICS TS directory under */pathprefix***/usr/lpp/cicsts**.

The full name is therefore */pathprefix***/usr/lpp/cicsts/ussdir**. **Ussdir** is a name that you can choose. The default for *ussdir* is the value of the TINDEX parameter in lowercase.

The default path is:

/pathprefix/usr/lpp/cicsts/cicsts31

Note: The name of the UNIX System Services directory after the root directory (**/usr/lpp**) is always **/cicsts**.

HFS0DSN

The dataset name of the HFS to be mounted at directory */pathprefix***/usr/lpp/cicsts/cicsts31**.

Note that these directory names are fixed. The default is data set name OMVS.USR.LPP.CICSTS .

See “The DFHIHFS0 Job” on page 43 for details of the job that uses this parameter.

HFS1DSN

The dataset name of the HFS to be mounted at directory */pathprefix***/usr/lpp/cicsts/ussdir**, where *ussdir* is the name of the directory specified on the **ussdir** parameter in the DFHISTAR job. The default is data set name OMVS.USR.LPP.CICSTS.CICSTS31.

See “The DFHIHFS1 Job” on page 43 for details of the job that uses this parameter.

HFSADSN

The dataset name of the HFS equivalent of the SMP/E “additional target zone”, to be mounted at directory */pathprefix***/usr/lpp/cicsts/ussdira**, where *ussdira* is the name of the directory specified on the **ussdira** parameter in the DFHISTAR job. The default data set name is OMVS.USR.LPP.CICSTS.CICSTS31.A.

See the list step about running DFHIHFSA on page “DFHIHFSA” on page 51 for details of the job that uses this parameter.

Specify extra qualifiers

Specify extra qualifiers that can optionally be inserted into the data set name of the 'target', 'distribution' and 'additional' zone data sets respectively, and inserted before the last data set qualifier. For example, XTRAQUAL JDOE . . changes the name of the target zone libraries to the values set by TINDEX.CICSTS31.CICS.JDOE.SDFHLOAD.

XTRAQUAL . . .

Three qualifiers to be used by 'target', 'distribution' and 'additional' zone data sets. If a qualifier is not required, specify a period (.).

Specify Block Sizes

Specify the block sizes to be used when allocating data sets during installation on the BLKFB80 and BLKU parameters:

BLKFB80 {0|blocksize}

The block size to be used when allocating data sets that have a fixed block record format and record length of 80 bytes.

The IBM-supplied value in DFHISTAR is 0. You are recommended to leave this value specified as 0 to allow OS/390 to determine the optimum block size for you.

BLKU {32760|blocksize}

The block size to be used when allocating data sets that have an *undefined* record length.

BLKISPF {3200|blocksize}

The block size to be used when allocating data sets in CICSplex System Manager that are intended to be used by ISPF.

Specify the Disk Unit for Work Data Sets

Specify the UNIT parameter for the disk or disks on which work data sets are stored on the WORKUNIT parameter:

WORKUNIT disktype

a unit identifier.

Specify SMS Option for DASD Allocations

Specifies the extent to which you want to leave the allocation of CICS TS installation data sets to SMS. You can either let SMS handle all DASD allocation, or you can opt to use volume parameters to control the allocations that do not have to be SMS-managed.

Note: Some CICS TS data sets are installed in PDSE data sets. These are:

- The SMP/E SMPLTS data set.
- The distribution library, ADFJMOD.
- The target libraries SDFJLOAD, SDFJLPA, and SDFJAUTH.

See the topic *DASD Storage Requirements* in the *Program Directory* for information about these data sets.

SMS YIN

If you specify SMS Y, the VOLUME parameter is omitted from the generated installation jobs, and all data set allocations are handled by SMS.

If you specify SMS N, the VOLUME parameter is included on the generated installation jobs, and will be honored according to your SMS configuration. The VOLUME parameters used are those specified on the ADDTVOL, DEFVOL, DISTVOL, CMACVOL, OPTVOL, SMPVOL, and TARGVOL parameters.

Specify Disk Volumes

If you intend installing CICS Transaction Server into disk space managed by the storage management subsystem (SMS)¹ component of MVS/DFP, you do not need to specify your own disk volumes; device assignment can be determined by SMS. In this case, proceed to “Specify SMP/E Zone Attributes” on page 30.

To allow you to make the best use of your disk space, you can specify your own disk volumes and device types to be used to install CICS Transaction Server. You can specify your own disk details on the following parameters:

DEFVOL volume disktype

Defines the default disk on which the contents of the disk volumes CMACVOL, DISTVOL, OPTVOL, SMPVOL, and TARGVOL will reside if the appropriate parameter is not coded in the DFHISTAR job. For example, if you do not code the DISTVOL parameter, the CICS distribution libraries will reside on the disk defined by DEFVOL.

volume

is one of the following:

- The volume serial identifier, in the range 1 through 6 characters, of the default volume.
- A period (.) if all volumes other than CMACVOL and SMPVOL that are not specifically defined by the appropriate parameter of the DFHISTAR job will be put onto any available volume. The CMACVOL and SMPVOL volumes will be put onto the same volume as the library specified by the TEMPLIB parameter.

disktype

is the UNIT parameter of the volume.

If you omit the DEFVOL parameter altogether, all volumes that are not specifically defined by the appropriate parameter of the DFHISTAR job will be put onto the same volume as the library specified by the TEMPLIB parameter.

DISTVOL volume disktype

Defines the disk on which the CICS Transaction Server distribution libraries will reside.

volume

is one of the following:

- The volume serial identifier, in the range 1 through 6 characters, of the volume on which the distribution libraries will reside.
- A period (.) if the CICS Transaction Server libraries are to be put onto any available volume.

1. For further information about installing system-managed storage, and about planning for and migrating storage to an SMS-managed environment, see the *MVS Storage Management Library: Storage Management Subsystem Migration Planning Guide*, SC26-4406.

disktype

is the UNIT parameter of the volume.

Note: If you omit the DISTVOL parameter, the distribution libraries will be put on the volume specified by the DEFVOL parameter. If the DEFVOL parameter is omitted, or if a period (.) is specified for its *volume* operand, the distribution libraries will be put onto any available volume.

TARGVOL volume disktype

Specifies details of the disk containing the CICS Transaction Server target libraries.

volume

is one of the following:

- The volume serial identifier, in the range 1 through 6 characters, of the volume on which the CICS Transaction Server target libraries are to reside.
- A period (.) if the CICS Transaction Server target libraries are to be put onto any available volume.

disktype

is the UNIT parameter for the volume.

Note: If you omit the TARGVOL parameter, the CICS Transaction Server target libraries will be put onto the volume specified by the DEFVOL parameter. If the DEFVOL parameter is omitted, or if a period (.) is specified for its *volume* operand, the CICS Transaction Server target libraries will be put onto any available volume.

SMPVOL volume disktype

Specifies the disk that contains the permanent, non-VSAM SMP/E data sets for CICS Transaction Server that are associated with global or distribution zones, and are therefore unique.

volume

is one of the following:

- The volume serial identifier, in the range 1 through 6 characters, of the volume on which the permanent non-VSAM SMP/E data sets are to reside.
- A period (.) if the permanent non-VSAM SMP/E data sets are to be put onto the same volume as the library specified by the TEMPLIB parameter.

disktype

is the UNIT parameter for the volume.

Note: If you omit the SMPVOL parameter, the permanent non-VSAM SMP/E data sets for CICS Transaction Server will be put on the volume specified by the DEFVOL parameter. If the DEFVOL parameter is omitted, or if a period (.) is specified for its *volume* operand, the data sets will be put onto the same volume as the library specified by the TEMPLIB parameter.

OPTVOL volume disktype

Specifies details of the disk onto which the optional source material is copied.

volume

is one of the following:

- The volume serial identifier, in the range 1 through 6 characters, of the volume on which the optional source material is to reside.
- A period (.) if the optional source material is to be put on any available volume.

disktype

is the UNIT parameter of the volume. This is needed only if *volume* is specified.

Note: If you omit the OPTVOL parameter, the optional source material will be put on the volume specified by the DEFVOL parameter. If the DEFVOL parameter is omitted, or if a period (.) is specified for its *volume* operand, the optional source material will be put onto any available volume.

CMACVOL volume

Defines the disk on which the VSAM KSDS, DFHMACD, will reside. This data set is used for the CICS Transaction Server messages facility (CICS-supplied transaction CMAC).

volume

is one of the following:

- The volume serial identifier, in the range 1 through 6 characters, of the volume on which the VSAM KSDS, DFHMACD, will reside
- A period (.) if the DFHMACD data set is to be put onto the same volume as the library specified by the TEMPLIB parameter.

Note: If you omit the CMACVOL parameter, the DFHMACD data set will be put onto the volume specified by the DEFVOL parameter. If the DEFVOL parameter is omitted, or if a period (.) is specified for its *volume* operand, the DFHMACD data set will be put onto the same volume as the library specified by the TEMPLIB parameter.

When Are These Volumes Used?

DFHISTAR Volume Parameter	Installing	Applying Service	Customizing	Assembling Resource Tables	Running CICS Transaction Server
SMPVOL	✓	✓	✓	✓	
DISTVOL	✓	✓	✓		
TARGVOL	✓	✓	✓	✓	✓
DZONECSI ¹	✓	✓	✓		
TZONECSI ¹	✓	✓	✓	✓	
GZONECSI ¹	✓	✓	✓	✓	

¹ The entries for xZONECSI parameters are also for the associated xZONE parameters.

During installation: The RELFILE data sets on SMPVOL are needed during installation only.

Applying Service or Customizing CICS Transaction Server: SMPVOL, DISTVOL, TARGVOL, DZONE, TZONE, and GZONE are needed whenever you apply service or customize your CICS Transaction Server programs.

SMPVOL and GZONE are needed whenever you apply service or customize your **alternative** libraries for use with the extended recovery facility.

Assembling CICS Transaction Server Tables: SMPVOL, TARGVOL, TZONE, and GZONE are needed whenever you assemble your CICS Transaction Server tables.

SMPVOL and GZONE are needed whenever you assemble CICS Transaction Server tables for the second (alternate) CICS Transaction Server region.

Running CICS Transaction Server: Only TARGVOL is needed to run CICS Transaction Server.

Allocate the Space for CICS Transaction Server Disk Volumes

Whether or not you use SMS-managed data sets, you still need enough disk space in which to create the CICS Transaction Server disk volumes.

The space required by the installation jobs on these volumes depends on the type of disk you intend to use. The number of cylinders required on the different types of DASD are given in Table 6. The size of the CICS Transaction Server distribution and target libraries are given in the topic *DASD Storage Requirements* in the *Program Directory*.

Table 6. DASD storage requirements for CICS Transaction Server

Identification	3380	3390
CICSTS31.TDFHINST	1	1
CICSTS31.XDFHINST	1	1
Relfile data sets on SMPVOL	325	300
SMP/E non-VSAM data sets on SMPVOL	26	25
DISTVOL	312	288
TARGVOL	749	678
DZONE	11	11
TZONE	11	11
GZONE	11	11
Total during installation	1447	1327
Total after installation	1122	1027

Allow up to 15% on the values in Table 6 for servicing requirements. Secondary allocations are 10% of the primary allocations.

If you intend to store other IBM software or your own application programs in these libraries, then you must modify the generated jobs accordingly.

Specify Attributes of the Temporary SMP/E Work Data Sets

You must define the attributes of the temporary SMP/E work data sets (SMPWRK1, SMPWRK2, SMPWRK4, and SMPWRK6): for the following CICS Transaction

Server jobs: DFHINSTJ, DFHLPJPN, DFHLPUMD, and DFHSMPE. You define the attributes of those SMP/E data sets on the SMPWORK parameter:

The CICS Transaction Server jobs used to install CICS Transaction Server for z/OS have DD statements for the SMP/E data sets that they need to know about.

SMPWORK disktype

This is the UNIT parameter for the disk that is to contain the temporary SMP/E work data sets (SMPWRK1, SMPWRK2, SMPWRK4, and SMPWRK6) needed to install CICS Transaction Server.

If you specify a value for *disktype*, or omit the SMPWORK parameter altogether, //SMPWRKn DD statements are added to the following jobs generated by the DFHISTAR job:

```
DFHINSTJ
DFHLPUMD
DFHSMPE
```

If you specify NO, a period (.), or a null string, CICS Transaction Server assumes that SMP/E knows about the temporary SMP/E work data sets. To define the attributes of the SMP/E work data sets, you must do one of the following:

- Provide appropriate DDDEFS for the temporary SMP/E work data sets.
- Have applied the SMP/E sample usermod (SMP0001) that contains superzap statements for updating the default attributes of the SMP/E data sets in the GIMMPDFT module.

The GIMMPDFT module, which is part of SMP/E, defines the default attributes of SMP/E data sets, and can be used to dynamically allocate data sets to be used by all zones. The usermod is in member GIMZPDFT in the SYS1.SAMPLIB library. You can use this usermod as a model, change it to meet your needs, or install it as supplied. For further information about the entries in the GIMMPDFT module and the sample entry values in the usermod SMP0001, see the *System Modification Program Extended: Reference* manual, SA22-7772.

Notes:

1. The SMPWRK6 data set must not be allocated to Virtual I/O (VIO). If you specify a value for *disktype*, ensure that this cannot happen.

Specify Attributes of the Permanent SMP/E Data Sets

Specify the attributes of the permanent SMP/E data sets on the following parameters:

SMPPTS dsname

Specifies the name of the SMP/E primary data set used to store temporarily PTF function SYSMODs or other fixes that are in RECEIVE or APPLY status; that is, PTF fixes that have not been rejected or accepted.

SMPMTS dsname

Specifies the name of the SMP/E macro temporary store (MTS) data set used to store updated versions of macros. Although required by SMP/E, this MTS data set is not used by CICS.

SMPSTS dsname

Specifies the name of the SMP/E source temporary store (STS) data set used to store updated versions of source elements. Although required by SMP/E, this STS data set is not used by CICS.

SMPSCDS dsname

Specifies the name of the SMP/E saved control data set (SCDS) used to store old target zone entries that have been modified by inline JCLIN processing in a SYSMOD.

SMPLTS dsname

Specifies the name of the linkedit temporary (LTS) data set used with the CALLLIBS function. This dataset must always be an SMS-managed PDSE, whether or not Java is installed unless you have installed the PTFs for HFS and PDSE support on non-managed SMS volumes listed in Flash10007 which can be found by links from:

<http://www.ibm.com/support/techdocs>

The CICS Transaction Server jobs that need to know the attributes of the SMP/E data sets have DD statements for them.

Specify SMP/E Zone Attributes

Specify the attributes of the SMP/E distribution zone, global zone, target zone, and any additional target zones.

Note: The CICS-DB2 attachment facility contains modules named with the DSN prefix. Therefore, to prevent existing DB2 modules with the same DSNxxxxx names from being overwritten, you should not install CICS Transaction Server into the same target and distribution zones as DB2.

To specify SMP/E zone attributes, use the following parameters:

GZONELOG dsname NEWIOLD

Specifies details of the SMP/E log for the global zone CSI.

dsname

is the name of the global zone log.

NEWIOLD

Specifies whether an existing global zone log is to be used. If you specify NEW, any existing global zone log with the specified *dsname* is deleted, and a new global zone log is allocated. If you specify OLD, an existing global zone log is used.

TZONELOG dsname NEWIOLD

Specifies details of the SMP/E log for the target zone CSI.

dsname

is the name of the target zone log.

NEWIOLD

Specifies whether an existing target zone log is to be used. If you specify NEW, any existing target zone log with the specified *dsname* is deleted, and a new target zone log is allocated. If you specify OLD, an existing target zone log is used.

DZONELOG dsname NEWIOLD

Specifies details of the SMP/E log for the distribution zone CSI.

dsname

is the name of the distribution zone log.

NEWIOLD

Specifies whether an existing distribution zone log is to be used. If you

specify NEW, any existing distribution zone log with the specified *dsname* is deleted, and a new distribution zone log is allocated. If you specify OLD, an existing distribution zone log is used.

GZONECSI cluster NEWIOLD volume disktype

Specifies details of the global zone CSI.

cluster

is the VSAM cluster name, minus the qualifier '.CSI'.

NEWIOLD

Specifies whether an existing global zone CSI is to be used. If you specify NEW, any existing global zone CSI with the specified *cluster* name is deleted, and a new global zone CSI is allocated. If you specify OLD, an existing global zone CSI is used.

volume

is either the volume serial (volser) identifier for the volume on which the global zone CSI is to be allocated or a period (.) if the CSI is to be put on a volume determined by the CICS Transaction Server installation process.

disktype

is the UNIT parameter for the volume.

TZONECSI cluster NEWIOLD volume disktype

Specifies details of the target zone CSI.

cluster

is the VSAM cluster name, minus the qualifier '.CSI'.

NEWIOLD

Specifies whether an existing target zone CSI is to be used. If you specify NEW, any existing target zone CSI with the specified *cluster* name is deleted, and a new target zone CSI is allocated. If you specify OLD, an existing target zone CSI is used.

volume

is either the volume serial (volser) identifier for the volume on which the target zone CSI is to be allocated or a period (.) if the CSI is to be put on a volume determined by the CICS Transaction Server installation process.

disktype

is the UNIT parameter for the volume.

DZONECSI cluster NEWIOLD volume disktype

Specifies details of the distribution zone CSI.

cluster

is the VSAM cluster name, minus the qualifier '.CSI'.

NEWIOLD

specifies whether an existing distribution zone CSI is to be used. If you specify NEW, any existing distribution zone CSI with the specified *cluster* name is deleted, and a new distribution zone CSI is allocated. If you specify OLD, an existing distribution zone CSI is used.

volume

is either the volume serial (volser) identifier for the volume on which the distribution zone CSI is to be allocated or a period (.) if the CSI is to be put on a volume determined by the CICS Transaction Server installation process.

disktype

is the UNIT parameter for the volume.

GZONE NEWIOLD options

Specifies whether the global zone to be used already exists.

NEWIOLD

Specifies whether an existing global zone is to be used. The DFHISTAR job as supplied specifies NEW. Optionally change this to OLD if you want to use an existing global zone. If you specify OLD, CICS Transaction Server is installed into an existing SMP/E global zone.

Note: Specify NEW if you want to preserve your existing releases of CICS Transaction Server in their current SMP/E zones and install the new release in its own zones.

If you specify OLD, the existing SMP/E zones are used and any existing release of the product is deleted.

If you specify OLD, but specify NEW for the GZONECSI parameter, both parameters are assigned the NEW disposition.

options

Specifies the name of the SMP/E options (on the SET BOUNDARY command) to be used.

TZONE zonename

Specifies the name of the target zone.

zonename

is the name of the target zone to be used by SMP/E. This name must be unique to the target zone. It must not be longer than 7 characters, and the leading character must be alphabetic.

DZONE zonename

Specifies the name of the distribution zone.

zonename

is the name of the distribution zone to be used by SMP/E. This name must be unique within the global zone. It must not be longer than 7 characters, and the leading character must be alphabetic.

SMP/E Zone and Zone Log Dispositions

As supplied, the DFHISTAR job assumes that you are going to install CICS Transaction Server into new target and distribution zones. However you can specify a new or old global zone, and new or old zone logs by the disposition option NEWIOLD on the associated parameters of the DFHISTAR job. The disposition option NEW means that the DFHINST3 job deletes any existing zone or zone log with name specified before redefining it. For example, if you specify the parameter `GZONELOG CICSTS31.GZONE.SMPLOG NEW`

the DFHINST3 job deletes any existing SMP/E global zone log with the name `CICSTS31.GZONE.SMPLOG` before defining a new SMP/E global zone log with that name.

Further, if you specify different dispositions for a zone parameter and its associated zone log parameter, they are both given the default disposition NEW. This is to ensure that both a zone and its zone log have the same disposition.

If you intend installing CICS Transaction Server using one new CSI for all zones, you must specify the disposition `NEW` on all three CSI parameters of the `DFHISTAR` job. For example:

```
DZONE          DZONE
DZONECSI      CICSTS31.SMPZONE NEW CICS31 SYSALLDA
DZONELOG      CICSTS31.DZONE.SMPLOG NEW
GZONE         NEW CICSOPT
GZONECSI      CICSTS31.SMPZONE NEW CICS31 SYSALLDA
GZONELOG      CICSTS31.GZONE.SMPLOG NEW
TZONE         TZONE
TZONECSI      CICSTS31.SMPZONE NEW CICS31 SYSALLDA
TZONELOG      CICSTS31.TZONE.SMPLOG NEW
```

Specify the High-level Qualifiers for SMP/E Data Sets

For each different high-level qualifier that you have specified for SMP/E zone CSIs, logs, and other SMP/E data sets, you must create an `ALIAS` definition in the master catalog before the data sets can be used.

Specify the distribution tape device type

Specify the type of device that is to be used to load the CICS Transaction Server distribution tape on the `TAPEUNIT` parameter:

TAPEUNIT devicetype

Specifies the device type to be used to read the distribution tape. Use `3480` for the 3480 tape cartridge, `3400-6` for the 6250 tape, or the unit names in use in your installation.

Specify Attributes of the CICS Transaction Server system Data Sets

Specify attributes of the CICS Transaction Server system data sets, to be created when you run the post-installation jobs `DFHCOMDS` and `DFHDEFDS`² jobs, on the `DSINFO` parameter:

DSINFO dsindex volume disktype qualifier

Defines the following attributes of CICS system data sets:

dsindex

Assigns a high-level index to all the data sets defined by the jobs, `DFHCOMDS` and `DFHDEFDS`.

The leading character of *dsindex* must be alphabetic. *dsindex* can have one or two levels of index, but each level must be no longer than eight characters. If you specify more than one level of index, the names must be separated by a period (for example, `CICSTS31.CICSHTC1`).

volume

is the volume identifier of the volume.

disktype

is the `UNIT` parameter for the volume.

qualifier

is a partial qualifier added to the index for the data sets created by the jobs `DFHCOMDS` and `DFHDEFDS`. You can specify a partial qualifier of up to four alphanumeric characters; these characters are appended to the characters `CICS` to make the qualifier. If you specify a period (`.`) no qualifier is used.

2. For more information about the post-installation jobs `DFHCOMDS` and `DFHDEFDS` jobs, see “Creating data sets common to all CICS regions, `DFHCOMDS` job” on page 191.

Specify Attributes of any additional target Libraries

If you want to create extra copies of the CICS Transaction Server target libraries, specify the attributes of those libraries on the following parameters:

AINDEX library_prefix

Assigns a high-level index to the additional set of CICS target libraries copied by a version of the DFHINSTA job.

Notes:

1. The high-level index for the additional SDFHLINK and SDFHLPA libraries is defined by the ALINDEX parameter.
2. The high-level index for the data sets created by the jobs DFHCOMDS and DFHDEFDS is defined by the *dsindex* operand of the DSINFO parameter.

The AINDEX value must be unique (for example, it must be different from the INDEX value), it must not be longer than 26 characters, and the leading character must be alphabetic. If you specify more than one level of index, the names must be separated by a period (for example, AINDEX CICSTS31.A.TEST).

ALINDEX library_prefix

Assigns a high-level index to the additional SDFHLPA and SDFHLINK libraries allocated by running a version of the DFHINSTA job.

The *library_prefix* value must not be longer than 26 characters, and the leading character must be alphabetic. If you specify more than one level of index, the names must be separated by a period (for example, ALINDEX SYS1.CICSTS31.A.TEST)

AZONELOG dsname

Specifies details of the SMP/E log for the additional target zone CSI.

dsname

is the name of the additional target zone log to be used by SMP/E.

AZONECSI cluster

Specifies details of the additional target zone CSI. The CSI data set is created on the volume and unit specified by the ADDTVOL parameter.

cluster

is the VSAM cluster name, minus the qualifier **.CSI**.

AZONE zonename

Specifies the name of the additional target zone, to be used for the set of CICS Transaction Server target libraries copied by a version of the DFHINSTA job.

zonename

is the name of the additional target zone to be used by SMP/E. This name must be unique to the target zone. It must not be longer than seven characters, and the leading character must be alphabetic.

ASMPSCDS dsname

Specifies the name of the additional zone SMP/E SCDS data set.

dsname

is the name of the additional zone SMP/E SCDS data set.

ASMPMTS dsname

Specifies the name of the additional zone SMP/E MTS data set.

dsname

is the name of the additional zone SMP/E MTS data set.

ASMPSTS dsname

Specifies the name of the additional zone SMP/E STS data set.

dsname

is the name of the additional zone SMP/E STS data set.

ASMPSTS dsname

Specifies the name of the additional zone SMP/E LTS data set.

dsname

is the name of the additional zone SMP/E LTS data set.

ADDTVOL volume disktype

Specifies the volume and unit type to contain all the additional zone data sets.

volume

is the volume serial identifier of the volume.

disktype

is the UNIT parameter for the volume.

USSDIRA dsname

Specifies the name of the UNIX System Services directory for the Additional Target zone. See job DFHINSTA.

The default is the value of the AINDEX parameter in lowercase.

The UNIX System Services directory path will start `/ussindex/cicsts/ussdira` where `ussindex` is the translated value of the USSINDEX parameter, and `ussdira` is the value of the USSDIRA parameter.

The default path will be: `/pathprefix/usr/lpp/cicsts/cicsts31.a`

Note: The name of the UNIX System Services directory after the root directory (`/usr/lpp/`) is always **cicsts**.

Specify the Data Set Name of the SISPLoad Library

Specify the full data set name, up to 44 characters, of the library that contains ISPLINK (SISPLoad for ISPF Version 4 and above, or ISPLoad for ISPF version 3 and below). For example, `SISPLoad SYS1.USERID.SISPLoad` changes the SISPLoad library name to `SYS1.USERID.SISPLoad`. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SISPLoad dsname

Up to 44 characters.

Specify the Data Set Name of the CSSLIB Library

Specify the full data set name, up to 44 characters, of the CSSLIB library. For example, `CSSLIB SYS1.USERID.CSSLIB` changes the CSSLIB library name to `SYS1.USERID.CSSLIB`. This library is accessed, as read-only, during the installation of CICS Transaction Server.

CSSLIB dsname

Up to 44 characters.

Specify the Data Set Name of the SCEECPP Library

Specify the full data set name, up to 44 characters, of the SCEECPP library. For example, `SCEECPP SYS1.USERID.SCEECPP` changes the SCEECPP library name to `SYS1.USERID.SCEECPP`. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCEECPP dsname
Up to 44 characters.

Specify the Data Set Name of the SCEELKED Library

Specify the full data set name, up to 44 characters, of the SCEELKED library. For example, SCEELKED SYS1.USERID.SCEELKED changes the SCEELKED library name to SYS1.USERID.SCEELKED. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCEELKED dsname
Up to 44 characters.

Specify the Data Set Name of the SCEELKEX Library

Specify the full data set name, up to 44 characters, of the SCEELKEX library. For example, SCEELKEX SYS1.USERID.SCEELKEX changes the SCEELKEX library name to SYS1.USERID.SCEELKEX. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCEELKEX dsname
Up to 44 characters.

Specify the Data Set Name of the SCEEOBJ Library

Specify the full data set name, up to 44 characters, of the SCEEOBJ library. For example, SCEEOBJ SYS1.USERID.SCEEOBJ changes the SCEEOBJ library name to SYS1.USERID.SCEEOBJ. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCEEOBJ dsname
Up to 44 characters.

Specify the Data Set Name of the SCEESAMP Library

Specify the full data set name, up to 44 characters, of the SCEESAMP library. For example, SCEESAMP SYS1.USERID.SCEESAMP changes the SCEESAMP library name to SYS1.USERID.SCEESAMP. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCEESAMP dsname
Up to 44 characters.

Specify the Data Set Name of the SCLBSID Library

Specify the full data set name, up to 44 characters, of the SCLBSID library. For example, SCLBSID SYS1.USERID.SCLBSID changes the SCLBSID library name to SYS1.USERID.SCLBSID. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCLBSID dsname
Up to 44 characters.

Specify the Data Set Name of the SCSQLOAD Library

Specify the full data set name, up to 44 characters, of the SCSQLOAD library. For example, SCSQLOAD SYS1.USERID.SCSQLOAD changes the SCSQLOAD library name to SYS1.USERID.SCSQLOAD. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCSQLOAD dsname
Up to 44 characters.

Specify the Data Set Name of the SCSQANLE Library

Specify the full data set name, up to 44 characters, of the SCSQANLE library. For example, SCSQANLE SYS1.USERID.SCSQANLE changes the SCSQANLE library name to SYS1.USERID.SCSQANLE. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCSQANLE dsname

Up to 44 characters.

Specify the Data Set Name of the SCSQCICS Library

Specify the full data set name, up to 44 characters, of the SCSQCICS library. For example, SCSQCICS SYS1.USERID.SCSQCICS changes the SCSQCICS library name to SYS1.USERID.SCSQCICS. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCSQCICS dsname

Up to 44 characters.

Specify the Data Set Name of the SCSQAUTH Library

Specify the full data set name, up to 44 characters, of the SCSQAUTH library. For example, SCSQAUTH SYS1.USERID.SCSQAUTH changes the SCSQAUTH library name to SYS1.USERID.SCSQAUTH. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCSQAUTH dsname

Up to 44 characters.

Specify the Name of the Java directory

Specify the name of the Java directory for use by CICS JVM application programs.

JAVADIR directory name

This parameter is appended to */pathprefix/usr/lpp/*, giving a full path name of */pathprefixusr/lpp/javadir*.

Specify the Data Set Name of the SDSNLOAD Library

Specify the full data set name, up to 44 characters, of the DB2 SDSNLOAD library. For example, SDSNLOAD SYS1.USERID.SDSNLOAD changes the SDSNLOAD library name to SYS1.USERID.SDSNLOAD. This library is accessed, as read-only, during the installation of CICS Transaction Server.

Note: The REXX for CICS element contains some modules that are link-edited against the DB2 load library, SDSNLOAD. If you do not have DB2 installed, the DFHINST6 job fails because SDSNLOAD cannot be allocated to the job. To avoid this, define a dummy SDSNLOAD data set, with LRECL=0 and RECFM=U, and specify the name of this empty data set on the SDSNLOAD parameter.

SDSNLOAD dsname

Up to 44 characters.

Specify the Data Set Name of the SEZARPCL and SEZACMTX libraries

Specify the full data set names, up to 44 characters, of the SEZARPCL and SEZACMTX libraries. For example, SEZARPCL SYS1.USERID.SEZARPCL changes the SEZARPCL library to SYS1.USERID.SEZARPCL and SEZACMTX

SYS1.USERID.SEZACMTX changes the SEZACMTX library name to SYS1.USERID.SEZACMTX. These libraries are accessed, as read-only, during the installation of CICS Transaction Server.

SEZARPCL dsname

Up to 44 characters.

SEZACMTX dsname

Up to 44 characters.

Specify the Data Set Name of the SCEECICS & SCEERUN libraries

Specify the full data set names, up to 44 characters, of the SCEECICS & SCEERUN libraries. For example, SCEECICS SYS1.USERID.SCEECICS changes the SCEECICS library to SYS1.USERID.SCEECICS and SCEERUN SYS1.USERID.SCEERUN changes the SCEERUN library name to SYS1.USERID.SCEERUN. These libraries are accessed, as read-only, during the installation of CICS Transaction Server.

SCEECICS dsname

Up to 44 characters.

SCEERUN dsname

Up to 44 characters.

Specify the Data Set Name of the SCEERUN2 & SCEELIB libraries

Specify the full data set names, up to 44 characters, of the SCEERUN2 & SCEELIB libraries. For example, SCEERUN2 SYS1.USERID.SCEERUN2 changes the SCEERUN2 library to SYS1.USERID.SCEERUN2 and SCEELIB SYS1.USERID.SCEELIB changes the SCEELIB library name to SYS1.USERID.SCEELIB. These libraries are accessed, as read-only, during the installation of CICS Transaction Server.

SCEERUN2 dsname

Up to 44 characters.

SCEELIB dsname

Up to 44 characters.

Specify the Data Set Name of the SCEEBND2 library

Specify the full data set name, up to 44 characters, of the SCEEBND2 library. For example, SCEEBND2 SYS1.USERID.SCEEBND2 changes the SCEEBND2 library to SYS1.USERID.SCEEBND2. This library is accessed, as read-only, during the installation of CICS Transaction Server.

SCEEBND2 dsname

Up to 44 characters.

Specify Log stream and Log stream Structure Attributes.

Specify attributes of the CICS Transaction Server log streams and the coupling facility structures that you will use when you run the post-installation jobs DFHILG1, DFHILG2, DFHILG3 and DFHILG4³ jobs, on the LOGGER-INFO parameter:

LOGGER-INFO strsfx logsz shuntsz jnlisz gensz sysname loghlq logmodel

Defines the following attributes of CICS Transaction Server system data sets:

3. For more information about the post-installation jobs DFHILG1, DFHILG2, DFHILG3 and DFHILG4 jobs, see Chapter 24, "Defining the logger environment for CICS journaling," on page 143.

strsfx

The last part of the coupling facility structure names, can be any three characters allowed in a structure name. Default 001. Used in DFHILG1, DFHILG2, DFHILG3 and DFHILG4.

logsz

The Avgbufsize for system log streams in the LOG_DFHLOG_strsfx structure. Default 500. Used in DFHILG1.

shuntsz

The Avgbufsize for shunted system log streams in the LOG_DFHSUNT_strsfx structure. Default 4096. Used in DFHILG1.

jnlisz

The Avgbufsize for unforced user journal log streams in the LOG_USERJRNL_strsfx structure. Default 64000. Used in DFHILG1.

gensz

The Avgbufsize for forced user journal log streams and forward recovery log streams in the LOG_GENERAL_strsfx structure. Default 2048. Used in DFHILG1.

sysname

The MVS system name used to create model log streams for DFHLOG and DFHSUNT. Default MVSX. Used in DFHILG1.

loghlq

The first qualifier of the model name for general logs and DFHLGLOG. Used in DFHILG3 and DFHILG4.

logmodel

The second qualifier of the model name for general logs. Used in DFHILG3.

Create RACF Profiles for the CICS Transaction Server Data Sets

Liaise with your Security Administrator to create appropriate RACF profiles for the CICS Transaction Server data sets, as described in the *CICS RACF Security Guide*.

At this stage, you need authority to access only the data set qualifiers specified on the TEMPLIB, LIB, and INDEX parameters. (The DFHISTAR job uses a temporary sequential data set, with the high-level qualifier specified on the INDEX parameter, to resolve the parameters to be substituted into the jobs being tailored.) However, it is worth coordinating the access authority for all the CICS Transaction Server data sets at the same time.

Run the DFHISTAR Job

When you have edited the DFHISTAR job with the values of installation parameters for your CICS Transaction Server environment, save it.

When you are ready to tailor the skeleton jobs, submit the DFHISTAR job.

In addition to the UNIX system services HFS jobs, there are three other HFS-related members supplied in SDFHINST. These are DFHBXP0, DFHBXP1, and DFHBXPA.

DFHBXP0

This member contains a MOUNT command for inclusion in a BPXPRMxx member of the SYS1.PARMLIB dataset. The MOUNT command applies to the

HFS dataset specified in the HFS0DSN parameter of the DFHISTAR job to be mounted at directory */pathprefixusr/lpp/cicsts*.

Add this mount command to the BPXPRMxx PARMLIB member after you have run the DFHIHFS0 job.

DFHBPXP1

This member contains a MOUNT command for inclusion in a BPXPRMxx member of the SYS1.PARMLIB dataset. The MOUNT command applies to the HFS dataset specified in the HFS1DSN parameter of the DFHISTAR job to be mounted at directory */pathprefixusr/lpp/cicsts/ussdir*, where *ussdir* is the name of the directory specified in the **ussdir** parameter in the DFHISTAR job

Add this mount command to the BPXPRMxx PARMLIB member after you have run the DFHIHFS1 job.

DFHBPXPA

This member contains a MOUNT command for inclusion in a BPXPRMxx member of the SYS1.PARMLIB dataset. The MOUNT command is for HFS dataset specified in the HFSADSN parameter of the DFHISTAR job to be mounted at directory */pathprefixusr/lpp/cicsts/ussdira*, where *ussdira* is the name of the directory specified in the **ussdira** parameter in the DFHISTAR job.

Add this mount command to the BPXPRMxx PARMLIB member after you have run the DFHIHFSA job.

When the DFHISTAR job has run, the jobs listed in the topic *Skeleton jobs in RELFILE(2) copied to the TDFHINST library* in the *Program Directory* (apart from the DFHISTAR job) are tailored to your CICS Transaction Server environment and added to the library that you specified on the LIB parameter of the DFHISTAR job (by default, the CICSTS31.XDFHINST library). If necessary, the DFHISTAR job creates the library specified on the LIB parameter.

The highest expected return code is 0.

Check the Output from the DFHISTAR Job

Check the output from the DFHISTAR job, and if needed, edit and submit the DFHISTAR job again.

The DFHISTAR job produces a job log and, if necessary, an error code:

- The output job log lists the values that were actually used for the parameters of the DFHISTAR job.
- If any error occurs when running the DFHISTAR job, an error code of 4 or 12 is returned. For error code 4, the skeleton jobs are tailored and added to the CICSTS31.XDFHINST library. For error code 12, the skeleton jobs are not tailored or copied. To resolve the cause of either error code, examine the output job log and, if necessary, edit and submit the DFHISTAR job again.

You can run the DFHISTAR job any number of times to alter the attributes of the jobs that it creates.

When running the DFHISTAR job after the first time, you can select specific jobs to be created, by using the SCOPE or SELECT parameter:

SCOPE ALLIBASEIPOST

Specifies whether you want to generate all the CICS Transaction Server installation and post-installation jobs, or only the post-installation jobs. When installing CICS Transaction Server from the distribution tape, you would

normally specify `SCOPE ALL` (the default). You would normally code the other options, if necessary, during some post-installation tasks, as described in Chapter 4, “Post-installation requirements,” on page 55.

ALL

Specifies that you want to generate all the CICS Transaction Server installation jobs and all the post-installation jobs.

BASE

Specifies that you want to generate only the six installation jobs `DFHINST1` through `DFHINST6` that you can use to install CICS Transaction Server from the distribution tape.

POST

Specifies that you want to generate only the post-installation jobs, that you can use to create the CICS Transaction Server data sets, and run the IVPs.

SELECT jobname newname

Specifies the new name for a copy of a post-installation job to be generated when you run the `DFHISTAR` job. You can specify several `SELECT` parameters to select several post-installation jobs to be regenerated in one run of the `DFHISTAR` job. The `SELECT` parameter overrides the `POST` parameter; that is, if you use the `SELECT` parameter in the `DFHISTAR` job, only those jobs specified by `SELECT` are generated.

Note: If you are using the `SELECT` parameter to generate copies of the post-installation jobs for a new CICS Transaction Server region, you should also change the `DSINFO` parameter to specify details of the data sets for the new CICS region.

For example, to create copies of the jobs `DFHDEFDS` and `DFHIVPOL` for the CICS Transaction Server region `CICSINS` you could specify the `DSINFO` and `SELECT` parameters of the `DFHISTAR` job:

```
DSINFO userid.CICSTS31 H3P061 SYSALLDA INS
SELECT DFHDEFDS INSDEFDS
SELECT DFHIVPOL INSIVPOL
```

If you then run the `DFHISTAR` job, it would create the `INSDEFDS` job as a copy of the `DFHDEFDS` job, and the `INSIVPOL` job as a copy of the `DFHIVPOL` job, substituting the values that you specified on `DSINFO` into the new jobs.

You could then change the `DSINFO` and `SELECT` parameters, and run the `DFHISTAR` job to create other copies of the post-installation jobs for another CICS Transaction Server region.

Check that You Are Ready to Run the Installation Jobs

Check that you are now ready to run the installation jobs:

1. Check the names of the data sets to be created by these jobs, because any existing data sets with those names are deleted by the installation jobs. If you want to keep an existing data set with a name specified in one of the installation jobs, you must change the name to be used for the new data set. For example, for the installation parameter `DZONECSI dsname NEW` the data set `dsname` is deleted and a new distribution zone `CSI` called `dsname` is allocated.
2. The CICS Transaction Server-supplied installation JCL will install CICS Transaction Server for z/OS into new target and distribution zones. If you want to install CICS Transaction Server into existing target and distribution zones, you must modify the `DFHINST3` job.

Caution: If you intend using an existing target or distribution zone that contains an earlier release of CICS Transaction Server, be aware that any earlier release of CICS Transaction Server will be cleared before being replaced by CICS Transaction Server.

3. If you intend installing CICS Transaction Server using both existing and new CSIs, any new CSIs must have the same control interval size as the existing CSIs.

If your existing CSIs do not have a control interval size of 4096 bytes, you must edit the DFHINST3 job (before running it) to change the CONTROLINTERVALSIZE(4096) parameter on the commands used to create the VSAM data sets for the new CSIs, to specify the same control interval size as the existing CSIs.

For further information about considerations for allocating CSI data sets, see the *System Modification Program Extended: Reference manual, SA22-7772*.

4. Ensure that you have appropriate RACF authority for the CICS Transaction Server data sets. For more information, see your Security Administrator and the *CICS RACF Security Guide*.

Run the installation Jobs

OMVS requirement

Before running the installation jobs:

- Ensure the MVS image was IPLed with OMVS in full-function mode.
- Ensure the userid under which you are running the jobs has superuser authority

After you have run the DFHISTAR job to create the installation jobs, submit those jobs in sequence to install CICS Transaction Server. This § describes the CICS Transaction Server installation jobs, and gives considerations that may affect how you use them.

The CICS Transaction Server jobs are in the CICSTS31.XDFHINST library as a result of running the DFHISTAR job, which you copied from the distribution tape, as described in the topic *Copy RELFILE(2) from the Distribution Tape in the Program Directory*.

These jobs should be run one at a time. Before you run a job, read the information about it (starting on page “DFHIHFS0” on page 43).

After you have run a job, check its output before proceeding to the next job. If a job terminates abnormally, find out why it failed (the job log lists the error messages produced on each run). Correct the error, and then proceed as advised in the job description. In any case, do not attempt to run the next job until the previous job has run successfully.

Run Times of the Installation Jobs

To give you an idea what run times to expect, we ran the installation jobs on an IBM 9672 RX5 using a single LPAR. The run times were:

Job	Processor Time	Elapsed Time
DFHIHFS0	1 second	7 seconds

Job	Processor Time	Elapsed Time
DFHIHFS1	1 second	7 seconds
DFHISMKD	1 second	1 second
DFHINST1	3 seconds	30 seconds
DFHINST2	3 seconds	30 seconds
DFHINST3	1 second	15 seconds
DFHINST4	1 second	15 seconds
DFHINST5	1 minute	11 minutes
DFHINST6	24 minutes	49 minutes

These time values are suitable to run the installation jobs on an IBM 9672 RX5 or bigger system. If you have a system smaller than an IBM 9672 RX5, you may need to review these values.

The DFHIHFS0 Job

This job:

- Creates the HFS specified on the HFS0DSN parameter of the DFHISTAR job
- Creates the **cicsts** directory at */pathprefix/usr/lpp/*
- Mounts the HFS at directory */pathprefix/usr/lpp/cicsts*
- Changes the permission settings for the **/cicsts** directory to:
 - Owner=RWX
 - Group=RWX
 - Other=R-X

(In octal form: 775)

Where:

- R equates to Read
- W equates to Write
- X equates to Execute
- - equates to no permission

Notes:

1. DFHIHFS0 only ever needs to be run *once*.
2. RACF ALTER ACCESS to the OMVS data sets must be granted before running this DFHIHFS0.
3. The **/cicsts** directory is common to all releases of CICS TS from 1.3 onwards.
4. The **/cicsts** directory contains only directories, each being a mount point.
5. CICS requires the MOUNT issued by DFHIHFS0 to access files stored in the HFS, but the MOUNT command is lost when you re-IPL MVS. SDFHINST member DFHBPXP0 contains a MOUNT command for */pathprefix/usr/lpp/cicsts*. Copy this command into a BPXPRMxx member of the SYS1.PARMLIB dataset to ensure the mount is restored when MVS is IPLed.
6. All steps of DFHIHFS0 must end with return code zero for the job to be successful.

The DFHIHFS1 Job

This job:

- Unmounts the HFS at directory `/pathprefix/usr/lpp/cicsts/ussdir` to allow the job to be rerun, and if necessary forces return code zero.
- Deletes from `/pathprefix/usr/lpp/cicsts` the directory defined by the `lussdir` parameter of the DFHISTAR job. This is to allow the job to rerun, and if necessary forces return code zero.
- Deletes the HFS specified in the HFS1DSN parameter of the DFHISTAR job to allow the job to rerun, and if necessary forces return code zero.
- Creates the HFS specified in the HFS1DSN parameter of the DFHISTAR job.
- Creates the `lussdir` directory at `/pathprefix/usr/lpp/cicsts`, where `lussdir` is the name of the directory specified on the `ussdir` parameter.
- Mounts the HFS at directory `/pathprefix/usr/lpp/cicsts/ussdir`
- Changes the permission settings for the `lussdir` directory to 775.

All steps of DFHIHFS1 must end with return code zero for the job to be successful.

CICS requires the MOUNT issued by DFHIHFS1 to access files stored in the HFS, but the MOUNT command is lost when you re-IPL MVS. SDFHINST member DFHBPXP1 contains a MOUNT command for `/pathprefix/usr/lpp/cicsts/ussdir`. Copy this command into a BPXPRMxx member of the SYS1.PARMLIB dataset to ensure the mount is restored when MVS is IPLed.

The DFHISMKD Job

This job creates the UNIX System Services directories.

This job **must** be run before any of the other installation jobs.

The highest expected return code is 0.

The DFHINST1 Job

This job allocates and catalogs CICS Transaction Server distribution and target libraries.

To ensure that this job can be rerun, it deletes (and uncatalogs) the data sets that are allocated in the second step of the job.

If the DFHINST1 job terminates abnormally, examine the job log to determine the cause, correct the problem, then rerun the job.

The highest expected return code is 0.

The DFHINST2 Job

This job allocates the CICS Transaction Server RELFILE data sets. If you run the DFHINST2 job now, you ensure that enough space has been allocated to the RELFILE data sets to allow the DFHINST5 job to complete.

To ensure that the job can be rerun, it deletes (and uncatalogs) the data sets (if they exist) that it allocates later.

If the DFHINST2 job terminates abnormally, examine the job log to determine the cause, correct the problem, then rerun the job.

The highest expected return code is 0.

DFHINST3 and DFHINST4 jobs.

DFHINST3 is a job that should be run if you have decided to allocate new SMP/E zones.

Be aware that the default specified in DFHISTAR is for the allocation of new zones. This is recommended, to ensure that existing releases of CICS Transaction Server are not deleted.

DFHINST4 is a job that will prime new SMP/E zones created in DFHINST3.

The DFHINST3 Job

This job allocates the CICS Transaction Server SMP/E data sets.

Before you run the DFHINST3 job

If you intend installing CICS Transaction Server using both existing and new CSIs, any new CSIs must have the same control interval size as the existing CSIs.

Caution: *If you intend using an existing target or distribution zone that contains an earlier release of CICS Transaction Server elements, be aware that any earlier release of CICS will be cleared before being replaced by CICS Transaction Server.*

If your existing CSIs do not have a control interval size of 4096 bytes, you must edit the DFHINST3 job (before running it) to change the CONTROLINTERVALSIZE(4096) parameter on the commands used to create the VSAM data sets for the new CSIs, to specify the same control interval size as the existing CSIs.

For further information about considerations for allocating CSI data sets, see the *System Modification Program Extended: Reference manual, SA22-7772*.

To ensure that the job can be rerun, it deletes (and uncatalogs) the data sets (if they exist) that it allocates later.

This job also sets up the global, target, and distribution zones, depending on the parameters that you specified to the DFHISTAR job, as follows:

1. If you specified NEW for GZONE, the global zone is deleted and redefined.
2. The distribution zone is deleted and redefined.
3. The target zone is deleted and redefined.
4. Member GIMZPOOL from SYS1.MACLIB is REPROed into the zones redefined in the previous steps.
5. If you specified OLD for GZONE, the entries for the DZONE and TZONE names are removed from the global zone.

If the DFHINST3 job terminates abnormally, examine the job log to find the cause, correct the problem, then rerun the job.

The highest expected return code is 0.

The DFHINST4 Job

This job primes the global zone, target zone, and distribution zone.

Before you run the DFHINST4 job

If you did not run the DFHINST2 job, increase the DSSPACE values in the DFHINST4 job, before submitting it.

If the DFHINST4 job terminates abnormally, examine the job log to determine the cause, correct the problem, then repeat all jobs, beginning with DFHINST1. This avoids SMP/E space problems, and consequent X37 abends, during reruns of these SMP/E jobs.

The highest expected return code is 0, if you install into new zones and 8 if you are installing into existing zones.

The DFHINST5 Job

This job RECEIVES the CICS Transaction Server software from the distribution tape into the RELFILE data sets created by the DFHINST2 job. It is the only installation job (apart from the initial IEBCOPY job) that requires the distribution tape to be mounted.

If the DFHINST5 job terminates abnormally, examine the job log to determine the cause, correct the problem, then repeat all jobs, beginning with DFHINST1. This avoids SMP/E space problems, and consequent X37 abends, during reruns of these SMP/E jobs.

The highest expected return code is 0.

The DFHINST6 Job

This job performs the SMP/E APPLY and ACCEPT functions needed to install CICS Transaction Server into the target and distribution libraries respectively.

Before you run the DFHINST6 job

- Ensure the DB2 SDSNLOAD library is available for this job. Without SDSNLOAD, DFHINST6 fails; see “Specify the Data Set Name of the SDSNLOAD Library” on page 37

If you run DFHINST6 with an empty SDSNLOAD library, the APPLY step completes with return code 4, and the return code from the binder is 8. The REXX for CICS modules, CICS SQL and CICDB2, which interface with DB2, are stored in SCICLOAD without the required DB2 routines and are not usable.

- **DFHINST6 must be run on the same MVS image on which the HFS is installed.**

If you have modified the other installation jobs (for example, to use existing libraries and therefore existing target and distribution zones), consider splitting the DFHINST6 job to do APPLY CHECK, APPLY, ACCEPT CHECK, and ACCEPT functions as four separate jobs.

The DFHINST6 job is the longest running of all the installation jobs (see “Run Times of the Installation Jobs” on page 42), and produces a large amount of printed

output. The region size for the DFHINST6 job is currently set to 'REGION=0M'. This is because this job requires more memory than the other install jobs. You may need to adjust your JES parameters (for example, with a JES2 /*JOBPARM LINES=99 statement) to avoid a system abend 722.

This job gives a return code of 4 when all is well. (See the “GIM23903W - LINK SUCCESSFUL . . .” message, listed in the report that is output by the apply job.) DFHINST6 job may issue messages GIM23903W and GIM23913W depending on the execution environment of the installer. Both these messages are acceptable.

The binder produces IEW2454W messages during the APPLY stage for unresolved external references while some CICS Transaction Server load modules are being link-edited during installation, giving return code 4. You may also receive numerous IEW2646W and IEW2651W messages, which are conflicts with user-specified RMODE and AMODEs respectively. You can ignore these IEWxxxx messages, which are output for component object modules of executable CICS Transaction Server load modules.

Messages IEW2689W, IEW2470E, IEW2648E and IEW2303E might be displayed, and can also be ignored.

When you have run the DFHINST6 job, you should see the following SMP/E message in the output from the job:

```
GIM20502I GIMSMP PROCESSING IS COMPLETE - THE HIGHEST RETURN CODE WAS 04 -
```

This SMP/E message can be ignored.

If any other SMP/E messages appear, see the *SMP/E: Messages & Codes* manual for guidance information about their meaning, and take the appropriate action.

If the DFHINST6 job terminates abnormally, examine the job log to determine the cause, correct the problem, then repeat all the jobs, beginning with DFHINST1. This avoids SMP/E space problems, and consequent X37 abends, during reruns of these SMP/E jobs.

Note: If the DFHINST6 job fails and you are using an existing global zone (that is, you specified the GZONE parameter of the DFHISTAR job with the disposition parameter OLD), you must first REJECT the CICS Transaction Server base-level function SYSMOD before rerunning the DFHINST1 job. When you rerun the installation jobs, some steps that were successfully completed in the previous run will produce return codes with a value of '8'.

The DFHIJVMJ Job

This job is provided to create a customized version of member DFHJVMEV from the SDFHENV data set. This dataset contains the JVM environment variables that are needed if you want to run a JVM program in CICS. Information about the JVM environment variables is given in the *CICS System Definition Guide*.

Check the Output from the Installation Jobs

When you have successfully run all of the installation jobs described in this chapter, CICS Transaction Server will have been loaded.

You now have CICS Transaction Server installed on your DASD. Back up the volume on which CICS Transaction Server resides. This avoids the need to re-run the installation jobs if any errors occur during customization later.

What next?

You should next copy the CICS Transaction Server procedures into a cataloged procedure library, load any CICS features that you have, and tailor the CICS Transaction Server to your needs. For information about copying the CICS Transaction Server procedures, and loading the CICS Transaction Server features, see the following topics:

- “Copy the CICS Transaction Server Procedures into a Procedure Library”
- “Create Extra Sets of CICS Transaction Server Target Libraries (Optional)” on page 50
- “Load the CICS Transaction Server Source Material (Optional)” on page 52
- “Load Other Optional Features” on page 53

. For information about tailoring CICS Transaction Server to your needs, see Chapter 27, “Tailoring the CICS-supplied skeleton jobs,” on page 185.

Copy the CICS Transaction Server Procedures into a Procedure Library

CICS Transaction Server supplies the procedures listed in Table 7.

Table 7. CICS Transaction Server-supplied procedures

Procedure	Description
DFHASMVS	Assembles some CICS Transaction Server programs and user-written assembler language programs.
DFHAUPL	Assembles and link-edits CICS Transaction Server control tables, and makes the assembly and link-edit information available to SMP/E. Note: DFHAUPL is installed in SDFHINST.
DFHBMSU	Runs the BMS load module disassemble utility program, DFHBMSUP.
DFHEBTAL	Translates, assembles, and link-edits assembler application programs using EXEC DLI commands in a batch environment under Language Environment.
DFHEITAL	Translates, assembles, and link-edits assembler application programs using the command-level interface.
DFHEXTAL	Translates, assembles, and link-edits assembler application programs using the external CICS Transaction Server interface.
DFHLNKVS	Link-edits CICS Transaction Server programs and application programs.
DFHMAPS	Prepares physical and symbolic maps.
DFHMAPT	Prepares physical and symbolic maps for C++.
DFHSMPE	Executes SMP/E. Note: DFHSMPE is installed in SDFHINST.
DFHSTART	Starts CICS. Note: DFHSTART is installed in SDFHINST.
DFHUPDVS	Updates.
DFHYBTPL	Translates, compiles, and link-edits PL/I application programs using EXEC DLI commands in a batch environment under Language Environment.
DFHYBTVL	Translates, compiles, and link-edits COBOL application programs using EXEC DLI commands in a batch environment under Language Environment.

Table 7. CICS Transaction Server-supplied procedures (continued)

Procedure	Description
DFHYITDL	Translates, compiles, and link-edits C/370™ application programs using the command-level interface under Language Environment.
DFHYITEL	Translates, compiles, and link-edits C++ application programs using the command-level interface under Language Environment.
DFHYITPL	Translates, compiles, and link-edits PL/I application programs using the command-level interface under Language Environment.
DFHYITVL	Translates, compiles, and link-edits VS COBOL application programs using the command-level interface under Language Environment.
DFHYXTDL	Translates, compiles, and link-edits C/370 application programs using the external CICS Transaction Server interface under Language Environment.
DFHYXTEL	Translates, compiles, and link-edits C++ application programs using the external CICS Transaction Server interface under Language Environment.
DFHYXTPL	Translates, compiles, and link-edits PL/I application programs using the external CICS Transaction Server interface under Language Environment.
DFHYXTVL	Translates, compiles, and link-edits VS COBOL application programs using the external CICS Transaction Server interface under Language Environment.
DFHZITCL	Translates, compiles, and link-edits COBOL application programs using the external CICS Transaction Server interface under Language Environment.
DFHZITDL	Translates, compiles, and link-edits XL C application programs using the external CICS Transaction Server interface under Language Environment.
DFHZITEL	Translates, compiles, and link-edits XL C++ application programs using the external CICS Transaction Server interface under Language Environment.
DFHZITFL	Translates, compiles, and link-edits XL C XPLINK programs using the external CICS Transaction Server interface under Language Environment.
DFHZITGL	Translates, compiles, and link-edits XL C++ XPLINK programs using the external CICS Transaction Server interface under Language Environment.
DFHZITPL	Translates, compiles, and link-edits PL/1 application programs using the external CICS Transaction Server interface under Language Environment.
ICCFCC	CICS foundation classes
ICCFCCL	CICS foundation classes
ICCFCGL	CICS foundation classes
ICCFCL	CICS foundation classes
Note:	
For further information about using the CICS Transaction Server-supplied procedures, see:	
<ul style="list-style-type: none"> • The <i>CICS Operations and Utilities Guide</i>, SC34-6431, for information about DFHCRST • “The CICS TS-supplied SMP/E procedure” on page 179, for information about DFHSMPE and DFHSTART • The <i>CICS System Definition Guide</i>, SC34-6428, for information about the other procedures. 	

The procedures DFHAUPLE, DFHSMPE, and DFHSTART are tailored to your CICS Transaction Server environment and stored in the CICSTS31.XDFHINST library when you run the DFHISTAR job. The other procedures are *not* modified by the DFHISTAR job and are copied into the CICSTS31.SDFHPROC library when you run the CICS Transaction Server installation jobs.

You should copy all these procedures into a cataloged procedure library (for example, SYS1.PROCLIB). **Before you copy the procedures**, read the following:

1. Your procedure library may already contain procedures, supplied with an earlier release of CICS, that have the same names as the new procedures but are, in fact, different. If so, you must find some way of selecting the right release. Here are some ways of using the new versions:
 - a. For the time being, rename either set of procedures, and modify the appropriate jobs to use the new names.
 - b. Insert the new procedures into the job streams that use them, and use the procedures as in-stream procedures. The inserted procedures should be placed between the JOB statement and the first EXEC statement. You must insert a // PEND statement after the inserted procedures. When the new release becomes the production system, you can copy the new procedures into your procedure library.
 - c. Indicate the DDNAME of the cataloged procedure library that is to be used to convert the JCL for the job. For example, you could use the JES2 /*JOBPARM PROCLIB=xxxxxxx. For further information about specifying DDNAMEs in JCL, see the *MVS/ESA JCL Reference* manual.
2. If service is applied to the CICS Transaction Server procedures, it is the versions in the libraries CICSTS31.CICS.SDFHINST and CICSTS31.CICS.SDFHPROC that will be updated by SMP/E. You must then copy the updated procedures into your procedure library.
3. The default for the symbolic parameter GZONE in the procedures DFHSMPE and DFHAUPLE is taken from the value that you specified by the GZONE parameter of the DFHISTAR job.
4. The default for the ZNAME symbolic parameter in the procedures DFHSMPE and DFHAUPLE is taken from the value that you specified by the TZONE parameter of the DFHISTAR job. For a description of how the ZNAME parameter is used, see the SMP_CNTL DD statement in “The CICS TS-supplied SMP/E procedure” on page 180.
5. Change the OUTC parameter as required.

When you have read these notes, and acted on them as necessary, copy the procedures into a cataloged procedure library.

Create Extra Sets of CICS Transaction Server Target Libraries (Optional)

You can use the CICS Transaction Server installation job, DFHISTAR, to generate an optional installation job, DFHINSTA, which you can use to create extra copies of the CICS Transaction Server target libraries and UNIX System Services directories.

Some of the benefits of using multiple libraries are:

- **Backing out PTFs and APARs** - if you apply PTFs or APARs to CICS Transaction Server and if they fail a fix-test, you can back out the changes with minimum disruption.
- **DASD failure** - multiple libraries protect you against failure of the DASD on which the CICS Transaction Server load libraries reside.

Base the decision to use multiple libraries for CICS Transaction Server on the following factors:

- Your need for high availability - as already stated, the use of multiple libraries can protect you against CICS Transaction Server downtime due to DASD failure or incorrect service (either from IBM-supplied PTFs or your own modifications to your CICS Transaction Server region).
- The extra DASD needed - multiple libraries require more disk space.
- Other ways of providing high availability; for example, use of a CICSplex, VTAM persistent sessions, and MVS functions to provide restart of CICS Transaction Server regions.
- The added complexity of maintaining multiple sets of CICS Transaction Server libraries - two or more sets of CICS Transaction Server target libraries, together with the SMP/E procedures needed to support them, increase the complexity of maintenance. You will need to define procedures to ensure that upgrades to the CICS Transaction Server libraries are kept under control.
- Alternative solutions - if you have already established a proven process for fix verification and for testing applications developed for your production CICS Transaction Server region, you may decide you don't need multiple CICS Transaction Server libraries.

You can use the DFHINSTA job, generated by the DFHISTAR job, to create extra sets of CICS Transaction Server target libraries fully under the control of SMP/E. Each time you run the DFHINSTA job, you can only generate one extra set of target libraries.

To create an extra sets of target libraries, you should complete the following steps. You can repeat the steps to create more sets of target libraries.

1. Edit the DFHISTAR job to specify values for:

- The ADDTVOL, AINDEX, ASMPSCDS, AZONE, AZONECSI, AZONELOG, and USSDIRA parameters, for the new set of target libraries.
- The INDEX, TZONE, TZONECSI, and TZONELOG parameters, for the primary target libraries you want to copy from. (The TZONE, TZONECSI, and TZONELOG parameters must specify the target zone that contains the CICS Transaction Server target libraries defined with the high-level qualifier provided by the INDEX parameter.)
- The DZONE, DZONECSI, and DZONELOG parameters, for the distribution libraries to be associated with the new set of target libraries.
- The SELECT parameter, to specify DFHINSTA (that you want to copy) and the member name you want the generated version of DFHINSTA to be stored as in the CICSTS31.XDFHINST library. For example,

```
SELECT DFHINSTA INSTA111
```

will store the generated version of DFHINSTA into member INSTA111 of the CICSTS31.XDFHINST library when you submit the DFHISTAR job.

Each time you copy DFHINSTA (to create a new set of target libraries), you should specify a new name on the SELECT parameter (to save each copy with a different name in case you need it again in the future).

For further information about editing the DFHISTAR job, and about the parameters of the DFHISTAR job, see "Edit the DFHISTAR Job" on page 17. The other parameters in the DFHISTAR job should not be changed.

2. Submit the DFHISTAR job

When you run the DFHISTAR job, it saves the generated version of the DFHINSTA job in the CICSTS31.XDFHINST library with the member name

specified on the SELECT parameter in the DFHISTAR job. The data set name of the CICSTS31.XDFHINST library is specified in the LIB parameter of the DFHISTAR job.

3. Consider running the DFHIHFSA job

If you decide to create an additional SMP/E target zone using job DFHINSTA, run the DFHIHFSA job first before running the DFHINSTA job. DFHIHFSA creates an additional SMP/E target zone for HFS. This job:

- Unmounts the HFS at directory */pathprefix/usr/lpp/cicsts/ussdir* to allow the job to rerun, and if necessary forces return code 0.
- Deletes the *ussdira* directory at */pathprefix/usr/lpp/cicsts*, where *ussdira* is the name of the directory specified on the **ussdira** parameter in the DFHISTAR job. This allows the job to rerun, and if necessary forces return code 0.
- Deletes the HFS specified in the HFSADSN parameter of the DFHISTAR job to allow the job to rerun, and if necessary forces return code 0.
- Creates the HFS specified in the HFSADSN parameter of the DFHISTAR job
- Creates the *ussdira* directory at */pathprefix/usr/lpp/cicsts*, where *ussdira* is the name of the directory specified in the **ussdira** parameter in the DFHISTAR job
- Mount the HFS at directory */pathprefix/usr/lpp/cicsts/ussdira*
- Changes the permission settings for the *ussdira* directory to 775

All steps of this job must end with return code zero for the job to be successful

CICS requires the MOUNT issued by DFHIHFSA to access files stored in the HFS, but the MOUNT command is lost when you re-IPL MVS. SDFHINST member DFHBPXPA contains a MOUNT command for */pathprefix/usr/lpp/cicsts/ussdira*. Copy this command into a BPXPRMxx member of the SYS1.PARMLIB dataset to ensure the mount is restored when MVS is IPLed.

4. Submit DFHINSTA

The DFHINSTA job (or a copy of it) copies the CICS Transaction Server target libraries specified by the INDEX parameter, and creates corresponding CICS Transaction Server SMP/E data sets for them. In particular, it allocates a new SMP/E CSI data set for the extra target zone.

So that DFHINSTA job can be run more than once, step 1 deletes previous copies of the data sets to be created. Step 3 deletes the SMP/E CSI data set. Step 6 removes the ZONEINDEX entry for the extra target zone.

The first time the DFHINSTA job is run, Step 6 will give the following messages:

```
GIM35701E ** ZINDEX SUBENTRY azone WAS NOT DELETED BECAUSE
                IT DOES NOT EXIST.
GIM25601I      THE SPECIFIED ENTRY WAS NOT UPDATED BECAUSE OF
                AN ERROR DURING UCLIN PROCESSING.
```

You can ignore these messages the first time the job is run.

Load the CICS Transaction Server Source Material (Optional)

You can use the sample job, DFHOPSRC, to load the optional CICS Transaction Server source from the distribution tapes. The DFHOPSRC job is generated in the CICSTS31.XDFHINST library when you run the DFHISTAR job.

The DFHOPSRC job runs the MVS IEBCOPY utility program to load the optional source data sets from the tapes into a single DASD data set.

For further information about the IEBCOPY program, see the *MVS/ESA Data Administration: Utilities Manual* (SC26-4516).

Note: The DFHOPSRC job loads the tape files to a DASD device of your choice, using a BLKSIZE parameter of 6160. You can specify a different BLKSIZE parameter on the DCB and SPACE statements if you want, in which case the space allocation should be reviewed (It may need to be changed.).

Load Other Optional Features

The sample job, DFHINSTJ, is supplied to be used to load other optional features that may be supplied. CICS Transaction Server V2R3 contains no optional features at General Availability time, but the sample job may be used if any optional features are shipped at a later date. The DFHINSTJ job is generated in the CICSTS31.XDFHINST library when you run the DFHISTAR job.

Activating CICS Transaction Server

After you have loaded CICS Transaction Server to disk, you should perform the following steps:

1. (If needed) Apply service, see Chapter 26, “Applying service to CICS Transaction Server for z/OS,” on page 179
2. Integrate CICS Transaction Server with MVS, see Part 2, “Setting up the MVS environment for CICS,” on page 65
3. Create CICS Transaction Server system data sets, see Chapter 28, “Creating the CICS data sets,” on page 189
4. (Optional) Install CICS-DATABASE 2 support, see Chapter 29, “Defining DL/I support,” on page 197
5. (Optional) Install MRO and ISC support, see Chapter 32, “Installing MRO and ISC support,” on page 211
6. (Optional) Run the installation verification procedures (IVPs), see Chapter 35, “Running the installation verification procedures,” on page 227.

Information about how to get CICS Transaction Server into operational status, is also included as part of the process of verifying the installation, see Chapter 35, “Running the installation verification procedures,” on page 227.

Checklist for the CICS Transaction Server for z/OS Installation

Table 8. CICS Transaction Server installation checklist

Step	Done?	Description	See page
1		Check that you have received the material that you ordered.	N/A
2		Check that you have all the installation prerequisites,	See the <i>Program Directory</i>
3		Copy RELFILE(2) from the distribution tape. (Record your name for the TDFHINST library: _____)	See the <i>Program Directory</i>
4		Edit the DFHISTAR job in the TDFHINST library	17
4.1		Specify the CICS Transaction Server temporary installation libraries	20
4.2		Specify the JOB parameters for installation jobs	20
4.3		Specify the scope of the installation	21
4.4		Specify the type of JES to be used	21
4.5		Specify the utilities to be used	21
4.6		Specify the prefix of CICS Transaction Server jobs	22

Table 8. CICS Transaction Server installation checklist (continued)

Step	Done?	Description	See page
4.8		Specify the prefix of the CSSLIB library	35
4.9		Specify the prefix of the SISpload library	35
4.10		Specify the indexes of CICS Transaction Server data sets	22
4.11		Specify block sizes	24
4.13		Specify the disk unit for work data sets	24
4.14		Specify disk volumes	25
4.15		Allocate the space for CICS Transaction Server disk volumes	28
4.16		Specify SMP/E zone attributes	30
4.17		Specify attributes of the temporary SMP/E work data sets	28
4.18		Specify attributes of the permanent SMP/E data sets	29
4.19		Specify the high-level qualifiers for SMP/E data sets	33
4.20		Specify the HFS directories and data sets	23
4.21		Specify the distribution tape device type	33
4.22		Specify attributes of the CICS Transaction Server system data sets	33
4.23		Specify attributes of any additional target libraries	34
5		Create RACF profiles for the CICS Transaction Server data sets	39
6		Run the DFHISTAR job	39
6.1		Check the output from the DFHISTAR job	40
7		Check that you are ready to run the installation jobs	41
8		Run the installation jobs	42
8.1		Check the output from the installation jobs	47
9		Copy the CICS Transaction Server procedures into a procedure library	48
10		Create any extra sets of CICS Transaction Server target libraries (optional)	50
11		Load the CICS Transaction Server optional source material (optional)	52
12		Load the Japanese national language feature (optional)	53

Chapter 4. Post-installation requirements

The main task after installing CICS TS is to prepare the z/OS environment so that you can run the CICS and CICSplex SM installation verification procedures (IVPs). These procedures start a CICS test region and the CICSplex SM starter-set of regions. For example, you cannot bring up a CICS TS region unless you install the required CICS modules in the MVS link pack area (LPA) and include others in the MVS linklist.

This chapter outlines the main steps and points you to where you can find more information to help you complete these tasks.

Implementing changes in your z/OS environment for CICS

If you are an existing CICS user and are planning to migrate to CICS Transaction Server for z/OS, Version 3 Release 1 in an established z/OS environment, most of the tasks described here will already have been done. In this case, review the following steps to check whether you need to make any changes. If you are setting up a new z/OS environment, perhaps on new hardware, you need to ensure that the required support for CICS is in place.

The following is a summary of the steps to follow to enable your z/OS environment to support CICS:

APF-authorize SDFHAUTH

Define the CICSTS31.CICS.SDFHAUTH library as an APF-authorized library. See “APF-authorizing CICS SDFHAUTH library” on page 56 for details.

Authorize CICS regions userids

Authorize to RACF each CICS region userid to permit access to the required MVS resources. See “Authorizing CICS region userids to RACF” on page 56 for details.

Note: It is assumed that the CICS TS libraries you have installed, and other MVS resources, are protected by RACF, or an equivalent external security manager (ESM).

Add SDFHLINK to LNKLST

Include the CICS linklist library, CICSTS31.CICS.SDFHLINK, in the MVS LNKLST concatenation.

Define CICS as a subsystem

Define CICS as an MVS subsystem if you intend using multiregion operation (MRO), the CICS console message-handling facility, or MVS workload management.

Define and install the CICS Type 3 SVC

Define the DFHCSVC module to MVS.

Schedule an IPL to install the CICS SVC routine, DFHCSVC, and other CICS-required modules in the MVS link pack area (LPA).

Review requirement for HPO

Ensure the DFHHPSVC module is included in the MVS nucleus if you are going to use the VTAM high-performance option (HPO), and ensure the HPO SVC is defined as a Type 6 SVC in the appropriate MVS IEASVCxx PARMLIB member.

Define VTAM APPLs for CICS TORs

Define to VTAM each CICS region that requires VTAM support (for example, all

your terminal-owning regions) and also ensure that any VTAM terminal definitions are properly specified for connection to CICS.

Defining VTAM APPL definitions for CICS application-owning regions (AORs) is optional.

Define log streams

Define the minimum logging environment for CICS system logs.

Install ASR exit for SYMREC macro support

Install an MVS ASR exit to enable CICS to use the SYMREC macro call.

Each of these tasks is discussed in more detail in the following sections.

There are also some optional tasks that you may need to perform at a later stage, but these are not essential to the initial install and operation of a basic CICS system. These tasks are connected with facilities such as VSAM record-level sharing, MVS automatic restart management, and MVS performance.

APF-authorizing CICS SDFHAUTH library

Add the CICS SDFHAUTH library to the list of APF-authorized libraries in the appropriate PROGxx (or IEAAPFxx) member in SYS1.PARMLIB. The SDFHAUTH library must be APF-authorized to enable certain CICS modules, such as DFHSIP, to run in supervisor state.

If your list(s) of APF-authorized libraries are specified in the dynamic format (in a PROGxx member), refresh the APF list dynamically using the SETPROG or SET PROG=xx command.

If your list(s) of APF-authorized libraries are specified in the static format (in IEAAPFxx members), schedule an MVS IPL for the APF-authorization to take effect.

For information about maintaining lists of APF-authorized libraries, see the *z/OS MVS Initialization and Tuning Reference*.

Authorizing CICS region userids to RACF

Ensure each CICS region userid (the userid under which a CICS region runs) has the required authority (READ, UPDATE, CONTROL, or ALTER) to access the various protected resources it needs to use. These include load libraries and other data sets, coupling facility structures, the VTAM ACB, and so on.

The resources for which you need to ensure access are:

Load libraries

The CICS load libraries, CICSTS31.CICS.SDFHAUTH and CICSTS31.CICS.SDFHLOAD. All CICS regions should have READ authorization to these data sets.

VTAM ACB

A VTAMAPPL general resource class profile protects a CICS region's APPLID. Each region userid should have READ authorization to its own VTAMAPPL profile.

SMSVSAM servers

A SUBSYSNM general resource class profile protects an SMSVSAM server. Each CICS region that opens an SMSVSAM control ACB during initialization must have READ authorization to a SUBSYSNM profile named with its own CICS APPLID.

MVS log streams

A LOGSTRM general resource class profile protects an MVS log stream. Each CICS region requires at least UPDATE authorization to its own system log LOGSTRM profile. If you expect a CICS region to create dynamically its log stream, it needs ALTER authority.

#

Data set services module ADDRRLVL

A PROGRAM general resource class profile may be used to protect access to the DFSMSdss module, ADDRRLVL. CICS links to this ADR module during initialization as part of its check on backup-while-open (BWO) support. Ensure CICS has READ access to this module if it is a protected resource in your MVS environment.

CICS category 1 transactions

The general resource class GCICSTRN (or TCICSTRN) protect all transactions, including CICS system transactions. Each CICS region requires READ authorization to the list of category 1 transactions as defined in member DFH\$CAT1 in the CICS SDFHSAMP samples library.

When you have defined the required authorizations for CICS regions in the RACF data base, activate the various resource classes with the RACF SETROPTS command.

Adding SDFHLINK to the MVS LNKLST

CICS provides a number of modules that are intended for use from the MVS LNKLST. These are supplied in the SDFHLINK library, and are in two categories:

1. CICS-supplied modules used by non-CICS jobs
2. Modules that must be consistent across several CICS regions.

Add the CICS SDFHLINK library to the MVS LNKLST concatenation. Note that many of the modules in SDFHLINK can only be used from an APF-authorized library, and therefore SDFHLINK also needs to be APF-authorized.

Note: CICS also loads some non-CICS modules, and these should also be made available through a library included in the LNKLST.

Defining CICS as an MVS subsystem

Define CICS as an MVS subsystem in an IEFSSNxx member of SYS1.PARMLIB if you plan to use any of the following CICS facilities:

- Multiregion operation (MRO)
- The console message-handling facility
- MVS workload management.

Defining and installing the CICS Type 3 SVC

Install the CICS TS Version 2 level of the CICS Type 3 SVC module, DFHC SVC, before you attempt to start a CICS region. To make the CICS Type 3 SVC ready for use:

1. Define the CICS SVC as a Type 3 SVC in the appropriate MVS IEASVCxx PARMLIB member. For example, to use the CICS default SVC number, add the following statements to the IEASVCxx:
`SVC Parm 216, REPLACE, TYPE(3), EPNAME(DFHC SVC)`
2. Include the CICS LPA library, SDFHLPA, in the MVS LPALST concatenation.
3. If you define to MVS an SVC number other than the default (216), specify the SVC number to CICS on the CICSSVC system initialization parameter.

CICS contains a test to verify that it is using the correct release level of the CICS DFHCSVC module. If CICS calls an SVC module using the SVC number specified on the CICSSVC system initialization parameter, and the module is not at the current level, CICS issues message DFHKE0104.

Reviewing the high-performance option

The high-performance option (HPO) is provided for users who want to optimize terminal response times and maximize transaction throughput. This option requires the CICS Type 6 SVC module, DFHHPSVC, to be included in the MVS nucleus. To help you decide on the use of HPO, see the *CICS Performance Guide*. If you decide to use this option, follow the steps described in Chapter 12, “Selecting the high-performance option,” on page 97.

Defining CICS regions as applications to VTAM

Define each CICS terminal-owning region to VTAM as a VTAM application—that is, as a VTAM application program major node (APPL). To do this, add the required APPL definition statements to a member of SYS1.VTAMLST. For example:

```
* APPL definition for CICS region CICSHTH1
*****
CICSHTH1 APPL AUTH=(ACQ,VPACE,PASS),VPACING=0,EAS=5000,PARSESS=YES X
          SONSCIP=YES
*****
```

Note: Specify the VTAM APPL name to CICS on a CICS APPLID system initialization parameter.

Also ensure that your VTAM terminals are properly defined for connection to CICS. This is particularly important if you intend using the CICS autoinstall function. For those terminals for which you want to use autoinstall, code VTAM LOGON mode table entries that correspond to the model TYPETERM/TERMINAL definitions defined to CICS. You can either code your own autoinstall models, or use the CICS-supplied model definitions that are generated for you when you initialize the CICS system definition data set (CSD).

For programming information about matching VTAM LOGMODE definitions with CICS model definitions, see the *CICS Customization Guide*.

For information about defining model and VTAM terminal definitions to CICS, see the *CICS Resource Definition Guide*.

Defining log streams

CICS automatically connects to its system log stream, unless you define a journal model resource definition to define the log stream as TYPE(DUMMY).

Each CICS region has only one system log, which is implemented as two MVS system logger log streams. These are used by CICS as the primary and secondary system log streams and together these form a single logical log stream. Thus, as a default each CICS region requires a minimum of two log streams.

Initially, you are recommended to define to the MVS system logger some model log streams, and let CICS create the system log streams dynamically. If you plan to use a coupling facility for CICS logging, you must also define the log structures required for the log streams. To get you started, however, using DASD-only log streams is

quicker and easier to define. Later, when you have more information available, you can plan to define coupling facility log structures with explicit log streams tailored to your requirements.

Define MVS model log streams using the naming convention that enables CICS to create log streams dynamically. Model names should be of the form *mvs_sysid*.DFHLOG.MODEL and *mvs_sysid*.DFHSHUNT.MODEL, where *mvs_sysid* is the system name of the MVS image in which the CICS region runs.

Example: If a CICS region, running in an MVS image with a sysid of MV10, issues a create log stream request for its primary log stream, the system logger requires a model log stream named MV10.DFHLOG.MODEL.

Running without a system log

You can define a CICS JOURNALMODEL resource definition with TYPE(DUMMY) to avoid having to define log streams. If you want to run the IVPs with the minimum effort, here's what to do:

- Define JOURNALMODEL resource definitions in the CSD for the primary and secondary system logs, DFHLOG and DFHSHUNT respectively, specifying TYPE(DUMMY); see Figure 3 for a sample job.
- Add the CSD group containing your dummy system log journal models to your own group list, and include your group list on the GRPLIST system initialization parameter.

Note that your group list must *follow* the IBM-supplied list, DFHLIST. DFHLIST includes group DFHLGMOD (which contains DFHLOG and DFHSHUNT JOURNALMODEL definitions) but concatenating your list after DFHLIST ensures that your DUMMY definitions replace the IBM definitions.

```
//CSDLGSTR JOB 1,BELL,MSGCLASS=A,MSGLEVEL=(1,1),CLASS=A
//CSDUP EXEC PGM=DFHCSDUP,REGION=1M,PARM='CSD(READWRITE)'
//STEPLIB DD DSN=CICSTS31.CICS.SDFHLOAD,DISP=SHR
//DFHCSD DD DSN=CICSTS31.CICS.CICSH###.DFHCSD,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSABOUT DD SYSOUT=*
//SYSABEND DD SYSOUT=*
//SYSUDUMP DD SYSOUT=*
//SYSIN DD *
*
* DEFINE JOURNAL MODELS FOR CICS LOG STREAMS AS DUMMY
*
DEFINE JOURNALMODEL(DFHLOG) GROUP(LOGTEST)
DESCRIPTION(DEFINE SYSTEM LOG AS DUMMY)
 JOURNALNAME(DFHLOG)
 TYPE(DUMMY)
*
DEFINE JOURNALMODEL(DFHSHUNT) GROUP(LOGTEST)
DESCRIPTION(DEFINE SYSTEM LOG AS DUMMY)
 JOURNALNAME(DFHSHUNT)
 TYPE(DUMMY)
/*
//
```

Figure 3. Sample job to define DUMMY JOURNALMODELs for CICS system logs

MVS ASR exit

A CICS program may call the first failure symptoms (FFS) component. This uses the MVS SYMREC macro to write a symptom record to the MVS SYS1.LOGREC dataset.

Install an MVS ASR exit to enable CICS to use the SYMREC macro call, otherwise the FFS call fails. For more information, see the *z/OS MVS Installation Exits* manual.

Planning for CICSplex SM

CICSplex SM provides both some basic IVPs and a CICSplex SM starter set:

- See the *CICSplex SM Concepts and Planning* manual, SC34-6459, for details of the CICSplex SM starter set.
- See Part 6, “CICSplex SM verification,” on page 405 for details of the IVPs.

You are recommended to run the basic IVPs and the CICSplex SM starter set before moving into a test environment.

Planning for CICSplex SM migration

If you are already a CICSplex SM user, plan and complete your migration to CICSplex SM before migrating your CICS regions.

CICS TS Version 3 CICSplex SM can manage CICS regions running under the following releases of CICS:

- CICS Transaction Server for z/OS Version 3
- CICS Transaction Server for z/OS Version 2
- CICS Transaction Server for OS/390 Version 1
- IBM CICS for MVS/ESA Version 3.3 and later
- IBM CICS for VSE/ESA Version 2.2 and later
- IBM CICS for OS/2 Version 2.0.1 and Version 3.0
- CICS/MVS Version 2.1.2

For detailed information about migrating to the CICS Transaction Server for z/OS Version 3 level of CICSplex SM, see the *CICS Transaction Server for z/OS Migration from CICS TS Version 2.3*.

Parallel Sysplex considerations

Although a coupling facility is not required to operate CICS TS, you may want to install CICS TS in a Parallel Sysplex® environment. For information about the hardware and software requirements for a Parallel Sysplex, see the *z/OS MVS Setting Up a Sysplex*, SA22-7625.

Chapter 5. Installing the CICS Information Center

The CICS Information Center runs in an Eclipse framework, commonly known as a *help system*, and consists of a number of documentation plug-ins, including various tools and connectors. The information center is supplied on CD-ROM with a readme. The readme file contains a complete list of all the plug-ins that are provided, and you can select which plug-ins to install based on your CICS environment. If you already have an Eclipse help system, or an Eclipse-based IDE such as WebSphere® Studio Enterprise Developer, you can opt to install only the CICS documentation plug-ins. You can run the information center locally on a workstation, or as a server with remote access. Before you begin to install the information center, read the following topics:

- “Requirements”
- “Installing the information center on a workstation”
- “Installing the information center on a server” on page 62
- “Installing the CICS plug-in in an Eclipse IDE or help system” on page 63

Requirements

The information center is supported on the following platforms:

- Windows 2000
- Windows XP
- AIX® 5.2 and 5.3
- Linux® RedHat Enterprise 3.0
- Linux SuSE Enterprise 3.0
- Linux RedHat Enterprise 8 and 9 for zSeries®
- Linux SuSE Enterprise 8 and 9 for zSeries
- z/OS 1.4 or later

Please note that support for the information center on Linux for zSeries and z/OS is only offered in server mode for remote access using a browser.

The information center uses a JRE. A JRE for each platform is provided with the information center, except for z/OS. If you want to run an information center on z/OS, you need to use the JRE provided with the operating system.

To get the best results when viewing the information center, it is recommended that you use one of the following browsers:

- Microsoft® Internet Explorer 6.0
- Mozilla 1.7

To view PDF documents within the information center, you require Adobe Acrobat Reader 4.05 or higher installed, and the Acrobat Web plug-in installed in your browser.

Installing the information center on a workstation

The information center can run locally from any directory on your workstation. If you do not have an Eclipse help system, you will need to install this first as it is required to run the information center. If you do have an Eclipse help system, see “Installing the CICS plug-in in an Eclipse IDE or help system” on page 63.

1. Select the appropriate folder for your operating system on the CD-ROM. This folder contains a zip file of the Eclipse help system.
2. Unzip the zip file to a new directory on your workstation. This creates an eclipse help system on your workstation.
3. Select the plug-ins folder on the CD-ROM. This folder contains all of the documentation plug-ins.
4. Copy the documentation plug-ins you require to the eclipse\plugins directory of the help system that you have just unzipped. The readme contains a complete list of the plug-in names and the products they refer to. It is recommended that you copy the CICS TS plug-in `com.ibm.cics.ts.doc`, the CICS support plug-in `com.ibm.cicsts.doc`, and associated support plug-ins `com.ibm.support.core.doc` and `com.ibm.support.core.doc.nl`.
5. At the highest directory level in your Eclipse help system, execute the file `IC_local_Start` to start the information center on your workstation. This should automatically launch a browser and display the information center.

Please note that you cannot run the information center locally on z/OS 1.4 or the Linux for z/OS platforms.

Installing the information center on a server

Running the information center on a server requires you to allocate a specific port number, to allow remote access using a browser. You can run the information center in server mode on any of the supported platforms listed in “Requirements” on page 61. If you already have a help system installed, see “Installing the CICS plug-in in an Eclipse IDE or help system” on page 63 for information on how to install just the CICS documentation plug-ins. To install the information center on UNIX, Linux and Windows servers, follow these steps:

1. Select the appropriate folder for your operating system on the CD-ROM. This folder contains a zip file of the Eclipse help system.
2. FTP the zip file to an appropriate directory on your server and then unzip it. This creates a help system on your server.
3. Select the plug-ins folder on the CD-ROM. This folder contains all of the documentation plug-ins.
4. Use the readme on the CD-ROM to select which documentation plug-ins you want to install. Copy the required plug-ins to the eclipse\plugins directory of the help system that you unzipped. It is recommended that you copy the CICS TS plug-in `com.ibm.cics.ts.doc`, the CICS support plug-in `com.ibm.cicsts.doc`, and associated support plug-ins `com.ibm.support.core.doc` and `com.ibm.support.core.doc.nl`.
5. At the highest directory level in your Eclipse help system, edit the file `IC_server_start` to specify the port number that you want the information center to use. The default is 29127.
6. Execute the file `IC_server_start` to start the information center in server mode.
7. To verify that you can access the information center, start up a browser and type the URL `http://\servername:port`, where *servername* is the name of the server where you installed the information center and *port* is the port number that you specified in the start up file.

The information center runs in the UNIX System Services (USS) component of z/OS. To install the information center on z/OS, follow these steps:

1. Select the z/OS folder on the CD-ROM, which contains a tar file of the Eclipse help system.

2. FTP the tar file to a suitable HFS directory in USS.
3. Un-tar the file using the command `tar -xvf filename`. This creates a help system on your server.
4. Select the plug-ins folder on the CD-ROM. This folder contains all of the documentation plug-ins.
5. Use the readme on the CD-ROM to select which documentation plug-ins you want to install. FTP the required plug-ins to the `eclipse\plugins` directory of the help system that you unzipped. It is recommended that you copy the CICS TS plug-in `com.ibm.cics.ts.doc`, the CICS support plug-in `com.ibm.cicsts.doc`, and associated support plug-ins `com.ibm.support.core.doc` and `com.ibm.support.core.doc.nl`.
6. At the highest directory level in your Eclipse help system, edit the file `IC_server_start.sh` to specify the directory path of a JRE at 1.4.2 that you want the information center to use. You can also change the port number from the default of 29127. Use the command `vi IC_server_start.sh` to open the file to edit it, or if connected through TSO you can use the command `oedit IC_server_start.sh`. Add the following command to the beginning of the file, using the appropriate path to the JRE. For example, you could specify:

```
export PATH=/u/lpp/java142/J1.4/bin:$PATH
```
7. Execute the start file using the command `./IC_server_start.sh &`. The `&` indicates that the information center should run as a background task. This means that if you log off, the information center will continue to run on the server.
8. To verify that you can access the information center, start up a browser and type the URL `http://servername:port`, where *servername* is the name of the server where you installed the information center and *port* is the port number that you specified in the start up file.

Installing the CICS plug-in in an Eclipse IDE or help system

If you already have an Eclipse help system installed on your workstation or server, or if you are using an Eclipse-based product such as WebSphere Studio Enterprise Developer, you can install the CICS documentation and run it within your existing software. Ensure that you shut down your help system or product before adding the CICS documentation plug-ins. Otherwise Eclipse will not recognize the newly added plug-ins. Follow these steps:

1. Select the plug-ins folder on the CD-ROM. This folder contains all of the documentation plug-ins.
2. Use the readme on the CD-ROM to select which documentation plug-ins you want to install. It is recommended that you copy the CICS TS plug-in `com.ibm.cics.ts.doc`, the CICS support plug-in `com.ibm.cicsts.doc`, and associated support plug-ins `com.ibm.support.core.doc` and `com.ibm.support.core.doc.nl`.
3. Copy the required documentation plug-ins to the `eclipse\plugins` directory of the help system or Eclipse IDE that you already have installed. For example, for a default installation of WebSphere Studio Enterprise Developer, you would copy the plug-ins to the directory `C:\Program Files\IBM\WebSphere Studio\eclipse\plugins`.
4. Start up the help system or Eclipse IDE to ensure that the CICS documentation is present.

Part 2. Setting up the MVS environment for CICS

The information about ACF/VTAM, MVS, RACF and other products given in this part is for guidance only. Always consult the current publications of the other products for the latest information. See “Books from related libraries” on page 469.

Note: “RACF” is used throughout this book to mean the MVS Resource Access Control Facility (RACF) or any other external security manager that provides equivalent function. The advice about using RACF applies only if you have security active in your system. If so, you must use an external security manager (such as RACF).

This part discusses what you should do after you have loaded the CICS Transaction Server elements to DASD, and before you run CICS. It contains the following chapters:

- Chapter 6, “Authorizing the hlq.SDFHAUTH library,” on page 67.
- Chapter 7, “Authorizing CICS regions to access MVS resources,” on page 69.
- Chapter 8, “Defining the default CICS userid to RACF,” on page 77.
- Chapter 9, “Installing CICS-required modules in the MVS linklist,” on page 79.
- Chapter 10, “Defining CICS as an MVS subsystem,” on page 83.
- Chapter 11, “Installing the CICS Type 3 SVC,” on page 93.
- Chapter 12, “Selecting the high-performance option,” on page 97.
- Chapter 13, “Defining CICS regions as applications to VTAM,” on page 99.
- Chapter 14, “Installing CICS modules in the MVS link pack area,” on page 107.
- Chapter 15, “Defining CICS IPCS exit control data to MVS,” on page 121.

The following chapters discuss the MVS definitions required for optional CICS functions.

- Chapter 16, “MVS Program properties table entries,” on page 123.
- Chapter 17, “MVS performance definitions,” on page 125.
- Chapter 18, “MVS automatic restart management definitions,” on page 127.
- Chapter 19, “MVS cross-system MRO definitions,” on page 129.
- Chapter 20, “PR/SM policy for handling MVS failures,” on page 131.
- Chapter 21, “MVS ASREXIT - SYMREC Authorization Exit,” on page 133.
- Chapter 22, “Definitions required for VSAM RLS support,” on page 135.
- Chapter 23, “Console messages,” on page 141.
- Chapter 24, “Defining the logger environment for CICS journaling,” on page 143.
- Chapter 25, “Enabling Unicode data conversion by z/OS,” on page 177.
- Chapter 26, “Applying service to CICS Transaction Server for z/OS,” on page 179.

Chapter 6. Authorizing the hlq.SDFHAUTH library

These instructions apply to the *hlq.SDFHAUTH* library, but if you require Java support, you should authorize the *hlq.SDFJAUTH* library in the same way. See “Authorizing the *hlq.SDFJAUTH* library” on page 210 for more information about that library.

Although, in general, CICS runs in problem state, the CICS initialization program, DFHSIP, needs to run in supervisor state for part of its execution.

For a module to be able to run in supervisor state, it must be link-edited as an authorized module into a partitioned data set, which must also be defined to the operating system as APF-authorized. For CICS-supplied modules, the link-editing has been done for you. The CICS-supplied DFHSIP module is link-edited with the **authorized** attribute (using SETCODE AC(1)), and is installed in the *hlq.SDFHAUTH* library.

APF-authorize the *hlq.SDFHAUTH* library by adding it to the list of APF-authorized libraries in the appropriate PROGxx (or IEAAPFxx) member in SYS1.PARMLIB. The *hlq.SDFHAUTH* library must be APF-authorized to enable certain CICS modules, such as DFHSIP, to run in supervisor state.

If your list(s) of APF-authorized libraries are specified in the dynamic format (in a PROGxx member), refresh the APF list dynamically using the SETPROG or SET PROG=xx command.

If your list(s) of APF-authorized libraries are specified in the static format (in IEAAPFxx members), schedule an MVS IPL for the APF-authorization to take effect.

For information about maintaining lists of APF-authorized libraries, see the *z/OS MVS Initialization and Tuning Guide*.

When you prepare your startup job stream, provide a STEPLIB DD statement for the *hlq.SDFHAUTH* library. When you define your STEPLIB DD statement, remember that all other libraries concatenated with the *hlq.SDFHAUTH* library must also be APF-authorized. This is because, if any of the libraries in a STEPLIB concatenation are not authorized, MVS regards all of them as unauthorized.

The *hlq.SDFHLOAD* library contains only programs that run in problem state, and should **not** be authorized. The *hlq.SDFHLOAD* library must be included in the CICS DFHRPL library concatenation. There is an example of this library DD statement in the sample job stream provided in the *CICS System Definition Guide*.

For information about authorizing access to CICS data sets, see the *CICS RACF Security Guide*.

Chapter 7. Authorizing CICS regions to access MVS resources

You should consider authorizing access to the following when planning your security requirements to run CICS:

CICS PDS libraries

Protect your CICS data sets that use RACF. See “Protecting CICS load module data sets.”

VTAM ACB

Authorize each CICS region userid to OPEN the VTAM ACB for the region’s specified APPLID. See “Authorizing access to a CICS region’s VTAM ACB” on page 70.

CICS system transactions

Authorize each CICS region userid to access the CICS category 1 system transactions. See “Authorizing the region userid to access category 1 transactions” on page 71.

SMSVSAM server

Authorize each CICS region to open the SMSVSAM control ACB if you plan to use CICS with VSAM record-level data sharing. See “Authorizing access to an SMSVSAM server” on page 71.

System logger log streams

Authorize each CICS region userid to access the MVS system logger log streams that are used by CICS. See “Authorizing access to MVS log streams” on page 72.

z/OS UNIX System Services

Include an OMVS segment in the CICS region's user profile, specifying the UID parameter, to ensure that your CICS regions have the required access to z/OS UNIX system services. See “Authorizing CICS region userids to z/OS UNIX System Services” on page 74.

RACF resource classes

Activate the appropriate RACF resource classes to enable terminal users to access CICS resources and user-defined resources. See “Activating RACF resource classes” on page 75.

Protecting CICS load module data sets

To prevent unauthorized or accidental modification of *hlq.SDFHAUTH* or *hlq.SDFJAUTH*, you should RACF-protect these libraries. Without such protection, the integrity and security of your MVS system are at risk. Additionally, if you require protection against the unauthorized use of DFHSIP, do not place this module in the LPA and do not include *hlq.SDFHAUTH* in the MVS LNKLST unless DFHSIP is RACF-protected as a controlled program with a profile in the RACF PROGRAM resource class.

You should also RACF-protect the other libraries (including *hlq.SDFHLOAD*) that make up the STEPLIB and DFHRPL library concatenations.

For information about authorizing access to CICS data sets, see the *CICS RACF Security Guide*.

Authorizing access to data set services modules

During initialization, CICS determines the availability of backup-while-open (BWO)
support by linking to the callable services modules IGWAMCS2 and IGWABWO.
CICS also checks the DFSMSdss (or DFSS) release level by linking to the module
ADRRELVL. If access to this data set services module is controlled by means of
RACF PROGRAM general resource profiles, security violation messages are issued
against the CICS region userid, unless the userid is authorized to access
ADR-prefixed module names.

You can avoid security violation messages against the CICS region userids, and still control access to data set services, as follows:

- #
- # • If you have generic PROGRAM profiles protecting access to ADR modules,
create a specific PROGRAM profile for the ADDRELVL module, and ensure your
CICS region userids have READ access to this specific profile.
 - # • Instead of using PROGRAM profiles to protect access to data set services, use
one of the following methods:
 - # – Define suitable profiles in the DASDVOL general resource class.
 - # – Defining profiles in the FACILITY general resource class that are supported by
DFSMS to control access to data set services.

For information about using DASDVOL and FACILITY class profiles to control the uses of data set services, see the *DFSMS/MVS DFSMSdss Storage Administration Reference*, SC26-4929, and the *DFSMS/MVS DFSMSdss Storage Administration Guide*, SC26-4930.

Authorizing access to a CICS region's VTAM ACB

You can control which users, among those who are running non-APF-authorized programs, can OPEN the VTAM ACB associated with a CICS address space (CICS region). This ensures that only authorized CICS regions can present themselves as VTAM applications that provide services with this APPLID, thus preventing unauthorized users from impersonating real CICS regions. (Note that the CICS region userid needs the OPEN access, not the issuer of the SET VTAM OPEN command.)

To enable CICS to start up with external security, you must first have authorized the CICS region userid to open the CICS region's VTAM ACB with the applid specified on the APPLID system initialization parameter.

For each APPLID, create a VTAMAPPL profile, and give the CICS region userid READ access. For example:

```
RDEFINE VTAMAPPL applid UACC(NONE) NOTIFY(userid)
PERMIT applid CLASS(VTAMAPPL) ID(cics_region_userid) ACCESS(READ)
```

The correct CICS APPLID to specify in the VTAMAPPL class is the specific APPLID, as specified in the CICS system initialization parameters. If you are using XRF (that is, if CICS is started with XRF=YES in effect), you must define two VTAMAPPL profiles — one each for both the active and alternate CICS region's specific APPLID (the second operand on the CICS APPLID startup option).

Notes:

1. The VTAMAPPL class must be active and RACLISTed for this protection to be in effect; for example:

```
SETROPTS CLASSACT(VTAMAPPL) RACLIST(VTAMAPPL)
```

2. If a CICS region is not to use VTAM, you do not need to authorize the CICS region userid for the CICS applid.
3. If you do not control the opening of a CICS region's VTAM ACB, a new VTAM application started with the same applid as that of a running CICS region has the following effect:
 - The running CICS region performs a FORCECLOSE of its VTAM ACB and issues message DFHZC0101.
 - The running CICS region either terminates or continues, depending on your use of the XXRSTAT exit. (The default is to terminate.) If the CICS region continues, it no longer uses VTAM.
 - The new application opens the VTAM ACB with the specified applid.
 - If the first running CICS region used VTAM persistent sessions, the new application recovers any VTAM sessions that persist from that CICS region.

For information about creating VTAMAPPL profiles for CICS region applids, see the *CICS RACF Security Guide*. For information about the XXRSTAT exit, see the *CICS Customization Guide*.

Authorizing the region userid to access category 1 transactions

To enable CICS to start up with external security, you must first have authorized the CICS region userid to access the category 1 system transactions. If the region userid does not have this authority at CICS startup, CICS issues message DFHXS1113, and terminates.

To give the region userid the authority to access the category 1 system transactions, edit and submit the sample job stream in Figure 4 to execute the CICS-supplied sample CLIST, DFH\$CAT1. This job uses the RACF commands in the CLIST to update the RACF database.

Note: Only a user with the RACF authority SPECIAL can execute the CLIST to update the RACF database.

```
//RACFMIG JOB 'accounting information',
//          CLASS=A,USER=userid,PASSWORD=password
//DEFINE   EXEC PGM=IKJEFT01
//SYSPRINT DD SYSOUT=A
//SYSPRINT DD SYSOUT=A
//SYSUDUMP DD SYSOUT=A
//SYSTEMSIN DD *
EXEC 'CICSTS31.CICS.SDFHSAMP(DFH$CAT1)' LIST
/*
//
```

Figure 4. Batch job to execute the sample CLIST, DFH\$CAT1

For information about category 1 transactions and about determining the CICS region userid, see the *CICS RACF Security Guide*.

Authorizing access to an SMSVSAM server

#

In a test environment you might wish to use the default action and allow any CICS region using VSAM RLS to connect to an SMSVSAM server. If you wish to protect this access, the RACF SUBSYSNM general resource class must be active and you must authorize each CICS region that connects to an SMSVSAM server to have access to that server. This means granting access to the appropriate profile in the

```
# RACF SUBSYSNM general resource class. You define profiles in the SUBSYSNM
# resource class to control access by subsystems like CICS that want to connect to
# SMSVSAM.
```

A SUBSYSNM profile name is the name by which a given subsystem, such as CICS, is known to VSAM. For CICS regions, you must use the CICS applid as the profile name in the SUBSYSNM general resource class.

When CICS attempts to register the control ACB during CICS initialization, SMSVSAM calls RACF to check that the CICS region userid is authorized to a profile name in the SUBSYSNM class that matches the CICS applid. If the CICS region userid does not have READ authority, the register fails.

For example, if the applid of a CICS AOR is CICSDA#1, and the CICS region userid (shared by a number of AORs) is CICSDA# # , define and authorize the profile as follows:

```
RDEFINE SUBSYSNM CICSDA#1 UACC(NONE) NOTIFY(userid)
PERMIT CICSDA#1 CLASS(SUBSYSNM) ID(CICSDA# # ) ACCESS(READ)
```

```
# You can use wildcard characters on the applid to specify more than one CICS
# region, for example:
```

```
# PERMIT CICS#%#% CLASS(SUBSYSNM) ID(CICSGRP) ACCESS(READ)
```

Authorizing access to MVS log streams

There is no facility within CICS for controlling LOGSTRM security checks. This is controlled by the MVS security administrator activating the LOGSTRM and FACILITY general resource classes by means of the SETROPTS command.

Users of the IXCMIAPU administrative data utility and CICS regions both require appropriate authorizations to log streams and IXLSTR coupling facility structures.

Authorizations for users of IXCMIAPU

You create log structures and define log streams using the IXCMIAPU administrative data utility to update the LOGR data set. To do this, your userid needs the appropriate level of authorization, as shown in the following examples:

Coupling facility structures

To define and delete log structures using IXCMIAPU, you need ALTER access to the LOGR resource profile named MVSADMIN.LOGR in the FACILITY general resource class. For example, use the following RACF command:

```
PERMIT MVSADMIN.LOGR CLASS(FACILITY) ACCESS(ALTER) ID(your_userid)
```

Coupling facility log streams

To define, delete, and update log streams (including log stream models) that are defined in coupling facility structures, you need:

- ALTER access to the appropriate log stream profile defined in the LOGSTRM general resource class
- UPDATE access to the coupling facility structure (IXLSTR) profile defined in the FACILITY general resource class (in this case, profile names are prefixed with IXLSTR).

For example, if the log stream and structure resource profiles are defined to RACF with the following commands:


```
RDEFINE LOGSTRM log_stream_profile UACC(NONE) [NOTIFY]
RDEFINE FACILITY IXLSTR.structure_name_a UACC(NONE) [NOTIFY]
```

use the following RACF commands to give your userid the required authorizations to these two profiles:

```
PERMIT log_stream_profile CLASS(LOGSTRM) ACCESS(ALTER) ID(your_userid)
PERMIT IXLSTR.structure_name_a CLASS(FACILITY) ACCESS(UPDATE) ID(your_userid)
```

Authorizations for CICS regions

If the LOGSTRM resource class is active, the level of authorization required depends on whether log streams are always explicitly defined to the MVS system logger.

Ensure that the CICS region userid is authorized to write to (and create if necessary) the log streams that are used for its system log and general logs (see Chapter 24, “Defining the logger environment for CICS journaling,” on page 143.) You do this by granting the appropriate access authorization to log stream profiles in the RACF LOGSTRM general resource class:

- If CICS is expected to create log streams dynamically, CICS must have **ALTER** authority to the relevant log stream (LOGSTRM) profiles, and **UPDATE** authority to the relevant coupling facility structure (IXLSTR) profiles. For example:

```
PERMIT region_userid.applid.* CLASS(LOGSTRM) ACCESS(ALTER)
      ID(region_userid)
PERMIT IXLSTR.structurename CLASS(FACILITY) ACCESS(UPDATE)
      ID(region_userid)
```

- If all the log streams that CICS writes to are already defined to MVS, CICS needs only **UPDATE** authority to the log stream profiles. For example:

```
PERMIT region_userid.applid* CLASS(LOGSTRM) ACCESS(UPDATE)
      ID(region_userid)
```

Note: In the above examples, *region_userid.applid.** is the generic profile name of the log stream resource. These examples illustrate a resource name prefixed by the region userid and applid. *region_userid* is the CICS region userid under which CICS is running, either as a started task or batch job.

Permit READ access to those users who need to read the CICS log streams. You must permit UPDATE access to those users who need to update journals by granting the user the appropriate authority to the log stream (in the LOGSTRM resource class) and to the JOURNALNAME (in the JCICSJCT class).

The generic profile in the following example could be defined to cover all the log streams referenced by the CICS region identified by its region userid and applid:

```
RDEFINE LOGSTRM region_userid.** UACC(NONE)
```

If, however, you have multiple CICS systems sharing the same region userid, but with differing security requirements, include the applid in the generic profile, as follows:

```
RDEFINE LOGSTRM region_userid.applid.* UACC(NONE)
```

The following example allows the CICS region userid under which CICS is running to write journal and log records to log streams in the named coupling facility structure:

```
PERMIT IXLSTR.structurename CLASS(FACILITY) ACCESS(UPDATE)
      ID(region_userid)
```

The following examples give access to two categories of user:

```
PERMIT region_userid.applid.* CLASS(LOGSTRM) ACCESS(READ)
      ID(authorized_browsers)
PERMIT region_userid.applid* CLASS(LOGSTRM) ACCESS(UPDATE)
      ID(archive_userid)
```

In these examples, *archive_userid* is the userid under which an application program runs to purge old data from CICS logs when the data is no longer needed, and *authorized_browsers* refers to the userids of users allowed to read log streams, but cannot purge data.

If several CICS regions share the same CICS region userid, you can make profiles more generic by specifying * for the *applid* qualifier.

The number of profiles you define depends on the naming conventions of the logs, and to what extent you can use generic profiling.

Authorizing CICS region userids to z/OS UNIX System Services

Some CICS facilities require access to z/OS UNIX System Services. These facilities are :

- CICS TCP/IP support provided by the CICS sockets domain when you specify TCP/IP=YES as a system initialization parameter. This support is required if you are planning to use HTTP, IIOPI, and ECI services.
- The Java Virtual Machine (JVM). CICS JVM support is required for Java programs that specify JVM=YES in their program resource definitions.
- EJB deployment.
- Using task-related user exits that are enabled with the OPENAPI option to exploit the CICS open transaction environment. This includes the task-related user exit of the CICS-DB2 attachment facility when CICS is connected to DB2 6.1 or later.

To ensure your CICS regions have the required access to z/OS UNIX system services, authorize the region userids by including an OMVS segment in the CICS region's user profile, specifying the UID parameter. In the OMVS segment, UID specifies the numeric user identifier.

When you are creating a new user profile for a CICS region userid:

- Add an OMVS segment with the UID parameter specified.
- Assign a home directory for the CICS region in the OMVS segment using the HOME parameter. For example, if the home directory is /u/cicsht## , specify:

```
HOME('/u/cicsht## ')
```
- Add a GID to the RACF group profile for the RACF group that is to be defined as the default group of the CICS region userid.
- Connect the CICS region's user ID to the RACF group that has the required GID

For CICS region userids that already exist, add the OMVS segment information using the ALTUSER command. For example:

```
ALTUSER CICS_HAA1 OMVS( UID(4127) HOME('/u/cics_haa1'))
```

where CICS_HAA1 is the CICS region userid of a CICS AOR that is initialized with TCP/IP support, 4127 is the UNIX System Services numeric user identifier of the CICS region, and /u/cics_haa1 is the home directory.

For information about defining OMVS segment parameters in a user profile, see the *z/OS Security Server RACF Command Language Reference*, SA22-7687.

For information about defining UNIX system services users, see the *z/OS UNIX System Services Planning*,

Activating RACF resource classes

Before you can use RACF for CICS resources and for user-defined resources, you must activate the associated RACF resource classes by using the RACF SETROPTS command.

To run the CICS-supplied IVPs with external security, you must activate the resource classes for CICS resources.

To use your own user-defined resources with external security in your CICS environment, you must:

- Define resource classes for your resources.
- Activate the resource classes.
- Optionally RACLIST resource classes to be used for QUERY SECURITY commands. This builds in-storage profiles for those resource classes.

For information about RACF resource classes, see the *CICS RACF Security Guide*.

Chapter 8. Defining the default CICS userid to RACF

If you intend using RACF to authorize terminal users to access CICS resources, you should define a default CICS userid to RACF and specify it on the CICS system initialization parameter, DFLTUSER. This default userid assigns the security attributes to be used for all CICS terminal users who do not sign on with the CESN transaction (or a user-written equivalent).

During startup, CICS tries to sign on the default userid. If it is not signed on (for example, if not defined), CICS issues message DFHSN0701 and terminates CICS initialization. After the valid default CICS userid is signed on, its security attributes are used for all CICS terminal users who do not sign on with the CESN transaction. If the default userid is defined to RACF with a CICS segment, the operator attributes in that segment are also used for users who do not sign on.

For information about defining the userid to RACF, see the *CICS RACF Security Guide*.

Chapter 9. Installing CICS-required modules in the MVS linklist

There are two categories of modules that CICS loads from the MVS linklist:

1. CICS-supplied modules
2. Modules of other MVS products (for example, DFSMS)

CICS-supplied modules required in the MVS linklist

CICS supplies the modules listed below in the *hlq.SDFHLINK* library, where *hlq* is defined by the LINDEX parameter in the DFHISTAR installation job.

AMDUSREF	Alias of DFHTG640.
AXMSC	AXM server connection routines for CICS data sharing servers.
AXMSI	AXM subsystem initialization routine for CICS data sharing servers.
DFHDTCV	Connection validation subroutine for shared data tables.
DFHDTSVC	Shared data tables SVC services.
DFHGTENV	Subroutine used by LOGR subsystem interface.
DFHLGCNV	Exit routine for LOGR subsystem interface.
DFHMVRMS	General MVS RESMGR exit stub.
DFHNCIF	Named counter server interface.
DFHNCOPT	Named counter server options.
DFHPD640	Dump formatting routine for use with IPCS.
DFHRPDUF	System dump formatting routine for ONC RPC.
DFHRPTRI	Trace interpretation routine for ONC RPC.
DFHRXSVC	RRS domain authorized services.
DFHSNNFY	RACF CICS segment changes notification routine.
DFHSNPTO	CICS RACF dynamic parse TIMEOUT keyword print routine.
DFHSNVCL	CICS RACF dynamic parse OPCLASS validation routine.
DFHSNVID	CICS RACF dynamic parse OPIDENT validation routine.
DFHSNVPR	CICS RACF dynamic parse OPPTRY validation routine.
DFHSNVTO	CICS RACF dynamic parse TIMEOUT validation routine.
DFHSSIN	CICS subsystem that initializes the console message handling facilities.
DFHSSMGT	CICS subsystem message table that contains the text of messages for the subsystem interface modules.
DFHTG640	Link module for the CICS GTF trace printing load module DFHTRGTF.
DFHTR640	Link module for the CICS GTF trace printing load module DFHTR640.
DFHTT640	Link module used for trace interpretation.

Note: It is not essential that DFHTT640 be included in the MVS Linklist, although it is recommended for the reasons given at the end of this list. If it is not in the linklist, an APF authorized library in the STEPLIB concatenation of the batch job is needed for every job which needs the module.

DFHXCSVC External CICS interface (EXCI) SVC services routine.

These modules are supplied in an APF-authorized library in the MVS linklist because:

1. They can be required by non-CICS regions such as batch jobs or a CICS data sharing server.
2. They must be consistent across several CICS regions.
3. They can be required by both CICS and non-CICS regions.
4. The RACF dynamic parse routines are required by the Security Administrator who executes the ADDUSER or ALTUSER commands under TSO. For information about the RACF interface routines, see the *CICS RACF Security Guide*.

These modules are in the *hlq.SDFHLINK* library when you install CICS.

Ensure the modules supplied in SDFHLINK are available from an APF-authorized library in the MVS linklist by:

- Adding these modules, as required, to an existing APF-authorized library defined in the MVS linklist, or
- Defining SDFHLINK itself as an APF-authorized library and including it in the MVS linklist.

Compatibility with earlier CICS releases

Unless otherwise stated, the CICS Transaction Server for z/OS, Version 3 Release 1 levels of the modules in SDFHLINK are compatible with earlier releases of CICS. The CICSplex SM modules in SEYULINK are not compatible with earlier releases. CICSplex SM modules in SEYULINK are release specific. See “Updating the MVS linklist” on page 284 for more information about CICSplex SM linklist modules.

Note: DFHPD640, DFHTG640, DFHTR640, and DFHTT640 are release dependant. If you run more than one release of CICS, ensure the correct versions are available (for example, DFHPD630 for CICS TS for z/OS, Version 2.3, DFHTG530 for CICS TS OS/390, Version 1 Release 3).

CICS shared data tables modules for the MVS linklist

CICS supplies the following modules, for the shared data tables facility, in the *hlq.SDFHLINK*. If you intend using the shared data tables facility, ensure that these modules are available in the MVS linklist or the MVS link pack area:

- DFHDTSVC and DFHDTCV, because all regions using shared data tables must use the same level of SVC code
- DFHMVRMS, the RESMGR exit stub, because CICS JOBLIB/STEPLIB data sets are unavailable at end-of-memory

Modules of other MVS products in the MVS linklist

There are some DFSMS modules that CICS loads from the MVS linklist. This requirement is either dependent on the function you are using (such as backup-while-open (BWO) support), or on the release of DFSMS. The modules are:

IGWABWO

This module, supplied in the MVS callable services library, SYS1.CSSLIB, is loaded by CICS from the MVS linklist if you are using BWO for files accessed in non-RLS mode.

Note: In addition to IGWABWO being in the linklist, IGWAMCS2 must be installed in the LPA. CICS tests for the presence of this module in the LPA to determine that BWO support is present in the MVS image before attempting to load IGWABWO.

For files that are accessed in RLS mode, CICS does not require IGWABWO or IGWAMCS2.

IGWARLS

CICS loads this module, supplied in the MVS callable services library SYS1.CSSLIB, from the MVS linklist. CICS issues the following message if it can not load IGWARLS:

```
DFHFC0116 APPLID THE LOAD OF CALLABLE
          SERVICE IGWARLS HAS FAILED WITH RETURN CODE
          X'EEEE'.
```

CICS initialization fails if CICS cannot load this callable services module.

Chapter 10. Defining CICS as an MVS subsystem

CICS must be defined as an MVS subsystem before you can use any of following facilities:

- The console message-handling facility
- Multiregion operation (MRO)
- CICS shared data tables
- External CICS interface (EXCI).
- Extended restart facility (XRF)

Also, if you are running CICS with XRF in a multi-MVS environment or a two-CPC (central processing complex) configuration, defining CICS as an MVS subsystem can reduce operator intervention during takeover if MVS or a CPC fails while more than one CICS is running.

For information about the console message-handling facility see “The console message-handling facility” on page 86.

For information about MRO, see the *CICS Intercommunication Guide*.

Defining CICS as an MVS subsystem involves three members of the SYS1.PARMLIB partitioned data set: IEASYSxx, IEFSSNaa , and DFHSSIyy. You only need member DFHSSIyy if you want the console message-handling facility.

Note: aa,xx,yy represent suffixes that are used to distinguish different versions of members of the SYS1.PARMLIB library.

Note that if you intend to start CICS with the START command you must either:

- Give the MVS started task procedure a name different from the subsystem name in IEFSSNaa (default ‘CICS’), or
- Issue the start command with the parameter SUB=JES2 or SUB=JES3 as appropriate.

For more information about the subsystem interface, see the *z/OS MVS Using the Subsystem Interface* .

The following topics cover:

- “The IEASYSxx MVS initialization member”
- “The IEFSSNaa MVS subsystem initialization member” on page 84
- “The SYS1.PARMLIB(BPXPRMxx) parameters” on page 84
- “The console message-handling facility” on page 86
- “EXCI pipe allocation” on page 91

The IEASYSxx MVS initialization member

In an IEASYSxx member (of the SYS1.PARMLIB library) used for MVS initialization, include the parameter SSN=aa, where aa refers to the SYS1.PARMLIB member IEFSSNaa that contains the definitions for all subsystems needed for this IPL of MVS, including the definition of CICS as an MVS subsystem.

The IEFSSNaa MVS subsystem initialization member

To define CICS as an MVS subsystem, code an entry in the IEFSSNaa member in the SYS1.PARMLIB library. If you want to use the console message handling facility, or to change the number of pipes that can be allocated in an EXCI address space, code the entry by using one of the following methods:

#

```
CICS,DFHSSIN,DFHSSIyy
```

or

```
SUBSYS SUBNAME(CICS)  
  INITRTN(DFHSSIN)  
  INITPARAM(DFHSSIyy)
```

This entry is used for every CICS region, that you have IPLed with this version of the IEFSSN member, that runs under MVS. You do not have to specify both DFHSSIN and DFHSSIyy, however apart from the suffix yy, you must code the entry for each parameter using the exact format given in the example. The meanings of the terms are as follows:

#

CICS is the name of the CICS subsystem.

DFHSSIN is the name of the CICS subsystem routine that initializes the console message-handling facilities, and the number of pipes that can be allocated in an EXCI address space. If you omit this name, CICS is defined as an MVS subsystem, but none of the console message-handling facilities are enabled, and the default number of pipes, that can be allocated in an EXCI address space will be used. That default is 100..

#

DFHSSIyy is the name of a SYS1.PARMLIB member, described below, in which you have defined initialization parameters for message-formatting and EXCI pipe allocation for the CICS subsystem. If you specify DFHSSIN but omit DFHSSIyy, the DFHSSIN routine tries to use the parameters that are defined in member DFHSSI00.

#

If the DFHSSI00 member does not exist, the routine uses the default values.

#

- For message formatting these are defined in the DFHSSIN member. They are described in “Default message-formatting initialization parameters” on page 88.
- For EXCI pipe allocation, this is the fixed default value, 100.

The IEFSSNaa member in the SYS1.PARMLIB library also contains the definitions for all the other subsystems needed for this IPL of MVS, for example JES2, IRLM, and DATABASE 2 (DB2).

The SYS1.PARMLIB(BPXPRMxx) parameters

Use of certain CICS functions and running a large number of CICS systems in an LPAR mean that the default options, shipped in the BPXPRMxx members of SYS1.PARMLIB, are not sufficient. You must review the default options for the following functions:

|
|
|
|
|
|
|
|
|
|

- C and C++ programs compiled using the XPLINK compiler option.
- Programs that run on open TCBs and use APIs other than the CICS API.
- SSL TCBs specified by the MAXSSLTCBS SIT parameters.
- Java or JVM programs

“Amending parameters in SYS1.PARMLIB(BPXPRMxx)” on page 210

Both the use of XPLINK and of non-CICS APIs require some increase to the MAXPROCUSER and MAXPROCSYS values. If CICS is configured to use SSL, you might need to increase the MAXTHREADS and MAXTHREADTASKS values. These should exceed the MAXSSLTCBS SIT parameter.

If your system uses two or more of these facilities, corresponding further increases in the values for these parameters is appropriate.

The z/OS MAXPROCSYS parameter specifies the maximum number of processes that can be active at the same time, and allows you to manage system resources by limiting the number of processes that the system is to support. If you set the MAXPROCSYS value too low, regions might abend because CICS cannot create a process when attempting to attach a TCB. However, avoid setting the MAXPROCSYS value too high because this value is shared between all the address spaces in a z/OS system.

CICS uses at least two processes for each CICS region, which means that if you have a large number of CICS regions, you must set your system limit to handle these processes. The following table explains which TCBs become processes, depending on the CICS system:

Table 9. TCBs that become processes

TCB	Is the TCB always a process?	Description
Jobstep	Yes	The jobstep TCB is always created.
SO	Yes	The SO TCB is always created.
SL	No	The SL TCB is created unless the system initialization parameter, TCPIP=NO, is specified.
QR	No	The QR TCB becomes a process when an OTE TCB is attached (that is; L8, L9, J8, J9, X8, or X9).
SP	No	The SP TCB becomes a process, and the associated S8 TCBs are created and become threads only when SSL is used.
JVM (J8 and J9)	No	The number of J8 or J9 TCBs is controlled by the MAXJVMTCBS SIT parameter. J8 and J9 TCBs running active JVMs require one process each.

In summary, there is always a minimum of two processes for each CICS region, up to a minimum of seven processes for each region, depending on which additional TCBs you are running.

You can issue the following command to give you a list of the processes that are running on your system:

```
D OMVS, A=addressspaceid
```

addresspaceid is the address space that you want to query.

If you run this command at system startup, and again when your system has stabilized; for example, when peak J8 and J9 TCBs are running, you can calculate the most appropriate number for MAXPROCSYS.

For more information about changing BPXPRMxx parameters, monitoring system limits and calculating values for system resources, see *z/OS Unix System Services Planning*.

The console message-handling facility

The console message handling facility is an optional feature of the CICS subsystem that can affect the appearance of CICS messages displayed on an MVS console. It is effective when you specify `FORMATMSG=YES` as an initialization parameter for the CICS subsystem. The subsystem reformatting is enabled when at least one of the following is executing in the MVS image where the subsystem is defined:

- Any version of CICS Transaction Server
- Any earlier version of CICS since CICS/MVS version 2 release 1.2
- A message automation subsystem (such as NetView®) which enables the MVS subsystem console message broadcasting service

When this facility is used, it affects the messages that are displayed on MVS system consoles in the following ways:

- The subsystem tries to ensure that all console messages issued by all CICS regions have a standard format. The format is:

```
+DFHnnnn  APPLID  MESSAGE-TEXT
```

In this message:

+DFHnnnn

- begins in column 1
- The “plus” sign (+) which precedes **DFHnnnn**, is added by MVS to indicate that a problem-state program issued the message. It is not present when CICS issues the message while it is in supervisor state.

APPLID

- begins in column 13
- The applid inserted into the message is the specific application identifier. This is the identifier that is specified in the system initialization parameter `APPLID`. It is the only operand when `XRF=NO` is also specified, or the second operand when `XRF=YES` is also specified.

MESSAGE-TEXT

- begins in column 22.

- The subsystem adds routecodes specified in the `ROUTECD` subsystem initialization parameter, so the messages might be sent to more destinations.
- The subsystem reformats messages for all CICS releases, even those issued by CICS/OS/VS version 1.

- The subsystem does not reformat messages that are issued by a CICS region that has not yet determined its applid. This includes messages that are issued while processing the system initialization table and its overrides.
- The subsystem routine that reformats the messages does not receive control until after the message has been recorded in the CICS job log. Therefore, the reformatting is not usually apparent in the job log.
- Messages issued by the message domain already contain the applid. The subsystem does not insert the applid into such messages, but it might insert blank characters to cause alignment into standard locations.
- If the original CICS message is a long one, adding the applid might cause the message to exceed the maximum length for an MVS console message. In this case, the original message is suppressed (does not appear on the console), and the reformatted message is issued using the MVS multiple-line console message service to split the message over several lines. Both the original message and perhaps several instances of the reformatted multiple-line message appear in the job log, but only one copy of the reformatted message is displayed on the console.
- For some messages where the applid normally follows a time and date stamp, inserting the applid in the standard position would have resulted in the applid being duplicated within the message. For these messages, the subsystem eliminates the time and date stamp, because these are available from other sources, and only one occurrence of the applied is shown.

The DFHSSlly message-formatting initialization member

You can specify message-formatting initialization parameters for the CICS subsystem in a member DFHSSlly of the SYS1.PARMLIB library, where yy is the suffix that identifies the SYS1.PARMLIB member used to define the CICS subsystem. These parameters, described in this section, are FORMATMSG, HIDEPASSWORD, and ROUTECODES. Code the parameters in columns 1 through 71 of the DFHSSlly member, for example:

```
FORMATMSG=YES,HIDEPASSWORD=YES,ROUTECODES=(1,2)
```

or

```
FORMATMSG=YES
HIDEPASSWORD=YES
ROUTECODES=(1,2,
3,4,
5,6)
```

FORMATMSG={YES|NO}

Specifies whether the CICS applid is to be inserted into all DFH console messages that do not use the CICS message domain.

YES

Insert CICS applid into messages.

NO

Do not insert CICS applid into messages.

HIDEPASSWORD={YES|NO}

Specifies whether to mask the password from MODIFY commands used to enter the CICS signon transaction at an MVS console.

YES

Mask the password.

NO

Do not mask the password.

ROUTECODES=(n1[,n2])

n1, n2... are numbers representing generic routecodes that are added to *all* DFH console messages issued by CICS. The routecodes 1-12 have special meanings:

- 1** Master console action.
- 2** Master console information.
- 3** Tape pool.
- 4** Direct access pool.
- 5** Tape library.
- 6** Disk library.
- 7** Unit record pool.
- 8** Teleprocessing control.
- 9** System security.
- 10** System error/maintenance.
- 11** Programmer information.
- 12** Emulators.

The status of other routecodes is as follows:

- 13-20** Available for customer use.
- 29-40** Reserved.
- 41-128** Available to authorized programs only.

For more information about these routing codes, see the *z/OS MVS Initialization and Tuning Reference* manual for your version of MVS.

Default message-formatting initialization parameters

You can define message-formatting initialization parameters for the CICS subsystem in a member DFHSSIyy of the SYS1.PARMLIB library.

To use parameters defined in a DFHSSIyy member other than the DFHSSI00 member, you must specify DFHSSIyy on the IEFSSNaa member in the SYS1.PARMLIB library used to define CICS as an MVS subsystem. If you do not specify DFHSSIyy, the DFHSSIN routine tries to use the parameters that are defined in the DFHSSI00 member. If the DFHSSI00 member does not exist, it uses the default parameters that are defined in the DFHSSIN routine.

If you specify DFHSSIyy but it does not exist, the DFHSSIN routine uses the default message-formatting initialization parameters that are defined in the DFHSSIN routine

The default message-formatting initialization parameters defined in the DFHSSIN routine are:

FORMATMSG=YES, HIDEPASSWORD=YES
(generic routecodes are not added to messages)

The default facilities:

- Insert the CICS applid into the CICS console message between the message identifier and the message text. The applid is inserted into only those console messages (starting with DFH) that do not use the CICS message domain. The CICS message domain inserts the CICS applid into all messages that it handles. If the original message is a long one, inserting the CICS applid might cause the message to exceed the maximum length for an MVS console message. In this case, the original message is suppressed (that is, does not appear on the console), and the reformatted message is issued using the MVS multiple-line console message service to split the message text over several lines. Both the

original message and perhaps several instances of the reformatted multiple-line message appear in the job log, but only one copy of the reformatted message is displayed on the console.

- Examine each MODIFY command to see if it resembles a MODIFY CICS,CESN ... command. If the MODIFY command contains an old or new password (PS=xxxx,NEWPS=xxxx), the default facilities obliterate the password with asterisks. If the MODIFY command does not contain a password, the password you enter at the MVS console is masked.

Note: If your primary subsystem is JES3, the old and new passwords still appear in the JES3 hardcopy log. JES3 records the MODIFY command before the CICS message formatting subsystem can obliterate the password. (This does not happen when the primary subsystem is JES2.) The passwords are suppressed from the console for both JES2 and JES3. For information about the CESN transaction, and about how to prevent passwords from appearing in the hardcopy log, see the *CICS Supplied Transactions* manual.

If you do not specify DFHSSIN in the IEFSSNaa entry that defines CICS, the message handling facilities are not enabled. Also, if you run CICS as a started task, you cannot use the name “CICS” for the procedure name.

Activating message formatting

After you have defined CICS as an MVS subsystem with support for the console message-handling facility (and have specified the message-formatting parameters in the DFHSSIyy member of the SYS1.PARMLIB library), the message-handling facility is activated by the next MVS subsystem to invoke the subsystem console message broadcasting service of MVS console support. This occurs when you start up a supported CICS region (see “The console message-handling facility” on page 86 for a list) or if an automated-operation program, such as NetView, is active in the MVS image.

A newly-started CICS region determines its own applid during initialization. Until the applid is known, the message-formatting facility cannot operate. Therefore, messages issued very early in CICS initialization are not formatted.

Modules needed to use the console message-handling facilities

To use the console message-handling facilities that are provided by the MVS subsystem functions of CICS, the following CICS modules must be available at MVS IPL time:

DFHSSN	The module that cleans up CICS resources at end-of-memory and at end-of-task.
DFHSSGC	The subsystem generic connect module that connects an active CICS region to the CICS subsystem.
DFHSSIN	The CICS subsystem initialization module.
DFHSSMGT	The subsystem message table that contains the text of messages for the subsystem interface modules.
DFHSSWT	The subsystem interface write-to-operator (WTO)

router that determines whether WTO calls should be routed to the appropriate CICS-dependent modules.

These modules must reside in the LPA or in an APF-authorized library in the MVS linklist, as follows:

- The modules DFHSSIN and DFHSSMGT, installed in the *hlq.SDFHLINK* library, must reside in an APF-authorized library in the MVS linklist.
- The DFHSEN module installed in the *hlq.SDFHLPA* library, must reside in the LPA.
- The modules DFHSSGC and DFHSSWT, installed in the *hlq.SDFHLPA* library, must reside either in the LPA or in an APF-authorized library in the MVS linklist.

Note: *hlq* is defined by the LINDEX parameter in the DFHISTAR installation job.

The current versions of these modules are compatible with earlier CICS releases that support console message handling.

For information about adding modules that are installed in the *hlq.SDFHLINK* library to the MVS linklist, see Chapter 9, “Installing CICS-required modules in the MVS linklist,” on page 79.

For information about adding modules installed in the *hlq.SDFHLPA* library to the LPA, see Chapter 14, “Installing CICS modules in the MVS link pack area,” on page 107.

Coexistence considerations

To use the message-handling facilities for CICS, you should note the following coexistence considerations:

Automated-operation programs

If your automation system needs to see the console messages before they are reformatted by CICS, its subsystem definition should be placed in IEFSSNXX before the definition for CICS. But if your automation system needs to see the reformatted messages, its definition must come after that of CICS. Consult the documentation of your automation package to determine which applies to you.

Other CICS releases

If the message-handling facility has been defined to MVS (by the CICS entry in the IEFSSNaa member of the SYS1.PARMLIB library), CICS regions running earlier releases of CICS in the same MVS image have the full benefit of the message handling that has been defined if either of the following is true:

- An automated-operation program, such as NetView, is active in the MVS image.
- A CICS region that supports message handling (see “The console message-handling facility” on page 86 for a list) is running in the same MVS image.

Note: A consequence of console messages now having a standard format is that they no longer include date, time and informational messages. If you use these as a token, you must make a change to the code so that it looks for a different token.

EXCI pipe allocation

The external CICS interface is an application programming interface that enables a
non-CICS program (a client program) running in MVS to call a program (a server
program) running in a CICS region and to pass and receive data by means of a
communications area. The CICS application is invoked as though it is linked to by
another CICS application program.

This programming interface allows a user to allocate and open sessions or pipes,
which operate in "half-duplex", flip-flop" mode, to a CICS region and to pass a
distributed program link (DPL) requests over them. The multiregion operation
(MRO) facility of CICS interregion communication (IRC) supports these requests,
and each pipe maps onto one MRO session, where the client program represents
the sending process and the CICS server region represents the receiving process.
There is a default limit of 100 pipes for each EXCI address space.

The DFHSSlyy initialization member

You can specify the EXCI pipe allocation limit for the CICS subsystem in a member
DFHSSlyy of the SYS1.PARMLIB library, where yy is the suffix that identifies the
SYS1.PARMLIB member used to define the CICS subsystem. The parameter,
described in this section, is LOGONLIM. Code the parameter in columns 1 through
71 of the DFHSSlyy member, for example:

```
# LOGONLIM=200
```

LOGONLIM=nn

The minimum and maximum values that can be specified for nn are 100
and 250.

If the parameter is omitted, or the value specified lies outside the allowed
range, then CICS will assume a limit of 100. You should code the
parameter only if you want to increase the limit from the default value of
100.

The EXCI pipe allocation limit

CICS will publish the limit if it is determined during subsystem initialization. It will do
so by creating a system level name token pair formatted as follows:

```
# Name: input, fixed length 16 byte type  
# Bytes 0-7 : The character string 'DFHIRP '  
# Bytes 8-15: The character string 'LOGONLIM'  
# Token: output, fixed length 16 byte type  
# Bytes 0-3 : The logon limit, held as fullword binary  
# Bytes 4-15: Reserved, set to nulls
```

You can use the callable service, IEANTRT, to retrieve the token. To do this, invoke
IEANTRT with level IEANT_SYSTEM_LEVEL (EQU 4). The return code is
interpreted as follows:

- # 0 The name/token pair exists and the token has been retrieved. The logon limit
can be extracted from the token.
- # 4 The name/token pair does not exist. The logon limit is assumed to be 100.

Any other value indicates that the callable service has detected an error.

Default EXCI pipe allocation limit initialization parameter

You can define the EXCI pipe allocation limit parameter for the CICS subsystem in
a member DFHSSlyy of the SYS1.PARMLIB library.

```
# To use parameters defined in DFHSSIyy member other than the DFHSSI00
# member, you must specify DFHSSIyy in the IEFSSNaa member in the
# SYS1.PARMLIB library used to define CICS as an MVS subsystem.
# • If you do not specify DFHSSIyy, the DFHSSIN routine tries to use the parameters
# that are defined in the DFHSSI00 member.
# • If the DFHSSI00 member does not exist, it uses the default parameters that are
# defined in the DFHSSIN routine.
# • If you specify DFHSSIyy but it does not exist, the DFHSSIN routine uses the
# default parameters that are defined in the DFHSSIN routine.
#
# The default EXCI pipe allocation initialization parameter defined in the DFHSSIN
# routine is LOGONLIM=100. You should code the parameter only if you want to
# increase the limit from the default of 100.
```

Chapter 11. Installing the CICS Type 3 SVC

Install the current level of the CICS Type 3 SVC, DFHCSVC, before you attempt to start a region. To install the CICS Type 3 SVC:

1. Define the DFHCSVC module to MVS. (See “Defining the CICS SVCs to your MVS.”)
2. Install the DFHCSVC module into the LPA.

Do not change DFHCSVC attributes

Do **not** relink-edit the DFHCSVC module in order to install it into the LPA. The term *install* means move or copy a module into the LPA by using SMP/E, or a copying method that re-blocks the copied modules when the target data set has a smaller block size than the data set you are copying from.

The DFHCSVC module, as supplied, has the attributes AMODE(31) and RMODE(ANY); do **not** change these attributes.

For further information about installing the DFHCSVC module in the LPA, see Chapter 14, “Installing CICS modules in the MVS link pack area,” on page 107.

3. Specify the DFHCSVC number on the CICSSVC system initialization parameter.

The current version of the CICS SVC module is compatible with all earlier releases of CICS, which enables you to run your earlier CICS regions with current regions in the same MVS image.

CICS contains a test to verify that it is using the correct level of the CICS DFHCSVC module. If CICS calls an SVC module using the SVC number specified on the CICSSVC system initialization parameter, and the module is not at the current level, CICS issues message DFHKE0104. As a result of this message, CICS either abends with a system dump, or prompts the operator to enter an alternative SVC number, depending on the option specified on the PARMERR system initialization parameter.

Defining the CICS SVCs to your MVS

You define both the CICS Type 3 SVC and the HPO SVC to your MVS system by specifying SVC Parm statements.

You must define the CICS SVCs in an IEASVCxx member of the SYS1.PARMLIB library, using SVC Parm statements. See the *z/OS MVS Initialization and Tuning Guide* and *z/OS MVS Initialization and Tuning Reference* manuals for a description of the SVC Parm statements. If you are using the default SVC numbers, the CICS entries are as follows:

```
SVC Parm 216,REPLACE,TYPE(3),EPNAME(DFHCSVC)
SVC Parm 215,REPLACE,TYPE(6),EPNAME(DFHHP SVC) [Only required for HPO]
```

For the current SVC modules, you must specify the EPNAME parameters as in the sample CICS entries.

Note: If you have a version of the DFHHP SVC module from an earlier release of CICS already link-edited into your MVS nucleus, you do not need to replace it with the latest version. Versions of the DFHHP SVC module from earlier

releases of CICS are compatible with the current release. The CSECT name (EPNAME) of the version of the DFHHP SVC module from earlier releases is IGC215 (or IGCnnn, if SRBSVC=nnn was used as a CICS system generation parameter in the earlier release).

If you are not using the default SVC numbers, change the values 215 and 216 to the SVC numbers you have chosen.

You select the required IEASVCyy member by coding the SVC parameter (SVC=yy) in a SYS1.PARMLIB member (IEASYSxx) which you use to IPL your MVS. When you code new SVC numbers, they do not come into effect until you next IPL your MVS.

Using more than one version of the CICS Type 3 SVC

You may need to use more than one version of the CICS Type 3 SVC, for example to test service applied to the DFHCSVC module while using the current version in a production system.

You can run several CICS regions, at different release levels, in the same MVS image, with each region using its own version of the CICS SVC. However, if some of those regions use MRO, all regions that use MRO must use the latest CICS Type 3 SVC (DFHCSVC module) and the latest DFHIRP module. For information about using the latest SVC with earlier releases of CICS, see “MRO between different CICS releases with a changed SVC number” on page 95 and a pre-Version 3 *Installation Guide*.

To use more than one version of the CICS SVC, rename the new SVC module in the LPA, then respecify the SVC in the SVC Parm statements, as outlined in “Defining the CICS SVCs to your MVS” on page 93. To rename the new CICS SVC module, use the renaming facility of ISPF or IEBCOPY, or the TSO command RENAME, renaming the module to a unique name of your choice. We recommend that you use SMP/E to rename the CICS SVC module in the SDFHLPA library. Use the SMP/E RENAME command to inform SMP/E of the change to the name of the CICS SVC module. Therefore, if you later use SMP/E to apply service to that module, the service is applied to the renamed module in the LPA, **not** the DFHCSVC module.

For example, you might want to use an SVC number 255 for a test CICS region, as well as the default CICS SVC number 216 for your production system:

1. Create and apply an SMP/E USERMOD to RENAME the new CICS SVC module:

```
++USERMOD(umod1) .
++VER(C150) FMID(HCI6400) .
++RENAME (DFHCSVC) TONAME(newname) .
```
2. You could then specify the number 255 for the new CICS SVC version by adding an appropriate statement to the list of SVC Parm statements. That list would then read:

```
SVC Parm 216,REPLACE,TYPE(3),EPNAME(DFHCSVC)
SVC Parm 215,REPLACE,TYPE(6),EPNAME(DFHHP SVC) [Only required for HP0]
SVC Parm 255,REPLACE,TYPE(3),EPNAME(newname) [New CICS SVC version]
```

Note: The EPNAME parameter for the new CICS SVC specifies the module name, not the CSECT name, for the new CICS SVC module.

All the SVC Parm statements apply to the same IEASVCxx member of the SYS1.PARMLIB library.

3. Re-IPL MVS to enable all the SVC versions specified in the SVC Parm statements. After you re-IPL MVS, you can use both versions of the CICS SVC, as long as both regions do not use MRO concurrently. If both systems use MRO, only the new, latest, version of the SVC (and the latest DFHIRP module) is used by both regions.
4. In the system initialization table (SIT) for your production system, specify (by the system initialization parameter CICSSVC) the number of the current CICS SVC. Similarly, in the SIT for your test system, specify the number of the new CICS SVC version.

MRO between different CICS releases with a changed SVC number

If a CICS TS region, and other CICS regions from earlier releases, in the same MVS image use MRO, all the regions must use the CICS TS SVC module. If when you install the CICS TS SVC in the LPA, you give the SVC a number different from the number defined to the earlier CICS regions, you must respecify the SVC number. On each earlier release CICS region to use the CICS TS SVC, specify the new SVC number on the CICSSVC system initialization parameter.

Chapter 12. Selecting the high-performance option

The high-performance option (HPO) is for users whose top priority is to optimize terminal response times and maximize transaction throughput. HPO improves performance by reducing the transaction path length; that is, the number of instructions needed to service each request.

Note: Use of HPO potentially allows CICS application programs to bypass all MVS integrity controls. If you decide to use HPO, ensure that the application programs used on your CICS system meet your own installation's integrity requirements.

The code to support the **VTAM authorized path** feature of HPO (the improved path through VTAM) is in CICS.

Defining DFHHPSVC to MVS

The DFHHPSVC module must be defined to MVS as a Type 6 SVC; the default HPO SVC number defined in the DFHSIT module is 215. If you want to change the default Type 6 SVC number:

1. Define the new number to MVS. (See “Defining the CICS SVCs to your MVS” on page 93.)
2. Define the new number to CICS by using the SRBSVC system initialization parameter.

If you are not using HPO, you should **not** load the DFHHPSVC module into the MVS nucleus. You choose to use HPO explicitly by coding HPO=YES in the system initialization table (SIT).

Loading module DFHHPSVC

Before you can use HPO, ensure that the HPO SVC module is included in the MVS nucleus by one of the following methods:

1. Copy the DFHHPSVC module into SYS1.NUCLEUS, renaming it to IGC215 or the appropriate name if you are not using the default, and specify it on an INCLUDE statement in the NUCLSTxx member of the SYS1.PARMLIB library. (You must also specify the name of the NUCLSTxx member on the NUCLST statement of the LOADxx member of the SYS1.PARMLIB library.) The NUCLSTxx method provides you with greater flexibility in customizing the MVS nucleus than the NMLDEF method described in the method 2.

For further information about coding a NUCLSTxx member, and about a comparison with using the NMLDEF macro, see the *z/OS MVS Initialization and Tuning Guide*.

2. Copy the DFHHPSVC module into SYS1.NUCLEUS and specify it in a nucleus module list (NML) for CICS, created using the NMLDEF macro shown in the sample job in Figure 5 on page 98. This NML selects the CICS members in SYS1.NUCLEUS that are to be loaded into the MVS nucleus, and eliminates the need for the MVS nucleus to be re-link-edited for the DFHHPSVC module (or any other module needed in the MVS nucleus).

For information about coding an NMLDEF macro, see the *z/OS MVS Programming: Authorized Assembler Services Reference Vol 3* manual.

```

//LOADSVC JOB 'accounting info',MSGCLASS=A,CLASS=A
//NMLDEF EXEC ASMHCL
//C.SYSIN DD *
IEANCnn NMLDEF NUCL=DFHHPSVC
//L.SYSMOD DD DSN=SYS1.NUCLEUS,UNIT=3380,DISP=OLD
//L.SYSIN DD *
        NAME IEANCnn
/*
//

```

where *nnn* is the number of the CICS NML, in the range 001 through 256. Choose the value of *nnn* to be unique within your MVS nucleus.

Figure 5. Sample job stream to load the CICS Type 6 SVC into the MVS nucleus

Removing existing DFHHPSVC modules from the MVS nucleus

You can remove a link-edited version of the DFHHPSVC module (for an earlier release of CICS) from the MVS nucleus by running a link-edit job to replace the existing version of the nucleus with one that does not contain the module to be removed.

Notes:

1. If the existing nucleus-resident DFHHPSVC module is known to SMP/E, use the SMP/E UCLIN statement to remove the module entry.
2. You must link-edit the nucleus module, IEANUC0x, with the scatter (SCTR) attribute. If you do not do this, MVS enters a non-restartable wait state at system initialization.
3. If you have a version of the DFHHPSVC module from an earlier release of CICS already installed in your MVS nucleus, you do not need to replace it with the latest version. Versions of the DFHHPSVC module from earlier releases of CICS are compatible with the current release.

Chapter 13. Defining CICS regions as applications to VTAM

To use VTAM terminals with CICS, ensure that your CICS regions are defined to VTAM before you attempt to run them.

To define your CICS regions to VTAM (as VTAM application programs):

1. Define VTAM application program minor nodes for your CICS regions, by specifying APPL definition statements in a member of the SYS1.VTAMLST library (or your own *user.VTAMLST* library). See “Defining specific CICS APPL statements to VTAM.”
2. Issue a VARY ACT command to activate the APPL definitions, and enable the CICS regions to connect to VTAM.
3. Ensure that you have properly defined your VTAM terminals for connection to CICS. This is particularly important if you intend using the CICS autoinstall function. For those terminals for which you want to use autoinstall, code LOGON mode table entries that match the model TYPETERM/TERMINAL definitions that CICS uses. You can either code your own autoinstall models, or use the CICS-supplied model definitions that are generated for you when you initialize the CICS system definition data set (CSD).

For information about defining model and terminal resource definitions to CICS, see the *CICS Resource Definition Guide*.

For programming information about matching VTAM LOGMODE definitions with CICS model definitions, see the *CICS Customization Guide*.

For further information about defining VTAM resources, see the *z/OS V1R4.0 Communications Server: SNA Resource Definition Reference* and *z/OS Communications Server: SNA Network Implementation* manuals.

Defining specific CICS APPL statements to VTAM

To define a CICS region to VTAM, specify the minor node name to be used for the CICS region on the VTAM APPL definition statement.

For example, you could use the following definition for the CICS region to be identified as CICSHTH1:

```
*****
* Specific APPL definition for CICS region CICSHTH1
*****
CICSHTH1 APPL  AUTH=(ACQ,VPACE,PASS),VPACING=0,EAS=5000,PARSESS=YES   X
              SONSCIP=YES,LUAPFX=XX
*****
```

Notes:

1. Code CICSHTH1 on the CICS system initialization parameter APPLID, to define the VTAM application identifier to CICS.
2. See “Naming conventions” on page 190 for information about the naming convention that is used for the CICSHTH1 applid.

VTAM APPL parameters for CICS regions

When you define your CICS system to ACF/VTAM, include the following parameters on the VTAM APPL statement:

ACBNAME=acbname

Specifies the minor node name (*acbname*) that is assigned to this application.

This name must be unique within the domain. If you do not specify this parameter, the name of the VTAM APPL statement is taken.

AUTH=(ACQ,VSPACE[,PASS])

ACQ allows CICS to acquire LUTYPE 6 sessions. VSPACE allows pacing of the intersystem flows. You need PASS if you intend using the EXEC CICS ISSUE PASS command to pass existing terminal sessions to other VTAM applications.

EAS=*number*

Specifies the number of network-addressable units. The number must include the total number of parallel sessions for this CICS system.

HAVAIL=YES

Indicates that the application supports XRF sessions and can initiate XRF sessions.

LOGMODE=*name*

(For CICS-to-CICS APPC systems.) Defines the name of the MODE table that contains the LU6.2 MODEENT for the secondary sessions.

LUAPFX_{string}

specifies the prefix characters of the LU alias to be assigned when a dynamically generated cross-network CDRSC (with NQNMODE=NQNAME) is created for a session with CICS. VTAM concatenates the characters specified with the next sequential number available to form a VTAM-generated LUALIAS name for the cross-network dynamic CDRSC.

string

indicates the two characters to be used as the prefix for all dynamically generated LUALIAS names for dynamic cross-network CDRSCs in session with the CICS region defined by the APPL statement. Remember to take into account the VTAM naming conventions when choosing this prefix. For CICS considerations when specifying the LU alias string, see “Choosing an LUAPFX value” on page 104.

Note: VTAM deletes a dynamically-generated LU alias after a terminal session is closed, or the last session of an APPC parallel sessions connection is closed, and the CDRSCTI-specified timeout interval has expired. The permitted range of timeout values is 1 second to 7 days, but generally the default of 8 minutes is acceptable in most situations. The CDRSCTI timer doesn't start until there are no more sessions involving the resource represented by a CDRSC.

For more information about CICS support for the VTAM dynamic LU alias facility, see “VTAM LU alias facility” on page 102.

PARSESS=YES

Specifies LUTYPE 6 parallel session support.

PERSIST=MULTI

Indicates that the application supports Multi Node Persistent Sessions (MNPS). For further information, see the *z/OS Communications Server: SNA Network Implementation*.

SONSCIP=YES

Specifies session outage notification (SON) support. SON enables CICS, in certain cases, to recover a session after session failure without operator intervention.

VPACING=number

Specifies the maximum number of normal-flow requests that another logical unit can send on an intersystem session before waiting to receive a pacing response. Start with a value of 5.

VTAM version and release level indicator

The terminal control modules in CICS are assembled against z/OS, 1.4 Communication Server. You can use any release of Communication Server VTAM from z/OS, 1.4 , or a later, compatible release. For details of the minimum level of products that you can use with the current release, see the *CICS Transaction Server for z/OS Release Guide*.

CICS can communicate with different levels of VTAM. It can find out which level you are using, and hence what level of function is available. This means that you can upgrade CICS and SecureWay™ Communication Server VTAM at different times. CICS finds out whether extra function is available when a new version of VTAM is installed, and produces a message if the facilities are not being exploited fully.

Message DFHZC3473 on opening the VTAM ACB

If the master terminal operator opens the VTAM ACB for the first time, using the command CEMT SET VTAM OPEN, but CICS is not using all available VTAM function, message DFHZC3473 is sent to the transient data destination called CSNE. The same message is sent there if the ACB is opened automatically during initialization, rather than by CEMT.

Cross-domain considerations

If you want to use VTAM services to access a CICS region on another MVS image, you must ensure that the required cross-domain services are defined to the VTAMs involved.

For example, to be able to use a VTAM APPC connection between a CICS region (applid CICSHTH1) on MVS image MVSH and a CICS region (applid CICSHAJ1) on MVS image MVSJ:

1. Define the cross-domain services (CDRSC) for accessing CICSHAJ1 in a member of the SYS1.VTAMLST library (or your own user.VTAMLST library) for MVSH.
2. Issue a VARY ACT command on MVSH to activate the CDRSC definition for accessing CICSHAJ1.
3. Define the cross-domain services (CDRSC) for accessing CICSHTH1 in a member of the SYS1.VTAMLST library (or your own user.VTAMLST library) for MVSJ.
4. Issue a VARY ACT command on MVSJ to activate the CDRSC definition for accessing CICSHTH1.

For example, you could:

1. Create the following CDRSC definition in a member of the VTAMLST library on MVSH:

```

CDIDHAJ1 VBUILD TYPE=CDRSC
*****
* CDRSC for access to applid CICSHAJ1 on MVSJ
*****
CICSHAJ1 CDRSC CDRM=IYAMCDRM  MVSJ

```

2. Issue the following command on MVSH to activate the cross-domain services to CICS SHAJ1 on MVSJ:

```
/V NET,ACT,ID=CDIDHAJ1
```
3. Create the following CDRSC definition in a member of the VTAMLST library on MVSJ:

```
CDIDH1 VBUILD TYPE=CDRSC
*****
* CDRSC for access to applid CICSHTH1 on MVSH
*****
CICSHTH1 CDRSC CDRM=IYALCDRM MVSH
```
4. Issue the following command on MVSJ to activate the cross-domain services to CICS HTH1 on MVSH:

```
/V NET,ACT,ID=CDIDH1
```

VTAM LU alias facility

Specifying a prefix string on the LUAPFX parameter of the CICS APPL statement indicates that VTAM is to generate LU ALIAS names for dynamic cross-network CDRSCs in session with the CICS region defined by the APPL statement. This enables CICS to use an LU alias for autoinstalled terminals and work stations and thus ensure unique names in a CICSplex comprising terminal-owning and application-owning regions (TORs and AORs). VTAM generates the LU ALIAS names dynamically.

CICS supports both forms of the VTAM alias function—predefined and dynamic—only where shown in the following table:

	CICS-to-CICS APPC connections (APPL definitions)		APPC devices (LU definitions)				Terminals	
	Synclevel 1	Synclevel 2	Synclevel 1		Synclevel 2			
	Predefined alias only		Predefined alias	Dynamic alias	Predefined alias	Dynamic alias	Predefined alias	Dynamic alias
VTAM	Yes	Yes	Yes	Yes	Yes	Yes	Yes	Yes
CICS	Yes	No	Yes	Yes	No	No	Yes	Yes

Notes:

1. The LU alias is used as the NETNAME for terminals and work stations that logon to a CICS region.
2. CICS does not support LU alias for synclevel 2 connections (LUTYPE 6.1 and 6.2) and ignores any LU alias for these LU types, and continues to use the network name defined in the VTAM APPL statement.

Dynamic LU alias support

CICS supports the use of a dynamic LU alias for CICS terminals and workstations that are autoinstalled only. You enable dynamic LU alias support by specifying LUAPFX on the VTAM APPL definition for any CICS terminal-owning region that could receive duplicate netnames. Also, when starting VTAM, specify the following options on the VTAM START command:

- NQNMODE=NQNAME
- CDRSCTI=*n* to specify the length of time that the session name should last after the last session has logged off.

Notes:

1. Make the time specified on CDRSCTI long enough to cover any time interval specified on CICS START commands that are issued against a terminal resource that uses a dynamic LU alias. This applies to STARTS with a delay that run on both a TOR or AOR. If the CDRSCTI time is not long enough, a resource could log off and then log back on again with a different network name and thus a different TERMID.
2. The CDRSCTI time interval should also be greater than that specified on the CICS AILDELAY system initialization parameter. However, if your applications have no dependency on the network name or termid, you can disregard CDRSCTI or set it to 1.

VTAM generates a dynamic LU alias only if LUAPFX is specified on the CICS APPL statement and the resource comes from another network. That is, it has a different network name from the network to which the CICS region belongs.

When to use dynamic LU alias: Use dynamic LU alias where:

- Your cross-network terminals and workstations that logon to CICS are mainly autoinstalled.

The CICS region receives logons from terminals and synclevel 1 connections (both parallel and single sessions) and those logons (or binds) are from cross-network resources that might have duplicate network names.

However, be aware that synclevel 1 connections could become synclevel 2 in the future. For example, if you have a connection between a TXSeries CICS and CICS TS it is synclevel 1, but if you change to using TXSeries CICS with a PPC gateway, synclevel 2 is used. CICS does not support dynamic LU aliases for synclevel 2 APPC connections.

- An AOR receives shipped terminals or connections with duplicate network names from different TORs.

Predefined LU alias support

CICS supports the use of a predefined LU alias for CICS terminals and workstations that are explicitly defined and those that are autoinstalled. You can also use a predefined LU alias for CICS regions that communicate using CICS intersystem communication (ISC). You enable predefined alias support by specifying LUALIAS=*alias* on any cross-domain resource (CDRSC) that needs a specific alias.

Note: A terminal or APPC sync level 1 work station that is defined to CICS on an explicit resource definition (that is, it is not autoinstalled) and is in a different network, requires a CDRSC definition with a specific alias on the LUALIAS parameter. This overrides the dynamic generation of an alias where LUAPFX is specified on the CICS region's APPL statement. To ensure that CICS can match the VTAM LU alias with the installed terminal definition, the LUALIAS value must match the NETNAME specified on the CICS TERMINAL resource definition.

An LUALIAS option in the CDRSC is effective if the resource comes from another VTAM domain (or network). That is, it is not used if the resource comes from the same MVS image, but is used if the resource comes from another MVS image regardless of whether it is from the same sysplex, another sysplex in the same network, or from a different sysplex. If an LU alias is predefined, a dynamic LU alias is not generated.

When to use predefined LU alias: Use predefined LU alias where:

- Dynamic LU alias is in operation in a CICS region and your terminals or workstations are explicitly defined on CICS terminal resource definitions with explicit terminal identifiers. In this case, you use predefined LU aliases to override the generation of dynamic LU aliases, which CICS would fail to match with any installed resource definition.
- Dynamic LU alias is not in operation in a CICS region, to avoid any conflict with duplicate network names.

Cross-network devices that need predefined LU alias: If the following VTAM cross-network resources are to be connected to a CICS region that is defined to VTAM with LUAPFX specified on its APPL statement, they must each have a CDRSC LUALIAS=netname entry:

- CICS RDO-defined terminals connected from another network. These include VTAM terminals that cannot be autoinstalled:
 - Pipeline terminals
 - Automatic teller machines (3614 and 3624)
 - Devices for which CICS does not receive logons, such as printers.
- LUTYPE 6.2 synclevel 1 connections that may be bound using limited resources. Like other LUTYPE 6.2 connections limited resource connections release their dynamic LU alias when CDRSCTI expires after the last session is unbound. However, these sessions are unbound whenever they are not in use, and if they rebind after the dynamic LU alias is released, CICS would install another connection, potentially with a different LU alias.
- CICS RDO-defined work stations (LUTYPE 6.2 synclevel 1 connections) connected from another network.
- Resources that require an LU name in a RACF profile definition, or resources for which prior knowledge of the LU name is required.

Choosing an LUAPFX value

When choosing an LUAPFX value, consider the scope of this parameter within the CICSplex, and also consider its scope within the sysplex in which your CICS regions operate.

A predefined LUALIAS name is supplied to CICS for cross-domain and cross-network resources. All the CICS regions in an MVS image share the same VTAM and are in the same domain. A CICS region in a different MVS image uses a different VTAM and is thus in a different domain. Resources coming from one VTAM to another, but which share the name NETID, are cross-domain resources

A dynamic LUALIAS name is only supplied to CICS for cross-network resources. A resource is a cross-network resource if it has a different network id (NETID). VTAM ensures that all the dynamic LUALIAS names assigned in one MVS image are unique. However, CICS needs network names to be unique across MVS images so that we do not get network name clashes in AORs.

It is important that all CICS regions across all connected networks use unique APPLIDs. This is true whether or not dynamic LUALIASs are used—it just makes it more important.

To ensure that all VTAM resources in a CICSplex have unique network names, use the LUAPFX prefix as follows:

- Specify LUAPFX on terminal-owning regions (TORs) only.

- Use the same LUAPFX value for all the CICS TORs in the same MVS image (that is, for all the TORs that are connected to the same VTAM), but ensure the LUAPFX is different in each MVS image in the sysplex..

If the LUAPFX values are not the same throughout an MVS image, you risk one resource having two different network names in the CICS regions in that image.

If the LUAPFX values are not unique to each MVS image in the sysplex, you risk two resources attempting to install in a TOR with the same dynamic LUALIAS, or having two resources with the same network name in an AOR.

To ensure the uniqueness of the LU prefix in each MVS, IBM recommends that you use model APPL definitions, and within these use an MVS system symbol (&SYSC clone) as suggested in the *z/OS V1R4.0 Communications Server: SNA Resource Definition Reference*.

Note: If you use VTAM generic resources and your CICS TORs are spread across different MVS images, be aware that if a resource with a dynamically allocated LU alias logs off and then logs on again, and VTAM switches the resource to a VTAM in another MVS image, a different LUALIAS is assigned because of the different LUAPFX value.

- Avoid using an LUAPFX value that corresponds to the first two characters of CICS RDO-defined terminal names or connection names installed in the CICSplex.

Other considerations when using LU aliases

The following are some other factors to consider when you are planning to use VTAM LU aliases with CDRSC resources:

Predictable termids

If you need autoinstalled terminal resources to have a predictable and reproducible TERMID for such things as temporary storage queue names and START requests, you may need to modify your autoinstall user-replaceable module (URM) to select a reproducible TERMID from the network qualified name (NQNAME) supplied in the CINIT or the BIND.

There is an example of such code (commented-out) in the sample autoinstall URM, which extracts the network qualified name from the CINIT and BIND. The example illustrates how to create a TERMID from the last non-blank character of the NETID and the last 3 non-blank characters of the *real* network name (NETNAME).

MVS workload management

If your MVS workload policies specify LU name classifications, remove the LU name for any cross-network resources that are autoinstalled by CICS.

Recovery and persistent sessions support

Resources for which CICS uses any VTAM LU alias (predefined or dynamic) and which come from a different network are not cataloged by a CICS region that is not using persistent session. This means the terminal sessions for the resources cannot be recovered during an emergency restart.

Resources for which CICS uses any VTAM LUALIAS (predefined or dynamic) and which come from a different network are cataloged if CICS is using persistent sessions. This enables CICS to restore resource terminal session information from the CICS catalog pending recovery of the session from VTAM. However, if the resource does not persist, the resource is deleted during an emergency restart.

This action is necessary because VTAM may have been restarted, which would cause dynamic LU aliases to be reissued to different sessions. CICS is unable to tell if VTAM has been restarted, and CICS cannot tell the difference between a predefined and a dynamic LU alias.

CLSDST PASS

If you ISSUE PASS (CLSDST PASS) for a terminal that uses a dynamic LU alias to pass control to another CICS region in another MVS image, the resource is known by a different network name in the receiving CICS. This is true if the APPL statement of only one or both the CICS regions specify LUAPFX to activate dynamic LU alias.

Generic resources

If a number of generic resource TORs are in two different MVS images, a terminal or work station that logs on to one image is assigned a different network name if it logs off and logs on to a TOR in another image.

FEPI

FEPI front end systems are not supported by VTAM LU alias.

Chapter 14. Installing CICS modules in the MVS link pack area

This section describes:

- What you should consider before you install modules in the MVS link pack area. This is in “Preparing to install CICS modules in the MVS link pack area.”
- What you should do to use CICS modules in the MVS link pack area. This is in “How to use modules in the MVS link pack area” on page 111, which provides specific information about the following:
 - “Space requirements for CICS modules in the MVS link pack area” on page 111
 - “Defining the CICS LPA library to your MVS” on page 111
 - “Installing CICS modules in the LPA” on page 112
 - “Controlling the use of modules from the MVS link pack area” on page 114

Preparing to install CICS modules in the MVS link pack area

Before you install modules in the MVS link pack area, you should consider the following points, described in subsequent topics:

- “Benefits of using the MVS link pack area”
- “What is meant by the MVS link pack area?” on page 108
- “Which modules must be in the MVS link pack area” on page 108
- “Which modules can be in the MVS link pack area?” on page 109
- “Service considerations” on page 110

Benefits of using the MVS link pack area

The benefits of placing code in the MVS link pack area are:

- It is protected from possible corruption by user applications. Because the MVS link pack area is in protected storage, it is virtually impossible to modify the contents of these programs.
- Performance can be improved, and the demand for real storage reduced, if you use the MVS link pack area for program modules. If more than one copy of the same release of CICS is running in multiple address spaces of the same processor, each address space requires access to the CICS nucleus modules. These modules may either be loaded into each of the address spaces or shared in the MVS link pack area. If they are shared in the MVS link pack area, this can reduce the working set and therefore, the demand for real storage (paging).
- You can decrease the storage requirement in the private area by judicious allocation of the unused storage in the MVS link pack area created by rounding to the next segment.

If you know the amount of space that you need in the LPA, and from that the total size of the MVS common area above the CICS private storage, you can determine which 1MB segment the boundary between the two areas lies on. This may indicate that there is some space in the MVS common area that is left unused, which you could use for CICS LPA-eligible modules. By moving more modules from CICS private storage to the LPA, you decrease the space that is needed for modules in CICS private storage.

What is meant by the MVS link pack area?

The MVS link pack area comprises several areas, both above and below 16 MB. In this publication, the term **MVS link pack area** refers to the pageable link pack areas above and below 16MB where modules that are used from the MVS link pack area are normally installed.

Note: The MVS link pack area has both pageable and fixed parts. Although you can install CICS modules into the fixed parts, we recommend that you use the pageable areas for performance reasons.

The term **LPA** specifically refers to the MVS link pack area below 16 MB, and the term **ELPA** specifically refers to the area above 16MB. A module that is link-edited with the RMODE(ANY) attribute is loaded into the ELPA.

If you install a module into the LPA or ELPA, that module will not be retrieved from
 # the until you re-IPL your MVS with CLPA specified. To use the new module and
 # avoid an IPL, you can use the MVS dynamic LPA in one of the following ways:

- # • With the SETPROG LPA command
- # • With an LPA statement in a PROGxx member of PARMLIB, which specifies the
 # SET PROG=xx command

Note that dynamic LPA must not be used with DFHIRP.

Which modules must be in the MVS link pack area

The CICS modules listed in Table 10 must be in the MVS link pack area for the reasons that are given in the notes after the table.

Table 10. CICS modules required in the MVS link pack area

Module	Description	When needed in LPA	See notes after this table
DFHCSVC	CICS Type 3 SVC	Always	1, 2, 3,4, and 6
DFHDSPEX	CICS post exit stub	Always	1, 3, and 5
DFHDUMPX	SDUMPX IEASDUMP QUERY exit	Always	1, and 3
DFHIRP	Interregion communication program	To use MRO, CICS shared database, or the console message-handling facility	1, 2, 3, and 6
DFHSSSEN	Subsystem interface end-of-memory / end-of-task clean up routine	To use the console message-handling facility	1, 2, 3, and 6
DFHSSGC	Subsystem generic connect module	To use the console message-handling facility	3, and 7
DFHSSWT	Subsystem interface WTO router	To use the console message-handling facility	3, and 7
DFH99SVC	Dynamic allocation - SVC services	Always	1, and 3

Notes:

1. Can be used only from the MVS link pack area, and must be installed there before CICS can be started.

#

2. You must always install the latest service level of the modules DFHCSVC, DFHIRP (if needed) and DFHSSEN.
3. The version of this module that is supplied with the current release, is downward-compatible with earlier releases of CICS. It works correctly with CICS regions running earlier releases. Therefore, if you are running different releases of CICS on the same MVS image, you should use the latest version of this module.
4. The DFHCSVC module must be defined to MVS as a Type 3 SVC (default SVC number is 216), and if you use a non-default SVC number, you must define it to CICS on the CICSSVC system initialization parameter.

Moving DFHCSVC into the MVS link pack area

Do **not** use the linkage editor to install the CICS SVC module into a library in the MVS link pack area. To copy or move the module from the *hlq.SDFHAUTH* library to the nominated library in the MVS link pack area, you should use either a suitable copy utility program, such as IEBCOPY, or an SMP/E USERMOD with ++MOVE statements.

5. If you are running earlier releases of CICS with the latest version, you must ensure that the latest version of the DFHDSPEX module is installed in the MVS link pack area. The DFHDSPEX module must be in the MVS link pack area for integrity reasons, but the post exit routine, DFHDSAUT, can reside either in the MVS link pack area, or in the CICS address space. This enables you to use different levels of the DFHDSAUT module in different CICS regions running in the same MVS image, because the DFHDSAUT module may not be compatible between CICS versions.
6. To communicate by MRO, all CICS regions in the same MVS image must use the latest level of the modules DFHCSVC, DFHIRP, and DFHSSEN in the MVS link pack area.
If a region detects that DFHIRP is at a lower level, when attempting to open interregion communication, it issues message DFHIR3799, and interregion communication fails to open.
7. To use the console message-handling facility, these modules must reside either in the MVS link pack area or in an APF-authorized library in the MVS linklist.

Which modules can be in the MVS link pack area?

Besides those CICS modules that must be in the MVS link pack area, other CICS modules and user application program modules are available from the MVS link pack area.

CICS modules

A CICS module optionally installed in the MVS link pack area (that is, not a module required in the MVS link pack area) can be used only by the release of CICS to which it relates.

Those CICS modules that can reside above 16MB (for example, the CICS message table, DFHMGT), are loaded above 16MB. Such modules can also be installed in the extended link pack area (ELPA).

CICS modules eligible to be used from the MVS link pack area are listed in the CICS-supplied USERMODs, DFH\$UMOD (for base CICS modules), which is in the *hlq.SDFHSAMP* library. Details of LPA-eligible modules are in “CICS modules

eligible for the MVS link pack area,” on page 447, to help you select those CICS modules that you want to install in the MVS link pack area.

User application programs

User application programs can be used from the MVS link pack area if they are read-only and:

- # • Written in COBOL, do not overwrite WORKING STORAGE, and are compiled using VS COBOL II, or later version. (The CICS translator generates a CBL statement with the required compiler options.)
- #
- #
- | • Written in PL/I (do not overwrite STATIC storage) and compiled using one of the versions of PL/1 listed in the *CICS Transaction Server for z/OS Release Guide* or later. (The CICS translator inserts the required REENTRANT option into the PROCEDURE statement.)
- |
- | • Written in C/370, compiled with the RENT option, and link-edited with the RENT option.
- | • Written in Assembler language, assembled with the RENT option, and link-edited with the RENT and REFR options.

Command-level user application programs compiled using a Language Environment-conforming compiler, or written in Assembler language or C/370, may be loaded above 16MB. (For information about installing application programs, see the *CICS Application Programming Guide*.)

A read-only module that may reside above 16MB is also eligible for the extended link pack area (ELPA).

Service considerations

Using modules with mismatching service levels can cause unpredictable results. To be safe, do not use the LPA version of a module if it differs from the version in the CICS libraries that you are using.

Load modules used from the LPA might be at a lower service level than the rest of your CICS region in any of the following circumstances:

- You are running CICS from libraries which belong to a target zone currently at a higher service level than the LPA zone.
- You have applied service to the LPA zone since the last IPL of MVS.
- You are not using the MLPA to replace service-updated load modules, but have applied service to the LPA zone since last IPL of MVS for which CLPA (create link pack area) was specified.

Thus, if you have applied service to a load module in your CICS libraries, you should also apply the service to the LPA version of the module, if one exists. This stipulation is there so that the MVS link pack area always contains tested load modules.

Use the SMP/E RESTORE function to back off the USERMOD before the LPA zone is updated or copied. Then apply the USERMOD again.

If you have used a copy of the CICS-supplied USERMODs to install modules into the MVS link pack area, and the original USERMOD is serviced, you may like to reflect the changes in your version of the USERMOD.

How to use modules in the MVS link pack area

To use CICS modules in the MVS link pack area:

1. Check that you have enough space for the selected modules.
2. Install the modules in the MVS link pack area.
3. Control the usage of modules from the MVS link pack area.

Space requirements for CICS modules in the MVS link pack area

Allow enough space in the MVS link pack area for you to install those CICS modules that you intend using from there. You can find out how much space you need by:

- Reviewing the sizes of the modules that you want to install in the MVS link pack area, as given in “CICS modules eligible for the MVS link pack area,” on page 447.
- Reviewing the module index of a system dump for the CICS region started with the system initialization parameter LPA=NO.
- Calculating the module sizes that are given for each module in the listing of modules that are provided by the IEHLIST utility program.

Remember also to allow space for any of your user application programs that you intend using from the MVS link pack area.

Note: The total space needed depends on how the operating system packages the modules into the MVS link pack area.

What next?

Once you have determined the space needed in the MVS link pack area, you must next create a library with enough space and define it to your MVS. This is in the topic “Defining the CICS LPA library to your MVS.”

Defining the CICS LPA library to your MVS

CICS supplies the library *hlq.SDFHLPA*. This library contains the modules that must be in the LPA. You can also use this library to install other CICS modules or application programs which you want to use from the LPA.

You can give the *hlq.SDFHLPA* library your own index, but if you do, you must specify the new index on the LINDEX parameter of the DFHISTAR job.

Add the full name of the *hlq.SDFHLPA* library to an LPALSTxx member of SYS1.PARMLIB. This ensures that the library contents are loaded into the PLPA at the next IPL of your system when CLPA is specified. Also APF-authorize the *hlq.SDFHLPA* library, by adding its name to an IEAAPFxx member of the SYS1.PARMLIB library.

For more information about this see Chapter 31, “Verifying your Java components installation,” on page 205.

You should also RACF-protect the *hlq.SDFHLPA* library, to prevent unauthorized or accidental modification of this library. For information about protecting the CICS libraries, see the *CICS RACF Security Guide*.

What next?

During migration to the current release use of the MVS link pack area, you may like to add a DD statement for the *hlq.SDFHLPA* library to the DFHRPL concatenation of your CICS startup job stream.

You can install into the *hlq.SDFHLPA* library the CICS modules to be used from the MVS link pack area. This is in “Installing CICS modules in the LPA.”

Installing CICS modules in the LPA

By *install*, we mean move or copy a module into a suitable LPA library, by using SMP/E, or by using a copying method that re-blocks the copied modules when the target data set has a smaller block size than the data set you are copying from (for example, use the COPYMOD function of the IEBCOPY program). A procedure for installing modules into the MVS link pack area by using SMP/E is in this section.

You should not relink-edit the modules in order to get them into the LPA library. CICS modules as supplied have the necessary attributes that cause MVS to load them automatically above the line (into the ELPA).

To install modules in the CICS LPA library, and to ensure that SMP/E can continue to service them, complete the following steps:

1. Select those modules that you want to use from the MVS link pack area, and specify them in the SMP/E USERMOD to be used to install the modules in the MVS link pack area.

You can use the CICS-supplied USERMOD, LPAMODS, or create and use your own version.

If you use your own version of a USERMOD, this can include ++MOVE statements from both CICS-supplied USERMODs.

2. Receive the USERMOD into the CICS global zone.
3. Apply the USERMOD to the LPA zone.

Note: When you have installed all your modules into the CICS LPA library (and defined it to MVS), you should re-IPL your MVS with CLPA specified to enable the modules to be used from the CICS LPA library.

These steps are in the following sections.

Selecting modules for the MVS link pack area

You should install in the MVS link pack area only those modules that you want to use from the MVS link pack area. “CICS modules eligible for the MVS link pack area,” on page 447 lists the CICS-supplied modules eligible for the MVS link pack area, and gives descriptions and other information to help you select those CICS modules that you want to use from the MVS link pack area.

To install modules in the MVS link pack area, you should use an SMP/E USERMOD that contains ++MOVE statements for only the modules to be installed in the MVS link pack area.

The CICS-supplied SMP/E USERMOD, DFHUMOD

CICS supplies an SMP/E USERMOD called DFHUMOD (in member DFH\$UMOD in the *hlq.SDFHSAMP* library). This USERMOD contains ++MOVE statements for all CICS modules, in the *hlq.SDFHAUTH* and *hlq.SDFHLOAD* libraries, that are eligible for the MVS link pack area. The USERMOD also indicates whether each module is LPA- or ELPA-eligible. You can choose which of the modules to install in the MVS link pack area by creating your own version of the USERMOD. Your selection is generally include modules in the working set of the installation.

Changing a CICS-supplied USERMOD

If you intend changing a CICS-supplied USERMOD, to choose modules to install in the MVS link pack area, take a copy of the USERMOD and update the copy only. If you have copied the *hlq.SDFHSAMP* library, for instance when changing user-replaceable programs, then you already have copies of the CICS-supplied USERMODs. If the original *hlq.SDFHSAMP* library is serviced, and the USERMOD is modified, you may like to reflect the changes in your version.

Preparing the USERMOD

To choose which read-only modules to install in the MVS link pack area, edit your copy of the SMP/E USERMOD to:

1. Comment out the ++MOVE statements for the modules that you do not want to install in the LPA, and
2. Move the remaining ++MOVE statements (for the modules that you do want to install in the LPA) one column to the left, so that the ++MOVE statements start in column one of the USERMOD module.
3. Add ++MOVE statements for your user application program modules that you want to install in the LPA, with the ++MOVE statements starting in column one of the DFH\$UMOD module.

Receiving and applying the USERMOD

Receive the USERMOD into the CICS global zone and apply it to the LPA target zone. This causes SMP/E to move those load modules you have specified from the named CICS target library (*hlq.SDFHLOAD* or *hlq.SDFHAUTH*) into the CICS LPA library. Applying the USERMOD also updates the corresponding LMOD entries within the target zone SMPCSI.

Do not accept the USERMOD into the distribution zone, and for the time being, do not apply it to any other target zone.

To receive and apply the CICS-supplied sample usermods in DFH\$UMOD, you can use the associated job DFHLPUMD which is tailored to your CICS environment and stored in the *hlq.XDFHINST* library when you run the DFHISTAR job.

What next?

To enable CICS to use the modules that you have installed in the MVS link pack area, re-IPL your MVS with CLPA specified.

Also specify to CICS that it is to use modules from the MVS link pack area. You can also control which modules are used from the MVS link pack area in several ways. This is in the topic “Controlling the use of modules from the MVS link pack area.”

Controlling the use of modules from the MVS link pack area

This topic describes what you must do to enable CICS to use modules from the MVS link pack area, and what you can do to specify that CICS **is not** to use eligible modules from the MVS link pack area.

The methods for controlling the use of modules from the MVS link pack area **do not** apply to the modules DFHCSVC, DFHDSPEX, and DFHIRP. These modules can be used only from the MVS link pack area.

Modules in the MVS link pack area from hlq.SDFHAUTH

CICS uses standard MVS load facilities for modules installed in the MVS link pack area from the CICS APF-authorized library, *hlq.SDFHAUTH*. That is, such a module is used from the first of the following locations that it is found in:

1. STEPLIB concatenation
2. MVS link pack area
3. MVS LNKLST

Using modules from the MVS link pack area

To use any of the CICS modules installed in the MVS link pack area from the *hlq.SDFHAUTH* library you must remove any version of the module from the *hlq.SDFHAUTH* library (or any other library in the STEPLIB concatenation).

Using modules from the STEPLIB

You can prevent CICS using modules installed in the MVS link pack area from the *hlq.SDFHAUTH* library by installing versions of those modules in a library in the STEPLIB concatenation. CICS then uses the versions of the modules from the STEPLIB concatenation into the CICS address space, rather than any versions that may be in the MVS link pack area.

Modules in the MVS link pack area from hlq.SDFHLOAD

The use of CICS modules installed in the MVS link pack area from the *hlq.SDFHLOAD* library is controlled by CICS system initialization parameters and resource definitions.

The *hlq.SDFHLOAD* library is used for non-nucleus CICS modules, and some CICS nucleus modules. You can also use the library for your own user application programs.

Using modules from the MVS link pack area

To use any of the CICS modules installed in the MVS link pack area from the *hlq.SDFHLOAD* library:

- Copy the modules into a CICS LPA library. (That is, you do not have to remove them from the *hlq.SDFHLOAD* library.)
- Specify the system initialization parameter LPA=YES. CICS then uses the following search order:
 1. MVS link pack area
 2. DFHRPL DD concatenation
- For a non-nucleus CICS module or user application program, specify USELPACOPY(YES) on the associated PROGRAM resource definition. These modules are identified in the CICS-supplied USERMODs by the statement:


```
/* Not loaded from LPA unless USELPACOPY is set to Y in the CSD */
```

For each CICS-supplied LPA-eligible module that needs USELPACOPY(YES) specified in its associated PROGRAM resource definition, you must create your own resource definition with USELPACOPY(YES) specified, and use it instead of the CICS-supplied resource definition. This is because you cannot modify the CICS-supplied resource definitions. For example, you could use the DFHCSDUP utility program to:

 1. Copy the CICS-supplied resource groups that contain the module definitions to new resource groups.
 2. For each module that needs USELPACOPY(YES), change the PROGRAM resource definition in the new resource groups to specify USELPACOPY(YES).
 3. Add your new resource groups to a new group list (that is, at the start of the list).
 4. Append the CICS-supplied group list DFHLIST (or your own equivalent of that group list) to your group list. Alternatively, include DFHLIST on the GRPLIST system initialization parameter as well as your group list.
 5. Remove the CICS-supplied groups that you have copied.

Once the program definitions have been changed on the CSD you should:

- Reinitialize the CICS catalogs if you have been using modules not in the MVS link pack area, and now want to use those modules from the MVS link pack area
- Specify your new group list (and DFHLIST if your group list does not include the list of resource groups provided in DFHLIST) on the GRPLIST system initialization parameter.

A sample DFHCSDUP job for all CICS LPA-eligible jobs is in Figure 6 on page 119.

Note: In the above example, instead of steps 3 and 4, you could use the CEDA transaction to:

- Copy your group list to create a new group list.
- Add the new (USELPACOPY(YES)) groups to the new group list **in the same place as** the original, CICS-supplied, groups.

Notes:

1. CICS uses eligible modules installed in the MVS link pack area, if:
 - You have **not** specified the name of the module on the CICS system initialization parameter PRVMOD.
 - The module has not been already loaded from the DFHRPL concatenation.
2. If CICS cannot find an eligible module in the MVS link pack area, it loads the private (non-shared) version into the CICS address space from the DFHRPL concatenation, after issuing the message DFHLD0107I to warn you that the

module is not in the MVS link pack area. (See page “The module-not-found warning message (DFHLD0107I)” on page 118 for more information about this message.)

3. CICS assumes that the PL/I modules, IBMBPSLA and IBMBPSMA, are installed in the MVS link pack area and issues message DFHLD0107I if it fails to find them there. If you want your PL/I application programs to run with the PL/I shared library facility, you must ensure that the modules IBMBPSLA and IBMBPSMA are installed in the MVS link pack area, or in the *hlq.SDFHLOAD* library (or another library in the CICS DFHRPL library concatenation).
4. Program list tables (PLTs) must be placed in the DFHRPL concatenation. However, before PROGRAM resource definitions for phase one PLTPI programs and PLTSD programs are installed (for example, early in CICS initialization) CICS scans the MVS link pack area for those programs, and issues message DFHLD0107I if it cannot find such a program there.
5. Likewise, before PROGRAM resource definitions for global and task-related user exit programs are installed (for example, early in CICS initialization) CICS scans the MVS link pack area for those programs, and issues message DFHLD0107I if it cannot find such a program there.

Specifying USELPACOPY(YES)

For every non-nucleus CICS module or user application program that you have moved to the MVS link pack area (that is, have removed from the DFHRPL concatenation), ensure that you have specified USELPACOPY(YES) on the associated PROGRAM resource definition. Otherwise, CICS is not able to find the module, and may fail to start up successfully.

Using modules from DFHRPL

You can prevent CICS using modules installed in the MVS link pack area from the *hlq.SDFHLOAD* library by either:

- Specifying NO on the LPA system initialization parameter.

This prevents CICS from using any modules installed into the MVS link pack area from the *hlq.SDFHLOAD* library. CICS tries to load the modules from libraries in the DFHRPL concatenation.

You might use this option when you want to run CICS to test a lot of LPA-eligible modules before installing them in the MVS link pack area. For example, you could add the *hlq.SDFHLPA* library to the DFHRPL concatenation while testing CICS modules for the MVS link pack area. Once you have verified the use of those modules from the MVS link pack area, you should specify the LPA=YES system initialization parameter, and remove the *hlq.SDFHLPA* library from the DFHRPL concatenation.

- Specifying the name of the module on the PRVMOD system initialization parameter:

```
PRVMOD={name|(name1,name2,...)}
```

This prevents CICS from using the specified modules from the MVS link pack area for only the run of CICS on which the PRVMOD parameter is specified. You might use the PRVMOD parameter when you want to run CICS to test a new version of an LPA-eligible module before replacing the version already in the MVS link pack area.

Specify the full module name on the PRVMOD parameter, including any suffix (for example, DFHMCP1\$). If only one module is named, the parentheses are optional. The PRVMOD parameter may span input lines. However, do not split

module names across lines, because CICS system initialization adds a comma at the end of every input line that does not already end with a comma. The only validity check performed on a module name is to ensure that it does not exceed eight characters.

You cannot code the PRVMOD parameter in the DFHSIT module; you can specify it in the PARM parameter, in the SYSIN data set, or through the system console.

- For a non-nucleus CICS module or user application program, specifying USELPACOPY(NO), the default, on the associated PROGRAM resource definition. These modules are identified in the CICS-supplied USERMODs by the statement:

```
/* Not loaded from LPA unless USELPACOPY is set to Y in the CSD */
```

You might use the USELPACOPY(NO) option of the PROGRAM resource definition for a more permanent exclusion of an LPA-resident module than for the single run of CICS control provided by the PRVMOD system initialization parameter.

Verifying modules for the MVS link pack area

While verifying new versions of modules to be installed into the MVS link pack area, you can instruct a CICS region to use the new versions from the DFHRPL concatenation by any of the following options:

- The LPA=NO system initialization parameter
- The PRVMOD system initialization parameter
- The USELPACOPY(NO) option of the associated PROGRAM resource definition (where applicable)

For further information about these options, see “Using modules from DFHRPL” on page 116

In all cases, you must install the new versions of the modules into the *hlq.SDFHLOAD* library, or another library in the DFHRPL concatenation.

If you are verifying many CICS LPA-eligible modules, you might like to add the *hlq.SDFHLPA* library to the DFHRPL concatenation. This allows you to check that the modules you have installed in the MVS link pack area are being loaded from there.

Note: The CICS-supplied usermods use SMP/E to move CICS LPA-eligible modules into the *hlq.SDFHLPA* library. Similarly, if you use SMP/E to apply service to any of those modules, the versions in the *hlq.SDFHLPA* library is updated. The updated versions of the modules are used from the MVS link pack area after you next re-IPL your MVS with CLPA specified. Until then, if you add the *hlq.SDFHLPA* library to the DFHRPL concatenation of your CICS region, and specify that CICS is not to use the version of the modules in the MVS link pack area, the updated versions of the modules are used from the DFHRPL concatenation.

After you have installed and verified the use of modules from the MVS link pack area, you should remove the versions of the modules from the DFHRPL concatenation of your CICS startup job.

You can find out whether CICS is loading modules from the MVS link pack area or the DFHRPL concatenation by reviewing the index of a system dump for the CICS

region started with the system initialization parameter LPA=YES. Modules loaded from the MVS link pack area have the dump option LD=3.

The module-not-found warning message (DFHLD0107I)

CICS issues message DFHLD0107I if it searches the MVS link pack area for a module installed there from *hlq.SDFHLOAD* and fails to find it.

If you encounter this message, check that you have specified USELPACOPY(YES) on the associated PROGRAM resource definition (if applicable). For further information about using modules loaded in the MVS link pack area from the *hlq.SDFHLOAD* library, see “Modules in the MVS link pack area from *hlq.SDFHLOAD*” on page 114.

CICS uses console routing code 11 for this particular message, which allows you to control the output of this message. For example, you can:

1. Exclude, as required, routing code 11 from specific MVS console definitions in the CONSOLxx member of SYS1.PARMLIB.

2. Use the MVS VARY command to prevent this message from appearing on specified consoles by omitting route code 11 from a VARY command that defines which routing codes go to specified devices. For example:

```
VARY devnum,CONSOLE,ROUT=(rtcode,rtcode,.,.,.)
```

Alternatively, you can remove route code 11 from those already defined by using the following VARY command:

```
VARY devnum,CONSOLE,DR0UT=(11)
```

3. Use the MVS message processing facility (MPF) to inhibit the message. To use this facility, code an entry specifying the CICS message number in the MPFLSTxx member of SYS1.PARMLIB.

CICS assumes that the following PL/1 modules are LPA eligible and issues message DFHLD0107I if it fails to find them there:

```
IBMBPSLA  
IBMBPSMA
```

Sample DFHCSDUP job to specify USELPACOPY(YES)

The standard IBM-supplied program definitions in the CSD all specify USELPACOPY(NO). If you copy, or move, to the LPA some (or all) of the IBM programs defined by definitions in the CSD, the next step is to modify the USELPACOPY attribute to ensure CICS uses the LPA copy.

To simplify this task:

- # IBM supplies, in the DFH\$ULPA member of the SDFHSAMP library, an alternate set of DEFINE statements for all the IBM-supplied programs. All the programs defined in DFH\$ULPA specify USELPACOPY(YES).
- # If you don't want all the programs to be defined for LPA use, edit the member to remove the programs that are to remain as USELPACOPY(NO).
- # The USELPACOPY(YES) versions are all defined in one new group called DFH\$ULPA. Change this group name if you want to use your own name.
- # The last statement in DFH\$ULPA adds the group to a startup list. Edit this to specify your own group list.
- # Run the sample DFHCSDUP job shown in Figure 6 on page 119 to add theDFH\$ULPA versions of the definitions to your CSD.

#

- There is no need to remove the standard definitions from DFHLIST. Specifying your group list after DFHLIST on the GRPLIST system initialization parameter ensures that the modified definitions override the standard definitions.

```
//LPAMODS    JOB  (account_details),MSGCLASS=A,MSGLEVEL=(1,1),  
//          CLASS=A,NOTIFY=userid  
//DEFULPA    EXEC PGM=DFHCSDUP  
//STEP LIB   DD  DSN=CICSTS31.CICS.SDFHLOAD,DISP=SHR  
//SYS PRINT  DD  SYSOUT=*  
//DFHCSD     DD  DSN=user.CICSTS31.CICS.DFHCSD,DISP=OLD  
//SYS IN     DD  DSN=CICSTS31.CICS.SDFHSAMP(DFH$ULPA),DISP=SHR  
/*  
/*
```

Figure 6. Sample DFHCSDUP job for all CICS LPA-eligible modules

Chapter 15. Defining CICS IPCS exit control data to MVS

If you use the MVS interactive problem control system (IPCS) to format and analyze CICS system dumps, you should ensure that the release-specific CICS formatting routines are defined and available to MVS.

The formatting routine for use under IPCS has the release identifier as part of its name; that is, DFHPD**640**. This is the formatting routine you must define to IPCS when formatting system dumps. The CICS formatting routine is release-specific, so if you run more than one release of CICS, ensure that you use the correct version for the system dump you are formatting.

The DFHIPCSP CICS exit control data

IPCS provides an exit control table with imbed statements to enable other products to supply exit control information. The IPCS default table, BLSCECT, normally in the SYS1.PARMLIB library, has the following entry for CICS:

```
IMBED MEMBER(DFHIPCSP) ENVIRONMENT(ALL) /* CICS          */
```

Ensure that your IPCS job can find the CICS-supplied DFHIPCSP module. The DFHIPCSP module is in the *hlq.SDFHPARM* library. You can either copy the DFHIPCSP module into SYS1.PARMLIB (so that it is in the same default library as BLSCECT) or provide an IPCSPARM DD statement to specify the library containing the IPCS control tables. For example:

```
//IPCSPARM DD DSN=SYS1.PARMLIB,DISP=SHR          For BLSCECT
//          DD DSN=CICSTS31.CICS.SDFHPARM,DISP=SHR For DFHIPCSP
```

Figure 7 shows the release-specific entries that are specified in DFHIPCSP.

```
EXIT EP(DFHPD212) VERB(CICS212) ABSTRACT(+
  'CICS Version 2 Release 1.2 analysis')
EXIT EP(DFHPD321) VERB(CICS321) ABSTRACT(+
  'CICS Version 3 Release 2.1 analysis')
EXIT EP(DFHPD330) VERB(CICS330) ABSTRACT(+
  'CICS Version 3 Release 3 analysis')
EXIT EP(DFHPD410) VERB(CICS410) ABSTRACT(+
  'CICS Version 4 Release 1 analysis')
EXIT EP(DFHPD510) VERB(CICS510) ABSTRACT(+
  'CICS Transaction Server for OS/390 Version 1 Release 1 analysis')
EXIT EP(DFHPD520) VERB(CICS520) ABSTRACT(+
  'CICS Transaction Server for OS/390 Version 1 Release 2 analysis')
EXIT EP(DFHPD530) VERB(CICS530) ABSTRACT(+
  'CICS Transaction Server for OS/390 Version 1 Release 3 analysis')
EXIT EP(DFHPD610) VERB(CICS610) ABSTRACT(+
  'CICS Transaction Server for z/OS Version 2 analysis')
EXIT EP(DFHPD620) VERB(CICS620) ABSTRACT(+
  'CICS Transaction Server for z/OS Version 2 Release 2 analysis')
EXIT EP(DFHPD630) VERB(CICS630) ABSTRACT(+
  'CICS Transaction Server for z/OS Version 2 Release 3 analysis')
EXIT EP(DFHPD640) VERB(CICS640) ABSTRACT(+
  'CICS Transaction Server for z/OS Version 3 Release 1 analysis')
```

Figure 7. Release-specific entries in DFHIPCSP for DFHPDnnn routines.

To use the DFHIPCSP member as it is, rename the CICS-supplied version of DFHPDX for earlier releases to the names that are shown in the table.

For information about using IPCS to format CICS system dumps, see the *CICS Operations and Utilities Guide*.

Implementing changes

You probably need to re-IPL MVS to bring the changes that are described in this chapter into effect before you attempt to run the IVPs.

Chapter 16. MVS Program properties table entries

There are some CICS properties that you can optionally define to MVS. These are in the following section.

You can define entries for CICS in the MVS program properties table (PPT). Figure 8 is an example of a CICS PPT entry in the SCHEDxx member of SYS1.PARMLIB.

```
/******  
/*          Program Properties table addition          */  
/*          for the CICS program, DFHSIP              */  
/*          */  
/* The following defaults apply to this CICS entry:   */  
/*          */  
/* No affinity to a particular processor      (AFF(NONE)) */  
/* Can be canceled                          (CANCEL)    */  
/* Requires data set integrity              (DSI)        */  
/* Not a privileged job                     (NOPRIV)     */  
/* Password protection is required         (PASS)       */  
/* Not a system task                       (NOSYST)     */  
/* Protection key 8                        (KEY(8))      */  
PPT PGMNAME(DFHSIP)          /* Add program name DFHSIP to the PPT*/  
    NOSWAP                   /* Non-swappable                    */  
    NOPREF                   /* No preferred storage required    */  
/*          */  
/*          */
```

Figure 8. Sample CICS PPT entry

For information about defining options in the PPT, see the *z/OS MVS Initialization and Tuning Guide*.

RACF password checking

If your installation has a PPT entry for the DFHSIP program, you should ensure that the PPTNOPAS option is **not** set in the PPT because this bypasses password and RACF authorization checking. However, you should consider making your CICS regions non-swappable by specifying the PPTNSWP option in the PPT. For information about defining CICS PPT entries in the SCHEDxx member of the SYS1.PARMLIB library, see the *z/OS MVS Initialization and Tuning Reference* manual.

Non-swappable CICS regions

For performance reasons, you should consider making your CICS regions non-swappable, by specifying the NOSWAP option in the PPT. However, you should be aware that the use of certain functions causes CICS regions to be made non-swappable automatically, regardless of what is specified in the PPT (for example, regions using cross-memory services for MRO).

MVS protection key for CICS

CICS can run only in MVS protection key 8 (the default). You must not define any other protection keys for CICS.

If you want to use the storage protection facility of CICS, you must specify the system initialization parameter STGPROT=YES, and must have the required hardware and software. If you operate CICS with storage protection, CICS observes the storage keys and execution keys that you specify in various system and resource definitions. For information about the CICS storage protection facility, and how it affects the storage allocation for the dynamic storage areas, see the *CICS System Definition Guide*. For information about hardware and software that is required by the CICS storage protection facility, see the *CICS Transaction Server for z/OS Program Directory*.

Chapter 17. MVS performance definitions

You can use the MVS workload management facility to manage sysplex resources across MVS subsystems, in parallel with the existing system resource management facilities.

For information about MVS workload management, see the *z/OS MVS Planning: Workload Management* manual.

If you want to use the MVS workload manager facility, you should:

1. Implement workload management on the MVS images that the CICS workload is to run on, as outlined in “Implementing MVS workload management.”
2. Ensure that CICS performance parameters correspond to the policies defined for MVS workload management, as outlined in “Matching CICS performance parameters to service policies” on page 126.

Implementing MVS workload management

The task of implementing MVS workload management is part of the overall task of planning for, and installing, MVS.

Implementing MVS workload management generally involves the following steps:

1. Establishing your workloads.
2. Setting your business priorities.
3. Understanding your performance objectives.
4. Defining critical work.
5. Defining performance objectives based on current business needs.
6. Get agreement for your workload performance objectives.
7. Specify a service level agreement or performance objectives.
8. Specify an MVS WLM service definition that uses the information from step 7.

Note: It is helpful at this stage to record your service definition in a form that helps you to enter it into the MVS workload manager ISPF application. You are recommended to use the worksheets provided in the *z/OS MVS Planning: Workload Management* manual, SA22-7602.

9. Install MVS.
10. Set up a sysplex with a single MVS image, and run in workload manager compatibility mode.
11. Upgrade your existing XCF couple data set.
12. Start the MVS workload manager ISPF application, and use it in the following steps.
13. Allocate and format a new couple data set for workload management. (You can do this from the ISPF application.)
14. Define your service definition.
15. Install your service definition on the couple data set for workload management.
16. Activate a service policy.
17. Switch the MVS image into goal mode.
18. Start up a new MVS image in the sysplex. (That is, attach the new MVS image to the couple data set for workload management, and link it to the service policy.)

19. Switch the new MVS image into goal mode.
20. Repeat steps 18 and 19 for each new MVS image in the sysplex.

Notes:

1. Current release support for MVS workload manager is initialized automatically during CICS startup.
2. All CICS regions (and other MVS subsystems) running on an MVS image with MVS workload management are subject to the effects of workload manager.

Matching CICS performance parameters to service policies

You must ensure that the CICS performance parameters are compatible with the workload manager service policies used for the CICS workload.

In general, you should define CICS performance objectives to the MVS workload manager first, and observe the effect on CICS performance. Once the MVS workload manager definitions are working correctly, you can then consider tuning the CICS parameters to further enhance CICS performance. However, you should use CICS performance parameters as little as possible.

Performance attributes that you might consider using are:

- Transaction priority, passed on dynamic transaction routing. (Use prioritization carefully, if at all.) The priority assigned by the CICS dispatcher must be compatible with the task priority that is defined to MVS workload manager.
- Maximum number of concurrent user tasks for the CICS region.
- Maximum number of concurrent tasks in each transaction class.

Chapter 18. MVS automatic restart management definitions

You can exploit the MVS automatic restart management facility that is provided by MVS to implement a sysplex-wide integrated automatic restart mechanism.

If you want to use the MVS automatic restart manager facility, you should:

1. Implement automatic restart management on the MVS images that the CICS workload is to run on.
2. Ensure that CICS startup JCL used to restart CICS regions is suitable for MVS automatic restart management.
3. Specify appropriate CICS START options.
4. Specify appropriate MVS workload policies.

If you do not wish to use the MVS automatic restart management facility, you can use XRF to provide restart of failed CICS regions. For information about XRF, see the *CICS/ESA 3.3 XRF Guide*.

Implementing MVS automatic restart management

The task of implementing MVS automatic restart management is part of the overall task of planning for and installing MVS. For information about MVS automatic restart management, see the *z/OS MVS Setting Up a Sysplex* manual.

Implementing MVS automatic restart management for CICS generally involves the following steps:

- Ensure that the MVS images available for automatic restarts have access to the databases, logs, and program libraries required for the workload.
- Identify those CICS regions for which you want to use automatic restart management.
- Define restart processes for the candidate CICS regions.
- Define ARM policies for the candidate CICS regions.
- Ensure that the system initialization parameter XRF=NO is specified for CICS startup.

For further information on implementing automatic restart management, see the *CICS Recovery and Restart Guide*.

Chapter 19. MVS cross-system MRO definitions

You can use the CICS interregion communication (IRC) facility for multiregion operation (MRO) between CICS regions across MVS images in a sysplex. This exploits the cross-system coupling facility (XCF) of MVS, and makes it unnecessary to use VTAM to communicate between MVS images within the same sysplex.

Within a sysplex, DFHIRP must be installed from the highest release of CICS running in that MVS image.

Sysplex overview

A sysplex consists of multiple MVS systems, coupled together by hardware elements and software services. In a sysplex, MVS provides a platform of basic multisystem services that multisystem applications like CICS can exploit. As an installation's workload grows, additional MVS systems can be added to the sysplex to enable the installation to meet the needs of the greater workload.

To use XCF to communicate in a sysplex, each CICS region joins an XCF group called DFHIR000 by invoking the MVS IXCJOIN macro using services that are provided by the DFHIRP module. The member name for each CICS region is always the CICS APPLID (NETNAME on the CONNECTION resource definition) used for MRO partners. Each CICS APPLID must be unique within any sysplex regardless of the MVS levels that are involved. Within the sysplex, CICS regions can communicate only with members of the CICS XCF group (DFHIR000).

MVS XCF considerations for MRO

Ensure that when you format the primary and alternate couple data sets used by the XCF component of MVS:

- The value specified for the MAXMEMBER parameter is large enough to handle the number of CICS regions and users of the EXCI in the CICS XCF group.

Each XCF group is limited to 2047 members, which is therefore the theoretical maximum number of CICS regions that can participate in XCF/MRO in a single sysplex. However, the maximum size of the XCF group is reduced if you set the MVS MAXMEMBER parameter, used to define XCF couple data sets, to a lower limit. When calculating the maximum number of members in the CICS XCF group, allow one member for:

- Each CICS region to run on an MVS image in the sysplex.
- Each pipe that is allocated by a user of the external CICS interface (EXCI). For information about EXCI users and pipes, see the *CICS External Interfaces Guide* manual.

To list the members in the CICS XCF group, you can use the MVS DISPLAY command. The name of the CICS group is always DFHIR000, so you could use the MVS command:

```
DISPLAY XCF,GROUP,DFHIR000,ALL
```

- The value specified for the MAXGROUP parameter is large enough for the CICS XCF group to be established.

Chapter 20. PR/SM policy for handling MVS failures

If you are running CICS under MVS in a Processor Resource/Systems Manager™ (PR/SM™) environment, you should define to MVS the preferred XCF PR/SM policy for handling MVS failures in a PR/SM environment, and define to PR/SM the authorization for each LPAR to cause reset or deactivation of another LPAR.

XCF PR/SM policy

The function that enables MVS images to take over the resources of other MVS images in the same sysplex. This function is also known as the PR/SM automatic reconfiguration facility (ARF).

Chapter 21. MVS ASREXIT - SYMREC Authorization Exit

A CICS program may call the first failure symptoms (FFS) component. This uses the MVS SYMREC macro to write symptom records to the MVS SYS1.LOGREC data set, in addition to, or instead of, a job log.

The SYMREC authorization exit, ASREXIT, must be in effect to allow CICS to use the SYMREC macro call, otherwise the call fails with return code 12, reason code 3868 (X'F1C').

When SYMREC is called by CICS, the ASREXIT routine issues a return code that permits the SYMREC to be successfully written.

The MVS sample exit programs ASREXT0 and ASREXT1, supplied in SYS1.SAMPLIB, are suitable for this purpose. For further information about these exits, see the *z/OS MVS Installation Exits* manual. The ASREXIT routine can determine if CICS is the caller by testing EPLPNAME for the value 'DFHSIP' except:

- When DFHSIP is renamed, in which case EPLPNAME contains the new name.
- When DFHSIP is the subject of an MVS LINK, in which case EPLPNAME contains the name of the program issuing the MVS LINK (unless it too is the subject of an MVS LINK).

If you choose this method, you may wish to code your ASREXIT routine to allow for these exceptions.

An alternative method of coding the ASREXIT routine is in Figure 9. This method is not affected by the exceptions that are mentioned above.

```
TITLE 'SYMREC SAMPLE EXIT'  
ASREPL  
PRINT NOGEN  
IHAPSA  
IKJTCT  
PRINT GEN  
DFHAFCD  
EJECT  
ASREXIT CSECT  
ASREXIT AMODE 31
```

Figure 9. An example of coding the ASREXIT routine. (Part 1 of 2)

```

ASREXIT  RMODE ANY
        USING *,R15          Temporary addressability
        MODID BR=YES
        DROP R15
        STM R14,R12,12(R13)  Save the caller's registers
        LR R12,R15
        USING ASREXIT,R12
        L R3,0(,R1)          Load the address of the EPL
        USING EPL,R3         Get addressability
        LA R15,RCREJECT      Preset "reject" return code
        USING PSA,0
        L R1,PSATOLD         Point at current TCB
        USING TCB,R1
        L R1,TCBEXT2        Point at TCB extension
        DROP R1
        USING TCBXTNT2,R1
        ICM R1,B'1111',TCBCAUF Point at AFCB; is there one?
        BZ SETRC             No, branch
        DROP R1
        USING DFHAFCB,R1
        CLC AFIDENT,='AFCX'  Is it a genuine CICS AFCB?
        BNE SETRC            No, branch
        CLI AFVER,AFVER1     Is it at least Version 1?
        BL SETRC             No, branch
        AH R1,AFLENG         Add length of AFCB's DW
        DROP R1              table.
        USING AFTSTART-AFPFXLEN,R1 Allow for AFCB prefix length
        ICM R1,B'1111',AFTAFCS Point at AFCS; is there one?
        BZ SETRC             No, branch
        DROP R1
        LA R15,RCWRITE       Set "write" return code
SETRC    DS 0H
        ST R15,EPLRETC       Store return code
        DROP R0
        DROP R3
        DROP R12
EXIT     LM R14,R12,12(R13)  Restore caller's registers
        BR R14              Return
        LTORG *
R1       EQU 1              Register 1
R3       EQU 3              Register 3
R12      EQU 12             Register 12
R13      EQU 13             Register 13
R14      EQU 14             Register 14
R15      EQU 15             Register 15
RCREJECT EQU X'0C'          Return code C
RCWRITE  EQU X'00'          Return code 0
        END*  CONSTANTS

```

Figure 9. An example of coding the ASREXIT routine. (Part 2 of 2)

Chapter 22. Definitions required for VSAM RLS support

If you plan to use VSAM RLS to enable CICS regions to share VSAM data sets, carry out the following steps:

1. Define the master coupling facility lock structure.
2. Define coupling facility cache structures and cache sets.
3. Define SMS storage classes for RLS access.
4. Alter data set characteristics, if necessary, to make data sets eligible for RLS access.
5. Define sharing control data sets.
6. Establish new authorization that is required by the VSAM RLS support.
7. Add new parameters to SYS1.PARMLIB.
8. Establish new procedures for VSAM RLS support.
9. Activate the coupling facility structures.

An overview of each of these steps follows.

Defining the master coupling facility lock structure

VSAM RLS support requires the coupling facility to define a master lock structure, IGWLOCK00, for cross system locking.

See the *z/OS DFSMSdfp Storage Administration Reference* manual for information about calculating the size you need for the lock structure.

The amount of coupling facility space required depends on several characteristics of your hardware configuration and the applications that you run, such as:

- The number of processors you have
- The power of your processors
- Your ratio of non-update activity to update activity
- Your ratio of recoverable updates to non-recoverable updates
- Your ratio of sequential requests to direct requests

You define the lock structure in the CFRM policy with the IXCMIAPU utility.

Defining coupling facility cache structures and cache sets

VSAM RLS support requires the coupling facility to define **cache structures** for cross system buffer invalidation. You need to determine the number and size of cache structures you require.

The number needed depends on factors such as:

- The number of coupling facilities you have
- The amount of space in each coupling facility
- The amount of data that is accessed through each coupling facility

See the *z/OS DFSMSdfp Storage Administration Reference* manual for information about calculating the amount of space you will need for the cache structures. If you have previously used data sets in LSR mode, the total amount of coupling facility space allocated to cache structures should not be less than the amount of storage you were using for LSR pools, including hiperspace buffers (if used).

You can achieve performance benefits by:

- Making the size of the cache larger
- The way in which you divide cache structures across coupling facilities

You define cache structures in the CFRM policy with the IXCMIAPU utility.

Defining cache sets

You define cache sets with the ISMF control data set (CDS) application.

A cache set maps on to one or more cache structures. If more than one cache set is specified, the data sets can be re-bound to another cache structure in the set in the event of a cache structure failure.

See the *z/OS DFSMSdfp Storage Administration Reference* manual for more information about cache sets.

Defining SMS storage classes for RLS access

Before you can use VSAM RLS, you need one or more storage classes which specify a non-blank cache set name.

The ISMF storage class application allows you to specify a cache set name when defining or altering a storage class, together with weighting parameters for tuning, such as CF DIRECT WEIGHT and CF SEQUENTIAL WEIGHT. See the *z/OS DFSMSdfp Storage Administration Reference* manual for more information about defining SMS storage classes.

Altering data set attributes for RLS access

Before you can use a data set in RLS access mode, you must ensure that it is eligible. To be eligible for RLS:

- Data sets must reside in SMS managed storage.
- Data sets must specify a storage class that has a non-blank cache set name.
- Data set recoverability attributes must be defined in the ICF catalog (not in the CICS file control resource definition, where they are ignored for RLS).

You can specify a data set's attributes using the Access Method Services (AMS) DEFINE CLUSTER or ALTER CLUSTER commands.

Specifying a LOG parameter of NONE, UNDO or ALL ensures that the recoverability of the data set is not undefined. You cannot open files in RLS mode if the LOG parameter of the associated data set is UNDEFINED. If you specify LOG(ALL), you must also specify a forward recovery log stream on the LOGSTREAMID parameter.

To use backup while open (BWO) for an RLS-accessed sphere, specify the BWO parameter. Specifying BWO(TYPECICS) means that backup while open can be used. All other values for BWO (including undefined) mean backup while open is not allowed. BWO(TYPECICS) is only valid if LOG(ALL) and LOGSTREAMID are also specified.

- Data sets must not specify the IMBED attribute.

If you have some data sets that specify imbed, you must remove the IMBED option before you can use the data sets in RLS mode. Redefine a new data set without IMBED and use the AMS REPRO function to copy the old data set to the new data set.

Note: RLS supports the REPLICATE cluster attribute. It does not provide any performance benefit, and removing it could save DASD space.

Defining sharing control data sets

VSAM RLS requires sharing control data sets. These are used to maintain data integrity in the sharing environment. The sharing control data set is used sysplex-wide by all the SMSVSAM servers, and is always duplexed.

Two active (and at least one spare) sharing control data sets must be available at all times.

The size required depends on the number of MVS images in the sysplex, and on the number of files that are expected to be open concurrently. The *z/OS DFSMSdfp Storage Administration Reference* manual gives information about calculating the amount of space that is needed for the sharing control data sets.

Sharing control data sets are VSAM linear data sets that must reside on volumes which have global connectivity. The data sets may have multiple extents, but only on the same volume. You define them using standard techniques for defining data sets. The names must have SYS1.DFPSHCDS as the first and second qualifiers. See the *z/OS DFSMSdfp Storage Administration Reference* manual for other rules relating to the definition of sharing control data sets.

You must not issue RESERVEs on any volumes on which sharing control data sets reside. Convert any such RESERVEs to enqueuees.

You can check that the data sets are available to the sysplex with the MVS DISPLAY SMS command, on any MVS image, as follows:

```
D SMS,SHCDS
```

This command shows the names of the two active, and the spare data set as in the following example:

Name	Size	%UTIL	Status	Type
ACTIVE1.VP2SS03 7920KB	7920KB	74%	Good	ACTIVE
ACTIVE2.VP2SS03 7920KB	7920KB	74%	Good	ACTIVE
SPARE.VP2SS03 7920KB	7920KB	74%	Good	SPARE

Note: The DISPLAY command shows only the third and fourth qualifiers of the sharing control data set names; the first and second qualifiers are always SYS1.DFPSHCDS.

The first time an SMSVSAM server is started in the sysplex, the sharing control data sets need to be varied online using

```
V SMS,SHCDS,NEW
```

for the active data sets, and

```
V SMS,SHCDS,NEWSPARE
```

for the spare data set (or data sets). The server cannot come up properly if this is not done.

Authorizing CICS userids for VSAM RLS support

Authorize each CICS userid that is to use VSAM RLS support to have read access to a profile in the SUBSYSNUM class which matches the applid. See “Authorizing access to an SMSVSAM server” on page 71 for more information.

You may want to restrict access to the AMS SHCDS LIST and REMOVE commands. The *DFSMS/MVS Access Method Services for ICF* manual gives information about using these commands.

Adding new parameters to SYS1.PARMLIB(IGDSMSxx)

To include RLS support in your system, specify the required parameters in the IGDSMSxx member of SYS1.PARMLIB, as follows:

- Specify RLSINIT(YES), otherwise SMSVSAM will not initialize automatically when you IPL MVS. Alternatively, you can start SMSVSAM using the VARY SMS,SMSVSAM,ACTIVE command.
- Specify a value for the deadlock detection interval with the DEADLOCK_DETECTION parameter.
- Specify time intervals for the creation and synchronization of VSAM RLS SMF records with the CF_TIME and SMF_TIME parameters.
- Specify the maximum size of the SMSVSAM local buffer pool with the RLS_MAX_POOL_SIZE parameter.

See the *z/OS DFSMSdftp Storage Administration Reference* manual for information about these parameters.

Establishing new procedures for VSAM RLS support

New operational procedures may be needed in a number of areas as a result of using VSAM RLS support. Areas to consider include:

- **Integrity of data in coupling facility caches**

To make sure that non-IBM products or user programs do not compromise the integrity of data in coupling facility caches when they modify the data on a volume, you should either vary the volume offline to each system in the sysplex, or CF-quiesce the volume using the

```
V SMS,CFVOL(volid),QUIESCE
```

command before running such programs

- **Management of the coupling facility and coupling facility structures**
- **Use of RESERVEs on volumes which contain sharing control data sets**

Make sure that this does not happen. You should convert RESERVEs on other volumes into enqueues.

- **Switching to non-RLS mode in order to run batch update jobs against recoverable data sets**

This subject is in greater detail in the *CICS Recovery and Restart Guide*.

- **Management of forward recovery and your forward recovery logs**

The differences from forward recovery for non-RLS access are:

- The forward recovery log stream must be in the ICF catalog.
- All forward recovery log records for a data set merge into the same log stream.

- Your forward recovery procedure needs to use the SHCDS FRSETRR, FRUNBIND, FRBIND, and FRRESETRR commands (CICSVR version 2 release 3 automatically issues these commands).

Refer to the DFSMS/MVS Version 1 Release 3 documentation for more details.

Activating the coupling facility structures

Once defined in the CFRM policy, the coupling facility structures must be activated using the SETXCF START POLICY command, specifying a TYPE of CFRM and the policy name.

Chapter 23. Console messages

The message domain supports the use of MVS message routing codes in the range 1 to 16 for those messages that are sent to the console. By default, if the issuing module specifies only CONSOLE (without a qualifying number) as the destination, CICS routes the message with MVS route codes 2 and 11 (for the master console – information). This support is available for all domain-type messages of the form DFHxxnnnn, where xx is the domain code, and nnnn is the message number.

CICS issues other messages (of the form DFHnnnn) with either no route code, or route codes other than 2 and 11.

The physical destination of these messages is controlled by the ROUTECODE parameter on the MVS console entries in a SYS1.PARMLIB member, CONSOLEnn. For further information about MVS console definitions, see the *z/OS MVS Initialization and Tuning Guide*.

Chapter 24. Defining the logger environment for CICS journaling

CICS uses the MVS system logger for all its logging and journaling requirements. Using services provided by the MVS system logger, the CICS log manager supports:

- The CICS system log, which is used for:
 - Dynamic transaction backout
 - Warm and emergency restarts
 - Cold starts, but only if the log contains information required for resynchronizing in-doubt units-of-work
- Forward recovery logs, auto-journals, and user journals.

The MVS system logger is a component of MVS. It provides a programming interface to access records on a log stream. For information about the MVS system logger, see the following MVS publications:

- *z/OS MVS Setting Up a Sysplex* for:
 - General information about the MVS system logger
 - Information about defining and formatting the LOGR couple data set
 - Information about how to plan the system logger configuration, plan and set up a system logger application, and plan for recovery for system logger applications.
- *z/OS MVS Programming: Assembler Services Reference, Volume 1* and *z/OS MVS Programming: Assembler Services Reference, Volume 2* for the syntax of system logger services
- *z/OS MVS Initialization and Tuning Reference* for information about the COUPLExx PARMLIB member.

Requirements planning and checklist

This section summarizes the requirements, and the steps that you need to follow, to set up the CICS logging environment. Some of the steps listed have a pointer to sections that provide more detailed information. These steps cover both MVS and CICS system programmer tasks and some security administrator tasks, and close cooperation between all groups is needed:

Planning

Consider the possible storage options, and choose which of the 3 available hardware options you want to use:

- **Non-volatile coupling facility**, where log stream data is duplexed in the MVS logger data space. Non-volatile storage involves the use of battery backup or an uninterruptible power supply (UPS):
 - When using a UPS, you use a hardware console command to update coupling facility status
 - When using battery backup, batteries must be online and charged.
- **Volatile coupling facility**, where log stream data is duplexed to a staging data set.
- **DASD-only**, where log stream data is duplexed in the MVS logger data space.

See “Coupling facility or DASD-only?” on page 150, to help you decide on one of these or a combination of both.

As part of the planning phase:

- Determine the number CICS regions that require logger support and hence system log streams.
- Determine the number of user journals and autojournals that your regions use.
- Determine the number of forward recovery logs required for VSAM data sets.
- Determine whether any user journal or forward recovery log streams are to be shared between regions (to create merged data automatically).

Note: The system log streams, DFHLOG and DFHSHUNT, cannot be shared.

DASD-only log streams can be shared only within the same MVS image.

- Decide on the number and sizes of the coupling facilities to be used.
- Determine the log stream sizes:
 - For coupling facility log streams, see “Coupling facility log streams” on page 151.
 - For DASD-only log streams, see “DASD-only log streams” on page 167.

For information about types of coupling facility, see the *z/OS MVS Setting Up a Sysplex*. Note that the minimum level of coupling facility supported by the MVS system logger is CFLEVEL=1, with the appropriate service level of the coupling facility control code that supports CFLEVEL=1.

Maintenance

Ensure that all maintenance affecting the MVS system logger, and the CICS log manager and its utilities, is applied:

- Logger serviceability APARs relating to the MVS system logger are identified with the LOGRSERVICE keyword.
- APARs relating to the CICS log manager are identified with the CICSLOGR keyword.

Run DFHLSCU

If you are migrating from CICS Version 3 or Version 4, run this log stream sizing utility using one or more CICS journal data sets as input:

- Use CICS journal data sets taken from periods of heavy production use.
- In each run of DFHLSCU, use only journal data sets that are to be migrated to the same MVS log stream

See “The log stream sizing utility, DFHLSCU” on page 160 for more information.

Create and format the LOGR couple data sets

In consultation with your MVS system programmer:

- Use MVS utility IXCL1DSU to create and format the primary and alternate LOGR couple data sets.
- Identify the LOGR couple data sets to the sysplex in the COUPLExx member in SYS1.PARMLIB
- Make the LOGR couple data set available to the sysplex.

See “Format the LOGR Couple Data Set and Make it Available to the Sysplex” in the *z/OS MVS Setting Up a Sysplex* manual for information about these steps.

Notes:

1. For this task you need know the number of log streams and, for coupling facility log streams, the number of structures. Each CICS region needs two system log streams and, optionally:
 - A log stream for the log of logs
 - One or more log streams for forward recovery logs
 - One or more log streams for autojournals
 - One or more log streams for user journals
2. If you are migrating from a release of OS/390, before release 3, (to meet the z/OS minimum requirement level for CICS TS) , you must reformat your LOGR data sets, because logging enhancements introduced in OS/390 Release 3 required LOGR couple data set of the sysplex to be formatted using OS/390 Release 3 or later.

The removal of the 168 data set limit (described in “General logs” on page 175) also requires the LOGR data set to be formatted with DSEXTENT(nnnnn). This does not apply to LOGR couple data sets formatted for DASD-only logging.

Define coupling facility structures

If you are using the coupling facility for some or all of your log streams, update your CFRM policy and your LOGR couple data set with the required structure definitions.

See “Defining coupling facility structures” on page 152 for details, including a sample job.

Establish the required security authorizations

Ensure that all the userids that are involved with running the system logger, or defining or accessing logger resources, are authorized, and that the required profiles are defined in the LOGSTRM general resource class :

- If the MVS system logger address space (IXGLOGR) is not given SAF privileged or trusted status, ensure you give the required authorization to the userid that runs IXGLOGR. For example, if the userid that runs IXGLOGR (defined in the RACF started procedures table (ICHRIN03), or defined in the RACF STARTED class profile) is SYSTASK:
 - SYSTASK requires ALTER access to IXLSTR structure profiles in the FACILITY general resource class for access to log stream coupling facility structures.
 - SYSTASK requires ALTER access to the data set profiles (*hlq.data_set_name*) in the DATASET general resource class, for each DASD log stream and staging data set.
- To use the MVS system logger IXCMIAPU utility to define, update and delete entries in the LOGR couple data set, you need appropriate authorizations to the relevant RACF profiles in the LOGSTRM and FACILITY general resource classes. See “Authorizations for users of IXCMIAPU” on page 72 for information and examples of how to do this.
- To enable CICS to create log streams dynamically, and to write to log streams, ensure that the CICS region userid has the required authorizations. See “Authorizations for CICS regions” on page 73 for information and examples of how to do this.

For more information about authorizations for the system logger, see the *z/OS MVS Setting Up a Sysplex* manual

Check sysplex definition in PARMLIB

To use the MVS system logger, each MVS image must be a member of a sysplex. Ensure your sysplex definition, in PARMLIB member IEASYSxx, specifies either PLEXCFG(MONOPLEX), for a single-member sysplex, or PLEXCFG(MULTISYSTEM), for a multi-member sysplex. Also ensure that you define a COUPLExx member in PARMLIB.

Note: The value specified on the SYSPLEX parameter in COUPLExx forms part of DASD-only and staging data set names.

Activate the LOGR subsystem

Ensure the LOGR subsystem is active to enable the CICS log manager batch utility, DFHJUP, to format and print log data. The LOGR subsystem is defined by the following entry in IEFSSNxx PARMLIB member:

```
SUBSYS SUBNAME(LOGR) INITRTN(IXGSSINT)
```

Plan staging data set requirements

Staging data sets are used for both DASD-only and coupling facility log streams, and if specified are dynamically allocated by the MVS system logger:

- For DASD-only log streams, staging data sets are the primary (interim) storage.
- For coupling facility log streams, staging data sets are allocated by the system logger to safeguard log data in the event of the log data being in a volatile configuration; that is:
 - There is a loss of the coupling facility battery backup
 - A structure failure that results in the only copy of log data being in MVS local storage buffers.

Consider the following parameters:

- STG_DUPLEX(YES) and DUPLEXMODE(COND) to cause the system logger to use staging data sets if the coupling facility is not failure independent (see “Staging data sets for coupling facility log streams” on page 166 for more information)
- STG_MGMTCLAS to specify the System Managed Storage (SMS) management class to be used for staging data set allocation (valid only when STG_DUPLEX(YES) or DASDONLY(YES) is specified)
- STG_STORCLAS to specify the SMS storage class to be used for staging data set allocation (valid only when STG_DUPLEX(YES) or DASDONLY(YES) is specified)
- STG_SIZE to specify the size of staging data sets
- SHAREOPTIONS(3,3) for log stream data sets and staging data sets (see “VSAM Share Options for System Logger” in *z/OS MVS Setting Up a Sysplex*)

Plan DASD space and SMS environment for logger secondary storage

System logger secondary storage comprises all log stream (offload) data sets. See “Managing secondary storage” on page 174 for information about size parameters and other attributes relating to secondary storage

Define log streams and log stream models

Define the specific log streams, and log stream models for dynamic creation of log streams, in the LOGR policy.

In particular, consider the following when defining your log streams:

- Set HIGHOFFLOAD no higher than 80% to allow the offload function to be activated before structures reach the 90% level and provide a buffer to enable CICS to continue writing records without filling the logstream before offload completes.
- Set LOWOFFLOAD for DFHLOG and DFHSHUNT in the range 40–60%. For user journals and the log of logs, specify LOWOFFLOAD as 0.
- Specify HLQ for the high level qualifier for offload data sets—it is not part of the CICS log stream name. The default is IXGLOGR.
- Specify STG_DUPLEX(YES) and DUPLEXMODE(COND) for log streams in the coupling facility to ensure that staging data sets are used automatically if the coupling facility is volatile or failure dependent.
- Set STG_SIZE to control the size, in 4K blocks, of staging data sets allocated by the system logger. For coupling facility log streams, the staging data set must hold at least as much data as the log stream in the structure, so that offloads are not triggered by the staging data sets. See The log stream sizing utility, DFHLSCU on pages 160 and 171 (for DASD-only).
- Specify LS_DATACLAS and LS_SIZE, for the SMS data class and the number of 4K allocation blocks respectively for log stream off load data sets (see “Managing log data sets” on page 174)
- Specify MODEL(YES) to indicate that a log stream definition is a model only and not an actual log stream. See SDFHINST members DFHILG2 (coupling facility) and DFHILG5 (DASD-only) for samples of model log streams.

Note: Use AUTODELETE(YES) with a suitable retention period (RETPD) for general logs but *not* for CICS system logs (DFHLOG and DFHSHUNT).

See “Defining coupling facility log streams” on page 156 for some sample IXCMIAPU jobs, and see *z/OS MVS Setting Up a Sysplex* for general information about updating LOGR policies.

Define JOURNALMODEL resource definitions

Define JOURNALMODEL resource definitions in the CICS CSD to enable CICS to map CICS journal names to MVS system logger log stream names. See the *CICS Resource Definition Guide* for information about JOURNALMODEL resource definitions.

Remove JCT definitions

When migrating a CICS region from a CICS/ESA 4.1 region (or earlier), remove all references to journal control tables (JCTs), and any DD statements for CICS journal data sets, from startup JCL.

See the *CICS Transaction Server for z/OS Migration from CICS TS Version 2.3* for CICS TS Version 1 Releases 1 and 2 for information about obsolete parameters and function relating to the old CICS journal control function and other migration information

Review AKPFREQ system initialization parameter

When migrating a CICS region from a CICS/ESA 4.1 region (or earlier), review the value specified for AKPFREQ.

This parameter now represents the number of write operations (log records) by CICS log manager to the log stream buffer before an activity keypoint is taken, whereas under the old journal control program it specifies the number of consecutive blocks written to the system log data set.

The parameter has a significant impact on the size of system logger primary (interim) storage, affecting the log tail management that takes place during activity keypoint (AKP) processing. The system logger:

- Deletes records that are no longer of interest to CICS
- Moves records to DFHSHUNT for those tasks that wrote log records within the last ACP.

Update JCL of batch jobs

When migrating a CICS region from a CICS/ESA 4.1 region (or earlier), update DFHJUP batch job JCL. To process log streams, these jobs require the SUSBSYS keyword on DD statement for the log stream being processed.

Evaluate results after implementation

After you have implemented the steps necessary to use the MVS system logger for CICS log streams and journals, evaluate the results on a continual basis. The following are aids that you can use:

- CICS interval statistics. You can collect these at specified intervals and end-of-day to obtain CICS log manager statistics. You can also collect statistics using the DFHOSTAT sample program.
- SMF Type 88 records. These are produced by the MVS system logger, and can be printed using IXGRPT1, which is supplied in SYS1.SAMPLIB. You can also print these records using IXGRPT1J and IXGRPT1L.

The following sections provide more detailed information to help you with the above steps:

- “Coupling facility or DASD-only?” on page 150
- “Coupling facility log streams” on page 151, which contains:
 - “Defining coupling facility structures” on page 152
 - “Planning considerations for the number of log structures” on page 155
 - “Log structure naming conventions” on page 156
 - “Defining coupling facility log streams” on page 156
 - “Sizing considerations for coupling facility log streams” on page 158
 - “Coupling facility requirements in an RLS environment” on page 165
 - “Staging data sets for coupling facility log streams” on page 166.
- “DASD-only log streams” on page 167, which contains:
 - “Defining DASD-only log streams” on page 168
 - “Sizing considerations for DASD-only log streams” on page 169
 - “Converting a DASD-only log stream to use a coupling facility” on page 172.
- “Managing secondary storage” on page 174.

Setting up the environment for CICS log manager

CICS system programmers need to consult with their MVS system programmers to plan for the storage that is required by the log streams needed by the many CICS log managers operating in the sysplex.

Each log stream is a sequence of blocks of data, which the MVS system logger internally partitions over three different types of storage:

1. Primary storage, which holds the most recent records that were written to the log stream. Primary storage can consist of either:
 - a. A structure within a coupling facility. Log data written to the coupling facility is also copied to either a data space or a staging data set.
 - b. A data space in the same MVS image as the system logger. Log data written to the data space is also copied to a staging data set.
2. Secondary storage—when the primary storage for a log stream becomes full, the older records automatically spill into secondary storage, which consists of

data sets managed by the storage management subsystem (SMS). Each log stream, identified by its log stream name (LSN), is written to its own log data sets.

3. Tertiary storage—a form of archive storage that is used as specified in your hierarchical storage manager (HSM) policy. Optionally, older records can be migrated to tertiary storage, which can be either DASD data sets or tape volumes.

See the different levels of log stream storage in Figure 10 and Figure 11 on page 150.




Figure 10. The types of storage used by the MVS system logger. This diagram shows a log stream that uses a coupling facility. Primary storage consists of space in a structure within the coupling facility, and either space in a staging data set or a data space in the same MVS image as the system logger. Secondary storage consists of a series of data sets on disk storage to which the elements of the log structure in the coupling facility are mapped. Tertiary storage is the DFHSM storage holding older levels of the secondary storage data sets.




Figure 11. The types of storage used by the MVS system logger. This diagram shows a log stream that uses DASD-only logging. Primary storage consists of a data space in the same MVS image as the system logger, and a single staging data set. Secondary storage consists of a series of data sets on disk storage to which hold successive copies of the single staging data set. Tertiary storage is the DFHSM storage holding older levels of the secondary storage data sets.

Coupling facility or DASD-only?

The CICS log manager supports the DASD-only option of the MVS system logger. This means that individual CICS log streams can use either coupling facility log structures or DASD-only logging.

Take the following points into account when deciding which log streams should be defined to use the coupling facility and which to use DASD-only:

- A coupling facility log stream must be used if you want to allow simultaneous access from CICS regions running in different MVS images. (Simultaneous access to a DASD-only log stream is limited to CICS regions in the same MVS image.)

For example, assume that you are using RLS and have several CICS application-owning regions (AORs) running on different MVS images. Because the forward recovery log must be accessible from all the AORs, it must be

defined as a coupling facility log stream. A CICS system log, on the other hand, is only ever accessed by a single CICS region, and can therefore always be defined as a DASD-only log stream.

Without a coupling facility, you cannot share general log streams across MVS images.

- Defining all your CICS log streams to use structures within a *single* coupling facility is not recommended—see “Coupling facility log streams.”
- DASD-only log streams are easier to define and administer than coupling facility log streams.
- The CPU cost of a log write to a DASD-only log stream is greater than that of a write to a coupling facility log stream. For more information, see the *CICS Performance Guide* .
- If the amount of available coupling facility space is limited, you may want to define some DASD-only log streams in order to minimize the amount of space allocated to log structures.

Notes:

1. Define a single-system sysplex (which must use a sysplex couple data set) with PLEXCFG=MONOPLEX. This is required for stand-alone MVS systems that use MVS system logger facilities.
2. Define sysplexes that have two or more MVS images with PLEXCFG=MULTISYSTEM.

Coupling facility log streams

If you use a coupling facility, the ideal environment is provided by two or more non-volatile coupling facilities that are failure-independent from any of the exploiting MVS images, using dedicated processor resources.

Should one coupling facility fail, or require maintenance, in such an environment, the system logger can rebuild its data in another coupling facility and continue. Running CICS systems would experience only minimal impact.

If you are unable to devote two coupling facilities for the purposes of the MVS system logger, the next most robust environment is provided by one dedicated coupling facility for normal logger and lock structure use, plus a coupling facility LPAR. This environment has the same advantages of rebuilding with minimal impact to running CICS systems. Furthermore, MVS detects that the LPAR coupling facility is not in a failure-independent domain, and causes the system logger to write log stream data to staging data sets for extra security.

Running with a single coupling facility is not recommended since its failure would cause the MVS system logger, and any other users of the coupling facility, to suspend normal operation until access to the coupling facility were restored. CICS would, effectively, be unusable in such a situation.

Unless you specify that the system logger is to use staging data sets, the recovery of log stream data depends on the MVS images remaining active so that the system loggers can use copies of log records held in storage to repopulate the coupling facility when it is again available. If you must run with a single coupling facility, you are recommended to specify **DUPLEXMODE(UNCOND)** to force the use of staging data sets.

Defining coupling facility structures

If you use a coupling facility for your CICS log streams, define the coupling facility structures needed for the log streams in your CFRM policy (in the CFRM data set), and in the LOGR policy (in the LOGR data set).

Updating the CFRM policy

Coupling facility space is divided into structures using the coupling facility resource management (CFRM) policy defined in the CFRM data set. The CFRM policy allows you to define how MVS is to manage coupling facility resources, and you update this using the IXCMIAPU utility. See Figure 12 on page 153 for a sample job to define coupling facility structures in the CFRM policy data set.

Updating the LOGR policy

You define structures in the MVS system logger LOGR policy in the system logger couple data sets using the DEFINE STRUCTURE specification of the IXCMIAPU utility. See Figure 13 on page 154 for a sample job to define coupling facility structures in the LOGR policy data set.

Remember

Before attempting to run any of the IXCMIAPU jobs, ensure that the MVS system logger (IXGLOGR) is running. If IXGLOGR is not running (for example if MVS is running in LOCAL mode), logstream definition jobs fail with rc=0814.


```

//CFRM      JOB (accounting-information),CLASS=A,MSGCLASS=A
//POLICY    EXEC PGM=IXCMIAPU
//STEPLIB  DD DSN=SYS1.MIGLIB,DISP=SHR
//SYSPRINT DD SYSOUT=*
//*****
//*
//* System logger structure definitions should be merged with      *
//* definitions for other structures required by the sysplex.      *
//*
//* Space values are for illustration only -- substitute values    *
//* appropriate to your number of logs and expected activity.      *
//*
//* NOTE: The values in this job are not matched with the other    *
//*       sample jobs.                                             *
//*****
//SYSIN     DD *
DATA TYPE(CFRM) REPORT(YES)
DELETE POLICY NAME(POL1)
DEFINE POLICY NAME(POL1)
  PREFLIST(cfname) REBUILDPERCENT(1)
/* Define coupling facilities */
CF NAME(cfname)
  TYPE(009674)
  MFG(IBM)
  PLANT(00)
  SEQUENCE(000000040032)
  PARTITION(3)
  CPCID(00)
  DUMPSPACE(8192)
/* Define other structures required by sysplex here . . . */
...
/* Define logger structures for CICS log streams. */
/* - If a choice of facilities is available, use non-volatile */
/*   facilities if possible */
/* - Specify low REBUILDPERCENT so that structures are rebuilt */
/*   in the event of connectivity failure */
/* - INITSIZE gives initial coupling facility size (based on sizing calcs) */
/* - SIZE should be larger to allow for rebuild to a larger */
/*   size if INITSIZE proves to be too small */
/* - SIZE and INITSIZE values are for illustration only - */
/*   substitute values appropriate for your intended usage. */

STRUCTURE NAME(LOG_DFHLOG_001) /* CICS system logs */
  INITSIZE(10000) SIZE(16000)
  PREFLIST(cfname) REBUILDPERCENT(1)

STRUCTURE NAME(LOG_DFHSUNT_001) /* CICS secondary logs */
  INITSIZE(10000) SIZE(16000)
  PREFLIST(cfname) REBUILDPERCENT(1)

STRUCTURE NAME(LOG_USERJNL_001) /* CICS user journals */
  INITSIZE(10000) SIZE(16000)
  PREFLIST(cfname) REBUILDPERCENT(1)

STRUCTURE NAME(LOG_GENERAL_001) /* Forward recovery logs */
  INITSIZE(10000) SIZE(16000)
  PREFLIST(cfname) REBUILDPERCENT(1)
/*
//

```

Figure 12. Sample policy job to define logger structures to CFRM 1/2

Multiple log streams can write data to a single coupling facility structure. This does not mean that the log data is merged; the log data stays segregated according to

log stream. You can specify the number of log streams that use the resources of a single coupling facility structure using the LOGSNUM parameter on the IXCMIAPU service to define a structure.

Each log stream is allocated a proportion of the structure space based on the number of currently connected log streams (up to the limit specified in LOGSNUM).

For example, a structure may be defined to contain a maximum of, say, 30 log streams. If only 10 log streams are connected, each log stream can use one tenth of the space in the structure. As other log streams are connected and disconnected, the MVS system logger adjusts the proportion of space to be used by each log stream.

It is important to plan carefully before specifying a value for LOGSNUM, because this parameter determines how much storage space in the structure is available to each log stream. A number in the range 10 to 20 is optimum in many environments.

The JCL in Figure 13 defines log stream coupling facility structures to the MVS system logger. It is meant for guidance only and you should substitute values appropriate to your requirements.

```
//DEFSTRUC JOB ...
//POLICY EXEC PGM=IXCMIAPU
//STEPLIB DD DSN=SYS1.MIGLIB,DISP=SHR
//SYSPRINT DD SYSOUT=*
//*****
//*
//* Define log stream coupling facility structures to the MVS logger *
//*
//* AVGBUFSIZE and LOGSNUM values are just for illustration, *
//* substitute values appropriate to your intended usage *
//*
//*****
//SYSIN DD *
DATA TYPE(LOGR) REPORT(YES)

/* System logs */
DEFINE STRUCTURE NAME(LOG_DFHLOG_001) LOGSNUM(10)
MAXBUFSIZE(64000) AVGBUFSIZE(500)

/* Secondary system logs */
DEFINE STRUCTURE NAME(LOG_DFHSHUNT_001) LOGSNUM(10)
MAXBUFSIZE(64000) AVGBUFSIZE(4096)

/* User journals with unforced writes */
DEFINE STRUCTURE NAME(LOG_USERJRNL_001) LOGSNUM(10)
MAXBUFSIZE(64000) AVGBUFSIZE(64000)

/* Fwd recovery logs and user jnl's that are forced */
DEFINE STRUCTURE NAME(LOG_GENERAL_001) LOGSNUM(10)
MAXBUFSIZE(64000) AVGBUFSIZE(2048)

/*
//
```

Figure 13. Sample JCL to define coupling facility structures to MVS system logger

See the *z/OS MVS Programming: Assembler Services Guide*/*z/OS MVS Programming: Assembler Services Guide* for information on planning coupling facility configurations.

Planning considerations for the number of log structures

Bear in mind the following points when planning the definition of your coupling facility structures:

- The CFRM policy allows a maximum of 255 structures for all purposes.
- Allow a maximum of 20 log streams per structure.
- Smaller structures are more quickly allocated, rebuilt, and recovered than larger ones.
- It is good practice to keep the log streams for test CICS systems (and other systems not in regular use) in structures separate from the structures holding the log streams of production CICS systems. This avoids the structure space available to production CICS systems being affected by structure usage of the test CICS systems.
- It is good practice to keep the log streams for terminal-owning regions (TORs) in structures separate to those accommodating log streams for application-owning regions (AORs). In addition, keep log streams for file-owning regions in structures separate to those accommodating log streams for TORs and AORs.
- Share structures between MVS images. If an MVS image or logger address space fails, and a surviving MVS image is using the same log stream structures (although not necessarily the same log streams), the surviving image is notified of the failure and can initiate immediate log stream recovery for the failing MVS. Recovery would, otherwise, be delayed until the next time that a system attempts to connect to a log stream in the affected structures, or until the logger address space of the failing system is restarted.

For example, in a 4-way sysplex comprising MVSA, MVSB, MVSC, and MVSD, you might have the CICS regions that normally run on MVSA and MVSB use structure LOG_DFHLOG_001, and the regions that run on MVSC and MVSD use structure LOG_DFHLOG_002. Thus each MVS image has a partner to recover its log streams in the event of an MVS failure. If a structure fails, the two MVS images using the other structure can take over the workload. Also, if you have more than one coupling facility, allocate the system log structures to different coupling facilities. See Figure 14 for an illustration of this example.




Figure 14. Sharing system logger structures between MVS images

- Use the appropriate buffer size. The average buffer size (AVGBUFSIZE) defined for a structure should be reasonably close to the actual buffer size of the log streams using the structure. If it is not, there is a risk that usable space will be exhausted long before the structure is actually full.

Important:

1. OS/390 (since Release 3) dynamically tunes the element/entry ratio, so the value you specify for AVGBUFSIZE is less important than it was on earlier releases of MVS.
 2. AVGBUFSIZE, like other structure definition attributes such as MAXBUFSIZE and LOGSNUM, cannot be updated unless you first delete the log streams in the structure definition.
- Set MAXBUFSIZE to slightly less than 64K - say, 64000. This allows CICS to write the maximum size user record and allows coupling facility storage to be allocated in 256-byte units. If you allow MAXBUFSIZE to default, coupling facility storage is allocated in 512-byte units. This can be wasteful of storage.
There is no significant advantage in setting MAXBUFSIZE lower than 64000 as far as the utilization of storage is concerned.
 - Set a low value for the REBUILDPERCENT parameter in the CFRM policy for log structures used for CICS system logs.

Log structure naming conventions

It is sensible to adopt a naming convention for your coupling facility structures that help to identify the purpose of the structure. A format such as LOG_*purpose_nnn* is recommended, where:

- *purpose* identifies the type of use of the structure.
- *nnn* is a sequence number to allow for more than one structure for each purpose.

Some examples are:

LOG_DFHLOG_001

For the CICS primary system log. The structure should be large to avoid the need to write data to DASD. The average buffer size would be small. See the sizing calculations in “Structure size for system log usage” on page 161.

LOG_DFHSUNT_001

For the CICS secondary system log. The structure should be small but requires a large buffer size. A structure of 150K per log stream may well be sufficient.

LOG_USERJRNL_001

For user journals where block writes are not forced. The average and maximum buffer sizes of these structures should be the same.

LOG_GENERAL_001

For forward recovery logs and user journals where block writes are forced periodically.

See also the section “Develop a naming convention for system logger resources” in the *z/OS MVS Setting Up a Sysplex* manual.

Defining coupling facility log streams

Use the MVS IXCMIAPU utility to define coupling facility log streams to the LOGR couple data set. The basic syntax to define a coupling facility log stream is as follows:

```

DEFINE LOGSTREAM NAME(log_stream_name)
                STRUCTNAME(structure_name)
                LOWOFFLOAD(low_offload) HIGHOFFLOAD(high_offload)
                STG_DUPLEX(YES|NO) DUPLEXMODE(COND|UNCOND)

```

For detailed information about the full range of log stream attributes, see the *OS/390 Setting Up a Sysplex* manual. Figure 15 shows example definitions for a pair of coupling facility log streams associated with a CICS system log.

```

//DEFLOGS JOB ...
//LOGDEFN EXEC PGM=IXCMIAPU
//STEPLIB DD DSN=SYS1.MIGLIB,DISP=SHR
//SYSPRINT DD SYSOUT=*
//*****
//*
//* Define coupling facility log streams for CICS system log.
//*
//* The LOWOFFLOAD value is for illustration only --
//* substitute a value appropriate for your environment.
//*
//*****
//SYSIN DD *
DATA TYPE(LOGR) REPORT(NO)
DEFINE LOGSTREAM NAME(region_userid.applid.DFHLOG)
                STRUCTNAME(LOG_DFHLOG_001)
                LOWOFFLOAD(40) HIGHOFFLOAD(80)
                STG_DUPLEX(YES) DUPLEXMODE(COND)
DEFINE LOGSTREAM NAME(region_userid.applid.DFHSUNT)
                STRUCTNAME(LOG_DFHSUNT_001)
                LOWOFFLOAD(40) HIGHOFFLOAD(80)
                STG_DUPLEX(YES) DUPLEXMODE(COND)

```

Figure 15. Example definitions of coupling facility log streams. The definitions are for the CICS primary and secondary system log streams. The value **region_userid** is the RACF userid under which the CICS address space is running; **applid** is the CICS region's VTAM APPL name (taken from the APPLID system initialization parameter).

Using model log streams

To avoid having to define explicitly each log stream used by each of your CICS regions, you can use model log stream definitions. Using models, log streams are defined to MVS dynamically, on their first usage. Figure 16 on page 158 shows an example of coupling facility model definitions for CICS primary and secondary system log streams.

```

//DEFLOGS JOB ...
//LOGDEFN EXEC PGM=IXCMIAPU
//STEPLIB DD DSN=SYS1.MIGLIB,DISP=SHR
//SYSPRINT DD SYSOUT=*
//*****
//*
//* Define coupling facility model log streams for CICS system log.*
//*
//* The LOWOFFLOAD value is for illustration only --
//* substitute a value appropriate for your environment.
//*
//*****
//SYSIN DD *
DATA TYPE(LOGR) REPORT(NO)
DEFINE LOGSTREAM NAME(sysname.DFHLOG.MODEL)
MODEL(YES)
STRUCTNAME(LOG_DFHLOG_001)
LOWOFFLOAD(40) HIGHOFFLOAD(80)
STG_DUPLEX(YES) DUPLEXMODE(COND)
DEFINE LOGSTREAM NAME(sysname.DFHSUNT.MODEL)
MODEL(YES)
STRUCTNAME(LOG_DFHSUNT_001)
LOWOFFLOAD(40) HIGHOFFLOAD(80)
STG_DUPLEX(YES) DUPLEXMODE(COND)

```

Figure 16. Example model definitions for coupling facility system log streams. The value **sysname** is the sysid of the MVS image in which the CICS region or regions are running.

For detailed information about using model log streams, see the *CICS Recovery and Restart Guide*. For information about the mapping of CICS journal definitions to log stream names, see the *CICS System Definition Guide*.

When using model log streams, you need to bear the following in mind:

- For coupling facility log streams, a model log stream definition determines the coupling facility structure in which the new log streams are created. On an MVS image that runs both CICS production and CICS test regions, take care that the system logs for the production regions are kept separate from the system logs for the test regions.
- There are recovery considerations when using model log streams to define CICS system logs—see the *CICS Recovery and Restart Guide*.

Sizing considerations for coupling facility log streams

This section discusses how to size the following types of coupling facility log stream:

- The CICS primary and secondary system log streams
- Forward recovery logs
- User journals and autojournals.

Sizing DFHLOG

For the CICS primary system log stream (DFHLOG), it is important to:

- **Minimize the amount of data that is offloaded to secondary storage:**
The MVS system logger begins the offload process when the high offload threshold (HIGHOFFLOAD) of the log stream is reached. The offload process consists of two steps:
 1. The MVS logger physically deletes the data in the log stream that has been marked for deletion by the CICS log-tail deletion process.

2. The MVS logger calculates how much data needs to be offloaded to secondary storage, based on the difference between HIGHOFFLOAD and LOWOFFLOAD, less the amount of data that has been deleted since the last offload event.

To minimize the amount of data offloaded from the CICS primary system log:

- Define a suitably-sized coupling facility structure. For advice, see “Recommendations.”
- Ensure that the log-tail deletion process is working effectively. For detailed information about the log tail deletion process, see the *CICS Recovery and Restart Guide*.

- **Avoid “structure-full” events:**

A structure-full event occurs when a log stream’s structure space becomes full before the offloading of data has completed.

For advice on monitoring and avoiding structure-full events, see the *CICS Performance Guide* .

Sizing DFHSHUNT

It is important to size the secondary system log stream (DFHSHUNT) to avoid structure-full events. However, it is normal for some data to be offloaded from DFHSHUNT to secondary storage.

Sizing general logs

It is important to size forward recovery logs, user journals, and autojournals to avoid structure-full events. However, because CICS does not delete data from these log streams, it is normal for data to be offloaded to secondary storage.

Recommendations

Table 11 summarizes how you should decide on the values for various attributes on the structure definition, log stream definition, and system definition.

Table 11. How to decide on the values of attributes

Facility	Attribute	Recommendation
Structure	INITSIZE	Use the DFHLSCU utility program or the formula on page “INITSIZE calculation” on page 161.
	SIZE	Use DFHLSCU or the formula on page “SIZE calculation” on page 163.
	AVGBUFSIZE	Use DFHLSCU or the formula on page “AVGBUFSIZE calculation” on page 162. Underestimate rather than overestimate.
	MAXBUFSIZE	64000
Primary system log stream (DFHLOG)	HIGHOFFLOAD	80
	LOWOFFLOAD	Use DFHLSCU or the formula on page “LOWOFFLOAD calculation” on page 163.
Secondary system log stream (DFHSHUNT)	HIGHOFFLOAD	80
	LOWOFFLOAD	0
General log stream	HIGHOFFLOAD	80
	LOWOFFLOAD	40 – 60
Log stream	STG_SIZE	Use DFHLSCU or the formula on page “Staging data set size calculation” on page 167. Overestimate rather than underestimate.

Table 11. How to decide on the values of attributes (continued)

Facility	Attribute	Recommendation
CICS system	AKPFREQ	4000

Note: Startup may take longer than you experienced when using earlier releases. This is due in part to the allocation and formatting of the staging data sets. The increased time that startup takes is dependent on such things as:

- Size of staging data set (STG_SIZE)
- DASD speed
- DASD contention

It can be reduced by avoiding the use of unnecessarily large staging data sets.

The log stream sizing utility, DFHLSCU

If you are migrating from CICS/ESA 3.3 or CICS/ESA 4.1, you are strongly recommended to use the CICS-supplied utility program, DFHLSCU, to help you calculate your space requirements. DFHLSCU takes as input “old-style” (pre-CICS Transaction Server for OS/390, Version 1 Release 1-format) journal records, and analyzes them to establish values for:

AVGBUFSIZE

The average buffer size, in bytes, of a log stream structure in the coupling facility. Although it is important, that the value you specify for AVGBUFSIZE reflects as accurately as possible the real size of most log blocks written to the structure. This leads to efficient use of the space in the coupling facility and minimum DASD offloading frequency. However OS/390 (since release 3) performs some dynamic tuning, reducing the importance of the value you specify for AVGBUFSIZE.

You define this attribute in your DEFINE STRUCTURE job.

INITSIZE

The initial amount of space, in kilobytes, to be allocated for the log stream structure in the coupling facility. You define this attribute in your CFRM policy.

HIGHOFFLOAD

The point in primary storage (that is, in either the coupling facility structure or the staging data set), as a percentage of space consumed, where the MVS system logger starts its offload process. You define this attribute in your DEFINE LOGSTREAM job.

LOWOFFLOAD

The point in primary storage, as a percentage of space consumed, where the MVS system logger stops offloading data from primary storage to log stream DASD data sets. You define this attribute in your DEFINE LOGSTREAM job.

SIZE The maximum size, in kilobytes, of the log stream structure in the coupling facility. You define this attribute in your CFRM policy. The value of the SIZE attribute is approximately 50% greater than the value of the INITSIZE attribute. You can dynamically increase the log stream structure size up to the value of the SIZE attribute.

STG_SIZE

The size, as a number of 4K blocks, of the staging data set for the log

stream. A coupling facility log stream may or may not use a staging data set. For advice on the use of staging data sets with coupling facility log streams, see “Staging data sets for coupling facility log streams” on page 166.

You define this attribute in the DEFINE LOGSTREAM statements of your IXCMIAPU job. If you are using a staging data set and do not specify STG_SIZE, the MVS logger determines the size from

- The STG_SIZE parameter of the log stream defined on the LIKE parameter
- Uses the maximum coupling facility structure size for the structure to which the log stream is defined. This value is obtained from the SIZE parameter of the structure in the CRFM policy.

For details on how to use DFHLSCU, see the *CICS Operations and Utilities Guide* .

If DFHLSCU is inappropriate for use in your environment

If it is inappropriate for you to use DFHLSCU to help you size your coupling facility structures and log streams (perhaps you have no CICS Version 4 or Version 3 journal records to use as input to DFHLSCU, or you are capacity planning for new applications), the following sections help you to calculate your space requirements.

The formulae provided help you to calculate values for:

- INITSIZE
- AVGBUFSIZE
- SIZE
- LOWOFFLOAD
- STG_SIZE

You must base your calculations on the journaling requirements of your applications. This provides the starting point for the following formulae.

Structure size for system log usage: You are recommended not to place the primary and secondary log streams in the same structure due to the large disparity in data volumes written to the primary and secondary system logs.

Generally, the volume of data that CICS keeps in the primary system log at any one time is slightly greater than the amount written during one activity keypoint interval. This volume is determined by the activity keypoint frequency, which is measured in the number of write requests to the CICS system log stream output buffer, and defined on the AKPFREQ system initialization parameter. Review the value specified on the AKPFREQ system initialization parameter when planning coupling facility structure sizes.

The **INITSIZE** value to be supplied in the CFRM policy can be calculated as follows:

$$\begin{aligned} \text{INITSIZE} &= 310 + (\text{LOGSNUM} * A * B / 1024) \\ \text{where } A &= 2000 + (\text{no. entries} + 5) \\ \text{and } B &= (\text{AVGBUFSIZE} * 1.1289) + 195 \end{aligned}$$

Figure 17. INITSIZE calculation

The value for the number of entries (no. entries) can be calculated as follows:

$$\text{no. entries} = ((\text{akpintvl} + \text{trandur}) * \text{writespersec}) / 0.9$$

where:

- akpintv1 is the interval between activity keypoints which varies with workload. It can be calculated as follows:

$$\text{akpintv1} = \text{AKPFREQ} / ((\text{N1} * \text{R1}) + (\text{N2} * \text{R2}) + (\text{Nn} * \text{Rn}))$$

where:

- N1, N2 Nn is the transaction rate for each transaction (transactions per second).
- R1, R2 Rn is the number of log records written by each transaction.
- trandur is the execution time (between syncpoints) of the longest-running transaction that runs as part of the normal workload.
If this duration is longer than akpintv1 value, you can either:
 - Increase the value of AKPFREQ, so increasing the value of akpintv1 (as long as this does not result in an unacceptably large coupling facility structure size).
 - Change the application logic to cause more frequent syncpoints.
 - Calculate a structure size based on a shorter transaction duration, and accept that DASD offloading occurs when the long-running transaction is used.
- writespersec = lesser of 25 or $((\text{N1} * \text{R1}) + \dots (\text{Nn} * \text{Rn}))$, where:
 - N1, N2 Nn are the transaction frequencies (transactions per second) of the most frequently executed transactions.
 - R1, R2 Rn is the number of log records written by each transaction.

You can calculate **AVGBUFSIZE** for DFHLOG from the weighted average of the data logged by the most frequently executed transactions in the system:

$$\text{AVGBUFSIZE} = (\text{bytespersec} / \text{writespersec}) + 48$$

where:

- bytespersec = $(\text{N1} * \text{D1}) + (\text{N2} * \text{D2}) + \dots (\text{Nn} * \text{Dn})$, where:
 - N1, N2 Nn are the transaction frequencies (transactions per second) of the most frequently executed transactions.
 - D1, D2 Dn are the bytes of data logged by each transaction.

You can calculate the amount of data (Dn) written to the system log for each transaction:

$$\begin{aligned} \text{Dn} = & \text{Ns} * \text{syncrcLen} + \\ & \text{Nfc} * (\text{fcrechdr} + \text{fcreclen}) + \\ & \text{Nts} * (\text{tsrechdr} + \text{tsreclen}) + \\ & \text{Ntd} * (\text{tdrechdr} + \text{tdreclen}) + \\ & \text{Nur} * (\text{urrechdr} + \text{urreclen}) \end{aligned}$$

where:

- Ns is the number of syncpoints per transaction - usually 1.
- syncrcLen is the syncpoint record length.
- Nfc, fcrechdr, fcreclen are, respectively, the number of recoverable updates made, the length of the record headers, and the length of the records for file control.

Count only READ UPDATE and WRITE ADD records. fcrechdr is **144** (136 bytes of record header plus 8 bytes of file name).

Similarly:

- Nts, tsrechdr, tsreclen are for recoverable temporary storage updates.
Count only TS PUT and TS UPDATE records.

For TS PUT records, tsrechdr is **108**, and tsreclen is **88**.

For TS UPDATE records, tsrechdr is **108**, and tsreclen is **52**.

- Ntd, tdtrechdr, tdreclen are for recoverable transient data updates. tdtrechdr is **108**, and tdreclen is **380**.
 - Nur, urrechdr, urreclen are for user records written to DFHLOG. urrechdr is **125**.
- See page “Writes per second calculation” on page 162 for details of how to calculate writespersec

If the result of the calculation shows a value for AVGBUFSIZE that is greater than the value defined for MAXBUFSIZE, then the value defined for MAXBUFSIZE is taken as the value for AVGBUFSIZE, and writespersec is calculated as follows:

$$\text{writespersec} = \text{bytespersec} / (\text{MAXBUFSIZE} - 48)$$

Round the final result of the INITSIZE formula up to the next multiple of 256.

The **SIZE** value to be supplied in the CFRM policy can be calculated as follows:

$$\begin{aligned} \text{SIZE} &= 480 + (\text{LOGSNUM} * \text{A} * \text{B} / 1024) \\ \text{where } \text{A} &= 2500 + (\text{no. entries} + 5) \\ \text{and } \text{B} &= (\text{AVGBUFSIZE} * 1.6821) + 289 \end{aligned}$$

Figure 18. SIZE calculation

Calculate the value for the number of entries as in the INITSIZE formula.

Round the final result of the SIZE formula up to the next multiple of 256. The formula for SIZE gives a result that is approximately fifty percent greater than the INITSIZE value.

Generally, the secondary system log stream needs to be only a fraction of the size of the primary log stream. Use the following formulae to calculate coupling facility space for **DFHSHUNT**:

$$\begin{aligned} \text{INITSIZE} &= (150 * \text{LOGSNUM}) + 310 \\ \text{SIZE} &= (230 * \text{LOGSNUM}) + 480 \end{aligned}$$

You can calculate a suitable value for **LOWOFFLOAD** for DFHLOG using the following formula:

$$\text{LOWOFFLOAD} = (\text{trandur} * 90) / (\text{akpintvl} + \text{trandur}) + 10 \quad (\text{where RETPD}=0 \text{ specified})$$

or

$$\text{LOWOFFLOAD} = (\text{trandur} * 90) / (\text{akpintvl} + \text{trandur}) \quad (\text{where RETPD}=dddd \text{ specified})$$

where:

- akpintvl is the interval between activity keypoints. See page 161 for the formula to calculate it.
- trandur is the execution time (between syncpoints) of the longest-running transaction that runs as part of the normal workload.

If this duration is longer than akpintvl value, you can either:

- Increase the value of AKPFREQ, so increasing the value of akpintvl (as long as this does not result in an unacceptably large coupling facility structure size).
- Change the application logic to cause more frequent syncpoints.

- Calculate a structure size based on a shorter transaction duration, and accept that DASD offloading occurs when the long-running transaction is used.

Structure size for forward recovery log usage: You can merge the forward recovery logs written by many CICS regions onto the same log stream. You can also use the same log stream for forward recovery data for multiple data sets.

See Figure 17 on page 161 and Figure 18 on page 163 for the formulae to calculate values for the **INITSIZE** and **SIZE** attributes.

Calculate a value for number of entries as follows:

$$\text{no. entries} = \text{writespersec} * 12.5$$

where:

$$\text{writespersec} = \text{lesser of } 25 \text{ or } (N1 + \dots + Nn)$$

where N1 Nn is the number of transactions per second writing to each data set.

You can calculate **AVGBUFSIZE** as follows:

$$\text{AVGBUFSIZE} = (\text{bytespersec} / \text{writespersec}) + 36$$

where:

- $\text{bytespersec} = (N1 * Wr1 * (D1 + \text{rechdr}) + \dots + (Nn * Wrn * (Dn + \text{rechdr})))$
- $\text{writespersec} = \text{lesser of } 25 \text{ or } (N1 + \dots + Nn)$, where:
 - N1 Nn is the number of transactions per second writing to each data set.
 - Wr1 Wrn is the number of write requests per transaction.
 - D1 Dn is the average record length for each data set.
- rechdr is the record header length of each record.

If the records are WRITE ADD, WRITE ADD COMPLETE, or WRITE ADD DELETE records, rechdr is **84** and is followed by the record key, and the record data (including its key).

If the result of the calculation shows a value for AVGBUFSIZE that is greater than the value defined for MAXBUFSIZE, then the value defined for MAXBUFSIZE is taken as the value for AVGBUFSIZE, and writespersec is calculated as follows:

$$\text{writespersec} = \text{bytespersec} / (\text{MAXBUFSIZE} - 36)$$

Structure size for user journal and autojournal usage: See Figure 17 on page 161 and Figure 18 on page 163 for the formulae to calculate values for the **INITSIZE** and **SIZE** attributes.

Calculate a value for number of entries as follows:

$$\text{no. entries} = \text{writespersec} * 12.5$$

See the explanation of writespersec below.

For journals where the log blocks are not forced to the log stream, the average block size tends to be slightly less than the MAXBUFSIZE value defined for the coupling facility structure.

For journals where the log blocks are forced to the log, (via the EXEC CICS WAIT JOURNALNAME or EXEC CICS WAIT JOURNALNUM commands, or via the WAIT

option of the EXEC CICS WRITE JOURNALNAME or EXEC CICS WRITE JOURNALNUM commands), you can calculate **AVGBUFSIZE** from the weighted average of the data logged for each journal logging to the same log stream for a given CICS system.

$$\text{AVGBUFSIZE} = (\text{bytespersec} / (\text{writespersec}) + 36$$

where:

- $\text{bytespersec} = (N1 * Wr1 * (D1 + \text{rechdr}) + \dots (Nn * Wrn * (Dn + \text{rechdr})))$
- $\text{writespersec} = \text{lesser of } 25 \text{ or } ((N1 * Wa1) + \dots + (Nn * Wan))$ where:
 - $N1, \dots, Nn$ is the number of transactions per second writing to the journal.
 - $Wr1 \dots Wrn$ is the number of write requests per transaction.
 - $Wa1 \dots Wan$ is the number of wait requests per transaction.
 - $D1 \dots Dn$ is the average record length of each journal record.
 - rechdr is the record header length of each record.

Autojournal records are issued from file control. They may be DATA SET NAME records which consist of a **204**-byte record header, and no further data. Alternatively, they may be READ ONLY, READ UPDATE, WRITE UPDATE, WRITE ADD, or WRITE ADD COMPLETE records. In this case, rechdr is **84** and is followed by the file control record itself.

User journal records consist of a **68**-byte record header, followed by the user prefix, and the user data.

If the result of the calculation shows a value for AVGBUFSIZE that is greater than the value defined for MAXBUFSIZE, then the value defined for MAXBUFSIZE is taken as the value for AVGBUFSIZE, and writespersec is calculated as follows:

$$\text{writespersec} = \text{bytespersec} / (\text{MAXBUFSIZE} - 36)$$

Coupling facility requirements in an RLS environment

When you move to an RLS environment from an environment in which multiple AORs have been accessing data sets in an FOR, the logging activity of the FOR is distributed across the AORs. As a consequence, the coupling facility structure size required by each AOR increases.

You can use the formulae for INITSIZE and SIZE, given in Figure 17 on page 161 and Figure 18 on page 163. However, you need to calculate values for:

- avgbufize
- number of entries
- akpintl .

using formulae which are different to those already described.

Use either reports produced by DFHLSCU for the CICS/ESA 4.1 AOR and FOR system logs, or log stream statistics from CICS Transaction Server for z/OS, to calculate

- The number of log write operations, and
- The amount of data written

in a reporting interval for the AORs and the FOR.

Calculating increased AOR coupling facility storage requirements

Use the following formulae to calculate:

- avgbufize
- number of entries
- akpintvl.

for the AORs in the new RLS environment.

Calculate the AOR AVGBUFSIZE value required by the INITSIZE and SIZE formulae as follows:

$$\text{AOR AVGBUFSIZE} = (\text{AOR_bytes} + (\text{FOR_bytes} / \text{no. of AORs})) / (\text{intvlen} * 25)$$

where:

- AOR_bytes is the number of bytes written to the system log by an AOR in the sampling interval.
- FOR_bytes is the number of bytes written to the system log by an FOR in the sampling interval.
- no of AORs is the number of cloned AORs using the FOR.
- intvlen is the length (in seconds) of the sampling interval (statistics or DFHLSCU).

Calculate the AOR 'number of entries' value required by the INITSIZE and SIZE formulae as follows:

$$\text{AOR no. entries} = ((\text{AOR_akpintvl} + \text{trandur}) * 25) / 0.9$$

where:

- $\text{AOR_akpintvl} = (\text{AKPFREQ} * \text{intvlen}) / (\text{AOR_recs} + (\text{FOR_recs} / \text{no. of AORs}))$

where:

- intvlen is the length (in seconds) of the sampling interval (statistics or DFHLSCU).
- AOR_rec s is the number of records written to the system log by an AOR in the sampling interval.
- FOR_rec s is the number of records written to the system log by an FOR in the sampling interval.
- no of AORs is the number of cloned AORs using the FOR.
- trandur is the execution time (between syncpoints) of the longest-running transaction that runs as part of the normal workload.

If this is longer than AOR_akpintvl, use AOR_akpintvl as the duration or consider increasing AKPFREQ.

Once you have calculated the values for AOR AVGBUFSIZE and AOR no. entries, use the formulae for INITSIZE and SIZE, as described in Figure 17 on page 161 and Figure 18 on page 163.

Staging data sets for coupling facility log streams

MVS normally keeps a second copy of the data written to the coupling facility in a data space, for use when rebuilding a coupling facility log in the event of an error. This is satisfactory as long as the coupling facility is failure-independent (in a separate CPC and non-volatile) from MVS.

Where the coupling facility is in the same CPC, or uses volatile storage, the MVS system logger supports staging data sets for copies of log stream data that would otherwise be vulnerable to failures that impact both the coupling facility and the MVS images.

The following **recommendations** are for guidance when defining log streams:

- Define STG_DUPLEX(YES) and DUPLEXMODE(COND) for those log streams associated with the system log. This ensures that the MVS system logger automatically copies to staging data sets if it detects that the coupling facility is not failure-independent and a single point of failure, and is therefore vulnerable to permanent log data loss.

A connection to a log stream contains a single point of failure if the coupling facility is volatile or it resides on the same CPC as the MVS system connecting to it. For example, if you have two CPCs, CPC1 and CPC2, and CPC1 has an MVS LPAR and a coupling facility, while CPC2 has only MVS LPARs, the connections from the MVS LPAR in CPC1 to the coupling facility are failure dependent—if you lose CPC1 you lose both MVS and its local buffers and the coupling facility. On the other hand, the connections from CPC2 are failure independent, because the system logger local storage and buffers are in a physically separate CPC from the coupling facility, and you would have to lose both to lose data. With DUPLEXMODE(COND), failure dependent connections result in staging sets, while failure independent connections are not allocated staging data sets.

- If you are operating with only a single coupling facility, you should define STG_DUPLEX(YES) and DUPLEXMODE(UNCOND) for those log streams associated with the system log.
- Define STG_DUPLEX(YES) and DUPLEXMODE(COND) for those log streams associated with forward recovery logs. If you do not, and there is a failure which causes loss of data from the log stream, you would need to take a new image copy of the associated VSAM data sets. There would be a consequent period of time until this was complete when the data sets would not be fully protected.
- If you operate a non-volatile, stand-alone coupling facility for normal logging, with a PR/SM LPAR configured as a coupling facility acting as backup, define all log streams with STG_DUPLEX(YES) and DUPLEXMODE(COND).
- Define each staging data set to be at least the same size as the log stream share of the coupling facility, but round the average block size up to 4K.

For example, the staging data set size corresponding to the basic coupling facility space requirement for each CICS system log stream (DFHLOG) can be calculated by the following formula:

$$\text{staging data set size} = \text{entries} * \text{rnd-avg-buf} / 4096$$

where:

$$\text{rnd-avg-buf} = \text{avgbufsize (rounded up to 4K)}$$

See page “number of entries calculation” on page 161 for the formula to calculate no. entries.

DASD-only log streams

The CICS log manager supports the DASD-only option of the MVS system logger. Individual CICS log streams can use either coupling facility log structures or DASD-only logging. Reasons for defining a log stream to use DASD-only logging include:

- You do not have a coupling facility.
- You want to preserve coupling facility space for other uses.

- You do not need to share the log stream across MVS systems. (The CICS system log can never be shared.)

See page “Setting up the environment for CICS log manager” on page 150 for advice about defining individual log streams to use coupling facility or DASD-only logging, based on their usage.

Defining DASD-only log streams

Use the MVS IXCMIAPU utility to define DASD-only log streams to the LOGR couple data set. The basic syntax to define a DASD-only log stream is as follows:

```
DEFINE LOGSTREAM NAME(log_stream_name)
    DASDONLY(YES)
    MAXBUFSIZE(max_bufsize)
    STG_SIZE(stg_size)
    HIGHOFFLOAD(high_offload)
    LOWOFFLOAD(low_offload)
```

For detailed information about the full range of log stream attributes, see the *OS/390 Setting Up a Sysplex* manual. Figure 19 shows example definitions for a pair of log streams associated with a DASD-only system log.

```
//DEFLOGS JOB ...
//LOGDEFN EXEC PGM=IXCMIAPU
//STEPLIB DD DSN=SYS1.MIGLIB,DISP=SHR
//SYSPRINT DD SYSOUT=*
//*****
//*
//* Define DASD-only log streams for CICS system log.
//*
//* The LOWOFFLOAD and STG_SIZE values are for illustration
//* only -- substitute values appropriate for your environment.
//*
//*****
//SYSIN DD *
DATA TYPE(LOGR) REPORT(NO)
DEFINE LOGSTREAM NAME(region_userid.applid.DFHLOG)
    DASDONLY(YES)
    MAXBUFSIZE(64000) STG_SIZE(3000)
    LOWOFFLOAD(40) HIGHOFFLOAD(80)
DEFINE LOGSTREAM NAME(region_userid.applid.DFHSUNT)
    DASDONLY(YES)
    MAXBUFSIZE(64000) STG_SIZE(500)
    LOWOFFLOAD(40) HIGHOFFLOAD(80)
```

*Figure 19. Example definitions of DASD-only log streams. The definitions are for the CICS primary and secondary system log streams. The value **region_userid** is the RACF userid under which the CICS address space is running; **applid** is the CICS region's VTAM APPL name (taken from the APPLID system initialization parameter).*

Using model log streams

To avoid having to define explicitly each log stream used by each of your CICS regions, you can use model log stream definitions. Using models, log streams are defined to MVS dynamically, on their first usage. Figure 20 on page 169 shows example DASD-only model definitions for CICS primary and secondary system log streams.


```

//DEFLOGS JOB ...
//LOGDEFN EXEC PGM=IXCMIAPU
//STEPLIB DD DSN=SYS1.MIGLIB,DISP=SHR
//SYSPRINT DD SYSOUT=*
//*****
//*
//* Define DASD-only model log streams for CICS system log.      *
//*                                                                *
//* The LOWOFFLOAD and STG_SIZE values are for illustration      *
//* only -- substitute values appropriate for your environment.  *
//*                                                                *
//*****
//SYSIN DD *
DATA TYPE(LOGR) REPORT(NO)
DEFINE LOGSTREAM NAME(sysname.DFHLOG.MODEL)
MODEL(YES)
DASDONLY(YES)
MAXBUFSIZE(64000)
STG_SIZE(3000)
LOWOFFLOAD(40) HIGHOFFLOAD(80)
DEFINE LOGSTREAM NAME(sysname.DFHSHUNT.MODEL)
MODEL(YES)
DASDONLY(YES)
MAXBUFSIZE(64000)
STG_SIZE(500)
LOWOFFLOAD(40) HIGHOFFLOAD(80)

```

Figure 20. Example model definitions for DASD-only system log streams. The value **sysname** is the sysid of the MVS image in which the CICS region or regions are running.

For information about the mapping of CICS journal definitions to log stream names, see the *CICS System Definition Guide*.

When using model log streams, bear in mind that, if you specify a STG_SIZE on the model definition, all new log streams created from the model have the same-sized staging data set.

Sizing considerations for DASD-only log streams

This section discusses how to size the following types of DASD-only log stream:

- The CICS primary and secondary system log streams
- Forward recovery logs
- User journals and autojournals.

Sizing DFHLOG

For the CICS primary system log stream (DFHLOG), it is important to:

- **Minimize the amount of data that is offloaded to secondary storage:**

The MVS system logger begins the offload process when the high offload threshold (HIGHOFFLOAD) of the log stream is reached. The offload process consists of two steps:

1. The MVS logger physically deletes the data in the log stream that has been marked for deletion by the CICS log-tail deletion process.
2. The MVS logger calculates how much data needs to be offloaded to secondary storage, based on the difference between HIGHOFFLOAD and LOWOFFLOAD, less the amount of data that has been deleted since the last offload event.

To minimize the amount of data offloaded from the CICS primary system log, you must:

- Define a suitably-sized staging data set. For advice, see “Recommendations” on page 170.

Note: It is possible to alter the size of a staging data set without deleting the log stream. To do this, use the UPDATE LOGSTREAM request of the MVS IXCMIAPU utility to change the value of the STG_SIZE parameter.

- Ensure that the log-tail deletion process is working effectively. For detailed information about the log tail deletion process, see the *CICS Recovery and Restart Guide*.

- **Avoid “staging-data-set-full” events:**

A staging-data-set-full event occurs when a log stream’s staging data set becomes full before the offloading of data has completed.

For advice on monitoring and avoiding staging-data-set-full events, see the *CICS Performance Guide*.

Sizing DFHSHUNT

It is important to size the secondary system log stream (DFHSHUNT) to avoid staging-data-set-full events. However, it is normal for some data to be offloaded from DFHSHUNT to secondary storage.

Sizing general logs

It is important to size forward recovery logs, user journals, and autojournals to avoid staging-data-set-full events. However, because CICS does not delete data from these log streams, it is normal for data to be offloaded to secondary storage.

Recommendations

Table 12 summarizes how you should decide on the values for various attributes on the log stream definition, and system definition.

Table 12. How to decide on the values of attributes

Facility	Attribute	Recommendation
Primary system log stream (DFHLOG)	HIGHOFFLOAD	80
	LOWOFFLOAD	Use DFHLSCU or the formula on page “LOWOFFLOAD calculations” on page 172.
	MAXBUFSIZE	64000
	STG_SIZE	Use DFHLSCU or the formula on page “Staging DS size calculation” on page 172.
Secondary system log stream (DFHSHUNT)	HIGHOFFLOAD	80
	LOWOFFLOAD	40 – 60
	MAXBUFSIZE	64000
	STG_SIZE	500 (4K blocks)
General log stream	HIGHOFFLOAD	80
	LOWOFFLOAD	0
	MAXBUFSIZE	64000
	STG_SIZE	Use DFHLSCU or the formula on page “Staging data set size calculation” on page 167.
CICS system	AKPFREQ	4000

Note: Startup may take longer than you experienced when using earlier releases. This is due in part to the allocation and formatting of the staging data sets. The increased time that startup takes is dependent on such things as:

- Size of staging data set (STG_SIZE)

- DASD speed
- DASD contention

It can be reduced by avoiding the use of unnecessarily large staging data sets.

The log stream sizing utility, DFHLSCU

If you are migrating from CICS/ESA 3.3 or CICS/ESA 4.1, you are strongly recommended to use the CICS-supplied utility program, DFHLSCU, to help you define your DASD-only log streams. DFHLSCU takes as input “old-style” (pre-CICS Transaction Server for OS/390, Version 1 Release 1-format) journal records, and analyzes them to produce a sample log stream definition containing suggested values for:

DASDONLY(YES)

Specifies that this log stream is not to be associated with a coupling facility list structure, but is to use DASD-only logging. If you specify DASDONLY(YES), you cannot use the STRUCTNAME(log_structure_name) keyword. The default is DASDONLY(NO).

HIGHOFFLOAD(high_offload)

Specifies the point in primary storage, as a percentage of space consumed, at which the MVS system logger starts its offload process.

LOWOFFLOAD(low_offload)

Specifies the point in primary storage, as a percentage of space consumed, at which the MVS system logger stops offloading data to secondary storage.

MAXBUFSIZE(max_bufsize)

Specifies the size, in bytes, of the largest block of data that can be written to the log stream. The value must be in the range 1–65532. The default value is 65532.

STG_SIZE(stg_size)

Specifies, as a number of 4K blocks, the size of the staging data set for the log stream. A DASD-only log stream, by definition, always uses a staging data set as part of its primary storage.

If you do not specify STG_SIZE for a DASD-only log stream, the MVS system logger does one of the following, in the order listed, to allocate space for staging data sets:

1. Uses the STG_SIZE of the log stream specified on the LIKE parameter, if LIKE is specified
2. Uses the size defined in the SMS data class for the staging data sets
3. If SMS is not available, uses dynamic allocation rules for allocating data sets.

For more information about managing staging data sets for DASD-only log streams, see the *Setting Up a Sysplex* manual.

For details on how to use DFHLSCU, see the *CICS Operations and Utilities Guide*.

If DFHLSCU is inappropriate for use in your environment

If it is inappropriate for you to use DFHLSCU to help you size your log streams (perhaps you have no CICS Version 4 or Version 3 journal records to use as input to DFHLSCU, or you are capacity planning for new applications), the following sections help you to calculate your space requirements.

The formulae provided help you to calculate values for:

- LOWOFFLOAD
- STG_SIZE

You must base your calculations on the journaling requirements of your applications. This provides the starting point for the following formulae.

Primary system log (DFHLOG): You can calculate **LOWOFFLOAD** for DFHLOG using the following formula:

$LOWOFFLOAD = (trandur * 90) / (akpintv1 + trandur) + 10$ (where RETPD=0 specified)

or

$LOWOFFLOAD = (trandur * 90) / (akpintv1 + trandur)$ (where RETPD=dddd specified)

where:

- akpintv1 is the interval between activity keypoints. It can be calculated as follows:

$akpintv1 = AKPFREQ / ((N1 * R1) + (N2 * R2) + (Nn * Rn))$

where:

- N1, N2 Nn is the transaction rate for each transaction (transactions per second).
- R1, R2 Rn is the number of log records written by each transaction.
- trandur is the execution time (between syncpoints) of the longest-running transaction that runs as part of the normal workload.

If this duration is longer than akpintv1 value, you can either:

- Increase the value of AKPFREQ, so increasing the value of akpintv1 (as long as this does not result in an unacceptably large staging data set size).
- Change the application logic to cause more frequent syncpoints.
- Calculate a staging data set size based on a shorter transaction duration, and accept that offloading to secondary storage occurs when the long-running transaction is used.

You can calculate **STG_SIZE** for DFHLOG using the following formula:

Staging DS size = (AKP duration) * No. of log writes per second
for system log (no. of 4k blocks)
where AKP duration = (CICS TS 390 AKPFREQ)/(No. buffers per second)

The values for the number of log writes per second and buffer puts per second can be taken from your CICS/ESA 4.1 statistics. (The value for log writes per second should not exceed 30.)

Converting a DASD-only log stream to use a coupling facility

You can upgrade a DASD-only log stream to use a coupling facility structure, without having to delete and redefine the log stream. To do this:

1. Make sure that there are no connections (neither active nor failed) to the log stream.
2. Use the UPDATE LOGSTREAM request of the MVS IXCMIAPU utility. Specify the STRUCTNAME keyword, and let the DASDONLY keyword default to 'NO'.
For example:

```

//LOGUPDT JOB ...
//LOGUPDT EXEC PGM=IXCMIAPU
//SYSPRINT DD SYSOUT=A,DCB=RECFM=FBA
//*****
//*
//* Convert DSAD-only log stream to coupling facility log stream.*
//*
//*****
//SYSIN DD *
  DATA TYPE(LOGR) REPORT(NO)
  UPDATE LOGSTREAM NAME(region_userid.applid.DFHLOG)
                STRUCTNAME(LOG_DFHLOG_001)
                STG_DUPLEX(YES) DUPLEXMODE(COND)

```

Figure 21. Converting a DASD-only log stream to use a coupling facility structure. This example shows the CICS primary system log stream. The value **region_userid** is the RACF userid under which the CICS address space is running; **applid** is the CICS region's VTAM APPL name (taken from the APPLID system initialization parameter).

Notes:

1. If you want to upgrade a DASD-only log stream to a coupling facility log stream that does *not* use a staging data set, you must explicitly specify STG_DUPLEX(NO). (This is because the DASD-only log stream by definition uses a staging data set; unless you specify STG_DUPLEX(NO), this is retained by the coupling facility log stream.)
2. You cannot use UPDATE LOGSTREAM to convert a log stream that uses a coupling facility structure to one that uses DASD-only. To do this, you must delete and redefine the log stream.

Analyzing SMF Type 88 records

When reviewing the output from the system logger reports produced by IXGRPT1, IXGRPT1J, and IXGRPT1L, look at the following key fields for CICS system logs:

- The number of bytes deleted from primary storage should be close to the number of bytes written
- The number of bytes deleted from the system log *after* writing to offload data sets should be very low:
 - If this number is high, overhead is being incurred to move data to the offload data set only to be later deleted.
 - This is a key indicator that log tail deletion is not working as effectively as it should.
 - Check the MVS system log for any DFHRM0205 and DFHLG0743 messages from the affected CICS region.
 - Look for long running tasks (using CICS monitoring data or a system monitoring package), or check if AKPFREQ is too high.
- In general offloads are acceptable, but offloads triggered by NTRY FULL indicators are not a good sign:
 - NTRY FULL indicates that the entry to element ratio is too high
 - It is probably the result of having unlike logstreams defined in the same structure
 - The offloads are being triggered by all the entries being used rather than triggered by the HIGHOFFLOAD value.
- TYPE3 I/O counts should not appear in the statistics for coupling facility log streams, because these indicate that I/O is being initiated when over 90% of the elements for the log stream are in use.
- Average buffer size is important because:

- If over 4K, the writes are asynchronous, with a greater overhead, rather than synchronous
- Buffer size is used to determine the entry to element ratio.
- If MAXBUFSIZE specified on the log stream definition is *less than* 65532 bytes, the element size is 256 bytes.
- If MAXBUFSIZE is 65532 bytes, the element size is 512 bytes.
- The entry to element ratio is calculated as (average-buffer-size plus 4 divided by 4)

Managing secondary storage

This section contains advice on how to manage secondary storage—that is, log stream data sets.

Managing log data sets

You are recommended to use System Managed Storage (SMS) to manage log stream data sets. You can specify the SMS characteristics of log data sets in a number of ways, depending on your installation:

Using automatic class selection (ACS) routines

You can use installation-written automatic class selection (ACS) routines to assign log data sets to SMS classes.

Using the LOGR policy,

When you define or update a log stream definition in the LOGR policy, you can assign the SMS storage class, data class, and management class for both the DASD log data sets and staging data sets.

- Use LS_DATACLAS to specify the SMS data class to be used for log stream data set allocation.
- Use LS_STORCLAS to specify the SMS storage class to be used for log stream data set allocation.
- Use LS_SIZE to specify the size, in 4K blocks, of the log stream DASD data sets. Specify a size so that each data set can contain multiple offloads of the primary storage: this is particularly important where *all* the data is offloaded for a log stream, as in the case of user journals and forward recovery logs. The MVS system logger issues message IXG256I if you specify less than 64K.

If you omit the size parameter, the size is taken from the ALLOCxx member of PARMLIB (the default is 2 tracks, which leads to a high number of new data set allocations). Specify a size that is large enough to avoid a high frequency of new data set allocations—aim for a new data set to be allocated less often than once an hour.

SHAREOPTIONS(3,3)

Always define logger data sets with SHAREOPTIONS(3,3), whether the system is a part of a multiple-member sysplex or a monoplex. The common symptom of not having SHAREOPTIONS(3,3) is return code 84A or 403 from the logger.

For more information about managing log data sets, see the *z/OS MVS Setting Up a Sysplex* manual.

Log tail management

Redundant data should be deleted from log streams periodically, to conserve storage, and because the MVS system logger imposes a limit on the number of data sets per log stream.

The system log

CICS manages the system log by deleting records, for completed units of work, during activity keypoint processing (log-tail deletion). With an appropriately sized log stream, the system log data remains in primary storage, so avoiding the overhead of data spilling to DASD.

Note that:

- **The CICS system log should be used only for short-lived data required for recovery purposes.** You should not write user records for such things as audit trails to it.
- **You should allow CICS to manage the size of the system log.**

However, if historically you have used the system log for such things as audit trails, you may need to preserve system log data beyond the time it would normally be deleted by CICS. You can use the RETPD MVS parameter to preserve system log data. Define DFHLOG and DFHSHUNT to MVS with AUTODELETE(NO) and RETPD(dddd). The default values are AUTODELETE(NO) and RETPD(0.) Specifying AUTODELETE(NO) means that CICS, rather than MVS, retains control of the log-tail trimming process; dddd is the number of days for which data is to be retained. This causes the MVS logger to physically delete an entire log data set when *all* of the data in the data set:

1. Has been marked for deletion by the CICS log-tail trimming process
2. Is older than the retention period specified for the log stream.

You can view log data that has been marked for deletion by CICS but not yet physically deleted by MVS, using the DFHJUP utility program or the VIEW=ALL option of the MVS IXGBRWSE macro.

General logs

The number of data sets per log stream recognized by the MVS logger is several million. This means that, in general, you do not need to be concerned about the limit being reached.

You can cause redundant data to be deleted from log streams automatically, after a specified period. To arrange this for general log streams, define the logs to MVS with AUTODELETE(YES) and RETPD(dddd), where dddd is the number of days for which data is to be retained. This causes the MVS system logger to delete an entire log data set when all the data in it is older than the retention period (RETPD) specified for the log stream.

Note: Support for the removal of the 168 data set limit, which applied only in early releases of OS/390, and support for the AUTODELETE and RETPD parameters, requires the sysplex's LOGR couple data set to have been formatted using OS/390 Release 3 or later. The removal of the 168 data set limit also requires the LOGR data set to have been formatted with DSEXTENT(nnnnn).

Chapter 25. Enabling Unicode data conversion by z/OS

z/OS can provide support for the conversion of Unicode data (either UTF-8 or UTF-16) to any of the EBCDIC CCSIDs, currently supported by CICS. If you intend to make use of this capability, you must enable the z/OS conversion services and install a conversion image which specifies the conversions that you want CICS to perform. See “Selecting conversion images” for more information.

Important

z/OS Support for Unicode must be activated before you start CICS.

Refer to the instructions in the z/OS manual *Support for Unicode: Using Conversion Services SA22-7649*. (Level -02 of that publication relates to z/OS release 1.4), to find out the steps needed to set up your system and configure a suitable conversion image.

If z/OS conversion services are not enabled, a message is issued by CICS to indicate this. That message can be suppressed if you do not need these services.

- If the message is encountered when starting a CICS region that is expected to make use of these services, then an IPL is necessary to enable the z/OS conversion services.

To discover the status of z/OS conversion services after an IPL, use one of these commands:

<code>/D UNI</code>	To show whether z/OS conversion services were enabled.
<code>/D UNI,ALL</code>	To show whether z/OS conversion services were enabled, and which conversions are supported by the system.

from an MVS console. For details of this, see the z/OS Support for Unicode: Using Conversion Services manual SA22-7649

Selecting conversion images

Appendix F of the *z/OS Support for Unicode: Using Conversion Services* manual, SA22-7649, records those conversions which are supported through these services. CICS now supports any of these character conversions by making use of the z/OS conversion services.

The conversions entries that you select must not specify type ER.

The z/OS conversion services support big endian byte ordered data (UTF-16BE), they do not support little endian byte ordered data (UTF-16LE). When asked to convert UTF-16LE source data to some other CCSID, CICS transforms the data to the big-endian form of UTF-16 before calling the z/OS conversion services. When the target data is identified as UTF-16 (CCSID 1200), CICS receives the converted data from the z/OS services in big-endian byte order, and returns it in this form.

There are 3 CCSIDs for UTF data,

- CCSID 1202 and CCSID 1201 indicate UTF-16LE and UTF16-BE respectively,
- CCSID 1200 indicates that the data carries a byte order marker which must be examined to see if what follows is big-endian or little-endian.

- When handling CCSID 1200, CICS respects the byte order marker for inbound conversions, but is not able to retain that information when handling a related outbound conversion. All outbound data for CCSID 1200 is UTF16-LE. Application programmers need to know about this and perform their own LE to BE conversions if they so require.

Chapter 26. Applying service to CICS Transaction Server for z/OS

Service material for CICS Transaction Server for z/OS is distributed as APAR fixes and PTFs. ⁴Both types of change are called SYSMODs (SYStem MODifications).

Using SMP/E control statements, you can process SYSMODs in three stages:

1. The **RECEIVE** control statement moves the SYSMOD into the PTF temporary store (PTS) data set. This operation is reversed by the **REJECT** control statement.
2. The **APPLY** control statement moves the SYSMOD into the target libraries. This operation is reversed by the **RESTORE** control statement.

At this point you can test the modified system.

3. The **ACCEPT** control statement moves the SYSMOD into the distribution libraries. This operation is not easily reversed.

When you are dealing with APAR fixes, you should APPLY the SYSMOD, but not accept it. If you later obtain a PTF that solves the problem in a different way, you may be asked to RESTORE (that is, remove) the APAR fix and APPLY the PTF instead.

When you are dealing with PTFs, you should APPLY the SYSMOD, then test it. Afterwards you can ACCEPT it.

For background information about SMP/E operations, see the *System Modification Program Extended: General Information* manual. For more detailed information, see the *System Modification Program Extended: Reference* manual.

Load library secondary extents

CICS supports load library secondary extents that are created while CICS is executing. If you define libraries in the DFHRPL concatenation with primary and secondary extents, and secondary extents are added while CICS is running, as a result of link-editing into the DFHRPL library, the CICS loader detects the occurrence and closes then reopens the library. This means that you can introduce new versions of programs by using the CEMT NEWCOPY command, even if the new copy of the program has caused a new library extent.

However, you should not attempt to apply service to data sets that are used by executing CICS TS components.

The CICS TS-supplied SMP/E procedure

There is a CICS TS-supplied procedure for applying service to the CICS and CICSplex SM components of CICS TS, called DFHSMPE. This procedure is tailored to your environment and stored in the *hlq.XDFHINST* library when you run the DFHISTAR job.

4. An APAR (Authorized Program Analysis Report) is raised when you and your IBM programming service representative agree that there is a CICS problem. You may then be given an APAR fix. When the problem has been analyzed, all users are sent a PTF (Program Temporary Fix) to correct the problem permanently on the current release. PTFs are incorporated into any future CICS release.

For information about how to apply corrective service with SMP/E, see the *System Modification Program Extended: User's Guide*.

Whenever you do any SMP/E processing on CICS or CICSplex SM software, and you use any of the examples quoted in the *System Modification Program Extended: User's Guide*, you should specify DFHSMPE as the name of the SMP/E procedure on the EXEC statement (that is, in place of SMPPROC, as used in the examples). The DFHSMPE procedure includes the following DD statement for supplying SMP/E control statements:

```
//SMPCNTL DD DSN=&&SETBDY,DISP=(OLD,DELETE)
//          DD DDNAME=DFHSMPIN
```

The ZNAME parameter of the DFHSMPE procedure generates a SET BDY command for the zone that is identified by the parameter. The command is stored in the temporary data set, SETBDY. The ZNAME parameter is set to the value of *zonename* that you specify for the TZONE parameter. If you do not specify any value for *zonename* for the TZONE parameter of the DFHISTAR job, *zonename* (and the ZNAME value) defaults to TZONE.

Note: The ZNAME parameter also generates a SET BDY command in DFHAUPLE, the CICS TS procedure supplied for assembling and link-editing CICS control tables.

If you supply an **override** SMPCNTL DD statement in the job that executes DFHSMPE, remember that it must come **before** any DD statements that are additional to the procedure. Furthermore, if you provide an override, you will get the following MVS system message:

```
IEF686I DDNAME REFERRED TO ON DDNAME KEYWORD IN PRIOR STEP WAS NOT RESOLVED
```

You receive this message because the DD statement for DFHSMPIN is missing as a result of the SMPCNTL DD override. However, the message is not a JCL error, and does not prevent the step from running successfully with a return code of 0.

If you supply any SMP/E control statements in your job via the DFHSMPIN ddname, they are prefixed by a SET BDY for the zone that you specify on the ZNAME parameter. It does not matter if you are running SMP/E with a command that does not need this SET BDY statement; it does not affect the execution of your job.

APAR fixes

Generally, you should **not** ACCEPT APAR fixes into distribution libraries. Subsequent PTFs may not include the APAR fix, and you may need to reapply the APAR fix.

If two APAR fixes are dependent on one another, and each is a prerequisite of the other, you must apply them both in the same SMP/E APPLY processing step.

PTFs

PTFs are intended for all users to install to avoid possible problems.

A PTF may contain fixes for several different problems. This means that several APAR fixes reported in RETAIN® may all be superseded by the more permanent PTF, which:

- Provides card-image changes that are functionally equivalent to those in the APAR fix.
- Contains object-module replacements for preassembled CICS TS programs.

For further information about using SMP/E to apply service, see the *System Modification Program Extended: User's Guide*.

CICS service considerations

If you use the CICS TS-supplied SMP/E usermod to install a module into the LPA (for example, into the *hlq.SDFHLPA* library), and later apply service to that module, it is the LPA-resident version of the module that is serviced. If you have not used the SMP/E usermod to install the module into the LPA, it is the original version in the *hlq.SDFHAUTH* library or *hlq.SDFHLOAD* library that is serviced.

Once you have installed CICS, and before you start the post-installation tasks described in this book, you should change the *TEMPLIB* parameter and the *SYSPROC DD* statement of the *DFHISTAR* job to refer to the *hlq.SDFHINST* library. This ensures that if you need to apply service to any of the skeleton jobs, the changes (applied to the *hlq.SDFHINST* library) are used in subsequent runs of *DFHISTAR*. In any such subsequent runs of *DFHISTAR*, you can use the *SELECT* parameter to select any jobs, affected by service, to be regenerated.

Notes:

1. If *DFHISTAR* is serviced, you should add the service changes to your *DFHISTAR* module in the *hlq.TDFHINST* library (to preserve your current installation parameters) or respecify your current installation parameters in the serviced *DFHISTAR* module (which you can copy from the *hlq.SDFHINST* library to the *hlq.TDFHINST* library).
2. Linkage editor messages *IEW0461*, *IEW2454*, *IEW2646*, *IEW2651* and *IEW2689* are produced during the *APPLY* stage for unresolved external references. These are issued, giving a return code of 4, when some CICS load modules are link-edited during PTF installation. You can ignore these *IEWxxxx* messages because they are produced for component object modules of executable CICS load modules.
3. *JCI640D* and *JCI640E* PTFs to ship Java service are often significantly larger than those for the base CICS product and may require more system resources during *APPLY* processing. To avoid errors caused by insufficient storage, it is recommended that the *SMP/E APPLY* step for such PTFs does not have a restricted region size. If a region size limit is used and the *APPLY* fails with errors relating to insufficient storage, it may be necessary to increase or remove the limit for the *SMP/E* job. In some cases a region size of 500M or more may be required.

CICSplex SM service considerations

When you are preparing to run the *EYUISTAR* job after completing the basic installation of CICSplex SM, you should verify that the *TEMPLIB* parameter and the *SYSPROC DD* statement of the *EYUISTAR* job refer to the *CICSTS31.CPSM.SEYUINST* library. This ensures that if you need to apply service to any of the skeleton jobs, the changes (applied to the *CICSTS31.CPSM.SEYUINST* library) are used in subsequent runs of the *EYUISTAR* job. For additional information, see “Sample JCL editing considerations” on page 373.

If you use the CICS TS- supplied SMP/E USERMOD to install modules into the LPA (for example, into the CICSTS31.CPSM.SEYULPA library), and later apply service to that module, it is the LPA-resident version of the module that is serviced. If you have not used the SMP/E USERMOD to install the module into the LPA, it is the original version in the CICSTS31.CPSM.SEYUAUTH library or CICSTS31.CPSM.SEYULOAD library that is serviced.

After applying CICSplex SM service, ensure that all CICSplex SM regions are running with a consistent set of CICSplex SM libraries. Failure to do so may cause unpredictable results.

More information on applying service to CICSplex SM can be found in “CICS Transaction Server for z/OS-supplied SMP/E procedure” on page 371.

Servicing the CICS messages data set

Some IBM-supplied service may include changes to CICS messages, and associated changes to the CICS messages data set, DFHMACD, used by the CICS-supplied transaction CMAC. When you have received and applied the service, you can update the CICS messages data set by running the job DFHMACU. DFHMACU is tailored to your CICS environment and stored in the *hlq.XDFHINST* library when you run the DFHISTAR job.

If a PTF contains an update to the DFHMACD data set, you will see a ++HOLD statement during the APPLY processing of the PTF to notify you that the DFHMACD data set needs to be updated. The PTF will include a member called DFHxxxxx, where xxxxx is the APAR number that is associated with the PTF. You should amend the DFHMACU job so it refers to the appropriate service member of the target library *hlq.SDFHMSGs* (that is, DFHxxxxx on the SYS01 card corresponds to the DFHxxxxx part shipped by the PTF). When you submit the DFHMACU job, it updates the entries in the DFHMACD data set for all messages that are changed by the IBM supplied service.

If you are applying more than one PTF which changes the DFHMACD data set, you should either run the DFHMACU job for each PTF, or alternatively, you may include all the PTFs within one job run, by altering the DFHMACU job as follows:

```
//CMACUPD EXEC PGM=IDCAMS
//SYSPRINT DD SYSOUT=*
//AMSDUMP DD SYSOUT=*
//SYS01 DD DSN=CICSTS31.CICS.SDFHMSGs(DFHXXXXX),DISP=SHR
//SYS02 DD DSN=CICSTS31.CICS.SDFHMSGs(DFHYYYYY),DISP=SHR
.
.
//DFHMACD DD DSN=&DSINDEX.DFHMACD,DISP=SHR
//SYSIN DD *
  REPRO INFILE (SYS01) -
  REPLACE -
    OUTFILE (DFHMACD)
  REPRO INFILE (SYS02) -
  REPLACE -
    OUTFILE (DFHMACD)
.
/*
```

Part 3. Getting ready to run CICS

This part describes how to tailor the CICS-supplied skeleton jobs, apply service to CICS and create the CICS data sets. It also describes how you can use DL/I support with CICS, how to include MRO and ISC in your CICS region, and how to use the CICS-supplied installation verification procedures (IVPs) to confirm that CICS is operational. It contains the following chapters:

- Chapter 27, “Tailoring the CICS-supplied skeleton jobs,” on page 185.
- Chapter 28, “Creating the CICS data sets,” on page 189.
- Chapter 29, “Defining DL/I support,” on page 197.
- Chapter 30, “Adding CICS support for programming languages,” on page 201.
- Chapter 31, “Verifying your Java components installation,” on page 205.
- Chapter 32, “Installing MRO and ISC support,” on page 211.
- Chapter 33, “Enabling TCP/IP in a CICS region,” on page 215.

Chapter 27. Tailoring the CICS-supplied skeleton jobs

If you used CBPDO to install CICS, edit and run DFHISTAR to tailor the CICS-supplied skeleton jobs that create the CICS data sets and run the CICS-supplied IVPs.

If you used the ServerPac to install CICS, the install job stream name is ISTAR01. ISTAR01 is produced from DFHISTAR during the ServerPac process, and placed in the SDFHINST library. DFHISTAR is not removed from the SDFHINST library by this process.

If you have used the distribution tape to install CICS, as described in the *CICS Transaction Server for z/OS Program Directory*, you would normally have tailored the skeleton jobs already, and should now be able to proceed to Chapter 28, “Creating the CICS data sets,” on page 189.

Which ever method you used to install CICS, you can edit and run DFHISTAR several times, to create different copies of the skeleton jobs or subsequently change them. For example, to create several copies of DFHDEFDS to define data sets unique to several CICS regions, or if you have to apply service to any of the installation-related jobs. This enables you to tailor the jobs to your CICS environment after you have loaded the CICS software into the SMP/E-supported CICS libraries.

The CICS installation libraries

When you use CBPDO to install CICS TS, you use the installation libraries shown in Figure 22.




Figure 22. Installation libraries for this release

The names of the CICS installation libraries in Figure 22 on page 185 and their use is explained in the following notes which refer to the numbers in the figure:

1. Skeleton installation-related jobs are copied from data set *HC16400.F2* on the distribution tape into *hlq.TDFHINST*.

hlq.TDFHINST

is used to store the DFHISTAR that you edit and run to tailor the skeleton installation-related jobs to your CICS environment. Until you have installed the CICS software into the SMP/E-supported CICS libraries, this library also stores the skeleton jobs to be tailored.

2. You edit DFHISTAR in the *hlq.TDFHINST* library, to specify CICS installation parameters specific to your CICS environment.
3. When you run DFHISTAR, the tailored copies of the skeleton jobs are copied from the *hlq.TDFHINST* library to the *hlq.XDFHINST* library.

hlq.XDFHINST

is used to store the tailored, executable, copies of the skeleton jobs that are to be run.

4. To install CICS, you run the tailored copies of the CICS-supplied installation jobs to transfer the CICS software from the distribution tape to the *hlq.ADFHINST* and *hlq.SDFHINST* libraries.

hlq.ADFHINST

is the SMP/E-supported distribution installation library.

hlq.SDFHINST

is the SMP/E-supported target installation library. After you have installed the CICS software into this and other SMP/E-supported libraries (named SDFHxxxx and ADFHxxxx), the skeleton jobs that you should use on any later runs of DFHISTAR are stored in the SDFHINST library.

Note: The actual names of the TDFHINST and XDFHINST libraries, and the prefix for those and other CICS libraries, are defined in DFHISTAR, which you edit as described in this chapter.

What you should do

To tailor the skeleton jobs you must run DFHISTAR. For information on how to do this, and the parameters involved, see *CICS Transaction Server for z/OS Program Directory*.

Running DFHISTAR

When you have edited DFHISTAR with the values for installation parameters for your CICS environment, submit DFHISTAR.

When you run DFHISTAR, it tailors the skeleton jobs selected in the DFHISTAR input (by the SCOPE or SELECT parameter) to your environment and adds them to the library that you specified on the LIB parameter (by default, *hlq.XDFHINST*). If necessary, DFHISTAR creates the library that is specified on the LIB parameter.

A Table in section 6.4 of the *CICS Transaction Server for z/OS Program Directory* lists those skeleton jobs installed in the *hlq.SDFHINST* library that you can tailor by running DFHISTAR.

Note: You must specify the full name of the installation library from which the skeleton jobs are obtained, on the `TEMPLIB` parameter and `SYSPROC DD` statement of DFHISTAR (by default, *hlq.TDFHINST*). For the post-installation tasks that are described in this book, you should specify `TEMPLIB SDFHINST`.

DFHISTAR produces a job log and, if necessary, an error code:

- The output job log lists the values that were actually used for the parameters of DFHISTAR.
- If any error occurs when running DFHISTAR, an error code of 4 or 12 is returned. For error code 4, the skeleton jobs are tailored and added to the *hlq.XDFHINST* library. For error code 12, the skeleton jobs are not tailored or copied. To resolve the cause of the error, examine the output job log and, if necessary edit and submit DFHISTAR again.

Chapter 28. Creating the CICS data sets

After you have installed CICS, and applied any necessary service, you can run the DFHCOMDS, DFHDEFDS, and DFHCMACI jobs to create the CICS data sets.

CICS supports access to the following types of data sets:

- Key-sequenced data set (KSDS). With releases of DFSMS/MVS 1.4 and later, a data set can be greater than 4 GB in size if it is defined as extended format and extended addressability in the storage class. CICS supports, in both RL and non-RLS mode, KSDS data sets that are defined with these extended attributes.
- Entry-sequenced data set (ESDS). With releases of DFSMS/MVS 1.5 and later, a data set can be greater than 4 GB in size if it is defined as extended format and extended addressability in the storage class. However, CICS does not support ESDS data sets that are defined with these extended attributes. Attempts to open data sets defined with the extended attribute fail with error message DFHFC0966, codes 8504, 0008, and 0068 for non-RLS access and message DFHFC0905 for RLS access.
- Relative record data set (RRDS). With releases of DFSMS/MVS 1.5 and later, a data set can be greater than 4 GB in size if it is defined as extended format and extended addressability in the storage class. CICS supports access to extended RRDS or VRRDS datasets if you use an RRN that can be specified in a four-byte RRN field to access the records that reside beyond the 4 GB boundary.

#

Data sets

The data sets created by the jobs described in this chapter are required by the IVPs described in Chapter 35, “Running the installation verification procedures,” on page 227.

VSAM Data sets and z/OS 1.3

If you are using z/OS 1.3 or above, read Information APAR II13288.

It reports that the level of DFSMS supplied with z/OS 1.3 has changed the way that index control interval size (CISIZE) is calculated for those VSAM data sets that have index components. As a result, large default CISizes can be expected, and this can cause open errors during CICS start-up.

This applies to both CICS data sets and your own application data sets.

Job	Function
DFHCOMDS	Deletes and recreates data sets common to all CICS regions.
DFHDEFDS	Deletes and recreates copies of data sets that are used only by one CICS region. You run a separate copy of this job to create the data sets for each CICS region.
DFHCMACI	Deletes and recreates the CICS messages data set, dsindex.DFHCMACD, and loads it with the data

from the CICS-supplied file, DFHMACD, in the *hlq.SDFHMSG* target library.

DFH0JCUS

Deletes and recreates the sample applications details data set, dsindex.SAMPLE.DFHCTCUS (and its associated alternate index and path), and loads it with the data from the CICS-supplied file, DFH0DCUS, in the *hlq.ADFHAPD2* library.

DFH0JHLP

Deletes and recreates the sample applications help data set, dsindex.SAMPLE.DFHCTHLP, and loads it with the data from the CICS-supplied file, DFH0DHLP, in the *hlq.ADFHAPD1* library.

When you ran DFHISTAR, these jobs were tailored to your environment and stored in the library that you specified on the LIB parameter of DFHISTAR (by default, *hlq.XDFHINST*). If you have not yet run DFHISTAR, you should do so before running any of the CICS post-installation jobs.

You can generate several copies of these jobs by rerunning DFHISTAR, selecting the jobs that you want to copy. To generate new copies of these jobs, edit DFHISTAR to specify new values for the DSINFO and SELECT parameters. Only those jobs that you name by the SELECT parameter are regenerated.

Naming conventions

There are no restrictions on the data set names you choose for CICS data sets, other than MVS constraints. In the examples in this book, *hlq* is the high-level qualifier, and the DD name is the lowest level. If you are running multiple CICS regions, and especially if you are running CICS with XRF, you can use the CICS APPLID as a third level qualifier.

You should use the *CTGI* naming convention, as in *System/390 MVS Sysplex Application Migration*. For example, if CICSHTH1 is the APPLID, the data set name for the CSD would be:

```
DFHCSD DD DSN=CICSTS31.CICS.CICSHTH1.DFHCSD,DISP=SHR
```

The *CTGI* naming convention is a recommended example of a naming convention that you can use for CICS 4-character names, and is based on the 4-character *CTGI* symbol, where:

- C identifies an entire CICSplex
- T identifies the type of region
- G identifies a group of regions
- I identifies iterations of regions within a group

Where names are allowed to be up to eight characters long, as for CICS APPLIDs, the general recommendation is that the letters CICS are used for the first four characters, particularly for production regions.

If the data set is shared between an active CICS region and an alternate CICS region, use the generic APPLID; but if the data set is unique to either the active or the alternate CICS region, use the specific APPLID. For information about actively and passively shared data sets, see the *CICS System Definition Guide*.

Creating data sets common to all CICS regions, DFHCOMDS job

You can use the DFHCOMDS job to delete and recreate the following data sets common to all CICS regions:

Name	Data set
DFHCSD	CICS system definition.
SYSIN	SYSIN data set.

Note: The CICS-supplied DFHCOMDS job creates one of each of these data sets common to all CICS regions. If you use separate copies of any of these data sets for each CICS region, you should move and edit the appropriate statements into the DFHDEFDS job. For further information about creating multiple copies of these data sets, see “Creating several copies of the DFHCSD and SYSIN data sets.”

The DFHCOMDS job comprises five job steps:

1. **DELETE** deletes the data sets.
2. **DEFCS** defines the VSAM cluster for the CICS system definition data set, dsindex.DFHCS, where dsindex is defined by the DSINFO parameter of DFHISTAR.
3. **INITCS** initializes the CICS system definition data set.
4. **DEFRPC** defines the VSAM cluster for ONC RPC.
5. **DEFSYSIN** creates the SYSIN PDS and copies the following modules from the *hlq.SDFHSAMP* library:

DFH\$SIPA	DFH\$SIPD	DFH\$SIPT	DFH\$SIP1
DFH\$SIP2	DFH\$SIP5	DFHRCNO	DFHRCYES

Creating several copies of the DFHCSD and SYSIN data sets

The CICS-supplied DFHCOMDS job creates one of each of the DFHCSD and SYSIN data sets common to all CICS regions. If you use separate copies of any of these data sets for each CICS region, you should:

- Move the statements that define the data set from the DFHCOMDS job to the DFHDEFDS job.
- Edit the statements in the DFHDEFDS job to specify the symbol ®NAME for the region qualifier in the name of the data set.

You should move and edit the appropriate data set statements before you create copies of the DFHDEFDS job for each CICS region. When you run DFHISTAR to create the new copies of the DFHDEFDS job, it substitutes your values for the CICS region qualifier (®NAME) and index (&INDEX) into the data set names.

For example: If you intend using a copy of the DFHCSD data set for each CICS region, you should copy the job steps DELCS, DEFCS, and INITCS from the DFHCOMDS job to the DFHDEFDS job. You should also add the symbol ®NAME for the qualifier to the name of the DFHCSD data set to give &DSINDEX.CICS®NAME.DFHCS. If you edit DFHISTAR to select the DFHDEFDS job to be copied, and specify the following DSINFO parameter:

```
DSINFO userid.CICSTS31.CICS H3P060 3390 IDA .
```

when you run the DFHDEFDS job, it creates the DFHCSD data set called `userid.CICSTS31.CICS.CICSIDA.DFHCSD` for the CICS region identified by the qualifier IDA. If you change the SELECT and DSINFO parameters of DFHISTAR (to specify an appropriate new job name and qualifier for another CICS region), you can create several copies of the DFHDEFDS job to create DFHCSD and SYSIN data sets for each CICS region.

Creating data sets unique to each CICS region, DFHDEFDS job

You can use the DFHDEFDS job to delete and recreate copies of the following data sets for each CICS region.

Name	Data set
DFHADEM	Resource manager for enterprise beans.
DFHAUXT	Non-VSAM auxiliary trace (A).
DFHBRNSF	Bridge.
DFHBUXT	Non-VSAM auxiliary trace (B).
DFHDMPA	Non-VSAM dump (A).
DFHDMPB	Non-VSAM (B) dump.
DFHEJDIR	Bridge.
DFHEJOS	Object store.
DFHGCD	Global catalog.
DFHHTML	HTML template data set.
DFHINTRA	Intrapartition transient data.
DFHLCD	Local catalog.
DFHLRQ	Local request queue.
DFHTEMP	Temporary storage.
FILEA	Sample program data.
DFHDPFMB	The debugging profiles base data set.
DFHDPFMP	The debugging profiles path data set.
DFHDPFMX	The debugging profiles alternate index data set.

Use DFHISTAR to create a copy of the DFHDEFDS job for each CICS region. Edit DFHISTAR, specifying the parameters DSINFO and SELECT, and run it once for each region.

In DFHISTAR, specify the following parameters:

- **SELECT DFHDEFDS newname** to specify the new name by which the copy of the DFHDEFDS job is to be known.
- **DSINFO** to specify the following details of the data sets for each CICS region:
 - The high-level index (*dsindex*)
 - The serial number of the volume (*volume*)
 - The unit type of the volume (*disktype*)
 - The region qualifier (*qualifier*)

The format of the data set names is:

`dsindex.CICSqualifier.dsname`

dsindex

is the high-level index for the data sets, specified on the DSINFO parameter of DFHISTAR. The default is *hlq*.

qualifier

is the region qualifier for the data sets that are used by this CICS region, specified on the DSINFO parameter of DFHISTAR. The default is no qualifier.

dsname

is the name of the data set being defined.

For example, the default name for the CICS local catalog is *hlq.CICS.DFHLCD*.

The DFHDEFDS job comprises the following job steps:

1. **DELETE** any existing copies of the data sets
2. **DEFINE** defines the clusters for the data sets
3. **INITDP** initializes the debugging profiles base data set
4. **DEFAULT** defines the alternate index for the debugging profiles data set
5. **BLDDP** builds the alternate index for the debugging profiles data set
6. **INITGCD** initializes the CICS global catalog
7. **INITLCD** initializes the CICS local catalog
8. **DEFTRACE** defines the trace data sets
9. **DEFDUMP** defines the dump data sets
10. **LOADFILE** loads the sample data into the FILEA data set
11. **LOADHTML** loads HTML templates for CICS supplied transactions.

Creating the CICS messages data set, DFHCMACI job

You can use the DFHCMACI job to delete and recreate the CICS messages data set DFHCMACD. This data set is used by the CICS messages facility (CICS-supplied transaction CMAC).

The DFHCMACI job comprises the following job steps:

1. **DELETE** deletes any existing copies of the DFHCMACD data set.
2. **DEFINE** defines the VSAM cluster for the CICS message data set `dsindex.DFHCMACD`, where `dsindex` is defined by the DSINFO parameter of DFHISTAR.
3. **CMACLOAD** loads the CICS message data set with data from the CICS-supplied file, DFHCMACD, in the *hlq.SDFHMSG*s target library.

Defining the DFHCMACD file and associated CICS resources

You can use the CICS messages facility to provide the CICS messages and codes descriptions online. Before you can use this facility (to access the DFHCMACD data set), you must define the resources needed by the facility, and make them available to your CICS region.

The file DFHCMACD, managed by CICS file control, accesses the DFHCMACD data set. You must create a definition for this file in the CSD. The CICS-supplied definition for the DFHCMACD file and other resources that are needed by the CICS messages facility are in the CSD group DFHCMAC. The CICS startup procedure,

DFHSTART, has a DD statement for the DFHMACD file, but for dynamic allocation you should copy the supplied resource definition for the DFHMACD file and add the DSNNAME option.

To use the CICS messages facility in your CICS region, you must create your own CSD group lists to include the DFHMAC group for the CICS messages facility and any other groups of resources that your CICS region needs. You must specify your new group lists on the GRPLIST system initialization parameter when you start up your CICS region. If the DFHLIST of resource groups are not included in your new group lists, you must specify DFHLIST on the GRPLIST system initialization parameter as well as your group lists. For example, GRPLIST=(DFHLIST,MYLIST,CICSHT# 1), where MYLIST and CICSHT# 1 are customer-created group lists.

You should specify the DFHMAC group of resources for the CICS messages facility only in those CICS regions that need to use the facility; for example on some terminal-owning regions, but perhaps not on data-owning regions.

Defining the sample applications data sets

CICS provides a range of samples that you can use to help develop your own applications, and test various CICS functions (for example, as an aid to verifying that CICS has installed correctly). These programs are in the *CICS 4.1 Sample Applications Guide* and the *Designing and Programming CICS Applications* book.

Before you can use some of these samples, you must create the data sets that they use, and make them available to your CICS region, as described below. You do not need to create these data sets, unless you intend using the associated sample applications.

The CUA text level application

You can use this sample application to demonstrate BMS support for the Common User Access (CUA) interface. The application uses an action bar, with associated pull-downs, pop-ups, and help panels. The application programs demonstrate how to code COBOL programs to display, overlay, and remove CUA style windows.

Creating the data sets

To create the data sets that are needed by the CUA text level application, submit the following jobs: DFH0JCUS and DFH0JHLP, installed in the *hlq.XDFHINST* library.

Making the data sets available to CICS

You can cause CICS to dynamically allocate the files for these data sets and open them after CICS initialization by installing the sample resource definitions in the group DFH\$CTXT. If no DD statement exists for these data sets in the CICS startup job stream, the files are allocated to the data sets with DSNAMES that are specified in the resource definitions: *hlq.SAMPLE.DFHCTCUS*, *hlq.SAMPLE.DFHCTHLP*, and *hlq.SAMPLE.DFHCTAIX*, for the data sets and the alternate index. Alternatively, you can add DD statements for the data sets to your CICS startup job, which causes CICS to use the DSNAMES specified on the DD statements instead of those in the resource definitions.

For information about this sample application, see the *CICS 4.1 Sample Applications Guide* .

The FILEA sample application programs

This comprises four sets of command-level application programs that operate on the sample VSAM file FILEA. There is one set for each of the four programming languages that are supported, (Assembler, C, COBOL, and PL/I). These programs show basic functions, such as inquire, browse, add, and update, that can serve as a framework for your own first programs. They were all written before publication of the Common User Access guidelines.

Creating the data set

A copy of the data set that is needed by the FILEA application is created when you submit the DFHDEFDS job, installed in the *hlq.XDFHINST* library.

Making the data set available to CICS

When you tailor the CICS installation-related jobs, as described in Chapter 27, “Tailoring the CICS-supplied skeleton jobs,” on page 185, a DD statement for the FILEA data set is added to the CICS IVP jobs and the DFHSTART procedure. If you want CICS to dynamically allocate the data set and open the file, you should remove the DD statement and install a FILE resource definition with an appropriate DSNNAME. (For example, as supplied in the group DFH\$FILA.)

For information about this sample application, see the *CICS 4.1 Sample Applications Guide*.

The CICS Application Programming Primer sample application

You can use this sample application to demonstrate the design and programming of a traditional CICS application. It provides online inquiry and maintenance facilities for a sample customer credit file in a department store. The application uses VSAM files, and 3270 display and printer terminals. It was written before publication of the Common User Access guidelines, and provides similar function (without CUA support) as the CUA sample application.

Creating the data sets

To create the data sets that are needed by the Primer sample application, edit and submit the sample job that is shown in Figure 23 on page 196.

Making the data sets available to CICS

You can cause CICS to dynamically allocate the files for these data sets and open them on first reference by installing the sample resource definitions in the group DFH\$ACCT. If no DD statement exists for these data sets in the CICS startup job stream, the files are allocated to the data sets with DSNAMES that are specified in the resource definitions: *hlq.ACCTFILE* and *hlq.ACIXFILE*. Alternatively, you can add DD statements for the data sets to your CICS startup job, which causes CICS to use the DSNAMES specified on the DD statements instead of those in the resource definitions.

For information about this sample application, see the *CICS Application Programming Primer*.

```

//DEFACCTF JOB (accounting parameters),MSGCLASS=A,MSGLEVEL=(1,1),
//          CLASS=A,NOTIFY=userid
//*
//*****
//*      CICS/ESA sample jobs to define ACCT files
//*
//* This job deletes and defines the following data sets for the
//* ACCT sample described in the CICS Application Programming Primer
//*
//* STEPS:
//* . DELETE AND DEFINE
//*   - DELETE/DEFINE THE CLUSTERS FOR:
//*     . CICS31.CICS.ACCTFILE
//*     . CICS31.CICS.ACIXFILE
//*
//* THE HIGH-LEVEL-QUALIFIER(S) OF THE DATASETS: CICS31.CICS
//* THE VOLUME SERIAL                          CICS31
//* THE UNIT TYPE                               3390
//*
//*****
//DELETE   EXEC PGM=IDCAMS,REGION=1M
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
DELETE CICS31.CICS.ACCTFILE
DELETE CICS31.CICS.ACIXFILE
SET MAXCC=0
/*
//DEFINE   EXEC PGM=IDCAMS,REGION=1M
//SYSPRINT DD SYSOUT=*
//SYSIN    DD *
/*          */
DEFINE CLUSTER(NAME(CICS31.CICS.ACCTFILE)-
              KEYS(5 0)-
              INDEXED -
              RECORDSIZE(383 383)-
              REC(80)-
              SHR(2 3)-
              VOLUMES(CICS31)) -
DATA(NAME(CICS31.CICS.ACCTFILE.DATA)-
UNIQUE)-
INDEX(NAME(CICS31.CICS.ACCTFILE.INDEX)-
UNIQUE)
/*          */
DEFINE CLUSTER(NAME(CICS31.CICS.ACIXFILE)-
              KEYS(17 0)-
              INDEXED -
              RECORDSIZE(63 63)-
              REC(80)-
              SHR(2 3)-
              VOLUMES(CICS31)) -
DATA(NAME(CICS31.CICS.ACIXFILE.DATA)-
UNIQUE)-
INDEX(NAME(CICS31.CICS.ACIXFILE.INDEX)-
UNIQUE)
/*
//*

```

Figure 23. Example JCL to create the Primer sample data sets

Chapter 29. Defining DL/I support

CICS can provide DL/I database support by using the IBM IMS Database Manager . For information about appropriate Versions and Releases, see the "CICS-IMS release compatibility" topic in the *CICS IMS Database Control Guide* . As they become available, versions of IMS newer than those listed will also be compatible.

You can use DL/I support with CICS through:

- Database control (DBCTL)
- CICS remote DL/I support, also known as **function shipping**

This chapter describes what you do to enable a CICS region to work with remote DL/I. For information about adding system and resource definitions for use with DBCTL, see the "Installing DBCTL, and defining CICS and IMS system resources" topic in the *CICS IMS Database Control Guide* .

The IMS libraries referred to in the job streams are identified by IMS.libnam (for example IMS.PGMLIB). If you use your own naming convention for IMS libraries, please rename the IMS libraries accordingly.

CICS provides a CICS-DBCTL interface which enables DBCTL, or IMS/ESA® or IMS/ESA DM/TM, to satisfy DL/I requests that are issued from the CICS region. New users should use this method because it is simpler than local DL/I to install and provides additional function. Details of installing and using DBCTL are in the *CICS IMS Database Control Guide* .

CICS support for access to DL/I databases using the IBM Information Management System (IMS) product is included in the base product, and no specific installation is required.

For more information about storage protection, see the "Storage protection" topic in the *CICS System Definition Guide* .

PDIRs

A directory of program specification blocks (PDIR) is a list of program specification blocks (PSBs) that define, for DL/I, the use of databases by application programs.

Your CICS region needs a PDIR to access a database owned by a remote CICS region (remote DL/I support). Your CICS region does not need a PDIR to access a DL/I database owned by DBCTL. For information about accessing DL/I databases owned by DBCTL, see the "Performance benefits of DBCTL" topic in the *CICS IMS Database Control Guide* .

The modules providing remote DL/I support are automatically loaded by CICS during startup when a DL/I PSB directory is specified via the PDIR= system initialization parameter. A PDIR is mandatory for remote DL/I support, but not required for database control support.

Adding remote DL/I support

Remote DL/I support is included in CICS Transaction Server for z/OS, and works with one of the supported levels of IMS, (see above for details of these). Usually, you use remote DL/I support, with either MRO or ISC connections, to access databases owned by another CICS region. You can also use CICS remote DL/I support to access, through another CICS region connected to DBCTL, databases owned by DBCTL. CICS regions accessing databases owned by DBCTL (that is, connected to DBCTL) must be running on the same MVS image as the DBCTL system. A simple overview is given in Figure 24.




Figure 24. Using CICS remote DL/I support to access DBCTL databases

Notes:

1. CICSB uses remote DL/I to access, through CICSA, databases owned by DBCTL 1 in MVS image 1. This is only needed if CICSB is not connected to DBCTL 1.
2. CICSB uses remote DL/I to access, through CICSB, databases owned by DBCTL 2 in MVS image 2.
3. CICSA (connected to DBCTL 1) is in the same MVS image as DBCTL 1. CICSB (connected to DBCTL 2) is in the same MVS image as DBCTL 2.

For information about accessing DL/I databases owned by DBCTL, see the *CICS IMS Database Control Guide*.

To add support in CICS for remote database access, you must:

1. Code, assemble, and link-edit a program specification blocks directory (PDIR).
2. Code the PDIR CICS system initialization parameter for remote DL/I support.

Defining a PSB directory

Code entries in a program specification block directory (PDIR), to indicate the identity of the remote CICS region, or regions, to which you want CICS to function ship DL/I requests. You do this by coding the SYSIDNT parameter in DFHDLPSB TYPE=ENTRY macros, which you assemble and link-edit to create a PDIR. You must also code the MXSSASZ parameter. You can, optionally, code the RMTNAME parameter to define the name by which the PSB is known in the remote CICS region. For information about creating PDIRs, see the *CICS Resource Definition Guide*.

Coding CICS system initialization parameters for remote DL/I support

The following is a summary of the DL/I parameters that you can, or must, code as CICS system initialization parameters:

PDIR={YES|xx} SUFFIX OF PSB DIRECTORY
(MANDATORY for REMOTE DL/I)
PSBCHK={NO|YES} SECURITY CHECK OF REMOTE TERMINAL INITIATING A TRANSACTION
XPSB={YES|name|NO} PSB ENTRIES TO BE CHECKED BY RACF

For details of these (and other) system initialization parameters, see *CICS System Definition Guide*.

Global user exits for DL/I

The following global user exits, if enabled, can be invoked when you have DL/I applications:

XDLIPRE and XDLIPOST

These exits follow the issue of an EXEC DLI command or DL/I call; XDLIPRE before the request is processed and XDLIPOST after the request is processed. If you are running CICS with remote DL/I support, these exits are invoked in both the CICS region executing the DL/I transactions (the AOR), and the CICS region to which the DL/I requests are function shipped (the DOR). However there are restrictions on what actions can be performed by an exit program running at exit point XDLIPRE or XDLIPOST when running in a DOR.

XRMIIN and XRMIOU

You can use these exits to monitor activity across the resource manager interface (RMI). For example, you can monitor control being passed to and from DFHEDP for EXEC DLI requests, DFHDBAT for DBCTL requests, or DSN2EXT1 for DB2 for DB2 commands. XRMIIN is invoked just before control is passed from the RMI to a task-related user exit. XRMIOU is invoked just after control is passed back to the RMI.

For programming information about these exits, see the *CICS Customization Guide*.

Chapter 30. Adding CICS support for programming languages

This section describes the steps necessary to add run-time support for the programming languages used with the CICS command level (EXEC) programming interface. Complete the appropriate actions described in the following before installing your application programs.

To write CICS application programs that request CICS services through the command-level application programming interface (API), you can use assembler language, C and C++, COBOL, or PL/I.

CICS provides the support needed to run application programs written in assembler language, and Language Environment provides the required support for all the other languages. The use of Language Environment is essential in CICS Transaction Server for z/OS, Version 3 Release 1. Supported compilers are listed in the *CICS Release Guide*.

The CICS Transaction Server for z/OS, Version 3 Release 1 programming guidance documentation expects that your CICS system is using the services of Language Environment, which provides a common run-time environment for IBM implementations of assembler and those high-level languages (HLLs) supported by CICS, namely COBOL, PL/I, C, and C++.

Note: Runtime support for OS/VS COBOL programs has been removed. OS/VS COBOL programs cannot run under CICS Transaction Server for z/OS Version 3, and must be upgraded to a supported level of COBOL.

Installing Language Environment support

This section describes CICS support for Language Environment and what to do to install that support. The use of Language Environment is essential in CICS Transaction Server for z/OS, Version 3 Release 1.

Language Environment support is provided by run-time libraries that establish a common execution environment for application programs compiled by high-level languages. All programs compiled by a high-level language, whether by a Language Environment-conforming compiler or not, must be run under CICS-Language Environment support.

The CICS-Language Environment interface is initialized automatically when CICS can:

1. Load the Language Environment interface modules, CEECCICS, CEEPIPI, and CEECTCB, from STEPLIB.
2. Successfully call the CEECCICS module to initialize the interface.

Language Environment initialization takes place during CICS startup, when CICS issues the message DFHAP1203I *applid* Language Environment is being initialized. The CEECCICS module is loaded, followed by a partition initialization call, before the start of second phase PLT processing. If Language Environment cannot successfully complete the initialization of all languages supported by CICS, or can only initialize some of them, it issues messages to the MVS console. If Language Environment initialization fails completely, it may be because the CEECCICS module could not be loaded, or something went wrong during the loading of a particular language routine.

Installing CICS support for Language Environment

To enable Language Environment support to be installed correctly by CICS:

- Specify enough storage for the ERDSA to run CICS and Language Environment together. They need a minimum of 3500KB. To this minimum, add an amount of storage sufficient for your own requirements.
- Ensure the CICS-Language Environment interface module, CEECCICS, and the Language Environment modules CEEPIPI and CEECTCB are installed in an APF-authorized library defined in the STEPLIB concatenation in the CICS startup JCL. You can do this by including the Language Environment SCEERUN library in an APF-authorized library in the STEPLIB concatenation of your CICS startup job (for example, in the CICSTS31.CICS.SDFHAUTH library), or in an APF-authorized library in the MVS LNKSTnn concatenation.
- Ensure that the program resource definitions for the Language Environment language interface modules have been added to the CICS CSD. These definitions are in the CEE group.

The CEE group is added automatically to the CSD and to the grouplist DFHLIST during CICS installation, as part of the DFHCOMDS job

The definitions are also supplied as DEFINE statements in the CEECCSD and CEECCSDX members of the SCEESAMP library.

You can add the CEE group to any CICS startup group list named in the GRPLIST system initialization parameter.

- Define the Language Environment transient data destinations, CESE, and CESO (DD names CEEMSG and CEEOUT). The CICS-supplied resource definition group, in the CSD, DFHDCTG, contains entries for CESE and CESO.

For information about the attributes needed for Language Environment transient data destinations, see the *IBM Language Environment for MVS & VM Programming Guide*, SC26-4818.

- Define the Language Environment runtime libraries on the CICS STEPLIB and DFHRPL DD statements as follows:

- Add the SCEERUN library, which contains CEECCICS and CEECTCB, and the SCEERUN2 library, which contains support that is required for the IBM Java Virtual Machine (JVM) and also support for other programming languages, to STEPLIB or to a library in the MVS LNKSTnn concatenation.

- Both the libraries, SCEERUN and SCEERUN2, must be APF-authorized.

- Add the SCEECICS, SCEERUN2, and SCEERUN libraries to DFHRP. (The order of the SCEERUN and SCEERUN2 libraries in relation to each other is not important.)

For example:

```
/*          CICS APF-authorized libraries
//STEPLIB DD DSN=hlg.CICS.SDFHAUTH,DISP=SHR
//          DD DSN=hlg.LE.SCEERUN2,DISP=SHR
//          DD DSN=hlg.LE.SCEERUN,DISP=SHR
/*          CICS load libraries
//DFHRPL  DD DSN=hlg.CICS.SDFHLOAD,DISP=SHR
//          DD DSN=hlg.LE.SCEECICS,DISP=SHR
//          DD DSN=hlg.LE.SCEERUN2,DISP=SHR
//          DD DSN=hlg.LE.SCEERUN,DISP=SHR
```

Use only these Language Environment runtime libraries for *all* your high-level language application programs.

|

|
|

Language Environment support for COBOL

Language Environment is a prerequisite for application programs written in COBOL. For information about Language Environment, see the *Language Environment for OS/390 Customization* manual, SC28-1941.

Support for OS/VS COBOL programs is now withdrawn. These programs, which had runtime support in CICS Transaction Server for z/OS Version 2, cannot run under CICS Transaction Server for z/OS Version 3. OS/VS COBOL programs must be upgraded to Language Environment conforming COBOL, and recompiled against a level of COBOL compiler supported by CICS. The *CICS Application Programming Guide* provides assistance with converting OS/VS COBOL programs to Language Environment conforming COBOL.

To run COBOL application programs:

- Install support for Language Environment, ensuring that CICS can initialize the Language Environment environment during startup.
- Install resource definitions for your programs with the LANGUAGE attribute specified as LANGUAGE(COBOL), or leave the language blank.

For your application programs, CICS can create and install program resource definitions automatically, or you can create them specifically in the CSD, and install them by using the GRPLIST system initialization parameter or CEDA INSTALL command. For more information about installing program resource definitions, see the *CICS Resource Definition Guide*.

For information about Language Environment support for programming languages, see the *Program Directory for IBM Language Environment for MVS and VM*.

Language Environment support for C and C++

Language Environment is a prerequisite for application programs compiled using IBM C/C++ for MVS or SAA AD/Cycle[®] C/370 compilers. Language Environment incorporates the run-time libraries required for both these C language compilers. For information about Language Environment, see the *Language Environment for OS/390 Customization* manual, SC28-1941.

To run under CICS your C application programs:

- Install support for Language Environment, ensuring that CICS can initialize the Language Environment environment during startup.
- Install resource definitions for your programs with the LANGUAGE attribute specified as LANGUAGE(C) or leave the language blank.

For information about installing program resource definitions, see the *CICS Resource Definition Guide*.

CICS supports application programs written in C++ that:

- Are compiled using the IBM C/C++ for MVS compiler (5655-121)
- Execute with the Language Environment run-time libraries

If you use Version 3 Release 2, or late, of the C/C++ compiler to compile a C++ program, specify the CXX parameter when options are passed to the compiler, otherwise the C compiler is invoked. Do not specify CXX if a C program is to be compiled. See the *IBM C/C++ for MVS/ESA Compiler and Run-Time Migration Guide Version 3 Release 2*, SC33-2002, for further information.

For information about Language Environment support for programming languages, see the *Program Directory for IBM Language Environment for MVS and VM*.

Language Environment support for PL/I

Language Environment is a prerequisite for application programs compiled using IBM PL/I for MVS or SAA AD/Cycle PL/I compilers. Language Environment incorporates the run-time libraries required for both these PL/I compilers. For information about Language Environment, see the *Language Environment for OS/390 Customization* manual, SC28-1941.

| PL/I support is also required if you use the Web services support in CICS; in
| particular, it is required if you use the CICS-supplied SOAP 1.1 and SOAP 1.2
| message handler programs.

To run CICS PL/I application programs :

- Install support for Language Environment, ensuring that CICS can initialize the Language Environment environment during startup.
- Install resource definitions for the programs with the LANGUAGE attribute specified as LANGUAGE(PLI) or leave blank.

For information about installing program resource definitions, see *CICS Resource Definition Guide*.

For information about Language Environment support for programming languages, see the *Program Directory for IBM Language Environment for MVS and VM*.

Language Environment support for CICS JVM programs

Language Environment is a prerequisite for CICS JVM programs. However, unlike the other languages, JVM programs do not require the CICS-Language Environment interface. JVM programs run with Language Environment support using MVS services (not CICS services). JVM programs require the Language Environment support provided by the SCEERUN and SCEERUN2 libraries only, which can either be defined in the CICS STEPLIB, or included in the MVS linklist. The SCEERUN and SCEERUN2 libraries also need to be added to DFHRPL.

#

Chapter 31. Verifying your Java components installation

CICS support for Java application programs is included in the base product, and no specific installation is required. Before you begin to set up and configure Java support in your CICS system, follow the steps below to verify that the Java components are correctly installed on your system.

1. Use the supplied checklist in “Verifying Java components checklist” to ensure that all of the required Java components are installed in the correct locations on your CICS system.
2. Read about the JVM components and the supplied sample definition files in more detail in “Java Virtual Machine sample definition files” on page 207, particularly if you have not performed a default installation.
3. Authorize the hlq.SDFJAUTH library. See “Authorizing the hlq.SDFJAUTH library” on page 210 for details on how to do this.
4. Amend the default parameters in the BPXPRMxx members of SYS1.PARMLIB so use the JVM supplied with CICS. See “Amending parameters in SYS1.PARMLIB(BPXPRMxx)” on page 210 for details on which parameters to change.

When you have verified your Java installation, use the task list in *Java Applications in CICS* to begin setting up your Java environment.

Verifying Java components checklist

The following components are unloaded from the distribution tapes during the standard installation process described in the CICS Transaction Server for z/OS Program Directory. Note that z/OS UNIX System Services must be active in **full function** mode during this process to enable files to be stored in HFS.

Table 13. Java components checklist

Java component	Location	Comments
Directories containing JAR files	HFS directories: <i>/pathprefix/usr/lpp/cicsts/cicsts31/lib</i> <i>/pathprefix/usr/lpp/cicsts/cicsts31/samples</i> <i>/pathprefix/usr/lpp/cicsts/cicsts31/docs</i>	<i>cicsts31</i> is a user-defined value specified on the USSDIR parameter in the DFHISTAR installation job.
Sample programs	HFS directory: <i>/pathprefix/usr/lpp/cicsts/cicsts31/samples</i>	The sample programs demonstrate the use of IIOF, EJBs, output redirection and the JCICS classes

Table 13. Java components checklist (continued)

<p>JVM profiles</p> <p>DFHJVMPR DFHJVMP DFHJVMP DFHJMCC DFHJMCD (DFHJMCD is reserved for the use of CICS)</p>	<p>HFS directory:</p> <p><i>/pathprefix/usr/lpp/cicsts/cicsts31/JVMProfiles</i> directory</p>	<p><i>cicsts31</i> is a user-defined value for the CICS_DIRECTORY variable in the DFHIJVMJ installation job. See “JVM profiles” on page 207 for more information about the JVM sample profiles.</p>
<p>JVM properties files</p> <p>dfjvmp.r.props dfjvmpc.r.props dfjvmpr.r.props dfjvmcc.r.props dfjvmcd.r.props</p>	<p>HFS directory:</p> <p><i>/pathprefix/usr/lpp/cicsts/cicsts31/props/</i></p>	<p><i>cicsts31</i> is a user-defined value for the CICS_DIRECTORY variable in the DFHIJVMJ installation job. For more information about the JVM sample properties files, see “JVM properties files” on page 208.</p>
<p>Java security policy file</p> <p>dfjejbpl.security</p>	<p>HFS directory:</p> <p><i>/pathprefix/usr/lpp/cicsts/cicsts31/lib/security/dfjejbpl.policy</i></p>	<p><i>cicsts31</i> is a user-defined value specified on the USSDIR parameter in the DFHISTAR installation job. See “JVM properties files” on page 208 for more information about the sample Java security policy file.</p>
<p>hlq.SDFJAUTH library</p>	<p>MVS PDSE libraries</p>	<p>Contains components of the SJ domain. See “Authorizing the hlq.SDFJAUTH library” on page 210 for more information.</p>
<p>hlq.SDFJLPA library</p>	<p>MVS PDSE libraries</p>	<p>The library is empty after installation, but is used for CICS modules that support the Java IIOF environment. See “The hlq.SDFJLPA library” on page 210 for more information.</p>

Java Virtual Machine sample definition files

CICS launches a JVM to execute a Java program that specifies a JVM in its program resource definition. The JVM is created using options specified in a series of text files:

- JVM initialization options are specified in a JVM profile, which is named by the JVMPROFILE attribute of the program definition.
- Further system properties for the JVM are specified in a JVM properties file, which is named in the JVM profile.
- A Java 2 security policy can be named in the JVM properties file to specify security options, if you are using JVMs to run Enterprise JavaBeans™.

CICS provides samples of all these, as described in the following sections. “Setting up JVM profiles and JVM properties files” in *Java Applications in CICS* has more information about these files and the relationships between them.

JVM profiles

CICS provides five sample JVM profiles in the partitioned dataset named SDFHENV. Each sample JVM profile can be used to create a different type of JVM. The sample JVM profiles are as follows:

Table 14. CICS-supplied sample JVM profiles

JVM profile	Purpose
DFHJVMPR	The default JVM profile if no other is specified on a PROGRAM resource definition. JVM is resettable. Does not use the shared class cache.
DFHJVMPD	JVM is resettable and uses the shared class cache.
DFHJVMPD	JVM is single-use. Not recommended for enterprise beans.
DFHJVMCC	Profile for the master JVM that initializes the shared class cache.
DFHJVMCD (reserved for the use of CICS)	Profile for CICS-defined programs. Do not use for your own applications. Only change as necessary.

In their supplied form, the JVM profiles are defined with JVMPROPS and LIBPATH parameters that use the symbols &CICS_DIRECTORY, &JAVA_HOME. These profiles are customized when you install CICS TS and run the DFHIJVMJ job, as follows:

&CICS_DIRECTORY

This symbol is replaced with the value you specify on the USSDIR parameter in the DFHISTAR installation job. The default is `cicsts31`, resulting, for example, in directory paths of the form `/pathprefix/usr/lpp/cicsts/cicsts31/lib` on LIBPATH.

&JAVA_HOME

This symbol is replaced with the value you specify on the JAVADIR parameter in the DFHISTAR installation job. The default is `java142/J1.4`, resulting in directory paths of the form `/pathprefix/usr/lpp/java142/J1.4/bin` and `/pathprefix/usr/lpp/java142/J1.4/bin/classic` on LIBPATH.

The string `java142/J1.4` is what you should specify on JAVADIR for use with the IBM Software Developer Kit for z/OS, Java 2 Technology Edition, Version 1.4.2.

Note: The extra // characters on each side of the symbols are removed during symbol substitution.

After you have run DFHIJVMJ to substitute your own values for the symbol names, the customized profiles are written to the directory `/pathprefix/usr/lpp/cicsts/cicsts31/JVMProfiles` in the hierarchical file store (HFS), where `cicsts31` is the value that you chose for the CICS_DIRECTORY variable used by the DFHIJVMJ job during CICS installation. Because the JVM profiles are stored in HFS, CICS requires access to z/OS UNIX System Services, and to directories and files in HFS, in order to create JVMs. “Giving CICS regions access to z/OS UNIX System Services and HFS directories and files” in *Java Applications in CICS* explains how to give CICS the access it requires.

“Setting up JVM profiles and JVM properties files” in *Java Applications in CICS* tells you how to enable CICS to locate the JVM profiles, how to choose an appropriate JVM profile for your Java programs, and how to customize the supplied sample JVM profiles to your system’s requirements. In particular, if you place the JVM profiles in a location other than the default directory `/pathprefix/usr/lpp/cicsts/cicsts31/JVMProfiles`, or if you choose a different name during CICS installation for this directory, you need to change the system initialization parameter JVMPROFILEDIR to specify the correct directory, or use UNIX soft links to link to the JVM profiles from the default directory. You also need to ensure that CICS has access to the HFS directory where the JVM profiles are stored.

Note that the JVM profiles DFHJVMPR and DFHJVMCD, and their associated JVM properties files, must always be available to CICS. DFHJVMPR is used if a Java program is defined as using a JVM but no JVM profile is specified, and it is used for sample programs. DFHJVMCD is used by CICS-defined programs, including the default request processor program (DFJIIRP) and the program that CICS uses to publish and retract deployed JAR files (DFJIIRQ, the CICS-key equivalent of DFJIIRP). Both these JVM profiles must therefore either be present in the directory that is specified by JVMPROFILEDIR, or linked to by means of UNIX soft links from that directory, and they must be configured correctly so that they can be used in your CICS region.

You can edit the JVM profiles with any text editor to customize them for your system. “Choosing a JVM profile and JVM properties file” in *Java Applications in CICS* tells you about some options that you might want to change, and the *CICS System Definition Guide* has the full lists of options that you can specify using JVM profiles and JVM properties files. For single-use JVMs (that is, with a JVM profile that specifies the option REUSE=NO or the older option Xresettable=NO), instead of customizing the JVM profile, you can override the options in it, using the user-replaceable program DFHJVMT. Normally, a JVM profile provides sufficient flexibility to configure a JVM as required. If you find that you need to make unusual modifications, the *CICS Customization Guide* has more information about using DFHJVMT.

As JVM profiles and JVM properties files are HFS files, case is important. CICS **does not** automatically convert the name of a JVM profile or JVM properties file to upper case. When you use the name of a JVM profile or JVM properties file anywhere in CICS, you must enter it using the same combination of upper and lower case characters that is present in the HFS file name.

JVM properties files

You use the JVMPROPS option in a JVM profile to specify the full path of the JVM properties file that is associated with the profile. CICS provides five sample JVM properties files in the SDFHENV partitioned data set, which are designed to support their corresponding JVM profile:

Table 15. CICS-supplied sample JVM properties files

JVM profile	Associated JVM properties file
DFHJVMPR	dfjjvmpr.props
DFHJVMPD	dfjjvmpr.props
DFHJVMPD	dfjjvmpr.props
DFHJVMPD	dfjjvmpr.props
DFHJVMPD	dfjjvmpr.props
DFHJVMPD (reserved for the use of CICS)	dfjjvmpr.props

The sample JVM properties files are defined with the &CICS_DIRECTORY symbol, which is replaced with your own value when you run the DFHIJVMJ installation job. When the symbol substitution is complete, the customized JVM properties files are copied to the HFS directory `/pathprefix/usr/lpp/cicsts/cicsts31/props/`, where `cicsts31` is the value that you chose for the CICS_DIRECTORY variable used by the DFHIJVMJ job during CICS installation.

The JVMPROPS option on a JVM profile references a JVM properties file by using its full path name. The CICS-supplied sample JVM profiles reference the sample JVM properties files as follows:

```
JVMPROPS=/pathprefix/usr/lpp/cicsts/cicsts31/props/dfjjvmpr.props
```

where `dfjjvmpr.props` is the name of the sample JVM properties file that matches with the sample JVM profile. If you change the name or location of a JVM properties file, or create your own JVM properties file, you need to change the JVMPROPS option to specify the correct path name in all the JVM profiles that reference that JVM properties file. You also need to ensure that CICS has access to the HFS directory where the JVM properties file is stored.

As for the JVM profiles, you can edit the JVM properties files with any text editor to customize them for your system. “Choosing a JVM profile and JVM properties file” in *Java Applications in CICS* tells you about some options that you might want to change, and the *CICS System Definition Guide* has the full lists of options that you can specify using JVM properties files. Remember that CICS **does not** automatically convert the name of a JVM properties file to upper case, so when you use the name of a JVM profile or JVM properties file anywhere in CICS, you must enter it using the same combination of upper and lower case characters that is present in the HFS file name.

Java 2 security policy for EJBs

CICS provides a sample Java 2 security policy that you can use, or modify to suit your own requirements. The sample policy is named `dfjejbpl.security`, and it defines security properties that are suitable for JVMs that are used by enterprise beans. The sample policy is supplied on the distribution tape in SDFHENV. During the installation process, the policy is customized and written to `/pathprefix/usr/lpp/cicsts/cicsts31/lib/security/dfjejbpl.policy`, where `cicsts31` is a user-defined value specified on the USSDIR parameter in the DFHISTAR installation job. “Protecting Java applications in CICS” in *Java Applications in CICS* tells you what changes you need to make to the sample JVM properties files to enable Java 2 security, how to set up a security policy file, and about the CICS-supplied sample security policy file `dfjejbpl.policy`.

Authorizing the hlq.SDFJAUTH library

This library is the partitioned data set extended (PDSE) version of SDFHAUTH, and it contains some of the components of the SJ domain. A separate library is needed because these components are now built using XPLink (Extra Performance Linkage). The SDFJAUTH library is required for Java support, and as for the SDFHAUTH library, you need to:

1. APF-authorize the SDFJAUTH library by adding it to the list of APF-authorized libraries in the appropriate PROGxx (or IEAAPFxx) member in SYS1.PARMLIB.
2. Provide a STEPLIB DD statement for the hlq.SDFJAUTH library in your startup job stream.

The procedure for authorizing the SDFHAUTH library is described in Chapter 6, "Authorizing the hlq.SDFHAUTH library," on page 67. Follow the same procedure to authorize the SDFJAUTH library.

The hlq.SDFJLPA library

This library is currently empty, but is supplied to allow those CICS modules that support the Java IIOF environment, and that are LPA eligible, to be included in the LPA. There are no CICS-supplied Java IIOF modules that must reside in the LPA, therefore the library is empty following the installation of CICS TS.

Note: The library SDFJLPA is a partitioned data set extended (PDSE). PDSEs cannot be loaded into the LPA at MVS IPL time, because MVS nucleus initialization processing does not recognize them. You can use the MVS SETPROG command after an IPL to dynamically add members of a PDSE into the LPA.

Amending parameters in SYS1.PARMLIB(BPXPRMxx)

The default options, shipped in the BPXPRMxx members of SYS1.PARMLIB are not sufficient for use with the JVM supplied in CICS. In particular, the values for IPCSEMNSEMS, MAXPROCSYS, MAXPROCUSER, MAXUIDS, MAXASSIZE, MAXFILEPROC, MAXPTYs, MAXTHREADS, MAXTHREADTASKS, and MAXCPUTIME are too low for CICS usage - increase them.

Recommendation:

Start by using the following values. Tailor them to your system's needs as you gain experience:

IPCSEMNSEMS	1000
MAXPROCSYS	500
MAXPROCUSER	512
MAXUIDS	500
MAXASSIZE	2000000000
MAXFILEPROC	512
MAXPTYs	256
MAXTHREADS	10000
MAXTHREADTASKS	5000
MAXCPUTIME	2147483647

For full details, see *z/OS UNIX System Services Planning*, GA22-7800, in section 14.8, "Customizing the BPXPRMxx parmlib members", and *z/OS MVS Initialization and Tuning Reference*, SA22-7592, in section 9.0, "BPXPRMxx (z/OS UNIX System Services parameters)".

Chapter 32. Installing MRO and ISC support

This chapter describes what you have to do to include the following communication facilities in your CICS region:

- Multiregion operation (MRO)
- Intersystem communication (ISC)

The information about ACF/VTAM and MVS that is given in this chapter is for guidance only. Always consult the current ACF/VTAM or MVS publications for the latest information. See “Books from related libraries” on page 469.

Installing MRO support

This section describes how to install support for multiregion operation (MRO) in your CICS regions.

CICS multiregion operation (MRO) enables CICS regions that are running in the same MVS image, or in the same MVS sysplex, to communicate with each other. MRO does not support communication between a CICS system and a non-CICS system such as IMS.⁵

MRO does not require ACF/VTAM or SNA networking facilities. The support within CICS that enables region-to-region communication is called **interregion communication (IRC)**. IRC is implemented in three ways:

1. Through support in CICS terminal control management modules and by use of a CICS-supplied interregion program, DFHIRP, loaded in the MVS link pack area. DFHIRP is invoked by a type 3 supervisory call (SVC).
2. By MVS cross-memory services, which you can select as an alternative to the CICS type 3 SVC mechanism. Here, DFHIRP only opens and closes the interregion links.
3. By the cross-system coupling facility (XCF) of MVS. XCF/MRO is required for links between CICS regions in different MVS images of an MVS sysplex. CICS selects XCF/MRO dynamically for such links, if available.

For information about the design and implementation of interregion communication, and about the benefits of cross-system MRO, see the *CICS Intercommunication Guide*.

To install support for MRO, complete the following steps (outlined in more detail in this chapter):

1. Define CICS as an MVS subsystem.
2. Install the current versions of the DFHIRP and DFHCSVC modules in the LPA.
3. If you give the SVC a new number, and you have CICS Version 1 or Version 2 regions that use MRO, regenerate the CICS modules DFHCRC and DFHDRPA for those CICS versions, specifying the SVC number.
4. Specify appropriate system initialization parameters to enable MRO for each CICS region startup.

If you intend using cross-system MRO (XCF/MRO) you must also:

5. The external CICS interface (EXCI) uses a specialized form of MRO link to support DCE remote procedure calls to CICS programs, and communication between MVS batch programs and CICS .

5. Install the required sysplex hardware and software.
6. Define the MVS images as systems in an XCF sysplex.

To use the MRO support, you must also:

7. Define and install the MRO connections appropriate to your CICS environment.

Provided you complete the above steps, you can use MRO to communicate with all
levels of CICS from CICS/ESA Version 4.1 onwards.

Should MRO be used to communicate between different releases of CICS, the
function provided on any connection is that of the lower-level release.

Defining CICS as an MVS subsystem

Multiregion operation with CICS requires MVS Subsystem Interface (SSI) support, and to obtain this you must define CICS as an operating system subsystem, as described in Chapter 10, “Defining CICS as an MVS subsystem,” on page 83.

Installing the modules DFHIRP and DFHCSVC in the LPA

To enable your regions to communicate by MRO, you must:

1. Install the current versions of the DFHIRP and DFHCSVC modules into the LPA, as described in Chapter 14, “Installing CICS modules in the MVS link pack area,” on page 107.

Note: If you are running CICS with MRO at different release levels, all
communicating CICS regions must use the latest DFHIRP module and
the latest SVC module, DFHCSVC, on the same MVS image. Do not use
the dynamic LPA function to replace DFHIRP for migration between
releases, as this can cause incompatibility between control blocks,
resulting in abend situations.

2. Define the SVC module, DFHCSVC, to MVS, as described in Chapter 11, “Installing the CICS Type 3 SVC,” on page 93.

Installing required hardware and software for XCF/MRO

To be able to use the cross-systems MRO to communicate between CICS regions on different MVS images, those MVS images must be running with appropriate hardware and software. The hardware and software that are required for MVS systems in a sysplex are in the *CICS Transaction Server for z/OS Program Directory*.

Defining MVS images as systems in an XCF sysplex

To use XCF/MRO, all participating MVS images must be defined as part of the same sysplex, as in Chapter 19, “MVS cross-system MRO definitions,” on page 129.

Note: Within a parallel sysplex, where MRO communication between MVS images is by XCF/MRO, the DFHIRP programs installed in the different MVS images can be at different release levels. However, DFHIRP must be installed from the highest release of CICS running in an MVS image. For example, a CICS Version 4 DFHIRP can communicate with a DFHIRP across XCF/MRO, but the CICS regions running in the MVS with the Version 4 DFHIRP cannot be later than CICS/ESA Version 4.

Defining MRO connections

Before you can use MRO, you must define and install connections with attributes appropriate to your CICS environment. For information about defining connections, see the *CICS Intercommunication Guide* .

Enabling MRO for CICS startup

For each CICS region that is to use MRO, you must specify `ISC=YES` to include the intersystem communication program DFHISP.

If you want a CICS region to establish MRO communication during startup, you should also specify `YES` on the `IRCSTART` system initialization parameter.

Alternatively, once your CICS region is running, you can establish MRO communication by using the `CEMT SET IRC OPEN` command or the `EXEC CICS SET IRC OPENSTATUS(cvda)` command.

Either method establishes MRO communication with every CICS region that is:

1. Currently active.
2. Defined to your region by `CONNECTION` and `SESSIONS` definitions that are installed from the CSD. (To establish MRO communication between two CICS regions, the installed `CONNECTION` definition must specify `INSERVICE(YES)` in both regions.)

Adding ISC support

For communication between CICS regions that are in different MVS images, you can use a SNA access method, such as ACF/VTAM, to provide the necessary communication protocols. This form of communication between regions through SNA is called **intersystem communication** (ISC). (You can also use ISC in the same CPC, through the application-to-application facilities of ACF/VTAM.)

This section outlines how to include ISC in a CICS region.

For information about the design and implementation of intersystem communication facilities, see the *CICS Intercommunication Guide* .

Unlike MRO, there are no special MVS operating system requirements for CICS intersystem communication.

Running a CICS region with ISC

You must include the following management programs in your CICS regions, (by specifying the system initialization parameters that are given in parentheses):

- DFHISC – the intersystem communication program (`ISC=YES`).
- DFHTCP – the terminal control program (`TCP=YES` is the default).

Establishing ISC

Intersystem communication requires VTAM support, and you must specify `VTAM=YES` as a system initialization parameter. If VTAM is running during CICS initialization, CICS opens the VTAM ACB. If VTAM is started after CICS, opening the VTAM ACB fails, and you must open it using the `CEMT SET VTAM OPEN` command when VTAM is available. CICS regions cannot communicate until they have established the VTAM connection.

Defining ISC connections

Before you can use ISC, you must define and install connections with attributes appropriate to your CICS (and VTAM) environment. If you intend using APPC for your ISC communications, you can take advantage of the autoinstall for APPC connections function. For information about defining connections, and about using the autoinstall for APPC connections function, see the *CICS Resource Definition Guide*.

Chapter 33. Enabling TCP/IP in a CICS region

TCP/IP support is provided by the CICS sockets domain, with network services supplied by z/OS. The sockets domain provides support for:

The listener

The listener monitors specified TCP/IP ports for incoming requests. It is configured by a TCPIP SERVICE resource definition to listen on a specific TCP/IP port and to attach a specified request receiver transaction to handle each connection. Once the connection has been established between a client program and a particular request receiver, all subsequent requests from the client program over that connection flow to the same request receiver. The listener supports user applications initiated by TCP/IP services for the following protocols:

External Call Interface (ECI)

The External Call Interface (ECI) allows client applications to use TCP/IP directly to CICS regions without any intervening products such as protocol-mapping software. The External Call Interface (ECI) is supported, but not the External Presentation Interface (EPI).

See the *CICS Family: Communicating from CICS on System/390®* manual for information about the External Call Interface.

Hypertext Transfer Protocol (HTTP)

HTTP messages are received and sent over the Internet, using CICS Web support. See the *CICS Internet Guide* for information about the transmission of HTTP messages on the Web.

Internet InterORB Protocol (IIOP)

IIOP messages are sent between client and server applications that conform to the Common Object request Broker Architecture (CORBA). See the *Java Applications in CICS* manual for information about IIOP messages.

Outbound socket support

This allows CICS to initiate an IP connection. Sockets can be created by one task, shared by other tasks, and remain active after task termination, for re-use by another task.

Using TCP/IP in a CICS region

To use TCP/IP in a CICS region, you must provide the following:

- Communications Server must be installed in the z/OS system (In earlier OS/390 releases this is called *eNetwork Communications Server*, or *Secureway Communications Server*). Ports belonging to Communications Server must be made available for use by the CICS region involved.
- The CICS system initialization parameter TCPIP must be set to YES.
- TCPIP SERVICE resource definitions must be provided to define each active port and the type of service associated with it. The CICS TCP/IP listener is activated for the specified ports when the TCPIP SERVICE is installed, if TCPIP (YES) has also been specified.
- If Secure Sockets Layer (SSL) authentication is used, you must define the KEYRING system initialization parameter, to identify the RACF key ring containing the keys and X.509 certificates used in the SSL handshake.
- The CICS listener regions need to be configured to talk to the same nameserver on z/OS that the MVS Workload Manager is configured to use. This means that

you may need to reconfigure the DNS server that CICS uses to resolve hostnames, because CICS needs to resolve its own hostname (using a call to the *gethostbyaddr* function.) using the DNS server configured for the connection optimization in the sysplex. This may not be the system configured name server if the sysplex is already configured for TCP/IP operation. The system name server may not even be on z/OS or on any of the systems in the sysplex.

You can change the resolver configuration of CICS either by altering system TCP/IP configuration files, or by adding or changing the DD name SYSTCPD in the CICS start-up JCL. This sets the RESOLVER_CONFIG environment variable to the MVS dataset you have specified. This file is described in the *z/OS IBM Communications Server: IP Configuration Guide*, SC31-8775. It contains a reference to the DNS server's IP address.

You must specify at least the following:

```
NSINTERADDR n.n.n.n
```

where *n.n.n.n* is the dotted decimal address of the name server to be used.

If the DD name is not included in the startup JCL, a number of system files are searched until one is found.

Note: The TCIPSERVICE resource definitions are for use only with the CICS-provided TCP/IP services, and have nothing to do with the z/OS Communications Server IP CICS Sockets interface. The TCP/IP Socket Interface for CICS is supplied with z/OS Communications Server, which is an integral part of z/OS and does not use the CICS SO domain.

Chapter 34. Enabling REXX for CICS

The REXX Development System for CICS and the REXX Runtime Facility for CICS--two program products collectively referred to as REXX for CICS--provide improved productivity for a wide range of CICS activities.

REXX for CICS enables you to write and execute REXX programs in a CICS region. These programs have access to most EXEC CICS commands, the CICS CEDA and CEMT transactions, and DB2 databases through the EXEC SQL interface.

To enable your CICS system to provide the facilities of REXX for CICS, perform the following steps:

- Step 1-- Consider your customization needs for REXX, see “Customization information for REXX” on page 219.

You might prefer to familiarize yourself with the procedure at the first reading by ignoring customization. (We intentionally show this step at the beginning and again at the end of the list to cater for those working through the list who need it first, and those reading it for the first time who would benefit from covering the topic last.)

- Step 2--“Step 1--Modify your RDO definitions to add required entries.”
- Step 3--“Step 2--Create the RFS filepools.”
- Step 4--“Step 3--BIND the CICS SQL program to your DB2 plan” on page 218.
- Step 5--“Step 4--Add DD statements to your CICS startup job” on page 218.
- Step 6--“Step 5--Modify member CICSTART” on page 218.
- Step 7--“Step 6--Format the RFS filepools” on page 218.
- Step 8--“Step 7--Verifying the installation” on page 219.
- Step 9--“Step 8--Accessing the supplied softcopy documentation” on page 219.
- Step 10--“Customization information for REXX” on page 219 (if you choose to skip step 1).

Step 1--Modify your RDO definitions to add required entries

Job CICRDOR (for Runtime Facility) or job CICRDOD (for Development System) in data set CICSTS31.REXX.SCICJCL adds the entries needed by the product, including REXX/CICS profiles, VSAM files, programs, transactions, and transient data queues. The transient data queues are used for REXX/CICS IMPORT and EXPORT commands. The jobs also contains the definitions for the REXX/CICS SQL interface that authorize the transactions to the DB2 plan. Review “Changing supplied CICS transaction codes” on page 220 if you plan to modify the transaction IDs and also review “RFS filepool definitions” on page 221 if you plan to change the REXX file system (RFS) pool names or the number of pools to install. Edit the JCL (ensuring that you uncomment the entries as explained in comments at the beginning of the JCL) and run the job.

A return code of 4 is acceptable.

Step 2--Create the RFS filepools

Job CICVSAM in data set CICSTS31.REXX.SCICJCL defines the clusters needed to create the VSAM data sets needed for the RFS filepools. See “RFS filepool definitions” on page 221 for customizing information about RFS filepools.

You receive a condition code of 8 for the delete control statements if the VSAM data sets do not exist. You receive a condition code of 0 for the define cluster control statements if the job runs correctly.

Step 3--BIND the CICSQL program to your DB2 plan

Job CICBIND in data set CICSTS31.REXX.SCICJCL binds CICSQL to the correct DB2 plan. Edit and run the job.

You might receive condition code 4 for the job depending upon the level of DB2 being used.

Step 4--Add DD statements to your CICS startup job

You need to add the following DD statements to your CICS startup job. See "Special exec data sets used by the REXX Development System" on page 222 for more information.

```
//CICAUTH DD DSN=CICSTS31.REXX.SCICMDS,DISP=SHR
//CICEXEC DD DSN=CICSTS31.REXX.SCICEXEC,DISP=SHR
//CICUSER DD DSN=CICSTS31.REXX.SCICUSER,DISP=SHR
```

Additionally a DD statement for CICSTS31.REXX.SCICLOAD must be added to the DFHRPL concatenation.

Step 5--Modify member CICSTART

Modify member CICSTART in data set CICSTS31.REXX.SCICEXEC. See "Customization information for REXX" on page 219 for more information.

Step 6--Format the RFS filepools

Bring up the CICS region and sign onto the CICS region with a userid defined as an authorized user. Enter REXX, the default transaction id associated with the CICRXTRY exec. You should see the following line at the top of the screen, "Enter a REXX command or EXIT to quit" and a "READ" in the lower right hand corner. The cursor is in the lower left hand corner. You have now entered the supplied exec which allows the execution of REXX and REXX/CICS commands interactively.

You may now prepare the filepools for use by entering the command: 'FILEPOOL FORMAT *pool1*' where *pool1* should be substituted by the filepool name you specified in the CICSTART exec.

Note: The command should be entered as shown, including the apostrophes.

The interactive environment will echo each command at the next available line on the screen and any requested output will also be displayed. The FILEPOOL FORMAT command does not display any information. To determine whether the FILEPOOL FORMAT command worked successfully, enter "SAY RC". If a "0" is displayed on the next available line, the FILEPOOL FORMAT command was successful.

Continue this process until all RFS filepools have been formatted. You only have to format the filepool when a new filepool has been defined, or if you delete and redefine the clusters for an existing filepool.

If, in the process of formatting the filepools or interactively executing REXX or REXX/CICS commands and instructions, you fill the screen, a "MORE" indicator will

appear at the bottom right hand corner. To clear the screen, press the ENTER key. Any time you want to clear the screen of data, you may press the CLEAR key. To exit from the interactive environment, you may press the PF3 key which simulates the entering of the "EXIT" REXX instruction. You may also enter the "EXIT" instruction yourself.

The interactive environment also provides for recalling previously entered commands. This is done by pressing the RETRIEVE key. The system has a default setting for this key of PF12. This may be customized using the SETSYS RETRIEVE command. Pressing the RETRIEVE key causes the previously entered line to be re-displayed at the input location. You can then modify this area if required and re-execute the instruction by pressing ENTER. Pressing the RETRIEVE key multiple times will continue to bring the next previously entered command to the input area.

Step 7--Verifying the installation

To verify the installation has been successful, three execs have been supplied. From the interactive REXX environment, enter, CALL CICV1P1. The exec will indicate what should occur.

Step 8--Accessing the supplied softcopy documentation

The REXX Development System for CICS/ESA and the REXX Runtime Facility for CICS/ESA Guide and Reference manual is included on the distribution tape in three different softcopy formats.

The supplied data set CICSTS31.REXX.SCICDOC contains two members.

Member CICR3270 contains the manual in LIST3270 format, a format that has an 80-character record length. CICR3270 is used as input by the online help facility which is described in "Online HELP facility" on page 223.

Member CICR3820 contains the manual in LIST3820 format. Job CICBPRNT in data set CICSTS31.REXX.SCICJCL contains a sample job, which may be modified and executed, that prints the manual to a device which supports LIST3820 formatted data.

The supplied data set CICSTS31.REXX.SCICBOOK contains one member, CICRBOOK. It contains the manual in BookManager/read format. If you have BookManager[®] installed you may use this data set to view the manual.

Customization information for REXX

This section provides customizing information. It should be reviewed prior to performing the steps listed in "Step 1--Modify your RDO definitions to add required entries" on page 217. It covers the following topics:

- "Changing supplied CICS transaction codes" on page 220.
- "RFS filepool definitions" on page 221.
- "TD queues needed for IMPORT and EXPORT commands" on page 221.
- "SQL definitions used for authorizing transactions to use DB2" on page 221.
- "Special exec data sets used by the REXX Development System" on page 222.
- "Special USER ids and their usage" on page 222.
- "Other considerations" on page 223.
- "Online HELP facility" on page 223.

Changing supplied CICS transaction codes

There are three transaction ids supplied by the product. They are: REXX, EDIT, and FLST. You can change these supplied transaction ids.

The functions of REXX, EDIT, and FLST

The functions of REXX, EDIT, and FLST are:

REXX is the default transaction id.

- If no additional operands are supplied the CICRXTRY exec starts. CICRXTRY allows the user to interactively enter REXX instructions and execute them.
- If REXX is entered and is followed by a string (separated from REXX by blanks), the string is interpreted as a REXX exec name followed by operands that are passed to the named REXX exec. This action causes the named exec to execute.

When the REXX exec ends, control is returned to CICS.

EDIT is the transaction id associated with the REXX Development System editor.

- If no additional operands are supplied the CICIPEDIT exec starts and the file "NONAME" in the user's current RFS directory is opened for editing.
- If EDIT is entered with an additional operand separated from the transaction id with a blank, the operand is interpreted as the name of a particular file in the user's current directory which is to be opened for editing.

When the EDIT session ends, control is returned to CICS.

FLST is the transaction id associated with the REXX Development System file list exec, CICIPFLST.

- If no additional operands are supplied, the CICIPFLST exec starts and the contents of the user's current RFS directory are displayed.
- If FLST is entered with an additional operand separated from the transaction id with a blank, the operand is interpreted as the name of a particular RFS directory whose contents are to be listed.

When the FLST session ends, control is returned to CICS.

Changing the supplied transaction ids

You can change the names of the supplied transaction ids, and you can add additional transactions which will call your own execs.

- The DEFTRNID commands in the member, CICSTART, in data set CICSTS31.REXX.SCICEXEC define the supplied transaction ids REXX, EDIT, and FLST, and associate them with their execs.

If you choose to change the supplied entries make sure that you update the RDO definitions to match your changes. If you do not want users to call the editor or file list execs directly from CICS, you can delete the DEFTRNID commands, for either or both of them, from CICSTART and also from the RDO definitions. Users will not be allowed access to these directly from CICS. Ensure that you do not remove the DEFTRNID statement for the CICRXTRY exec.

- If you want to add additional transactions which call your own execs directly from CICS, add RDO definitions for the transaction ids and add further DEFTRNID commands to your CICSTART exec. Your newly defined transactions become available to your users when you restart your CICS system. An authorized user

can enter the DEFTRNID command directly to give immediate availability, but until the CICSTART member is changed, these definitions are lost when CICS is restarted.

RFS filepool definitions

The supplied member, CICVSAM in CICSTS31.REXX.SCICJCL, creates the VSAM data sets for two RFS filepools. The names for these VSAM data sets can be changed to match your installation standards. If you do change these names make sure to make matching changes to the member, CICRDOD, as well. Since the RDO definitions supplied contain the data set names, DD statements are not needed in the CICS startup job. This technique can be used to add additional files to an RFS pool or to add additional RFS filepools without restarting your CICS system.

The FILEPOOL DEFINE commands in member, CICSTART in data set CICSTS31.REXX.SCICEXEC have two purposes. The first is to define the names of the supplied filepools. They are: POOL1 and POOL2. You can modify these names to your installation standards. They can be from 1 to 8 characters. They should not contain special characters, “:” or “\”. The second purpose is to associate the filepool ids to the FCT definitions for the VSAM data set used for its directory and the first VSAM file used for data storage.

If you want to add additional RFS filepools to your system you need to add RDO definitions and add FILEPOOL DEFINE commands to your CICSTART member. If you intend to allow users to add RFS files to the new filepool you must define the filepool to include a \USERS directory.

To make these new filepools available for use, you must restart CICS. However, you can also add filepools while your CICS system is active as follows.

- add the RDS definitions for the new files and define them using a batch job
- then get an authorized user to enter the FILEPOOL DEFINE command and the FILEPOOL FORMAT command
- be sure to modify CICSTART or your new definitions are lost when you restart your CICS system

TD queues needed for IMPORT and EXPORT commands

The REXX Development System uses dynamic allocation to IMPORT members from a partitioned data set or to EXPORT RFS files to a partitioned data set. The member CICRDOD in data set CICSTS31.REXX.SCICJCL defines three Transient Data entries used as input for IMPORT and 3 Transient Data entries for output for EXPORT. This allows three users to concurrently IMPORT and three users to concurrently EXPORT from and to partitioned data sets.

Modify the number of TDQ entries to suit your needs, but you should allow for at least one input and one output entry. The TDQUEUE NAME must begin with REX and be suffixed with a valid character. Ensure there are no other applications using TDQUEUE names that begin with REX because IMPORT/EXPORT will use them and may cause files to become corrupted.

SQL definitions used for authorizing transactions to use DB2

The member CICRDOD in data set CICSTS31.REXX.SCICJCL authorizes the transactions, REXX, EDIT, FLST, and DXB0 to use the DB2 plan. The first three of these transactions are REXX for CICS transactions and the DXB0 transaction is added if you have OfficeVision/MVS and want to use DB2 interface calls which may

run under the OV/MVS transaction id. If you choose to modify the supplied transactions for the REXX Development System, you need to modify the DB2 entry definitions also.

If you implement new transactions which use the DB2 interface code then you should also add these DB2 entry definitions to your RDO group.

Special exec data sets used by the REXX Development System

There are three data set concatenations which are used by the REXX Development System which have no FCT entries. They are the DD names, CICCMDS, CICEXEC, and CICUSER. These data sets are partitioned data sets and are accessed using MVS facilities.

CICCMDS

The CICCMDS DD name concatenation should start by referencing the data set CICSTS31.REXX.SCICCMDS. This data set contains those execs which implement REXX Development System authorized commands. Only authorized users or execs authorized to use authorized commands may access these execs. If you choose to extend the REXX Development System with your own authorized commands, you should concatenate your data set to this DD name concatenation.

CICEXEC

The CICEXEC DD name concatenation should start by referencing the data set CICSTS31.REXX.SCICEXEC. This data set contains those execs which are supplied by the REXX Development System that use authorized commands. If you choose to extend the REXX Development System with your own execs which use authorized commands then you should concatenate your data set to this DD name concatenation.

CICUSER

The CICUSER DD name concatenation should start by referencing the data set CICSTS31.REXX.SCICUSER. This data set contains those execs which are supplied by the REXX Development System that do not use authorized commands. If you choose to extend the REXX Development System with your own execs which do not use authorized commands then you should concatenate your data set to this DD name concatenation.

The facilities used to access these data set concatenations use CICS WAIT EXTERNAL capabilities to avoid placing the CICS region into a wait.

Special USER ids and their usage

It is recommended that external security be used in the CICS environment. This is needed because individual user's information is maintained by the REXX Development System by the user's userid designation. Each user should have his own identification and there should not be two users signed on to the REXX Development System with the same userid at the same time. Two users with the same userid operating at the same time could have unusual results.

If a user is not signed on to the CICS region then the special userid of “*RCUSER*” is used to access the RLS and RFS facilities.

Authorized users are identified to the REXX Development System through the AUTHUSER command. This command is an authorized command and can only be

used by an authorized user or an exec which is authorized to use authorized commands. CICSTART is such an exec because it resides in the CICEXEC DD name concatenation.

The member, CICSTART in the supplied data set CICSTS31.REXX.SCICEXEC then should be modified to contain an AUTHUSER statement to identify at least one userid which should be an authorized user. It is important to add the AUTHUSER statement after the existing AUTHUSER statement for RCUSER. For example:

```
'AUTHUSER RCUSER'  
  IF RC ^= 0 THEN EXIT RC  
'AUTHUSER your-userid'  
  IF RC ^= 0 THEN EXIT RC
```

You could also call another exec of your choosing, within the CICEXEC concatenation, which could contain the userids of those users who should be authorized users.

Other considerations

The member, CICSTART in data set CICSTS31.REXX.SCICEXEC, contains default definitions for the REXX Development System. It is executed when the first user who executes a transaction that uses the CICREXD program after the CICS system has been started. This exec should be updated with any changes in customization if those changes are required to be effective across CICS executions.

The REXX Development System provides the capability to execute execs in either pseudo-conversational or conversational mode. The system default for conversational mode is specified with the SETSYS PSEUDO statement in the member, CICSTART in the data set CICSTS31.REXX.SCICEXEC. The default supplied provides for pseudo-conversational to be used. CICSTART must run in conversational mode because the system has not yet been initialized enough to ensure correct operation.

The CICSTART member also contains EXECLOAD commands which are commented as shipped. EXECLOADing execs will reduce the amount of storage used by the REXX Development System because users will then share the same exec. Also performance may be increased because these execs will not have to be loaded into CICS memory each time they are executed. EXECLOADed execs are used before any other execs. Therefore, if you EXECLOAD an exec "TEST.EXEC" and you have an exec in your RFS current directory by the same name, you will not be able to execute your RFS copy. Care should then be used both in the naming of your execs and EXECLOADing them. The authorization associated with the special DD names is maintained when execs are EXECLOADed from those DD name concatenation.

Online HELP facility

An online HELP facility is provided which may be used as an example of the REXX/CICS panel facility. It provides the means to search and display the LIST3270 manual which is supplied with the product. There are several steps which must be done in order to activate the online help.

Note: If PTF maintenance has been applied that affects data sets for the procedure outlined below, then you should use the target library; otherwise, the distribution library should be used.

First, modify member CICSTART in the data set CICSTS31.REXX.SCICEXEC to reflect the correct RFS filepool and path where the online help files should be. If you choose to use the default no changes to CICSTART are necessary.

Next copy the supplied data set CICSTS31.REXX.SCICDOC to a data set whose highest level data set qualifier matches the userid of the user who will be executing the CICHPREP exec. The reason for this is the supplied security exit for the REXX/CICS IMPORT and EXPORT commands checks the highest level qualifier and it must match the userid for the user who issues the IMPORT command.

Next copy the supplied data set CICSTS31.REXX.SCICPNL to a data set whose highest level data set qualifier matches the userid of the user who will be executing the CICHPREP exec. This data set contains the panel definitions which are used by the online help. They must be IMPORTed into the RFS filepool and path defined for the online help.

Next sign onto REXX/CICS using the REXX transaction id. If you have changed the default transactions, this is the transaction id associated with the CICRXTRY exec. Issue the command, 'EXEC CICHPREP'. Follow the instructions issued by the exec. This exec will read the LIST3270 format of the manual from the data set you name, into the RFS directory specified in CICSTART. It also splits the manual into multiple files for usage by the online help. Additionally, the panels used by the online help are IMPORTed into the RFS system.

The online HELP facility is now ready for use.

There are several ways the user may access the online HELP.

Enter 'HELP' on the command line from the interactive environment and a table of contents is displayed. You also may enter this command from the command line of the REXX/CICS editor or the REXX/CICS filelist facilities.

Entering 'HELP xxxxx' searches the INDEX of the manual for the xxxxx entry. If found you are taken directly to that section of the manual.

There also is a HELP key defined for the editor and the filelist facility. It is defined in the customizing macros for the editor and the filelist facilities. The supplied default for this key is PF1. You may choose to modify the supplied default by modifying these profiles.

Part 4. CICS verification

This part describes the processes and procedures you should follow to run the installation verification procedures for CICS. It contains the following chapters

- Chapter 35, “Running the installation verification procedures,” on page 227.

Chapter 35. Running the installation verification procedures

After you have installed CICS, and applied any necessary service, you can use the CICS-supplied installation verification procedures (IVPs) to confirm that CICS is operational.

There are two IVP jobs:

1. DFHIVPBT (verify batch)

This job starts up CICS, specifying a pair of sequential input and output devices (CARDIN and PRINTER) to be used instead of an ordinary terminal. It then executes a number of CICS transactions that are read from CARDIN. The last transaction in the input stream shuts down CICS.

2. DFHIVPOL (verify online)

This job can run CICS with either XRF=NO, or XRF=YES. It is generated with XRF=NO specified as an override, which you change when you are ready to verify CICS with XRF.

You can use this CICS region to automatically install (**autoinstall**) an IBM 3270 Information Display System terminal, with which you can:

- Use the master terminal transaction, CEMT. You can also use CEMT from the MVS system console. For information about using CEMT, see the *CICS Supplied Transactions* manual.
- Use the resource definition online transaction, CEDA. For information about using CEDA, see the *CICS Resource Definition Guide* .
- Use the sample application transaction AMNU, to access the sample VSAM file, FILEA. For a description of the FILEA sample applications, see the *CICS 4.1 Sample Applications Guide* .

Before you run the IVP jobs, you will need to prepare your system. The steps you need to perform are described in “Preparation for running the IVPs.”

Preparation for running the IVPs

Perform the following steps:

- Create the CICS data sets for the IVP jobs
- Install the CICS SVC for the IVP jobs
- Define and activate the CICS applids
- Authorize the IVP userid
- Review security requirements for the IVP jobs
- Define log streams
- Specify system initialization parameters for the IVP jobs

Create the CICS data sets for the IVP jobs

Before you can run any of the CICS-supplied IVP jobs, create the data sets that they use. For further information about creating the data sets for the IVP jobs, see Chapter 28, “Creating the CICS data sets,” on page 189.

Install the CICS SVC for the IVP jobs

All the IVP jobs require the CICS Type 3 SVC, which must be installed in the LPA. If you have not already installed the CICS SVC in the LPA (as described under

Chapter 14, “Installing CICS modules in the MVS link pack area,” on page 107), do so now before attempting to run any of the IVP jobs. The IVP jobs do not use the Type 6 SVC (DFHHPSVC).

Define and activate the CICS applids

If you want to use VTAM with a CICS region started by any of the CICS IVP jobs, create and activate a VTAM APPL definition for the CICS regions’s application identifier (applid). The applid defined to VTAM must match the applid that is specified on the APPLID system initialization parameter that is used by the IVP job. For example, to be able to logon to the CICS region that is started by the DFHIVPOL job, you must do one of the following:

- Create and activate an APPL definition for your own applid, which you specify on the APPLID parameter of the DFH\$SIP1 member of the SYSIN data set.
- Define and activate an APPL definition for the default applid DBDCCICS, which you specify on the APPLID parameter of the DFH\$SIP1 member of the SYSIN data set.

For more information about creating and activating VTAM APPL definitions for CICS, see Chapter 13, “Defining CICS regions as applications to VTAM,” on page 99 and “Naming conventions” on page 190.

Further, if you want to use VTAM cross-domain services to communicate between CICS regions on separate MVS images, you must create and activate VTAM CDRSC definitions in both MVS images involved in the communication. For more information about creating and activating VTAM CDRSC definitions for CICS, see “Cross-domain considerations” on page 101.

Authorize the IVP userid

To run the IVP jobs with external security, you must define to RACF an IVP default CICS userid that has authority to run the transactions used as part of the IVP jobs. These transactions include the CICS-supplied transactions that are listed in Table 16. The level of authority that is required by the IVP userid depends on what security you want to use for the IVP jobs. For more information, see “Review security requirements for the IVP jobs” on page 229.

Note: On a production system the default user should *not* have access to any CICS-supplied transactions except those you need in your CICS environment. The resource access authorizations that you give to the default user should clearly be limited to those resources that you intend to be universally available, and therefore not restricted in any way.

For information about the security requirements for CICS-supplied transactions, and about CICS security in general, see the *CICS RACF Security Guide* .

Table 16. Transactions used as part of the IVP jobs

Application	Transactions
DFH\$BTCH	CWTO, CEMT, CEOT, CSFE
FILEA samples	
DFH\$MNU	AMNU, MENU, PMNU, DMNU
DFH\$ALL	AINQ, INQY, PINQ, DINQ AADD, ADDS, PADD, DADD AUPD, UPDT, PUPD, DUPD

Table 16. Transactions used as part of the IVP jobs (continued)

Application	Transactions
DFH\$xBRW	ABRW, BRWS, PBRW, DBRW
DFH\$REN	AORD, OREN, PORD, DORD
DFH\$xCOM	AORQ, OREQ, PORQ, DORQ
DFH\$REP	AREP, REPT, PREP, DREP
Other functions	CETR, CEDA, CMAC, CMSG, CSGM

Review security requirements for the IVP jobs

You can run the IVP jobs with or without external security.

As supplied, the system initialization table, DFHSIT, used by the IVP jobs, specifies that external security is on. However, the IVP jobs have been set up with SEC=NO, indicating that external security is not on. DFHSIT also specifies that the IVP jobs are subject to transaction security (XTRAN=YES), resource security (Xyyy=YES), and command security (XCMD=YES).

Note: As supplied, the DFH\$SIP2 member of the SYSIN data set used by the DFHIVPBT job specifies the SIT override SEC=NO, so that you can run this job without external security.

If you choose to run the IVP jobs with external security, you must:

- Define CICS resource profiles to RACF.
- Define an IVP default CICS userid to RACF.
- Specify the IVP userid on the DFLTUSER=userid system initialization parameter.

You must also give the IVP userid sufficient authority to use transactions and resources that are needed to run the IVP jobs. That is, you must:

- Authorize the IVP userid to run the transactions that are used as part of the IVP jobs. (See Table 16 on page 228.) To do this you must add the IVP userid, with READ access, to the access list of the RACF profiles for the transaction member class (TCICSTRN) or the transaction group class (GCICSTRN).

If you define the transactions as prefixed resources, you must also specify the system initialization parameter SECPRFX={YES |prefix} for the IVP jobs.

- Authorize the IVP userid to access the resources that are used by the transactions. To do this you must add the IVP userid, with appropriate authority, to the access list for the resource class profiles.
- Authorize the IVP userid to issue SP-type commands using the CEMT master terminal transaction. To do this, you must add the IVP userid, with appropriate authority, to the access list of the RACF profiles for the resource member class (CCICSCMD) or the resource group class (VCICSCMD). You must give the IVP userid UPDATE access for the SHUTDOWN resource class, otherwise the userid will not be able to terminate the IVP jobs. You should also give the IVP userid UPDATE access for the DUMPDS and SYSTEM resource classes, if the DFHIVPBT job is to be run with external security.

For information about implementing external security, see the *CICS RACF Security Guide*. Alternatively, you can run the IVP jobs with limited security, for example:

#

- Without command security (XCMD=NO), the IVP userid would be able to run the IVP jobs without the need for authority to use the CEMT SP-type commands and the resources that they access.
- With only transaction security (Xyyy=NO including XCMD=NO), the IVP userid would be able to run the IVP jobs if authorized only to use the transactions used as part of the IVP jobs.

Define log streams

CICS automatically attempts to connect to its system log stream, unless you define a journal model resource definition to define the log stream as TYPE(DUMMY). This means that you need to decide whether you want to run the IVPs with system logs, or to run with dummy logging.

If you decide to run with actual log streams, see Chapter 24, “Defining the logger environment for CICS journaling,” on page 143 for information about defining log streams.

Alternatively, you can define a CICS JOURNALMODEL resource definition with TYPE(DUMMY) to avoid having to define log streams. If you want to run the IVPs with the minimum effort:

- Define JOURNALMODEL resource definitions in the CSD for the primary and secondary system logs, DFHLOG and DFHSHUNT respectively, specifying TYPE(DUMMY); see Figure 25 for a sample job.
- Add the CSD group that contains your dummy system log journal models to your own group list, and include your group list on the GRPLIST system initialization parameter.

Note that your group list must *follow* the IBM-supplied list DFHLIST. DFHLIST includes group DFHLGMOD (which contains DFHLOG and DFHSHUNT JOURNALMODEL definitions) Concatenating your list after DFHLIST ensures that your DUMMY definitions replace the IBM definitions.

```
# //CSDLGSTR JOB 1,BELL,MSGCLASS=A,MSGLEVEL=(1,1),CLASS=A
# //CSDUP EXEC PGM=DFHCSDUP,REGION=1M,PARM='CSD(READWRITE)'
# //STEPLIB DD DSN=CICSTS31.SDFHLOAD,DISP=SHR
# //DFHCSD DD DSN=CICSTS31.CICSH###.DFHCSD,DISP=SHR
# //SYSPRINT DD SYSOUT=*
# //SYSABOUT DD SYSOUT=*
# //SYSABEND DD SYSOUT=*
# //SYSUDUMP DD SYSOUT=*
# //SYSIN DD *
# *
# * DEFINE JOURNAL MODELS FOR CICS LOG STREAMS AS DUMMY
# *
# DEFINE JOURNALMODEL(DFHLOG) GROUP(LOGTEST)
# DESCRIPTION(DEFINE SYSTEM LOG AS DUMMY)
# JOURNALNAME(DFHLOG)
# TYPE(DUMMY)
# *
# DEFINE JOURNALMODEL(DFHSHUNT) GROUP(LOGTEST)
# DESCRIPTION(DEFINE SYSTEM LOG AS DUMMY)
# JOURNALNAME(DFHSHUNT)
# TYPE(DUMMY)
# /*
# //
#
#
#
```

Figure 25. Sample job to define DUMMY JOURNALMODELs for CICS system logs

Specify system initialization parameters for the IVP jobs

All the IVP jobs use the system initialization parameters that are specified in the associated DFH\$SIPn member of the SYSIN data set. The DFH\$SIPn members, as supplied by CICS, default to the unsuffixed SIT, DFHSIT, and the resources defined to CICS are adequate only for a basic CICS region. For example, in the case of the DFHIVPOL job, the resources defined limit the number of terminals you can use.

The DFH\$SIPn members of the SYSIN data set also contain some system initialization parameters to exclude CICS resources not required by the IVP jobs, or to include some not specified by the default SIT.

One such parameter is TCT=5\$, specifying the CICS sample terminal control table, in the *hlq.SDFHLOAD* library. This TCT defines the pair of sequential input and output devices, CARDIN and PRINTER. (These are the only devices that are defined in DFHTCT5\$.)

The DFH\$SIPn members of the SYSIN data set may need to be edited for:

- The default SVC number is 216. To use a different SVC number, specify CICSVC=nnn in the appropriate DFH\$SIPn member. For more information about defining CICS SVCs, see “Defining the CICS SVCs to your MVS” on page 93.

The IVP jobs do not require the Type 6 SVC.

- The applid used is CICSIVP1. To use a different applid, change the system initialization parameter (APPLID=CICSIVP1) in the appropriate DFH\$SIPn member.
- The IVP jobs had external security switched off. To run with security (SEC=YES), define a suitable default userid (for example IVPUSER) with the required authority to run the IVP transactions. Add DFLTUSER=IVPUSER in the appropriate DFH\$SIPn member. For more information about defining the IVP userid, see “Authorize the IVP userid” on page 228.

Transactions can be defined as prefixed resources by using the IVP userid, IVPUSER or any other prefix, as the prefix (for example, IVPUSER.CEMT or prefix.CEMT). To do this, add SECPRFX=YES, or SECPRFX=prefix in the appropriate DFH\$SIPn member for the IVP job.

This enables transactions to be run as part of the IVP jobs without affecting other CICS regions. For example, when the DFH\$BTCH batch stream is run, CICS sends authorization requests to RACF for the transactions and identifies them as IVPUSER.xxxx, where xxxx is the transaction ID (CWTO, CEMT, and so on).

- Language Environment support, for all the high-level language sample programs, was added as described in the *CICS System Definition Guide*. CICS requires either pre-defined CSD definitions, for the Language Environment modules, to be installed or Program autoinstall to be active.

The IVP jobs include the required DD statements for the Language Environment libraries as comments.

- The resources for the CICS messages facility were defined, as described in “Resources for the CICS messages facility, CMAC” on page 232, and the DFHCMAC resource group added to a group list used for the IVP jobs.
- The IVP jobs run with auxiliary trace switched on (AUXTR=ON), and the auxiliary trace data set switching facility set to switch once only (AUXTRSW=NEXT).

Other notes about changes to the system initialization parameters for the IVP jobs, and about the IVP jobs generally, are in the sections that describe the IVP jobs.

#

If you want to use system initialization parameters to modify or enhance the scope of the IVP jobs, see the *CICS System Definition Guide* for details about the parameters.

Resources for the CICS messages facility, CMAC

You can use the CICS messages facility (CICS-supplied transaction CMAC) to provide the messages and codes descriptions online. Before you can use this facility, you must create and initialize the CICS messages data set DFHCMACD, define the resources needed by the facility, and make them available to your CICS region.

For information about creating and initializing the DFHCMACD data set, see “Creating the CICS messages data set, DFHCMACI job” on page 193.

The file DFHCMACD, managed by CICS file control, accesses the DFHCMACD data set. You must create a definition for this file in the CSD. The CICS-supplied definition for the DFHCMACD file and other resources that are needed by the CICS messages facility are in the CSD group DFHCMAC. The CICS startup procedure (in the IVP jobs) has a DD statement for the CMAC file, but for dynamic allocation you should copy the supplied resource definition for the DFHCMACD file and add the DSNNAME option.

You should specify the DFHCMAC group of resources for the CICS messages facility only in those CICS regions that need to use the facility; for example on some terminal-owning regions, but perhaps not on data-owning regions.

The CICS startup procedure, DFHSTART

All the IVP jobs include a procedure to start up CICS. You can use this procedure as a basis for your own CICS startup procedures. This procedure, DFHSTART, comprises the following steps:

1. CICSNTL—determine whether CICS is to be started
2. DTCNTL—determine whether dump and trace analysis is to be performed
3. CICS—execute CICS
4. PRTDMPA—print any contents of the CICS DFHDMPA dump data set
5. PRTDMPB—print any contents of the CICS DFHDMPB dump data set
6. PRTAUXT—print any contents of the auxiliary trace DFHAUXT data set
7. PRTBUXT—print any contents of the auxiliary trace DFHBUXT data set.

The following symbolic parameters are defined in the IVP jobs:

INDEX1	is the high-level index of the CICS run-time data sets, as specified on the DSINFO parameter of the DFHISTAR job. Default: INDEX1=hlq
INDEX2	is the high-level index of the CICS load libraries, as specified on the INDEX parameter of the DFHISTAR job. Default: INDEX2=hlq
REGNAM	is the REGION name for a single or MRO region. Default: REGNAM=TR
REG	defines the MVS region size for the CICS step. Default: REG=32M
START	is the type of CICS startup to be performed. Default: START=AUTO

DUMPTR	specifies whether dump and trace analysis is required. Default: DUMPTR=YES
RUNCICS	specifies whether CICS is to be started. Default: RUNCICS=YES
OUTC	is the output print class. Default: OUTC='*'
SIP	is the suffix of the DFH\$SIP member (in the SYSIN data set) to be used during CICS startup. Default: SIP=T

Notes:

1. The step CICS (to start up CICS) is executed only if you code RUNCICS=YES (the default). Code RUNCICS=NO if you want to perform dump and trace analysis without starting CICS.
2. The steps PRTDMPA, PRTDMPB, DFHAUXT, and DFHBUXT are executed only if you specify DUMPTR=YES (the default).
3. When you run the DFHISTAR job, it overrides the default values in the IVP jobs with the values you specified in the DFHISTAR job.

DD statements for CICS data sets

The startup job step contains DD statements for the CICS data sets that are listed in Table 17.

Table 17. DD statements for CICS data sets in the DFHSTART procedure

DDname	Description
SYSIN	SYSIN data set, containing the DFH\$SIPn members that specify system initialization parameter overrides.
DFHCMACD	Messages data set, needed for the CICS messages transaction, CMAC.
FILEA	Sample VSAM data set, needed by the FILEA sample applications.
DFHTEMP	Auxiliary temporary storage data set, needed by the FILEA sample applications.
DFHINTRA	Transient data intrapartition data set, needed by the FILEA sample applications.
DFHAUXT DFHBUXT	First auxiliary trace (A) data set. Second auxiliary trace (B) data set. The auxiliary trace data sets, DFHAUXT and DFHBUXT, are needed because the IVP jobs run with auxiliary trace switched on, and the auxiliary trace data set switching facility set to switch once only.
DFHLCD	(Mandatory) CICS local catalog data set (VSAM), used by the CICS domains to save some of their information between CICS runs, and to preserve this information across a cold start.
DFHGCD	(Mandatory) CICS global catalog data set (VSAM), has a variety of uses, including: during a CICS run, holding resource definitions that are installed; and, during a controlled shutdown, recording part of the warm keypoint information.
DFHCXRF	Transient data extrapartition data set, used by CICS as the target for messages sent to any transient data destination before CICS has completed intrapartition transient data initialization. Use of this DDname is optional, but if it is not used, any messages that would have been written here are lost.

Table 17. DD statements for CICS data sets in the DFHSTART procedure (continued)

DDname	Description
DFHLRQ	The local request queue data set is used to store pending BTS requests; for example, timer requests or requests to run activities. It is recoverable and used to ensure that, if CICS fails, no pending requests are lost. For more information, see the <i>CICS Business Transaction Services</i> .
LOGUSR	Data set for the extrapartition transient data destination, LOGA, used by the CICS sample programs.
MSGUSR	Data set for the extrapartition transient data destination, CSSL, used by a number of CICS services.
PLIMSG	Data set for the extrapartition transient data destinations used by PL/I application programs. This data set is the destination for PL/I statistics and messages (CPLI).
COUT	Data set for the extrapartition transient data destinations used by C/370 application programs. This data set is the destination for the C/370 output data streams, stdout (CCSO) and, indirectly, stderr (CCSE).
DFHDMPA DFHDMPB	First transaction dump (A) data set. Second transaction dump (B) data set. The dump data sets are included because CICS always tries to open a transaction dump data set, and issues a warning message if it is unable to do so for any reason.
DFHCSD	(Mandatory) CICS system definition data set (VSAM).

#

Verify batch job, DFHIVPBT

The CICS-supplied verify batch job, DFHIVPBT, is tailored to your CICS environment and stored in the *hlq.XDFHINST* library when you run the DFHISTAR job.

Note: Before submitting the DFHIVPBT job, run the DFHRMUTL program to reset the global catalog control record to perform an INITIAL start on the next CICS startup.

This IVP comprises the following job steps:

1. **Job step GENINPT** unloads the member DFH\$BTCH from the *hlq.SDFHSAMP* library into the CARDIN data set (using the MVS utility program, IEBGENER).
2. **Job step DFHSTART** invokes the CICS initialization program, DFHSIP, to startup CICS. The DFHSIP program reads startup system initialization parameters from the DFH\$SIP2 member of the SYSIN data set.

The DFH\$BTCH data set (see Figure 26 on page 235) is used as terminal input, and this should produce a printout similar to the sample output shown in Figure 28 on page 238.

```

CWTO START OF BATCH STREAM DFH$BTCH\
CEMT S TIME(120)\
CEMT S DUMPDS SWITCH\
CEOT\
CSFE\
PRINT\
THIS MESSAGE HAS BEEN RECEIVED FROM THE TERMINAL AND IS BEING SENT BACK\
END\
CSXX\
CWTO END OF BATCH STREAM DFH$BTCH - SHUTTING DOWN CICS\
CEMT P SHUT\
EXIT TIME INTVL TO 120 MILLISEC
SWITCH FROM DUMP A TO B
INQUIRE TERMINAL STATUS
F. E. TERMINAL TEST REQUEST
TO SEND ALL CHARACTERS
TO END THE TEST
INVALID TRANSACTION IDENT.
NORMAL TERMINATION OF CICS

```

where \ is the End Of Data Input character X'E0'.

Figure 26. DFH\$BTCH data set, input to the DFHIVPBT job

Sample job log for the DFHIVPBT job

When you run the DFHIVPBT job, your job log should look similar to the example shown in Figure 27.

```

1          JES2 JOB LOG -- SYSTEM MV26 -- NODE WINMVS2C
0
16.24.15 JOB35409 ---- TUESDAY, 18 JAN 2005 ----
16.24.15 JOB35409 ICH70001I CICINST LAST ACCESS AT 16:23:52 ON TUESDAY, JANUARY 18, 2005
16.24.15 JOB35409 $HASP373 DFHIVPBT STARTED - INIT 60 - CLASS A - SYS MV26
16.24.15 JOB35409 IEF403I DFHIVPBT - STARTED - TIME=16.24.15
16.24.15 JOB35409 -
16.24.15 JOB35409 --TIMINGS (MINS.)--          ----PAGING COUNTS----
16.24.15 JOB35409 -JOBNAME STEPNAME PROCSTEP  RC  EXCP  CPU  SRB  CLOCK  SERV  PG  PAGE  SWAP  VIO  SWAPS  STEPNO
16.24.15 JOB35409 -DFHIVPBT      GENINPT    00   28   .00   .00   .00   175  0    0    0    0    0    1
16.24.15 JOB35409 -DFHIVPBT CICS  CICSCNTL   01   20   .00   .00   .00   168  0    0    0    0    0    2
16.24.15 JOB35409 -DFHIVPBT CICS  DTCNTL    01   19   .00   .00   .00   154  0    0    0    0    0    3
16.24.15 JOB35409 DFHPA1101 CICSIVP1 DFHSIT  IS BEING LOADED.
16.24.15 JOB35409 DFHPA1108 CICSIVP1 DFHSIT  HAS BEEN LOADED. (GENERATED AT: MM/DD= 01/12 HH:MM= 13:57).
16.24.15 JOB35409 DFHPA1100 CICSIVP1 OVERRIDE PARAMETERS FROM JCL EXEC STATEMENT: START=AUTO,SYSIN
16.24.15 JOB35409 DFHPA1102 CICSIVP1 OVERRIDE PARAMETERS FROM SYSIN: 1
16.24.15 JOB35409 DFHPA1927 CICSIVP1 TCT=5$,          SEQUENTIAL DEVICES          00020000
16.24.15 JOB35409 DFHPA1927 CICSIVP1 TS=(,0),          00030000
16.24.15 JOB35409 DFHPA1927 CICSIVP1 AUXTR=ON,          00040000

```

Figure 27. Sample job log for the DFHIVPBT job (Part 1 of 3)

```

16.24.15 JOB35409 DFHPA1927 CICSIVP1 AUXTRSW=NEXT, 00050000
16.24.15 JOB35409 DFHPA1927 CICSIVP1 FCT=NO, 00070000
16.24.15 JOB35409 DFHPA1927 CICSIVP1 XRF=NO, 00090000
16.24.15 JOB35409 DFHPA1927 CICSIVP1 SEC=NO, 40000000
16.24.15 JOB35409 DFHPA1927 CICSIVP1 SRT=NO, 40000100
16.24.15 JOB35409 DFHPA1927 CICSIVP1 TRTABSZ=64, 40000200
16.24.15 JOB35409 DFHPA1927 CICSIVP1 APPLID=CICSIVP1, 40000300
16.24.15 JOB35409 DFHPA1927 CICSIVP1 CICSSVC=233, 40000400
16.24.15 JOB35409 DFHPA1927 CICSIVP1 .END 70000000
16.24.15 JOB35409 DFHPA1103 CICSIVP1 END OF FILE ON SYSIN.
16.24.16 JOB35409 +DFHTR0103 TRACE TABLE SIZE IS 64K
16.24.16 JOB35409 +DFHSM0122I CICSIVP1 Limit of DSA storage below 16MB is 5,120K. 2
16.24.16 JOB35409 +DFHSM0123I CICSIVP1 Limit of DSA storage above 16MB is 30M.
16.24.16 JOB35409 +DFHSM0113I CICSIVP1 Storage protection is not active.
16.24.16 JOB35409 +DFHSM0126I CICSIVP1 Transaction isolation is not active.
16.24.16 JOB35409 +DFHDM0101I CICSIVP1 CICS is initializing.
16.24.17 JOB35409 +DFHSI1500 CICSIVP1 CICS startup is in progress for CICS Transaction Server Version 3.1.0
16.24.17 JOB35409 +DFHDH0100I CICSIVP1 Document domain initialization has started.
16.24.17 JOB35409 +DFHEJ0101 CICSIVP1 747
747 Enterprise Java domain initialization has started. Java is a
747 trademark of Sun Microsystems, Inc.
16.24.17 JOB35409 +DFHLG0101I CICSIVP1 Log manager domain initialization has started.
16.24.17 JOB35409 +DFHRX0100I CICSIVP1 RX domain initialization has started.
16.24.17 JOB35409 +DFHSO0100I CICSIVP1 Sockets domain initialization has started.
16.24.17 JOB35409 +DFHWP0109I CICSIVP1 Web domain initialization has started.
16.24.17 JOB35409 +DFHXS1100I CICSIVP1 Security initialization has started.
16.24.17 JOB35409 +DFHRX0101I CICSIVP1 RX domain initialization has ended.
16.24.17 JOB35409 +DFHSI1501I CICSIVP1 Loading CICS nucleus.
16.24.17 JOB35409 +DFHDM0304I CICSIVP1 Transaction Dump Data set DFHDMPA opened.
16.24.17 JOB35409 +DFHXS1102I CICSIVP1 Security is inactive. 3
16.24.19 JOB35409 +DFHTR0113 CICSIVP1 Auxiliary trace is being started on data set DFHAUXT.
16.24.19 JOB35409 +DFHCQ0100I CICSIVP1 Console queue initialization has started.
16.24.19 JOB35409 +DFHCQ0101I CICSIVP1 Console queue initialization has ended.
16.24.19 JOB35409 +DFHCQ0103I CICSIVP1 MVS console queue is open.
16.24.19 JOB35409 +DFHCQ0200I CICSIVP1 CEKL transaction enabled.
16.24.19 JOB35409 +DFHXS1101I CICSIVP1 Security initialization has ended.
16.24.19 JOB35409 +DFHRM0140 CICSIVP1 Recovery manager autostart override found with value: 'AUTOINIT'.
16.24.19 JOB35409 +DFHRM0149I CICSIVP1 Recovery manager autostart override record will be deleted.
16.24.19 JOB35409 +DFHDH0101I CICSIVP1 Document domain initialization has ended.
16.24.19 JOB35409 +DFHSO0101I CICSIVP1 Sockets domain initialization has ended.
16.24.19 JOB35409 +DFHMMN0105I CICSIVP1 Using default Monitoring Control Table.
16.24.19 JOB35409 +DFHWP0110I CICSIVP1 Web domain initialization has ended.
16.24.19 JOB35409 IEC031I D37-04,IFG0554P,DFHIVPBT,CICS,DFHAUXT,D306,P2P0C6,INST.CICSTS31.CICS.DFHAUXT
16.24.19 JOB35409 +DFHTR0110 - AUXILIARY TRACE DATA SET DFHAUXT FULL - SWITCHING TO DFHBUXT
16.24.19 JOB35409 +DFHMMN0110I CICSIVP1 CICS Monitoring is inactive.
16.24.19 JOB35409 IEC031I D37-04,IFG0554P,DFHIVPBT,CICS,DFHBUXT,D50B,P2P14B,INST.CICSTS31.CICS.DFHBUXT
16.24.19 JOB35409 +DFHTR0109 - AUXILIARY TRACE DATA SET DFHBUXT FULL - AUXILIARY TRACE HAS BEEN STOPPED
16.24.19 JOB35409 +DFHSI1502I CICSIVP1 CICS startup is Initial.
16.24.19 JOB35409 +DFHTS0100I CICSIVP1 Temporary Storage initialization has started.
16.24.19 JOB35409 +DFHLG0102I CICSIVP1 Log manager domain initialization has ended.
16.24.19 JOB35409 +DFHSI1503I CICSIVP1 Terminal data sets are being opened.
16.24.19 JOB35409 +DFHSI1592 CICSIVP1 CICS applid not (yet) active to VTAM.
16.24.19 JOB35409 +DFHSI1572 CICSIVP1 Unable to OPEN VTAM ACB - RC=00000008, ACB Code=5A.
16.24.19 JOB35409 +DFHKE0406I CICSIVP1 786
786 CICS is about to wait for predecessors defined in the MVS automatic
786 restart management policy for this region.
16.24.20 JOB35409 +DFHKE0412I CICSIVP1 CICS WAITPRED call to automatic restart manager has completed.
16.24.20 JOB35409 +DFHCP0101I CICSIVP1 CPI initialization has started.
16.24.20 JOB35409 +DFHPR0104I CICSIVP1 Partner resource manager initialization has started.
16.24.20 JOB35409 +DFHAI0101I CICSIVP1 AITM initialization has started.
16.24.20 JOB35409 +DFHFC0100I CICSIVP1 File Control initialization has started.
16.24.20 JOB35409 +DFHTD0100I CICSIVP1 Transient Data initialization has started.
16.24.20 JOB35409 +DFHTS0101I CICSIVP1 Temporary Storage initialization has ended.
16.24.20 JOB35409 +DFHTD0101I CICSIVP1 Transient Data initialization has ended.
16.24.20 JOB35409 +DFHFC0101I CICSIVP1 File Control initialization has ended.
16.24.20 JOB35409 +DFHCP0102I CICSIVP1 CPI initialization has ended.
16.24.20 JOB35409 +DFHPR0105I CICSIVP1 Partner resource manager initialization has ended.
16.24.20 JOB35409 +DFHAI0102I CICSIVP1 AITM initialization has ended.
16.24.20 JOB35409 +DFHSI1511I CICSIVP1 Installing group list DFHLIST. 4
16.24.22 JOB35409 +DFHLG0103I CICSIVP1 System log (DFHLOG) initialization has started.
16.24.22 JOB35409 IXG231I IXGCONN REQUEST=CONNECT TO LOG STREAM CICINST.CICSIVP1.DFHLOG 801
801 DID NOT SUCCEED FOR JOB DFHIVPBT. RETURN CODE: 00000008 REASON CODE: 5
801 0000080B DIAG1: 00000008 DIAG2: 0000F801 DIAG3: 05030004 DIAG4:
801 05020010
16.24.24 JOB35409 +DFHLG0104I CICSIVP1 808

```

Figure 27. Sample job log for the DFHIVPBT job (Part 2 of 3)

```

808          System log (DFHLOG) initialization has ended. Log stream
808          CICINST.CICSIVP1.DFHLOG is connected to structure LOG_GENERAL_008. 6
16.24.24 JOB35409 +DFHLG0103I CICSIVP1 System log (DFHSHUNT) initialization has started.
16.24.25 JOB35409 IXG231I IXGCONN REQUEST=CONNECT TO LOG STREAM 810
810          CICINST.CICSIVP1.DFHSHUNT DID NOT SUCCEED FOR JOB DFHIVPBT. RETURN
810          CODE: 00000008 REASON CODE: 0000080B DIAG1: 00000008 DIAG2:
810          0000F801 DIAG3: 05030004 DIAG4: 05020010
16.24.27 JOB35409 +DFHLG0104I CICSIVP1 817
817          System log (DFHSHUNT) initialization has ended. Log stream
817          CICINST.CICSIVP1.DFHSHUNT is connected to structure LOG_GENERAL_008.
16.24.27 JOB35409 +DFHAP1203I CICSIVP1 Language Environment is being initialized.
16.24.27 JOB35409 +DFHAP1200 CICSIVP1 A CICS request to the Language Environment has failed. Reason code '0011020'.
16.24.27 JOB35409 +DFHAP1208 CICSIVP1 Language Environment cannot support the Cobol language. 7
16.24.27 JOB35409 +DFHAP1209 CICSIVP1 Language Environment cannot support the C/C++ languages. 7
16.24.27 JOB35409 +DFHAP1210 CICSIVP1 Language Environment cannot support the PL/I language. 7
16.24.27 JOB35409 +DFHAP1211I CICSIVP1 Language Environment initialization completed.
16.24.27 JOB35409 +DFHWP1007 CICSIVP1 Initializing CICS Web environment.
16.24.27 JOB35409 +DFHWP1008 CICSIVP1 CICS Web environment initialization is complete.
16.24.27 JOB35409 +DFHSI1517 CICSIVP1 Control is being given to CICS.
16.24.27 JOB35409 +DFHEJ0102 CICSIVP1 Enterprise Java domain initialization has ended.
16.24.28 JOB35409 +DFHIVPBT SAMA START OF BATCH STREAM DFH$BTCH
16.24.29 JOB35409 +DFHUU0303I CICSIVP1 Transaction Dump Data set DFHDMPA closed.
16.24.29 JOB35409 +DFHUU0304I CICSIVP1 Transaction Dump Data set DFHDMPB opened.
16.24.29 JOB35409 +DFHUU0305I CICSIVP1 Transaction Dump Data set switched to DFHDMPB
16.24.34 JOB35409 +DFHIVPBT SAMA END OF BATCH STREAM DFH$BTCH - SHUTTING DOWN CICS
16.24.35 JOB35409 +DFHTM1715 CICSIVP1 CICS is being quiesced by userid CICSUSER in transaction CEMT at terminal SAMA.
16.24.35 JOB35409 +DFHDM0102I CICSIVP1 CICS is quiescing.
16.24.35 JOB35409 +DFHTM1782I CICSIVP1 All non-system tasks have been successfully terminated.
16.24.35 JOB35409 +DFHCQ0104I CICSIVP1 MVS console queue is closed.
16.24.35 JOB35409 +DFHCESD CICSIVP1 SHUTDOWN ASSIST TRANSACTION CESD STARTING. SHUTDOWN IS NORMAL.
16.24.37 JOB35409 +DFHRM0204 CICSIVP1 There are no indoubt, commit-failed or backout-failed UOWs.
16.24.38 JOB35409 +DFHRM0130 CICSIVP1 Recovery manager has successfully quiesced.
16.24.39 JOB35409 +DFHUU0303I CICSIVP1 Transaction Dump Data set DFHDMPB closed.
16.24.39 JOB35409 +DFHKE1799 CICSIVP1 TERMINATION OF CICS IS COMPLETE.
16.24.39 JOB35409 -DFHIVPBT CICS CICS 00 3549 .03 .00 .39 23015 0 1 446 0 1 4
16.24.39 JOB35409 -DFHIVPBT CICS PRTDMPA 00 135 .00 .00 .00 261 0 0 0 0 0 5
16.24.39 JOB35409 -DFHIVPBT CICS PRTDMPB 00 138 .00 .00 .00 257 0 0 0 0 0 6
16.24.42 JOB35409 -DFHIVPBT CICS PRTAUXT 00 1838 .01 .00 .03 13823 0 0 0 0 0 7
16.24.42 JOB35409 $HASP375 DFHIVPBT ESTIMATED LINES EXCEEDED
16.24.42 JOB35409 $HASP375 DFHIVPBT ESTIMATE EXCEEDED BY 5,000 LINES
16.24.42 JOB35409 $HASP375 DFHIVPBT ESTIMATE EXCEEDED BY 10,000 LINES
16.24.42 JOB35409 $HASP375 DFHIVPBT ESTIMATE EXCEEDED BY 15,000 LINES
16.24.43 JOB35409 $HASP375 DFHIVPBT ESTIMATE EXCEEDED BY 20,000 LINES
16.24.43 JOB35409 $HASP375 DFHIVPBT ESTIMATE EXCEEDED BY 25,000 LINES
16.24.43 JOB35409 $HASP375 DFHIVPBT ESTIMATE EXCEEDED BY 30,000 LINES
16.24.43 JOB35409 $HASP375 DFHIVPBT ESTIMATE EXCEEDED BY 35,000 LINES
16.24.43 JOB35409 $HASP375 DFHIVPBT ESTIMATE EXCEEDED BY 40,000 LINES
16.24.43 JOB35409 -DFHIVPBT CICS PRTBUXT 00 1313 .01 .00 .02 13246 0 0 0 0 0 8
16.24.43 JOB35409 IEF404I DFHIVPBT - ENDED - TIME=16.24.43
16.24.43 JOB35409 -DFHIVPBT ENDED. NAME=CICINST TOTAL CPU TIME= .06 TOTAL ELAPSED TIME= .47
16.24.43 JOB35409 $HASP395 DFHIVPBT ENDED

```

Figure 27. Sample job log for the DFHIVPBT job (Part 3 of 3)

Notes:

1 For information about the system initialization parameters used by the IVP jobs, see page 231. (See also **2** below.)

2 The DFHSM0122 and DFHSM0123 messages inform you of the limits available for the dynamic storage areas below and above 16MB. For information about these storage areas, see the *CICS System Definition Guide*.

Note: Storage for the extended read-only DSA, ERDSA, is obtained from read-only key 0 protected storage, because the default SIT specifies RENTPGM=PROTECT.

3 The DFHIVPBT job was run without external security active, because SEC=NO is specified as a SIT override parameter.

4 The default group list, DFHLIST, is used for this run of the DFHIVPBT job. Non-default functions (for example, the CICS online messages facility) are not available, because their CICS resources are not defined in this group list.

5 These messages are issued when CICS is initialized and the log streams do not exist. CICS issues a request to create the log stream dynamically using MVS define log stream services.

6 If system log initialization fails, CICS abends. (See also **1** in Figure 28.)

7 If you want COBOL, C, C++ and PL/I languages, remove the comment marks from the SCEERUN and SCEERUN2 libraries, and increase the memory size for the job.

Output from the DFHIVPBT job

Output from the DFHIVPBT job (see Figure 28) includes CICS messages written to one of the extrapartition destinations, responses to the transactions in the DFH\$BTCH data set, and an auxiliary trace.

```
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBLT has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBPA has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBPW has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBPW1 has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBPW2 has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBPW3 has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBPW4 has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBST has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBTC has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBTL has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBTRU has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBTTA has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBTTB has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBTTC has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBUN has been added.
DFHPG0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY PPT entry for DFHWBXN has been added.
DFHXM0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CWBA has been added.
DFHXM0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CWBC has been added.
DFHXM0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CWBG has been added.
DFHXM0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CWXN has been added.
DFHXM0101 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CWXU has been added.
DFHTS0104 01/18/2005 16:24:20 CICSIVP1 CICSUSER CSSY TSMODEL entry for DFHWEB has been added.
DFHDH0105 01/18/2005 16:24:20 CICSIVP1 Document template definition DFHWBPW1 has been added as PROGRAM(DFHWBPW1) with
template name DFHWBPW1.
DFHDH0105 01/18/2005 16:24:20 CICSIVP1 Document template definition DFHWBPW2 has been added as PROGRAM(DFHWBPW2) with
template name DFHWBPW2.
DFHDH0105 01/18/2005 16:24:20 CICSIVP1 Document template definition DFHWBPW3 has been added as PROGRAM(DFHWBPW3) with
template name DFHWBPW3.
DFHDH0105 01/18/2005 16:24:20 CICSIVP1 Document template definition DFHWBPW4 has been added as PROGRAM(DFHWBPW4) with
template name DFHWBPW4.
DFHAM4893 I 01/18/2005 16:24:20 CICSIVP1 Install for group DFHWEB has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPIAP has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPIDSH has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPIDSQ has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPIEP has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPILSQ has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPIRT has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPISN1 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPISN2 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPITP has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPITQ1 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPIVAL has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHPIXE has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CPIH has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CPIL has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CPIQ has been added.
```

Figure 28. Sample job log for the DFHIVPBT job (Part 1 of 4)

```

DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHPIPE has completed successfully.
DFHFC0202 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY FCT entry for DFHLRQ has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHCBS has completed successfully.
DFHKO102 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PFT entry for DFHCICSI has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHIIRRS has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHXOPUS has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFJIIRP has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFJIIRQ has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CIRR has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CIRR has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHIIOP has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHIEP has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CIEP has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHIPECI has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDLLOD has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHEJDNX has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHJVCVT has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHSJJML has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFJ1ESN has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFJ1ICS has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFJ1ICSB has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFJ1ZDTC has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CJMJ has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHJAVA has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHOTR has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CJTR has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHOTS has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHRZJN has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHRQS has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for ICCFCDLL has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHCFC has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDHEI has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHDOC has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHBRVCV has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHBRMP has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHL3270 has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHBR has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHZPCT has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHZRTP has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHZSGN has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CPCT has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CPSS has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CRTP has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHPSSGN has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHADMS has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHADDRM has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHADJR has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CREA has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CREC has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHADST has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHEJEP has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHEJBU has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPMS has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPCP has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPIN has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPLU has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CADP has been added.
DFHXM0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CIDP has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHDP has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWB has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWM0 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWM1 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWM2 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWM3 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWM4 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWM5 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWM6 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWT0 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWT1 has been added.

```

Figure 28. Sample job log for the DFHIVPBT job (Part 2 of 4)

```

DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWT2 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWT3 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWT4 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWT5 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHDPWT6 has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHDPWB has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHSOCI has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for DFHSOLI has been added.
DFHAM4893 I 01/18/2005 16:24:21 CICSIVP1 Install for group DFHSO has completed successfully.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CELCLEM has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CELCLRH has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEECBLDY has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEECCICS has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEECMI has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEECRHP has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEECZST has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEDATE has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEDATM has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEDAYS has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEDCOD has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEDSHP has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEDYWK has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEEV003 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEEV005 has been added.
DFHPG0101 01/18/2005 16:24:21 CICSIVP1 CICSUSER CSSY PPT entry for CEEEV010 has been added.

..... the rest of group CEE

DFHPG0101 01/18/2005 16:24:22 CICSIVP1 CICSUSER CSSY PPT entry for IIGZMSGT has been added.
DFHXM0101 01/18/2005 16:24:22 CICSIVP1 CICSUSER CSSY TRANSACTION definition entry for CLER has been added.
DFHAM4893 I 01/18/2005 16:24:22 CICSIVP1 Install for group CEE has completed successfully.
DFHFC0204 01/18/2005 16:24:22 CICSIVP1 CICSUSER CSSY FCT entry for DFHCSD has been updated.
DFHLG0502 01/18/2005 16:24:23 CICSIVP1 Log stream CICINST.CICSIVP1.DFHLOG defined to MVS using model stream 1
MV26.DFHLOG.MODEL.
DFHLG0302 01/18/2005 16:24:24 CICSIVP1 Journal name DFHLOG has been installed. Journal type: MVS 2
CICINST.CICSIVP1.DFHLOG.
DFHLG0502 01/18/2005 16:24:25 CICSIVP1 Log stream CICINST.CICSIVP1.DFHSHUNT defined to MVS using model stream 1
MV26.DFHSHUNT.MODEL.
DFHLG0302 01/18/2005 16:24:27 CICSIVP1 Journal name DFHSHUNT has been installed. Journal type: MVS 2
CICINST.CICSIVP1.DFHSHUNT.
DFHLG0744 01/18/2005 16:24:27 CICSIVP1 All records in log stream CICINST.CICSIVP1.DFHLOG have been deleted.
DFHLG0744 01/18/2005 16:24:27 CICSIVP1 All records in log stream CICINST.CICSIVP1.DFHSHUNT have been deleted.
DFHRM0205 01/18/2005 16:24:37 CICSIVP1 An activity keypoint has been successfully taken.
DFHLG0743 01/18/2005 16:24:37 CICSIVP1 Tail of log stream CICINST.CICSIVP1.DFHLOG deleted at block id
X'0000000000000001'.

```

MESSAGE HAS BEEN SENT

```

Aging( 32768 )
Akp( 04000 )
Cicstslevel(030100)
Cmdprotect(Cmdprot)
Db2conn()
Debugtool( Nodebug )
Dfltuser(CICSUSER)
Dsalimit( 05242880 )
Dsrtprogram( NONE )

```

Figure 28. Sample job log for the DFHIVPBT job (Part 3 of 4)


```

Dtrprogram( DFHDYP )
Dumping( Sysdump )
Edsalimit( 0031457280 )
Forceqr( Noforce )
Logdefer( 00005 )
Maxtasks( 005 )
Mrobatch( 001 )
Oslevel(010400)
Progautoctlg( Ctlgmodify )
Progautoexit( DFHPGADX )
Progautoinst( Autoinactive )
Reentprotect(Reentprot)
Release(0640)
Runaway( 0005000 )
Scandelay( 0500 )
Sdtran(CESD)
Sosstatus(Notsos)
Storeprotect(Inactive)
Time( 0001000 )
Tranisolate(Inactive)
TIME < SCANDELAY
RESPONSE: 1 ERROR TIME: 16.24.29 DATE: 01.18.05
SYSID=CICS APPLID=CICSIVP1

Dumpds
Currentdds(B)
Openstatus( Open )
Switchstatus( Noautoswitch )
NORMAL
RESPONSE: NORMAL TIME: 16.24.30 DATE: 01.18.05
SYSID=CICS APPLID=CICSIVP1

Ter(SAMA) Tra(CEOT) Pri(000) Aut Ins Tti
CEOT SYNTAX:
< Pageable | Autopageable >
< Ati | Noati >
< Tti | Notti >
< Uctran | Nouctran | Tranidonly >
RESPONSE: NORMAL TIME: 16.24.30 DATE: 01.18.05
SYSID=CICS APPLID=CICSIVP1

```

Figure 28. Sample job log for the DFHIVPBT job (Part 4 of 4)

Notes:

- 1** CICS messages issued when the log stream is created.
- 2** This message is sent to the CRDI destination.

Verify interactive job, DFHIVPOL

The verify interactive job, DFHIVPOL, is tailored to your CICS environment and stored in the *hlq.XDFHINST* library when you run the DFHISTAR job. You can use the DFHIVPOL job to start up a CICS region and try out the current facilities; for example you can use the master terminal transaction, CEMT, and the resource definition transaction, CEDA. You can also run some CICS sample application programs (for example, the FILEA applications).

You need either an IBM 3270 Information Display System terminal or a **console device**. You can use both if you wish.

If you use an IBM 3270 Information Display System terminal with this IVP, you can try CEDA, CEMT and the sample applications.

From a console device, the CEDA transaction can be used only to INSTALL resource definitions. The sample programs cannot be executed from a console device.

If you want to communicate with CICS from an MVS console, you must define a console in the CSD before starting the IVP. (You cannot define a console in the TCT.) For more information, see “Defining an MVS console” on page 244.

If you want to communicate with CICS from a TSO session, you must define the TSO user as a console device in the CSD before starting the IVP. For more information, see “Defining a TSO user as a console device” on page 245.

The DFHIVPOL job invokes the CICS initialization program DFHSIP to start up CICS. The DFHSIP program reads system initialization parameters from the DFH\$SIP1 member of the SYSIN data set.

TCT=NO is specified as a SIT override which causes CICS to use the dummy terminal control table, DFHTCTDY. This dummy TCT contains only the CICS and VTAM control blocks that you need for use with VTAM terminals: there are no terminal entries.

For information about system initialization parameters specified as overrides for the run of the DFHIVPOL job, see “Specify system initialization parameters for the IVP jobs” on page 231.

Defining a terminal for the online IVP

You can define a VTAM terminal by either of the following two methods:

1. Use the autoinstall facility, which is the recommended method, avoiding the need to define terminals to CICS explicitly before they can be used.
2. Define a terminal explicitly in the CSD, using the DEFINE command of DFHCSDUP, the batch utility for updating the CSD.

Using autoinstall for a VTAM terminal

If you use the autoinstall function of CICS, you avoid the need for each VTAM terminal that requires access to CICS being explicitly defined in the CSD. With autoinstall, the resource definitions you create using RDO can act as models or templates for many resources of the same type. You then leave CICS to match real resources with one of the models. CICS installs table entries for these real resources dynamically, as and when they are needed.

When using autoinstall, you should be aware that when CICS processes an autoinstall request, it uses data from the VTAM logmode table. This is an important consideration. An autoinstall request will succeed only when the logmode data (which is passed to CICS in the BIND image) matches one of the model terminal definitions recorded in the autoinstall model table (AMT) from the CSD. For programming information about the LOGMODE definitions that match the CICS-supplied model definitions for autoinstall, see the *CICS Customization Guide*. Before attempting to start CICS and autoinstall a terminal for this IVP, check your VTAM definitions with those given in the *CICS Customization Guide*. If CICS fails to match model and logmode data, you receive message DFHZC6987I. For information about the suggested course of action if you receive message DFHZC6987I, see the *CICS Messages and Codes* manual.

CSD resource definitions for autoinstall: The CSD is defined and initialized for all the IVP jobs when you run the DFHCOMDS job (see Chapter 28, “Creating the CICS data sets,” on page 189), and includes some IBM-supplied definitions for use with autoinstall. These are defined in the following groups:

Group Name	Description
DFHTERM	Model terminal definitions for use with the autoinstall facility. For example, two of the TERMINAL definitions are 3270 and LU2.
DFHTYPE	Partial terminal definitions (TYPETERMs) defining common terminal properties, or attributes. For example, two of the TYPETERM definitions are DFH3270 (to define a non-SNA 3270 terminal) and DFHLU2E2 (to define a SNA 3270 model 2 terminal). The DFHLU2E2 resource definition matches the VTAM-supplied logmode SNX32702.

The DFHTERM and DFHTYPE groups are included in the CICS-defined group list called DFHLIST, which is defined in the GRPLIST operand in the sample SIT. If the CICS-supplied definitions are not suitable for your installation, you can create additional TYPETERM and model TERMINAL definitions in the CSD, but without a terminal you will have to do this offline, using the DFHCSDUP utility program. For information about autoinstall definitions, see the *CICS Resource Definition Guide*.

Autoinstall also requires a user program to assign terminal identifiers, and, if necessary, to control access to the system. When you run the online IVP, you are unlikely to have any special requirements for terminal identifiers, or to control access, in which case you can use the IBM-supplied autoinstall user program, DFHZATDX. (If you are using autoinstall for APPC connections and terminals, the sample autoinstall user program is called DFHZATDY.)

Defining a VTAM terminal in the CSD

If you want to use an explicitly defined terminal, rather than let CICS autoinstall a terminal, you will need to define it offline using the DFHCSDUP utility program. The normal way to create resource definitions in the CSD is to use the CEDA DEFINE command from a CICS master terminal, but without a terminal you can only do this using the DFHCSDUP utility program. For an example of a DFHCSDUP job to define a VTAM terminal in the CSD, see Figure 29. For information about the keywords and operands of the DFHCSDUP DEFINE commands, see the *CICS Resource Definition Guide*.

```
//DEFTERM JOB (accounting information),MSGCLASS=A,
//          MSGLEVEL=(1,1),CLASS=A,NOTIFY=userid
//VTAMDEF EXEC PGM=DFHCSDUP
//STEPLIB DD DSN=CICSTS31.CICS.SDFHLOAD,DISP=SHR
//DFHCSD DD DSN=CICSTS31.CICS.DFHCSD,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
*
DEFINE TERMINAL(trmidnt) NETNAME(vtamname) GROUP(grpname)
          TYPETERM(name) INSERVICE(NO) AUTINSTMODEL(NO)
*
APPEND LIST(DFHLIST) TO(yourlist)
*
ADD GROUP(grpname) LIST(yourlist)
*
LIST LIST(yourlist) OBJECTS
/*
//
```

Figure 29. Defining a terminal by using the DFHCSDUP utility program

You must substitute your own values for the operands that are coded in lowercase in the DEFTERM job shown in Figure 29:

TYPETERM

Specify a unique name to identify the resource definition that matches the properties of the type of terminal you are using. For example, to define a SNA 3270 model 2 terminal, specify the CICS-supplied TYPETERM definition DFHLU2E2. For a list of the CICS-supplied TYPETERM definitions, or for information about creating your own definitions, see the *CICS Resource Definition Guide*.

GROUP

Code a unique name for the group to which the terminal resource definition is to belong.

TERMINAL

Code a unique 4-character terminal identifier as the name by which CICS is to know the terminal.

NETNAME

Code the 8-character VTAM name that identifies this terminal to your VTAM system.

TO(yourlist) and LIST(yourlist)

Code a unique name for *yourlist*. If your new group list does not include all the CICS-supplied resources as well as your own, you must specify DFHLIST and yourlist on the GRPLIST system initialization parameter of your CICS startup job.

To include the CICS-supplied list of resources in a new group list, create a new list by copying the CICS-supplied list, DFHLIST, using the APPEND command. (The CICS-supplied group list, DFHLIST, is a protected group that you cannot modify.) You can then add your resource definition groups to the new list. Before you run the IVP, make sure you define your new group list to CICS, by adding a SIT override to the SYSIN data set in the DFHIVPOL job stream.

Defining the CICS APPLID to VTAM

You must ensure that either:

- VTAM knows the CICS application identifier (APPLID)
- or
- You change the CICS APPLID to one that is already known to your VTAM system.

If you use the default APPLID (DBDCCICS), define this to VTAM as described in “VTAM APPL parameters for CICS regions” on page 99, before starting the DFHIVPOL job.

Defining an MVS console

If you want to use an MVS console with the DFHIVPOL job, CICS requires an installed definition for the console. You can achieve this using one of the following:

- An autoinstall model definition, in conjunction with autoinstall support for consoles. The model definition can specify any CONSNAME value, and references a TYPETERM definition that specifies DEVICE(CONSOLE).
- A predefined TERMINAL resource definition for a console, which specifies the console name on the CONSNAME attribute, and references a TYPETERM definition that specifies DEVICE(CONSOLE).

You define these resources using the DFHCSDUP utility program. The CICS-supplied TYPETERM group, DFHTYPE, contains a typeterm definition called

DFHCONS, which is predefined with the required console properties. The DFHTERM group, however, does not contain any corresponding terminal entries for MVS consoles. You identify the console by the CONSNAME(*name*) attribute, even if the TERMINAL definition is an autoinstall model (the console name on an autoinstall model is a dummy value, and replaced by the real console name at install-time).

For an example of the DEFINE command required to define a console, see Figure 30 on page 246.

For information about defining MVS consoles to CICS, see the *CICS System Definition Guide*.

Defining a TSO user as a console device

A TSO user can enter MODIFY commands from terminals logged on to TSO, using either the TSO CONSOLE command or from SDSF. MVS activates a console using, by default, the user's TSO user ID as the console name. To CICS, the console name passed on the MODIFY command is treated like an MVS system console, and requires an entry in the CICS system definition (CSD) file.

As in the case of the MVS system console, you can achieve this using one of the following:

- An autoinstall model definition, in conjunction with autoinstall support for consoles. The model definition can specify any CONSNAME value, and references a TYPETERM definition that specifies DEVICE(CONSOLE)
- A predefined TERMINAL resource definition for a console, which specifies the console name on the CONSNAME attribute, and references a TYPETERM definition that specifies DEVICE(CONSOLE).

You are recommended to define consoles to CICS with preset terminal security, using the USERID attribute on the TERMINAL definition. This avoids the TSO user having to sign on using the CESN transaction. Otherwise, the TSO user's CICS signon password is displayed when entered on the CESN transaction.

For an example of a DEFINE command to define a TSO user, see Figure 30 on page 246.

```

//DEFTERM JOB (accounting information),MSGCLASS=A,
//          MSGLEVEL=(1,1),CLASS=A,NOTIFY=userid
//CONSDEF EXEC PGM=DFHCSDUP
//STEPLIB DD DSN=CICSTS31.CICS.SDFHLOAD,DISP=SHR
//DFHCSD  DD DSN=CICSTS31.CICS.DFHCSD,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSIN   DD *

* Define a console
DEFINE TERMINAL(trmidnt)  GROUP(grpname)    TYPETERM(DFHCONS)
                        CONSNAME(consname)  DESCRIPTION(MVS CONSOLE consname)
                        USERID(tsouser)

* Define a TSO user as a console device
DEFINE TERMINAL(trmidnt)  GROUP(grpname)    TYPETERM(DFHCONS)
                        CONSNAME(tsouser)  DESCRIPTION(TSO USER tsouser)
                        USERID(tsouser)

*

APPEND LIST(DFHLIST) TO(yourlist)
*
ADD GROUP(grpname) LIST(yourlist)
*
LIST LIST(yourlist) OBJECTS
/*
//

```

Figure 30. Defining a console and a TSO user by using the DFHCSDUP utility program

Note: Substitute your own values for the operands that are shown in italics in the DEFTERM job shown in Figure 30.

To include the CICS-supplied list of resources at startup, specify DFHLIST on the GRPLIST system initialization parameter, as well as your own group list name. For example, specify GRPLIST=(DFHLIST,*userlista*,*userlistb*) in the CICS SYSIN data set member.

Running the DFHIVPOL job

The DFHIVPOL job includes a procedure, DFHSTART, to start up CICS. When you have successfully logged on to CICS, you can carry out any of the interactive operations described on page 250.

While logged on to CICS, you should perform a CEMT SET DUMPDS SWITCH to ensure that both dump data sets are initialized before DFHDU640 is run when you shut down CICS.

Finally, you can shut down CICS.

Sample job log for the DFHIVPOL job

When you run the DFHIVPOL job, your job log should look similar to the sample log shown in Figure 31 on page 247.

```

1 JES2 JOB LOG -- SYSTEM MV26 -- NODE WINMVS2C
0
17.17.29 JOB35727 ---- TUESDAY, 18 JAN 2005 ----
17.17.29 JOB35727 ICH70001I CICINST LAST ACCESS AT 16:24:15 ON TUESDAY, JANUARY 18, 2005
17.17.29 JOB35727 $HASP373 DFHIVPOL STARTED - INIT 69 - CLASS A - SYS MV26
17.17.29 JOB35727 IEF403I DFHIVPOL - STARTED - TIME=17.17.29
17.17.29 JOB35727 -
--TIMINGS (MINS.)--
-----PAGING COUNTS-----
17.17.29 JOB35727 -JOBNAME STEPNAME PROCSTEP RC EXCP CPU SRB CLOCK SERV PG PAGE SWAP VIO SWAPS STEPNO
17.17.29 JOB35727 -DFHIVPOL CICS CICSCNTL 01 23 .00 .00 .00 167 0 0 0 0 0 1
17.17.29 JOB35727 -DFHIVPOL CICS DTCNTL 01 19 .00 .00 .00 147 0 0 0 0 0 2
17.17.30 JOB35727 DFHFA1101 CICSIVP1 DFHSIT IS BEING LOADED.
17.17.30 JOB35727 DFHFA1108 CICSIVP1 DFHSIT HAS BEEN LOADED. (GENERATED AT: MM/DD= 01/12 HH:MM= 13:57).
17.17.30 JOB35727 DFHFA1100 CICSIVP1 OVERRIDE PARAMETERS FROM JCL EXEC STATEMENT: START=AUTO,SYSIN
17.17.30 JOB35727 DFHFA1102 CICSIVP1 OVERRIDE PARAMETERS FROM SYSIN: 1
17.17.30 JOB35727 DFHFA1927 CICSIVP1 XRF=NO,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 AUXTR=ON,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 AUXTRSW=NEXT,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 APPLID=CICSIVP1, 2
17.17.30 JOB35727 DFHFA1927 CICSIVP1 FCT=NO,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 TCT=NO,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 SRT=NO,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 SEC=NO,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 TRTABSZ=64,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 PGRET=P/,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 PGPURGE=T/,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 PGCOPY=C/,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 PGCHAIN=X/,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 CICS SVC=233,
17.17.30 JOB35727 DFHFA1927 CICSIVP1 .END
17.17.30 JOB35727 DFHFA1103 CICSIVP1 END OF FILE ON SYSIN.
17.17.31 JOB35727 +DFHTR0103 TRACE TABLE SIZE IS 64K
17.17.31 JOB35727 +DFHSM0122I CICSIVP1 Limit of DSA storage below 16MB is 5,120K. 3
17.17.31 JOB35727 +DFHSM0123I CICSIVP1 Limit of DSA storage above 16MB is 30M.
17.17.31 JOB35727 +DFHSM0113I CICSIVP1 Storage protection is not active.
17.17.31 JOB35727 +DFHSM0126I CICSIVP1 Transaction isolation is not active.
17.17.32 JOB35727 +DFHDM0101I CICSIVP1 CICS is initializing.
17.17.32 JOB35727 +DFHWP0109I CICSIVP1 Web domain initialization has started.
17.17.32 JOB35727 +DFHS00100I CICSIVP1 Sockets domain initialization has started.
17.17.32 JOB35727 +DFHRX0100I CICSIVP1 RX domain initialization has started.
17.17.32 JOB35727 +DFHRX0101I CICSIVP1 RX domain initialization has ended.
17.17.33 JOB35727 +DFHLG0101I CICSIVP1 Log manager domain initialization has started.
17.17.33 JOB35727 +DFHEJ0101 CICSIVP1 296
296 Enterprise Java domain initialization has started. Java is a
296 trademark of Sun Microsystems, Inc.
17.17.33 JOB35727 +DFHDH0100I CICSIVP1 Document domain initialization has started.
17.17.33 JOB35727 +DFHXS1100I CICSIVP1 Security initialization has started.
17.17.33 JOB35727 +DFHSI1500 CICSIVP1 CICS startup is in progress for CICS Transaction Server Version 3.1.0
17.17.33 JOB35727 +DFHDM0304I CICSIVP1 Transaction Dump Data set DFHMPA opened.
17.17.33 JOB35727 +DFHXS1102I CICSIVP1 Security is inactive.
17.17.33 JOB35727 +DFHSI1501I CICSIVP1 Loading CICS nucleus.
17.17.34 JOB35727 +DFHTR0113 CICSIVP1 Auxiliary trace is being started on data set DFHAUXT.
17.17.34 JOB35727 +DFHCQ0100I CICSIVP1 Console queue initialization has started.
17.17.34 JOB35727 +DFHCQ0101I CICSIVP1 Console queue initialization has ended.
17.17.34 JOB35727 +DFHCQ0103I CICSIVP1 MVS console queue is open.
17.17.34 JOB35727 +DFHCQ0200I CICSIVP1 CEKL transaction enabled.
17.17.34 JOB35727 +DFHXS1101I CICSIVP1 Security initialization has ended.
17.17.34 JOB35727 +DFHRM0141 CICSIVP1 Recovery manager autostart override record is not present.
Normal processing continues.
17.17.34 JOB35727 +DFHDH0101I CICSIVP1 Document domain initialization has ended.
17.17.34 JOB35727 +DFHMN0105I CICSIVP1 Using default Monitoring Control Table.
17.17.34 JOB35727 +DFHMN0110I CICSIVP1 CICS Monitoring is inactive.
17.17.34 JOB35727 +DFHS00101I CICSIVP1 Sockets domain initialization has ended.
17.17.35 JOB35727 IEC031I D37-04,IFG0554P,DFHIVPOL,CICS,DFHAUXT,D306,P2P0C6,INST.CICSTS31.CICS.DFHAUXT
17.17.35 JOB35727 +DFHTR0110 - AUXILIARY TRACE DATA SET DFHAUXT FULL - SWITCHING TO DFHBUXT
17.17.35 JOB35727 +DFHWP0110I CICSIVP1 Web domain initialization has ended.
17.17.35 JOB35727 IEC031I D37-04,IFG0554P,DFHIVPOL,CICS,DFHBUXT,D50B,P2P14B,INST.CICSTS31.CICS.DFHBUXT
17.17.35 JOB35727 +DFHTR0109 - AUXILIARY TRACE DATA SET DFHBUXT FULL - AUXILIARY TRACE HAS BEEN STOPPED
17.17.35 JOB35727 +DFHSI1502I CICSIVP1 CICS startup is Warm.
17.17.35 JOB35727 +DFHTS0100I CICSIVP1 Temporary Storage initialization has started.
17.17.35 JOB35727 +DFHLG0103I CICSIVP1 System log (DFHLOG) initialization has started.
17.17.35 JOB35727 +DFHLG0104I CICSIVP1 322
322 System log (DFHLOG) initialization has ended. Log stream
322 CICINST.CICSIVP1.DFHLOG is connected to structure LOG_GENERAL_008.
17.17.35 JOB35727 +DFHLG0103I CICSIVP1 System log (DFHSHUNT) initialization has started.
17.17.35 JOB35727 +DFHSI1503I CICSIVP1 Terminal data sets are being opened.
17.17.36 JOB35727 +DFHLG0104I CICSIVP1 327
327 System log (DFHSHUNT) initialization has ended. Log stream
327 CICINST.CICSIVP1.DFHSHUNT is connected to structure LOG_GENERAL_008.

```

Figure 31. Sample job log for the DFHIVPOL job (Part 1 of 2)

```

17.17.36 JOB35727 +DFHLG0102I CICSIVP1 Log manager domain initialization has ended.
17.17.36 JOB35727 +DFHKE0406I CICSIVP1 329
329 CICS is about to wait for predecessors defined in the MVS automatic
329 restart management policy for this region.
17.17.36 JOB35727 +DFHKE0412I CICSIVP1 CICS WAITPRED call to automatic restart manager has completed.
17.17.36 JOB35727 +DFHCP0101I CICSIVP1 CPI initialization has started.
17.17.36 JOB35727 +DFHPR0104I CICSIVP1 Partner resource manager initialization has started.
17.17.36 JOB35727 +DFHAI0101I CICSIVP1 AITM initialization has started.
17.17.36 JOB35727 +DFHFC0100I CICSIVP1 File Control initialization has started.
17.17.36 JOB35727 +DFHTD0100I CICSIVP1 Transient Data initialization has started.
17.17.39 JOB35727 +DFHTS0101I CICSIVP1 Temporary Storage initialization has ended.
17.17.39 JOB35727 +DFHER5730 CICSIVP1 User recovery beginning
17.17.39 JOB35727 +DFHLG0745I CICSIVP1 System log full scan has started.
17.17.39 JOB35727 +DFHLG0748I CICSIVP1 System log selective scan has started.
17.17.39 JOB35727 +DFHLG0749I CICSIVP1 System log scan has completed.
17.17.40 JOB35727 +DFHER5731 CICSIVP1 No active user records on the system log
17.17.40 JOB35727 +DFHER5732 CICSIVP1 User recovery completed
17.17.40 JOB35727 +DFHTD0101I CICSIVP1 Transient Data initialization has ended.
17.17.40 JOB35727 +DFHFC0101I CICSIVP1 File Control initialization has ended.
17.17.40 JOB35727 +DFHTC1575 CICSIVP1 No TCT entry for SAMA
17.17.40 JOB35727 +DFHCP0102I CICSIVP1 CPI initialization has ended.
17.17.40 JOB35727 +DFHPR0105I CICSIVP1 Partner resource manager initialization has ended.
17.17.40 JOB35727 +DFHAI0102I CICSIVP1 AITM initialization has ended.
17.17.40 JOB35727 +DFHAP1203I CICSIVP1 Language Environment is being initialized.
17.17.40 JOB35727 +DFHAP1200 CICSIVP1 A CICS request to the Language Environment has failed. Reason code '0011020'.
17.17.40 JOB35727 +DFHAP1208 CICSIVP1 Language Environment cannot support the Cobol language. 7
17.17.40 JOB35727 +DFHAP1209 CICSIVP1 Language Environment cannot support the C/C++ languages. 7
17.17.40 JOB35727 +DFHAP1210 CICSIVP1 Language Environment cannot support the PL/I language. 7
17.17.40 JOB35727 +DFHAP1211I CICSIVP1 Language Environment initialization completed.
17.17.40 JOB35727 +DFHWB1007 CICSIVP1 Initializing CICS Web environment.
17.17.40 JOB35727 +DFHWB1008 CICSIVP1 CICS Web environment initialization is complete.
17.17.40 JOB35727 +DFHSI1517 CICSIVP1 Control is being given to CICS.
17.17.40 JOB35727 +DFHEJ0102 CICSIVP1 Enterprise Java domain initialization has ended.
17.23.42 JOB35727 +DFHFC0208I CICSIVP1 069
069 LSR pool 1 is being built dynamically by CICS because all of the
069 necessary parameters have not been supplied. Either there is no
069 LSRPOOL definition or it is incomplete. The following are not
069 defined: 'CI SIZE' 'STRINGS' 'MAXKEYLENGTH'. A delay is possible.
17.24.17 JOB35727 +DFHFC0208I CICSIVP1 137
137 LSR pool 1 is being built dynamically by CICS because all of the
137 necessary parameters have not been supplied. Either there is no
137 LSRPOOL definition or it is incomplete. The following are not
137 defined: 'CI SIZE' 'STRINGS' 'MAXKEYLENGTH'. A delay is possible.
17.24.28 JOB35727 +DFHTM1715 CICSIVP1 CICS is being quiesced by userid CICSUSER in transaction CEMT
at netname IYCQTC70. 4
17.24.28 JOB35727 +DFHDM0102I CICSIVP1 CICS is quiescing.
17.24.28 JOB35727 +DFHTM1782I CICSIVP1 All non-system tasks have been successfully terminated.
17.24.28 JOB35727 +DFHZC2305I CICSIVP1 Termination of VTAM sessions beginning
17.24.28 JOB35727 +DFHCESD CICSIVP1 SHUTDOWN ASSIST TRANSACTION CESD STARTING. SHUTDOWN IS NORMAL.
17.24.29 JOB35727 +DFHZC2316 CICSIVP1 VTAM ACB is closed
17.24.29 JOB35727 +DFHCQ0104I CICSIVP1 MVS console queue is closed.
17.24.31 JOB35727 +DFHRM0204 CICSIVP1 There are no indoubt, commit-failed or backout-failed UOWs.
17.24.32 JOB35727 +DFHRM0130 CICSIVP1 Recovery manager has successfully quiesced.
17.24.32 JOB35727 +DFHDU0303I CICSIVP1 Transaction Dump Data set DFHDMPA closed.
17.24.32 JOB35727 +DFHKE1799 CICSIVP1 TERMINATION OF CICS IS COMPLETE.
17.24.33 JOB35727 -DFHIVPOL CICS CICS 00 5757 .02 .00 7.05 21599 0 0 0 0 3
17.24.33 JOB35727 -DFHIVPOL CICS PRTDMPA 00 136 .00 .00 .00 286 0 0 0 0 4
17.24.34 JOB35727 -DFHIVPOL CICS PRTDMPB 00 135 .00 .00 .00 285 0 0 0 0 5
17.24.37 JOB35727 -DFHIVPOL CICS PRTAUXT 00 1559 .01 .00 .05 13828 0 0 0 0 6
17.24.37 JOB35727 $HASP375 DFHIVPOL ESTIMATED LINES EXCEEDED
17.24.38 JOB35727 $HASP375 DFHIVPOL ESTIMATE EXCEEDED BY 5,000 LINES
17.24.38 JOB35727 $HASP375 DFHIVPOL ESTIMATE EXCEEDED BY 10,000 LINES
17.24.38 JOB35727 $HASP375 DFHIVPOL ESTIMATE EXCEEDED BY 15,000 LINES
17.24.38 JOB35727 $HASP375 DFHIVPOL ESTIMATE EXCEEDED BY 20,000 LINES
17.24.39 JOB35727 $HASP375 DFHIVPOL ESTIMATE EXCEEDED BY 25,000 LINES
17.24.39 JOB35727 $HASP375 DFHIVPOL ESTIMATE EXCEEDED BY 30,000 LINES
17.24.39 JOB35727 $HASP375 DFHIVPOL ESTIMATE EXCEEDED BY 35,000 LINES
17.24.40 JOB35727 -DFHIVPOL CICS PRTBUXT 00 1572 .01 .00 .05 13923 0 0 0 0 7
17.24.40 JOB35727 IEF404I DFHIVPOL - ENDED - TIME=17.24.40
17.24.40 JOB35727 -DFHIVPOL ENDED. NAME=CICINST TOTAL CPU TIME= .06 TOTAL ELAPSED TIME= 7.18
17.24.40 JOB35727 $HASP395 DFHIVPOL ENDED

```

Figure 31. Sample job log for the DFHIVPOL job (Part 2 of 2)

Notes:

1 For information about the system initialization parameters used by the IVP jobs, see page 231. (See also **2** and **3** below.)

2 For more information about defining an applid for the CICS IVP jobs, see Chapter 13, “Defining CICS regions as applications to VTAM,” on page 99. An applid of CICSIVP1 has been used in Figure 31 on page 247 page=no.

3 The DFHSM0122 messages inform you of the limits available for the dynamic storage areas below and above 16MB. For information about these storage areas, see the *CICS System Definition Guide* .

Note: Storage for the extended read-only DSA, ERDSA, is obtained from read-only key 0 protected storage, because the sample SIT specifies RENTPGM=PROTECT (the default).

4 The DFHTM1715 message is issued because the CICS region was shut down by the terminal user (with netname IYCWTC30) issuing a CEMT PERFORM SHUTDOWN command.

7 If you want COBOL, C, C++ and PL/I languages, remove the comment marks from the SCEERUN and SCEERUN2 libraries, and increase the memory size for the job.

Logging on at a VTAM terminal

When the DFHIVPOL job displays the console message CONTROL IS BEING GIVEN TO CICS, you can log on to CICS using an IBM 3270 Information Display system terminal. Use the CICS application identifier that you specified when you brought up CICS to log on through your VTAM terminal. For example, unless you changed the APPLID specified as a SIT override parameter, (it is CICSIVP1), enter LOGON APPLID(CICSIVP1).

If you are using autoinstall, your logon request is passed to CICS and, provided all the autoinstall requirements described in “Using autoinstall for a VTAM terminal” on page 242 have been met, CICS installs your terminal. It does this by creating a TCT terminal entry (TCTTE) using the model definitions defined in the group list, DFHLIST, and the terminal identifier returned by the autoinstall user program (DFHZATDX in this case).

If you are using a terminal defined in the CSD explicitly, and included in the group list specified in the startup job stream, CICS identifies the installed resource definitions by the VTAM net name, and creates the required TCTTE.

When you log onto CICS, your terminal can display a “good morning” message, by the transaction specified on the GMTRAN system initialization parameter. The default transaction, CSGM, displays the message shown in Figure 32 on page 250, as defined by the GMTEXT system initialization parameter.

```

WELCOME TO CICS      12:56:28

      *****\  *****\  *****\  *****\ (R)
*****\ *****\ *****\ *****\
**\ \ \ \ \ **\  **\ \ \ \ \ **\  **\ \ \ \ \ **\
**\  \ \  **\  **\  \ \  **\  \ \  **\  \ \
**\      **\  **\      *****\
**\      **\  **\      *****\
**\      **\  **\      \ \ \ \ **\
**\  **\  **\  **\  **\  **\  **\
*****\ *****\ *****\ *****\
*****\ \ *****\ *****\ \ *****\ \
\ \ \ \ \  \ \ \ \ \  \ \ \ \ \  \ \ \ \ \

```

Figure 32. Screen layout for default logon message transaction, CSGM

Using CICS-supplied transactions through a terminal

After you have started CICS with the DFHIVPOL job, you can use the CICS-supplied transactions to try out various functions of CICS, to help you verify that CICS is working properly. You can use the transactions at a CICS terminal and, if you defined one, the system console.

Table 18 on page 251 shows some typical terminal interactions, including use of the CEMT transaction. For information about the CICS transactions that you can try with the DFHIVPOL job, and about the message-switching responses to those transactions, see the *CICS Supplied Transactions* manual.

Table 18. Typical terminal interactions

Operator Input	System Response
CEMT	Status: ENTER ONE OF THE FOLLOWING Discard Inquire Perform Set
I	Status: ENTER ONE OF THE FOLLOWING OR HIT ENTER FOR DEFAULT (Followed by a list of options)
PROG Press ENTER key	STATUS: RESULTS - OVERTYPE TO MODIFY Prog(CEECBLDY) Len(0000000) Ass Pro Ena Pri Res(000) Use(0000000000) Any Cex Ful
Press PF3 key Press CLEAR key	
CEMT PERFORM STATISTICS	
Press PF3 key Press CLEAR key	SESSION ENDED
CETR	See "Screen layout for the CETR transaction" on page 252
Press PF3 key Press CLEAR key	Clear or PF3 pressed Normal termination of CETR
CEMT I TA	Displays list of tasks in the system
Press PF3 key Press CLEAR key	SESSION ENDED
CEMT I PROG(DFHFEP)	Prog(DFHFEP)Len(005848) Ass Pro Ena Pri Res(000) Use(0000000) Any Cex Ful Qua
Press PF3 key Press CLEAR key	SESSION ENDED
CEOT (Inquire about this terminal)	Ter (tmid) Tra (CEOT) Pri (nnn) Pag Ins Ati Tti (Remember 'tmid' for use in next transaction, CMSG)
Press PF3 key Press CLEAR key	SESSION ENDED
CMSG 'HELLO',R=tmid,S	(Send the message 'HELLO' to your terminal) MRS OK MESSAGE HAS BEEN ROUTED (briefly at bottom right of screen) HELLO (at top left of screen)

You may enter your CEMT input in either uppercase or lowercase, because the master terminal transaction translates all input to uppercase. Use the CLEAR key and the PF3 key as indicated.

If you enter the CETR transaction, CICS displays the status of the various trace options. The screen layout in Figure 33 on page 252 shows what the CETR display looks like. For information about the CETR transaction, and the other information panels available by using specified PF keys, see the *CICS Supplied Transactions*

manual.

```
CETR                                CICS/ESA Trace Control Facility      sysid applid

Type in your choices.

Item                                Choice      Possible choices
Internal Trace Status               ===> STARTED  STArted, STOpped
Internal Trace Table Size           ===> 64      K    16K - 1048576K

Auxiliary Trace Status              ===> STOPPED  STArted, STOpped, Paused
Auxiliary Trace Dataset             ===> B        A, B
Auxiliary Switch Status             ===> NO      NO, NExt, All

GTF Trace Status                    ===> STOPPED  STArted, STOpped

Master System Trace Flag            ===> ON      ON, OFF
Master User Trace Flag              ===> ON      ON, OFF

When finished, press ENTER.

PF1=Help      3=Quit      4=Components      5=Ter/Trn      9=Error List
```

Figure 33. Screen layout for the CETR transaction

You can alter the status of any of the trace options by overtyping the current value, indicated by ===> on the CETR display.

Using the CEDA transaction

When DFHIVPOL starts up CICS, it uses the unsuffixed SIT, DFHSIT. This system initialization table specifies GRPLIST=DFHLIST, causing all the CICS resource definitions that are needed for normal running to be installed. You can see which resources are included in DFHLIST by using the CEDA transaction. For example, **CEDA EXPAND LIST(DFHLIST)** gives a screen similar to that in Figure 34 on page 253.

Press PF8 to see the continuation of the list. If you started the DFHIVPOL job with your own group list specified instead of the DFHLIST group list, specify the name of your list in the CEDA EXPAND command. The CICS-defined groups all begin with DFH. For information about CEDA and the interactions for a typical sequence of CEDA commands, see the *CICS Resource Definition Guide*.

```

EXPAND LIST(DFHLIST)
ENTER COMMANDS
NAME      TYPE      LIST      DATE      TIME
DFHDCTG  GROUP    DFHLIST  95.349    15.49.57
DFHBMS   GROUP    DFHLIST  95.349    15.49.57
DFHCONS  GROUP    DFHLIST  95.349    15.49.57
DFHDBCTL GROUP    DFHLIST  95.349    15.49.57
DFHDB2   GROUP    DFHLIST  95.349    15.49.57
DFHEDF   GROUP    DFHLIST  95.349    15.49.57
DFHEDP   GROUP    DFHLIST  95.349    15.49.57
DFHFE    GROUP    DFHLIST  95.349    15.49.58
DFHHARDC GROUP    DFHLIST  95.349    15.49.58
DFHINQUI GROUP    DFHLIST  95.349    15.49.58
DFHINTER GROUP    DFHLIST  95.349    15.49.58
DFHISC   GROUP    DFHLIST  95.349    15.49.58
DFHMISC  GROUP    DFHLIST  95.349    15.49.58
DFHMSWIT GROUP    DFHLIST  95.349    15.49.58
DFHOPCLS GROUP    DFHLIST  95.349    15.49.58
DFHOPER  GROUP    DFHLIST  95.349    15.49.58
+ DFHPGAIP GROUP    DFHLIST  95.349    15.49.58

                                SYSID=CICS APPLID=CICSIVP1
RESULTS: 1 TO 17 OF 47          TIME: 16.09.50 DATE: 95.349
PF 1 HELP          3 END 4 TOP 5 BOT 6 CRSR 7 SBH 8 SFH 9 MSG 10 SB 11 SF 12 CNCL

```

Figure 34. Screen layout for CEDA EXPAND LIST(DFHLIST) command

The DFHLIST group list does not include any of the sample applications groups, the group names of which all begin with DFH\$. To use the sample programs, therefore, you must first install the resource definitions for the required samples. For example, to use the FILEA sample application:

1. Install the sample programs that are needed for the FILEA applications. You can do this by the command:

```
CEDA INSTALL GROUP(DFH$AFLA)
```

2. Make the FILEA data set available to CICS. You can do this by one of the following:

- Install a FILE resource definition for the FILEA data set. You can do this by the command:

```
CEDA INSTALL GROUP(DFH$FILA)
```

- Provide a DD statement for the FILEA data set in your CICS startup JCL. For example,

```
//FILEA DD DISP=SHR,DSN=CICSTS31.CICS.CICSHTH1.FILEA
```

To end the CEDA session, press PF3.

Invoking and executing sample programs

To try the assembler-language version of the FILEA sample application, install group DFH\$AFLA then enter the AMNU transaction.

For information about the CICS sample application programs, see *CICS 4.1 Sample Applications Guide*.

Using transactions from a console device

CICS transactions (other than CECI) can be invoked from a console device, and other CICS operators can communicate with the console operator. In particular, you

can use the console device for CICS master terminal functions, to control CICS terminals or to control several CICS regions in conjunction with multiregion operation. Normal operating-system use of the console device is not inhibited, and CICS supports multiple console devices where present.

Notes:

1. The CEDA transaction can be used from a console device only to INSTALL resource definitions.
2. The CECI transaction and the sample programs cannot be used from a console device.

If you issue the MVS command `d consoles`, this displays a list of console devices. This list identifies the console devices by name.

You can use a console device to submit MODIFY commands from your job stream if you define a console device in your CSD as `CONSNAME(INTERNAL)`.

For further information about defining consoles, see “Defining an MVS console” on page 244. For further information about defining TSO users as consoles, see “Defining a TSO user as a console device” on page 245.

To enter a command, use:

```
{MODIFY|F} jobname,[']command[']
```

where:

jobname

is the region identifier for the CICS region. This is either the name of the job being used to execute CICS (for example, DFHIVPOL) or the name of a procedure if CICS was initiated as a started task.

command

is a string of data, starting with a CICS transaction identifier. If the transaction requires further input, the operator is prompted in the same way as any normal terminal operator. The message from CICS contains a reply number that must be quoted in the reply.

You can use the commands shown in Figure 35 on page 255 to verify the CEMT and CEOT transactions from the MVS console. (For information about these transactions, see the *CICS Supplied Transactions* manual.)

Entering commands from TSO

A TSO user can enter CICS commands as above after invoking the TSO command `CONSOLE`, in either of the following formats:

```
CONSOLE {MODIFY|F} cicsid,[']command[']  
  
CONSOLE  
{MODIFY|F} cicsid,[']command[']  
END
```

When the TSO command `CONSOLE` is used, TSO checks the user for authority to issue console commands. Further, if console operator command security is active, the TSO user must be specifically authorized to issue `MODIFY cicsid`.

The TSO user can interact with an alternate CICS by using the command `CONSOLE MODIFY altcics,CEBT`.

You can also use TSO CLIST processing to issue sequences of CICS commands.

Operator Input	System Response
f dfhivpol,'cent i terminal'	Displays a list of terminals attached to CICS
f dfhivpol,'cent i dump'	Displays status of transaction dump data sets
f dfhivpol,'cent p statistics'	CICS writes statistics to SMF data sets
f dfhivpol,'cent i ta'	Displays number and types of tasks currently running
f dfhivpol,'cent p dump'	CICS invokes SDUMP macro for system dump to be taken
f dfhivpol,'cent i prog(dfhpep)'	Displays details of DFHPEP module
f dfhivpol,'ceot'	Displays details of operator console
f dfhivpol,'cent i journalname'	Displays status of CICS logs

Figure 35. Using an MVS console for master terminal operations

Terminating CICS

To terminate CICS, enter: CEMT P SHUT from the VTAM terminal or MVS console. (This is a short form of CEMT PERFORM SHUTDOWN.) The system responds with message DFH1713, and those that follow, as shown in the sample job log shown on page 247.

Verifying shared data tables support

To verify that the shared data tables function can be used, you can:

1. Start up a CICS region on which you have installed support for shared data tables.

Note: To use shared data tables, you must install the following modules: DFHDTSVC, DFHDTCV, and DFHMVRMS in either an authorized system library in the MVS linklist (LNKLST concatenation of the MVS system) or in the LPA. When you install CICS, these modules are installed into the *hlq.SDFHLINK* library (which you should normally include in the MVS linklist).

2. Define and install a user-maintained data table.
3. Try a generic read command on your data table, using the CECI transaction. (Generic reads of user-maintained data tables are allowed only with shared data tables.) If shared data tables is operational, you should see a normal response. If shared data tables is not operational, you would see an INVREQ response.

Note: This verification process uses user-maintained data tables throughout, because the behavior of CICS-maintained data tables is transparent to their users. For example, a normal response is returned for a generic read of a CICS-maintained data table, regardless of whether or not shared data tables is operational.

To verify that the cross-memory services of shared data tables are working:

4. Start up a second CICS region (the **requester**) that has an interregion communication (IRC) connection to the first CICS region (the **server**, which contains the user-maintained data table and source data set).
5. On the requester CICS region, do the following:
 - a. Define and install a remote file referring to (associated with) the user-maintained data table on the server CICS region.
 - b. Close the interregion communication connection between the two CICS regions so that function shipping is impossible; that is, only the cross-memory services of shared data tables can be used to access the shared data table from the requester CICS region. To close the connection, you can enter the command:


```
CEMT SET IRC CLOSED
```

To verify that function shipping cannot work, try a remote READ of a file (not a data table) on the server CICS region; you will get a SYSIDERR response.
 - c. Try a generic read command on your data table, using the CECI transaction. If the cross-memory services of shared data tables can be used, you should see a normal response.
6. To restore interregion communication between the two CICS regions, open the connection again. To do this, you can enter the command:


```
CEMT SET IRC OPEN
```

Example verification of shared data tables

As an example verification test of shared data tables, the following steps were completed for the CICS shared data tables environment shown in Figure 36 on page 257:

1. A CICS region, CICSIDC, was started. (CICSIDC is the server CICS region in this example.)
2. On CICSIDC, the following steps were completed:
 - a. The user-maintained data table, MYS DT, was defined and installed. The MYS DT data table was based on the sample data set, *hlq.CICSIDC.FILEA*, installed on that region.
 - b. The following generic READ command was entered at a terminal:


```
CECI READ FILE(MYS DT) RIDFLD(00092) KEYLENGTH(5) GE GTEQ
```

Figure 37 on page 258 shows the initial response (LOADING), and Figure 38 on page 258 shows the subsequent response when the command was repeated after the data table had completed loading.

The following steps were completed to verify the cross-memory services of shared data tables:

3. A second CICS region, CICSIDA, was started with support for shared data tables. (CICSIDA is the requester CICS region in this example.)

4. The following IRC connections and sessions were defined and installed on the associated CICS regions:

Region	CONNECTION	SESSION
CICSIDA	CICA	ATOC
CICSIDC	CICC	CTOA

See Figure 41 on page 260 and Figure 42 on page 261 for the parameters used for the CICA and ATOC resource definitions. The parameters for the CICC and CTOA resource definitions were similar.

5. On CICSIDA, the following steps were completed:
- The file, REMSDT, was defined and installed as remote, referring to the MYSDT data table on CICSIDC. See Figure 43 on page 261 for the parameters used for the REMSDT resource definition.
 - The file, REMFIL, was defined and installed as remote, referring to the FILEA sample file on CICSIDC.
 - The CEMT SET IRC CLOSED command was used to close the IRC connection to CICSIDC.

- d. The following generic READ command was entered at a terminal:

```
CECI READ FILE(REMFIL) RIDFLD(00092) KEYLENGTH(5)
LENGTH(80) GE GTEQ
```

Figure 39 on page 259 shows the response (SYSIDERR), because the remote file cannot be accessed by function-shipping. (This response would also be observed for the remote data table, REMSDT, if the IRC connection was closed.)

- e. The following generic READ command was entered at a terminal:

```
CECI READ FILE(REMSDT) RIDFLD(00092) KEYLENGTH(5)
LENGTH(80) GE GTEQ
```

Figure 40 on page 260 shows the response (NORMAL). This only works if MYSDT is already open on CICSIDC, as achieved by step 2b on page 256.




Figure 36. CICS environment for example verification of shared data tables

```

read file(MYSDT) ridfld(00092) keylength(5) ge gteq
STATUS:  COMMAND EXECUTION COMPLETE                NAME=
EXEC CICS  READ
  File( 'MYSDT ' )
  < SYsid() >
  ( SEt() | Into( '' ) )
  < Length( +00000 ) >
  RIdfld( '00092' )
  < Keylength( +00005 ) < GGeneric > >
  < RBa | RRn | DEBRec | DEBKey >
  < GTeq | Equal >
  < UNcommitted | Consistent | REpeatable | UDate <token()> >
  < Nosuspend >

RESPONSE: LOADING                EIBRESP=+0000000094 EIBRESP2=+0000000104
PF 1 HELP 2 HEX 3 END 4 EIB 5 VAR 6 USER 7 SBH 8 SFH 9 MSG 10 SB 11 SF

```

Figure 37. On CICSIDC, response to initial CECI generic READ FILE command with SDT support. (The data table is loaded on first reference, and generic READ commands are not allowed for a user-maintained data table while it is loading.)

```

read file(MYSDT) ridfld(00092) keylength(5) ge gteq
STATUS:  COMMAND EXECUTION COMPLETE                NAME=
EXEC CICS  READ
  File( 'MYSDT ' )
  < SYsid() >
  ( SEt()
    | Into( ' 000983J. S. TILLING          WASHINGTON, DC          34512' ... ) )
  < Length( +00080 ) >
  RIdfld( '00092' )
  < Keylength( +00005 ) < GGeneric > >
  < RBa | RRn | DEBRec | DEBKey >
  < GTeq | Equal >
  < UNcommitted | Consistent | REpeatable | UDate <token()> >
  < Nosuspend >

RESPONSE: NORMAL                EIBRESP=+0000000000 EIBRESP2=+0000000000
PF 1 HELP 2 HEX 3 END 4 EIB 5 VAR 6 USER 7 SBH 8 SFH 9 MSG 10 SB 11 SF

```

Figure 38. On CICSIDC, response to CECI generic READ FILE command with SDT support. Normal response

```

read file(FILEA) ridfld(00092) keylength(5) length(80) ge gteq
STATUS:  COMMAND EXECUTION COMPLETE          NAME=
EXEC CICS  READ
  File( 'FILEA  ' )
  < SYsid() >
  ( SEt()
    | Into( '          ' ... ) )
  < Length( +00080 ) >
  RIdfld( '00092' )
  < Keylength( +00005 ) < GEneric > >
  < RBa | RRn | DEBRec | DEBKey >
  < GTEq | Equal >
  < UNcommitted | Consistent | REpeatable | UPdate <token()> >

  < Nosuspend >

RESPONSE: SYSIDERR          EIBRESP=+0000000053 EIBRESP2=+0000000130
PF 1 HELP 2 HEX 3 END 4 EIB 5 VAR 6 USER 7 SBH 8 SFH 9 MSG 10 SB 11

```

Figure 39. On CICSIDA, response to remote CECI generic READ FILE command, with IRC closed. SYSIDERR response for file, REMFIL, attempting to use function shipping for associated file, FILEA, on CICSIDC

```

read file(MYSDT) ridfld(00092) keylength(5) length(80) ge gteq
STATUS:  COMMAND EXECUTION COMPLETE          NAME=
EXEC CICS  READ
  File( 'MYSDT  ' )
  < SYsid() >
  ( SET()
    | Into( ' 000983J. S. TILLING          WASHINGTON, DC          34512' ... ) )
  < Length( +00080 ) >
  RIDfld( '00092' )
  < Keylength( +00005 ) < GGeneric > >
  < RBa | RRn | DEBRec | DEBKey >
  < GTeq | Equal >
  < UNcommitted | Consistent | REpeatable | UDate <token()> >
  < Nosuspend >

RESPONSE: NORMAL          EIBRESP=+0000000000 EIBRESP2=+0000000000
PF 1 HELP 2 HEX 3 END 4 EIB 5 VAR 6 USER 7 SBH 8 SFH 9 MSG 10 SB 11 SF

```

Figure 40. On CICSIDA, response to remote CECI generic READ FILE command, with IRC closed. Normal response for file, REMSDT, using cross-memory services for associated shared data table, MYSDT, on CICSIDC

```

OBJECT CHARACTERISTICS          CICS RELEASE = 0640

Connection      : CICA
Group           : CICAGRP
Description     : MRO CONNECTION CICSIDA TO CICSIDC
CONNECTION IDENTIFIERS
Netname        : CICSIDC
INDsys        :
REMOTE ATTRIBUTES
REMOTESystem   :
REMOTENAME    :
CONNECTION PROPERTIES
ACcessmethod  : IRC          Vtam | IRc | INdirect | Xm
Protocol      :             Appc | Lu61
SINGLEsess     : No          No | Yes
DATAstream    : User        User | 3270 | SCs | STRfield | Lms
RECORDformat  : U           U | Vb
OPERATIONAL PROPERTIES
AUTOconnect   : No          No | Yes | All
INService     : Yes         Yes | No

```

Figure 41. Example CONNECTION resource definition, CICA, installed on CICSIDA. Only relevant parameters are shown; other parameters were allowed to default

```

OBJECT CHARACTERISTICS                                     CICS RELEASE = 0640

Sessions          : ATOC
Group             : CICAGRP
DEscription      : SESSION FOR MRO CICA TO CICC
SESSION IDENTIFIERS
Connection       : CICA
SESSName         :
NETnameq        :
MOfename        :
SESSION PROPERTIES
Protocol         : Lu61                               Appc | Lu61
MAMaximum       : 000 , 000                           0-999
RECEIVEPfx     : RB
RECEIVECount    : 005                               1-999
SENDPfx        : SB
SENDCount       : 003                               1-999
SENDSize       : 04096                             1-30720
RECEIVESize    : 04096                             1-30720
SESSPriority    : 100                               0-255

```

Figure 42. Example SESSION resource definition, ATOC, associated with connection, CICA. Only relevant parameters are shown; other parameters were allowed to default

```

OBJECT CHARACTERISTICS                                     CICS RELEASE = 0640

File            : REMSDT
Group           : CICCGRP
DEscription    :
VSAM PARAMETERS
DSName         :
Password       :                                     PASSWORD NOT SPECIFIED
RLSaccess     : No                               No | Yes
Lsrpoolid     : 1                               1-8 | None
READInteg     : Uncommitted                     Uncommitted | Consistent | Repeat
DSNSharing    : Allreqs                         Allreqs | Modifyreqs
STRings       : 001                             1-255
Nsrgroup      :
REMOTE ATTRIBUTES
REMOTESystem   : CICC
REMOTENAME     : MYSDT
RECORDSize    :                               1-32767
Keylength     :                               1-255
INITIAL STATUS
STatus        : Enabled                         Enabled | Disabled | Unenabled

```

Figure 43. Example remote FILE resource definition, REMSDT, installed on CICSIDA. Only relevant parameters are shown; other parameters were allowed to default

Verifying the CICS-DBCTL interface

This section describes how to use the installation verification procedure, DFHIVPDB, which you can use to verify that the CICS-DBCTL interface can be used successfully.

Before you can run the DFHIVPDB job successfully, you must:

1. Tailor the DFHIVPDB job to your CICS and IMS environment.

You can do this as part of the process of tailoring all CICS sample post-installation jobs, as described in Chapter 29, “Defining DL/I support,” on page 197. When you run the DFHISTAR job as part of the CICS installation process, the DFHIVPDB job is installed in the *hlq.XDFHINST* library.

Note: Change the prefix of the IMS.SDFSRESL (previously called IMS.RESLIB)
library in the DFHIVPDB job to the prefix that you use for your IMS
libraries.

2. Create the data sets needed by the CICS region used by the the DFHIVPDB job.

To do this, you can tailor and run copies of the following CICS sample jobs:

DFHCOMDS

This job creates the CICS data sets common to all CICS regions.

DFHDEFDS

This job creates the data sets needed for each CICS region.

When you run the DFHISTAR job as part of the CICS installation process, these jobs are installed in the *hlq.XDFHINST* library.

3. Run the IMS installation verification procedures, as outlined in “The IMS installation requirements for the DFHIVPDB job.”

The IMS installation requirements for the DFHIVPDB job

The DFHIVPDB job depends on you running the IMS installation verification procedures, as part of the INSTALL/IVP process described in the *IMS Installation Guide*. The following assumptions about the IMS INSTALL/IVP process are made:

1. The IMS sample database, DI21PART, has been successfully defined. This comprises two data sets:
 - DI21PART
 - DI21PARO
2. The DI21PART database has been loaded with the IMS-supplied sample data.
3. The following IMS-supplied procedures have been installed in an executable procedure library:
 - ACBGEN
 - PSBGEN
4. The sample DRA startup table, DFSPZPIV, has been built and installed in the IMS.SDFSRESL (previously called IMS.RESLIB).
5. The sample DBCTL system, IVP3, is available.

#

For information about installing IMS, the INSTALL/IVP process, and running the IMS IVPs, see the *IMS Installation Guide*.

The DFHIVPDB job steps

The DFHIVPDB job consists of the following job steps:

1. **GEN.** This step unloads the member DFH\$DBAN from the *hlq.SDFHSAMP* library into a temporary sequential data set called CARDIN. This member contains the transactions to invoke the assembler versions of the DL/I sample applications that CICS reads from CARDIN as soon as initialization is complete.

Note: The sequential data set CARDIN is defined in the sample terminal control table, DFHTCT5\$, as a simulated terminal.

The COBOL version, DFH\$DBCBC, and the PL/I version, DFH\$DBPL, of the sample DL/I transactions are also in the *hlq.SDFHSAMP* library. If you want to run the COBOL or PL/I versions, modify this job step to load CARDIN with the appropriate member.

Output generated by the transactions is sent to a similar device – a sequential data set defined as PRINTER.

2. **CICS.** This job step executes the DFHSTART procedure to start up CICS, with the CICS-supplied resource group list DFH\$IVPL. CICS attempts to connect to the DBCTL system IVP3, run the sample DLI transactions, and then shutdown the CICS region.

Note: If the DBCTL system, IVP3, is not running, the sample DLI transactions will abend.

If you want to examine the sample members used by this IVP, here is a list of them, and where you can find each one:

DFHIVPDB

This IVP contains some explanatory comments, and was installed in the *hlq.XDFHINST* library when you ran the DFHISTAR job. For details of the DFHISTAR job, see Chapter 27, “Tailoring the CICS-supplied skeleton jobs,” on page 185.

DFH\$SIP5

This is the member of the *hlq.SYSIN* data set that contains the system initialization parameter overrides specific to the DFHIVPDB job.

Note: You will probably want to specify other system initialization parameters (for example, APPLID, CICSSVC, and DFLTUSER) for the DFHIVPDB job; the DFH\$SIP5 member of the *hlq.SYSIN* data set is a convenient place to do so.

DFHTCT5\$

This is the sample TCT that specifies the sequential devices that CICS uses in this IVP as a simulated terminal, with a terminal name of SAMA. The source statements are in the member, DFH\$TCTS, of the *hlq.SDFHSAMP* library.

Running the DFHIVPDB job

Before submitting the DFHIVPDB job, run the DFHRMUTL program, as shown below, to reset the global catalog control record to perform an INITIAL start on the next CICS startup.

```
//DFHRMUTI JOB 24116475,'DFHRMUTL',  
//          CLASS=A,MSGCLASS=H,NOTIFY=userid  
//*  
//*-----*/  
//* RESET GLOBAL CATALOG CONTROL RECORD TO INITIAL START */  
//*-----*/  
//DFHRMUTL EXEC PGM=DFHRMUTL,REGION=1M  
//STEPLIB DD DSN=CICSTS31.CICS.SDFHLOAD,DISP=SHR  
//SYSPRINT DD SYSOUT=*
```

```
//DFHGCD DD DSN=CICSTS31.CICS.DBCCICX.DFHGCD,DISP=OLD
//SYSIN DD *
SET_AUTO_START=AUTOINIT
/*
```

When you are satisfied that you have made all the necessary preparations, and that all the prerequisite jobs have been run, submit the DFHIVPDB job. The job loads the DL/I transactions into CARDIN. CICS reads the transactions, and sends the output to the PRINTER sequential data set.

Notes:

1. The first transaction copied from the DFH\$DBAN member of the *hlq.SDFHSAMP* library to CARDIN is CDBC CONNECT SUFFIX(IV). This connects CICS to DBCTL, using the sample DRA startup table, DFSPZP/IV.
2. The final transaction copied from the DFH\$DBAN member of the *hlq.SDFHSAMP* library to CARDIN is CEMT PERFORM SHUT.

If you want to use some commands online before CICS shuts down, then delete the CEMT command before you run the job. You will then be able to issue CEMT, CEDA and other CICS-supplied transactions, and initiate a shutdown either from a CICS terminal or through an MVS console. If you want to communicate with CICS through an MVS console, you must define a console to CICS before you start DFHIVPDB, as described in "Defining an MVS console" on page 244. If you want to enter MODIFY commands from terminals connected to TSO, you must define the TSO users as console devices, as described in "Defining a TSO user as a console device" on page 245.

A sample job log from a run of the DFHIVPDB job is given in Figure 44. The results you get from the transaction processing should be similar to those shown in Figure 44, Figure 45, and Figure 46.

```
1
0
JES2 JOB LOG -- SYSTEM MV26 -- NODE WINMVS2C
09.36.19 JOB36923 ---- WEDNESDAY, 19 JAN 2005 ----
09.36.19 JOB36923 ICH700011 CICINST LAST ACCESS AT 08:27:32 ON WEDNESDAY, JANUARY 19, 2005
09.36.19 JOB36923 $HASP373 DFHIVPDB STARTED - INIT 4 - CLASS A - SYS MV26
09.36.19 JOB36923 IEF403I DFHIVPDB - STARTED - TIME=09.36.19
09.36.19 JOB36923 -
09.36.19 JOB36923 --TIMINGS (MINS.)-- ----PAGING COUNTS----
09.36.19 JOB36923 -JOBNAME STEPNAME PROCSTEP RC EXCP CPU SRB CLOCK SERV PG PAGE SWAP VIO SWAPS STEPNO
09.36.19 JOB36923 -DFHIVPDB GEN 00 53 .00 .00 .00 184 0 0 0 0 0 1
09.36.19 JOB36923 -DFHIVPDB CICS CICSCNTL 01 16 .00 .00 .00 148 0 0 0 0 0 2
09.36.19 JOB36923 -DFHIVPDB CICS DTCNTL 01 15 .00 .00 .00 161 0 0 0 0 0 3
09.36.20 JOB36923 DFHPA1101 CICSIVP1 DFHSIT IS BEING LOADED.
09.36.20 JOB36923 DFHPA1108 CICSIVP1 DFHSIT HAS BEEN LOADED. (GENERATED AT: MM/DD= 01/12 HH:MM= 13:57).
09.36.20 JOB36923 DFHPA1100 CICSIVP1 OVERRIDE PARAMETERS FROM JCL EXEC STATEMENT: START=AUTO,SYSIN
09.36.20 JOB36923 DFHPA1102 CICSIVP1 OVERRIDE PARAMETERS FROM SYSIN:
09.36.20 JOB36923 DFHPA1927 CICSIVP1 GRPLIST=DFH$IVPL, INCLUDE DLI SAMPLE PROGRAMS & TRANSACTIONS 20000000
09.36.20 JOB36923 DFHPA1927 CICSIVP1 FCT=NO, 30000000
09.36.20 JOB36923 DFHPA1927 CICSIVP1 TCT=5$, TCT INCLUDES SEQ DEVICES 40000000
09.36.20 JOB36923 DFHPA1927 CICSIVP1 XRF=NO, 50000000
09.36.20 JOB36923 DFHPA1927 CICSIVP1 STNTR=OFF, 53000000
09.36.20 JOB36923 DFHPA1927 CICSIVP1 STNTRFC=1, TRACE FILE CONTROL AND DLI EVENTS 56000000
09.36.20 JOB36923 DFHPA1927 CICSIVP1 AUXTR=ON, 60000000
09.36.20 JOB36923 DFHPA1927 CICSIVP1 AUXTRSW=NEXT, 70000000
09.36.20 JOB36923 DFHPA1927 CICSIVP1 SRT=NO, 70001100
09.36.20 JOB36923 DFHPA1927 CICSIVP1 SEC=NO, 70000200
09.36.20 JOB36923 DFHPA1927 CICSIVP1 TRTABSZ=64, 70000300
09.36.20 JOB36923 DFHPA1927 CICSIVP1 APPLID=CICSIVP1, 70000400
09.36.20 JOB36923 DFHPA1927 CICSIVP1 CICSVC=233, 70000500
09.36.20 JOB36923 DFHPA1927 CICSIVP1 .END 80000000
09.36.20 JOB36923 DFHPA1103 CICSIVP1 END OF FILE ON SYSIN. 09.36.21 JOB36923 +DFHTR0103 TRACE TABLE SIZE IS 64K
09.36.21 JOB36923 +DFHSM0122I CICSIVP1 Limit of DSA storage below 16MB is 5,120K.
09.36.21 JOB36923 +DFHSM0123I CICSIVP1 Limit of DSA storage above 16MB is 30M.
09.36.21 JOB36923 +DFHSM0113I CICSIVP1 Storage protection is not active.
09.36.21 JOB36923 +DFHSM0126I CICSIVP1 Transaction isolation is not active.
09.36.21 JOB36923 +DFHDM0101I CICSIVP1 CICS is initializing.
```

Figure 44. Sample job log output from the DFHIVPDB job (Part 1 of 3)


```

09.36.23 JOB36923 +DFHWB0109I CICSIVP1 Web domain initialization has started.
09.36.23 JOB36923 +DFHS00100I CICSIVP1 Sockets domain initialization has started.
09.36.23 JOB36923 +DFHRX0100I CICSIVP1 RX domain initialization has started.
09.36.23 JOB36923 +DFHRX0101I CICSIVP1 RX domain initialization has ended.
09.36.23 JOB36923 +DFHLG0101I CICSIVP1 Log manager domain initialization has started.
09.36.23 JOB36923 +DFHEJ0101I CICSIVP1 790
790 Enterprise Java domain initialization has started. Java is a
790 trademark of Sun Microsystems, Inc.
09.36.23 JOB36923 +DFHDH0100I CICSIVP1 Document domain initialization has started.
09.36.23 JOB36923 +DFHXS1100I CICSIVP1 Security initialization has started.
09.36.23 JOB36923 +DFHSI1500 CICSIVP1 CICS startup is in progress for CICS Transaction Server Version 3.1.0
09.36.23 JOB36923 +DFHXS1102I CICSIVP1 Security is inactive.
09.36.23 JOB36923 +DFHUU0304I CICSIVP1 Transaction Dump Data set DFHDMPB opened.
09.36.23 JOB36923 +DFHSI1501I CICSIVP1 Loading CICS nucleus.
09.36.26 JOB36923 +DFHTR0113 CICSIVP1 Auxiliary trace is being started on data set DFHAUXT.
09.36.26 JOB36923 +DFHCQ0100I CICSIVP1 Console queue initialization has started.
09.36.26 JOB36923 +DFHCQ0101I CICSIVP1 Console queue initialization has ended.
09.36.26 JOB36923 +DFHCQ0103I CICSIVP1 MVS console queue is open.
09.36.26 JOB36923 +DFHCQ0200I CICSIVP1 CEKL transaction enabled.
09.36.26 JOB36923 +DFHXS1101I CICSIVP1 Security initialization has ended.
09.36.26 JOB36923 +DFHRM0140 CICSIVP1 Recovery manager autostart override found with value: 'AUTOINIT'.
09.36.26 JOB36923 +DFHRM0149I CICSIVP1 Recovery manager autostart override record will be deleted.
09.36.26 JOB36923 +DFHDH0101I CICSIVP1 Document domain initialization has ended.
09.36.26 JOB36923 +DFHMN0105I CICSIVP1 Using default Monitoring Control Table.
09.36.26 JOB36923 +DFHS00101I CICSIVP1 Sockets domain initialization has ended.
09.36.26 JOB36923 +DFHWB0110I CICSIVP1 Web domain initialization has ended.
09.36.26 JOB36923 +DFHMN0110I CICSIVP1 CICS Monitoring is inactive.
09.36.26 JOB36923 +DFHSI1502I CICSIVP1 CICS startup is Initial.
09.36.26 JOB36923 +DFHTS0100I CICSIVP1 Temporary Storage initialization has started.
09.36.26 JOB36923 +DFHSI1503I CICSIVP1 Terminal data sets are being opened.
09.36.27 JOB36923 +DFHLG0102I CICSIVP1 Log manager domain initialization has ended.
09.36.27 JOB36923 IEC161I 080-053,DFHVPDB,CICS CICS,DFHTEMP,,
09.36.27 JOB36923 IEC161I INST.CICSTS31.CNTL.CICS.DFHTEMP,
09.36.27 JOB36923 IEC161I INST.CICSTS31.CNTL.CICS.DFHTEMP.DATA,
09.36.27 JOB36923 IEC161I ICFCAT.SYSPLX2.CATALOGB
09.36.27 JOB36923 +DFHTS0102I CICSIVP1 About to format the temporary storage data set (359 control intervals).
09.36.27 JOB36923 +DFHKE0406I CICSIVP1 825
825 CICS is about to wait for predecessors defined in the MVS automatic
825 restart management policy for this region.
09.36.27 JOB36923 +DFHKE0412I CICSIVP1 CICS WAITPRED call to automatic restart manager has completed.
09.36.27 JOB36923 +DFHCP0101I CICSIVP1 CPI initialization has started.
09.36.27 JOB36923 +DFHPR0104I CICSIVP1 Partner resource manager initialization has started.
09.36.27 JOB36923 +DFHAI0101I CICSIVP1 AITM initialization has started.
09.36.27 JOB36923 +DFHFC0100I CICSIVP1 File Control initialization has started.
09.36.27 JOB36923 +DFHTD0100I CICSIVP1 Transient Data initialization has started.
09.36.27 JOB36923 +DFHFC0101I CICSIVP1 File Control initialization has ended.
09.36.27 JOB36923 +DFHTD0101I CICSIVP1 Transient Data initialization has ended.
09.36.27 JOB36923 +DFHTS0101I CICSIVP1 Temporary Storage initialization has ended.
09.36.27 JOB36923 +DFHCP0102I CICSIVP1 CPI initialization has ended.
09.36.27 JOB36923 +DFHPR0105I CICSIVP1 Partner resource manager initialization has ended.
09.36.27 JOB36923 +DFHAI0102I CICSIVP1 AITM initialization has ended.
09.36.28 JOB36923 +DFHSI1511I CICSIVP1 Installing group list DFH$IVPL.
09.36.29 JOB36923 IEC031I D37-04,IFG0554P,DFHVPDB,CICS,DFHAUXT,D306,P2P0C6,INST.CICSTS31.CICS.DFHAUXT
09.36.29 JOB36923 +DFHTR0110 - AUXILIARY TRACE DATA SET DFHAUXT FULL - SWITCHING TO DFHBUXT
09.36.29 JOB36923 IEC031I D37-04,IFG0554P,DFHVPDB,CICS,DFHBUXT,D50B,P2P14B,INST.CICSTS31.CICS.DFHBUXT
09.36.29 JOB36923 +DFHTR0109 - AUXILIARY TRACE DATA SET DFHBUXT FULL - AUXILIARY TRACE HAS BEEN STOPPED
09.36.30 JOB36923 +DFHLG0103I CICSIVP1 System log (DFHLOG) initialization has started.
09.36.31 JOB36923 +DFHLG0104I CICSIVP1 844
844 System log (DFHLOG) initialization has ended. Log stream
844 CICINST.CICSIVP1.DFHLOG is connected to structure LOG_GENERAL_008.
09.36.31 JOB36923 +DFHLG0103I CICSIVP1 System log (DFHSHUNT) initialization has started.
09.36.31 JOB36923 +DFHLG0104I CICSIVP1 846
846 System log (DFHSHUNT) initialization has ended. Log stream
846 CICINST.CICSIVP1.DFHSHUNT is connected to structure LOG_GENERAL_008.
09.36.31 JOB36923 +DFHAP1203I CICSIVP1 Language Environment is being initialized.
09.36.31 JOB36923 +DFHAP1200 CICSIVP1 A CICS request to the Language Environment has failed. Reason code '0011020'.
09.36.31 JOB36923 +DFHAP1208 CICSIVP1 Language Environment cannot support the Cobol language. 7
09.36.31 JOB36923 +DFHAP1209 CICSIVP1 Language Environment cannot support the C/C++ languages. 7
09.36.31 JOB36923 +DFHAP1210 CICSIVP1 Language Environment cannot support the PL/I language. 7
09.36.31 JOB36923 +DFHAP1211I CICSIVP1 Language Environment initialization completed.
09.36.31 JOB36923 +DFHWB1007 CICSIVP1 Initializing CICS Web environment.
09.36.32 JOB36923 +DFHWB1008 CICSIVP1 CICS Web environment initialization is complete.
09.36.32 JOB36923 +DFHSI1517 CICSIVP1 Control is being given to CICS.
09.36.32 JOB36923 +DFHEJ0102 CICSIVP1 Enterprise Java domain initialization has ended.
09.37.54 JOB36923 +DFHTM1715 CICSIVP1 CICS is being quiesced by userid CICSUSER in transaction CEMT at terminal SAMA.
09.37.54 JOB36923 +DFHDM0102I CICSIVP1 CICS is quiescing.
09.37.54 JOB36923 +DFHDB8122I CICSIVP1 CICS is about to disconnect from DBCTL for CICS shutdown.
09.37.54 JOB36923 +DFHCESD CICSIVP1 SHUTDOWN ASSIST TRANSACTION CESD STARTING. SHUTDOWN IS NORMAL.
09.37.54 JOB36923 +DFHDB8123I CICSIVP1 CICS disconnection from DBCTL for CICS shutdown has completed successfully.
09.37.54 JOB36923 +DFHTM1782I CICSIVP1 All non-system tasks have been successfully terminated.
09.37.55 JOB36923 +DFHZC2305I CICSIVP1 Termination of VTAM sessions beginning
09.37.55 JOB36923 +DFHZC2316 CICSIVP1 VTAM ACB is closed
09.37.55 JOB36923 +DFHCQ0104I CICSIVP1 MVS console queue is closed.
09.37.58 JOB36923 +DFHRM0204 CICSIVP1 There are no indoubt, commit-failed or backout-failed UOWs.
09.37.59 JOB36923 +DFHRM0130 CICSIVP1 Recovery manager has successfully quiesced.
09.37.59 JOB36923 +DFHUU0303I CICSIVP1 Transaction Dump Data set DFHDMPB closed.

```

Figure 44. Sample job log output from the DFHVPDB job (Part 2 of 3)

```

09.37.59 JOB36923 +DFHKE1799 CICSIVP1 TERMINATION OF CICS IS COMPLETE.
09.37.59 JOB36923 -DFHIVPDB CICS CICS 00 4070 .03 .00 1.66 23769 0 0 0 0 0 4
09.38.00 JOB36923 -DFHIVPDB CICS PRDMPA 00 137 .00 .00 .00 289 0 0 0 0 0 5
09.38.00 JOB36923 -DFHIVPDB CICS PRDMPB 00 138 .00 .00 .00 291 0 0 0 0 0 6
09.38.03 JOB36923 -DFHIVPDB CICS PRTAUXT 00 1935 .01 .00 .04 13326 0 0 0 0 0 7
09.38.04 JOB36923 $HASP375 DFHIVPDB ESTIMATED LINES EXCEEDED
09.38.04 JOB36923 $HASP375 DFHIVPDB ESTIMATE EXCEEDED BY 5,000 LINES
09.38.05 JOB36923 $HASP375 DFHIVPDB ESTIMATE EXCEEDED BY 10,000 LINES
09.38.05 JOB36923 $HASP375 DFHIVPDB ESTIMATE EXCEEDED BY 15,000 LINES
09.38.05 JOB36923 $HASP375 DFHIVPDB ESTIMATE EXCEEDED BY 20,000 LINES
09.38.05 JOB36923 $HASP375 DFHIVPDB ESTIMATE EXCEEDED BY 25,000 LINES
09.38.06 JOB36923 $HASP375 DFHIVPDB ESTIMATE EXCEEDED BY 30,000 LINES
09.38.06 JOB36923 -DFHIVPDB CICS PRTBUXT 00 1909 .01 .00 .05 13560 0 0 0 0 0 8
09.38.06 JOB36923 IEF4041 DFHIVPDB - ENDED - TIME=09.38.06
09.38.06 JOB36923 -DFHIVPDB ENDED. NAME=CICINST TOTAL CPU TIME= .06 TOTAL ELAPSED TIME= 1.78
09.38.06 JOB36923 $HASP395 DFHIVPDB ENDED

```

Figure 44. Sample job log output from the DFHIVPDB job (Part 3 of 3)

Note:

1 The DFHIVPDB job uses the unsuffixed SIT, DFHSIT, as used by all the CICS IVPs. It also uses some system initialization parameters included in the DFH\$SIP5 member of the SYSIN data set, to override the parameters in DFHSIT. Further, the DFH\$SIP5 member was edited to specify other system initialization parameters to create the DFHIVPDB job log shown. For information about these extra system initialization parameters used by the IVP jobs, see page 231.

7 If you want COBOL, C, C++ and PL/I languages, remove the comment marks from the SCEERUN and SCEERUN2 libraries, and increase the memory size for the job.

You should see messages similar to those in Figure 45 at the end of the MSGUSER section of the job output.

```

DFHLG0302 01/19/2005 09:36:31 CICSIVP1 Journal name DFHLOG has been installed. Journal type: MVS
CICINST.CICSIVP1.DFHLOG.
DFHLG0302 01/19/2005 09:36:31 CICSIVP1 Journal name DFHSHUNT has been installed. Journal type: MVS
CICINST.CICSIVP1.DFHSHUNT.
DFHLG0744 01/19/2005 09:36:31 CICSIVP1 All records in log stream CICINST.CICSIVP1.DFHLOG have been deleted.
DFHLG0744 01/19/2005 09:36:31 CICSIVP1 All records in log stream CICINST.CICSIVP1.DFHSHUNT have been deleted.
DFHDB8116 I 01/19/2005 09:36:32 CICSIVP1 Connection to DBCTL IM7D is proceeding. Startup Table Suffix used is IV.
DFHDB8101 I 01/19/2005 09:36:32 CICSIVP1 Connection to DBCTL IM7D is now complete. Startup Table Suffix used is IV.
DFHZC3441 I 01/19/2005 09:37:55 CICSIVP1 Orderly termination of VTAM sessions requested. ((1) Module name: DFHZSHU)
DFHRM0205 01/19/2005 09:37:58 CICSIVP1 An activity keypoint has been successfully taken.
DFHLG0743 01/19/2005 09:37:58 CICSIVP1 Tail of log stream CICINST.CICSIVP1.DFHLOG deleted at block id
X'000000000000FDD'.

```

Figure 45. Sample job log output from the end of the MSGUSER section of the DFHIVPDB job

You should see messages similar to those in Figure 46 on page 267 in the Printer section of the job output.

IDFHDB8210D Connection to DBCTL is proceeding. Check CDBC TD queue.
 DFHDB8225I CICSIVP1 The DBCTL ID is IM7D. The DRA Startup Table suffix is IV.

```

INPUT: ASMCDDPA02MS16995-28
PART=02MS16995-28      DESC= SCREW
  AREA  INV  PROJ  DIV  UNIT  CURRENT  ON  IN  TOTAL  COUNT  BACK
        DEPT  CD   PRICE  REQMTS  ORDER  STOCK  DISBURSE  TAKEN  ORDR
1.     AA  165  11  0.152  260     0   300  4030  N     0
2.     BA  165  15  0.069  60     0   80   5000  N     0
3.     FF  554  6D  0.069  440     0  430  5000  N     0
4.  2   59  109  26  6.980  950     0  1000  5000  N     0
  
```

```

INPUT: ASMCDDPA02JAN1976B
PART=02JAN1976B      DESC= DIODE CODE-A
  AREA  INV  PROJ  DIV  UNIT  CURRENT  ON  IN  TOTAL  COUNT  BACK
        DEPT  CD   PRICE  REQMTS  ORDER  STOCK  DISBURSE  TAKEN  ORDR
1.  2   55  091  26  0.000  170    2000  170  4710  N     0
  
```

Figure 46. Sample job log output from the Printer section of the output of the DFHIVPDB job

Testing the CICS-DB2 environment

This section outlines how you can test the CICS-DB2 environment. It uses Phase 5 of the DB2 installation verification procedure. It is intended as an overview of what is involved, and what you would expect to see.

To use the DB2 installation verification procedure, and Phase 5 in particular, see the *IBM DATABASE 2 Administration Guide*. That publication gives the latest information about the procedure, and describes the steps involved in much more detail.

Run DB2 jobs DSNTEJ5C and DSNTEJ5P

To prepare the sample applications to be used in a CICS-DB2 environment, run the jobs DSNTEJ5C and DSNTEJ5P supplied with DB2.

Job DSNTEJ5C installs the sample application transactions in COBOL and prepares the organization application. Job DSNTEJ5P installs the transactions in PL/I and prepares the organization, project, and phone applications.

Both these jobs perform the following functions:

- Compile and link-edit the CICS online applications.
- Bind the CICS online applications.
- Create the BMS maps for the online applications.

Starting a DB2 organization or project application

After logging on to CICS, you can start an organization or project application by entering one of the following CICS transaction codes:

- D8PP, which starts the PL/I project version
- D8PS, which starts the PL/I organization version
- D8CS, which starts the COBOL organization version

If you enter one of these transaction codes, the panels shown in Figure 47 on page 268 or Figure 48 on page 268 are displayed.

```

                                ACTION SELECTION
MAJOR SYSTEM ....: 0           ORGANIZATION
ACTION .....:
OBJECT .....:
SEARCH CRITERIA.:
DATA .....:
SELECT AN ACTION FROM FOLLOWING LIST

A   ADD (INSERT)
D   DISPLAY (SHOW)
E   ERASE (REMOVE)
U   UPDATE (CHANGE)

```

Figure 47. Initial panel for the DB2 project application in CICS

```

                                ACTION SELECTION
MAJOR SYSTEM ....: P           PROJECTS
ACTION .....:
OBJECT .....:
SEARCH CRITERIA.:
DATA .....:
SELECT AN ACTION FROM FOLLOWING LIST

A   ADD (INSERT)
D   DISPLAY (SHOW)
E   ERASE (REMOVE)
U   UPDATE (CHANGE)

```

Figure 48. Initial panel for the DB2 project application in CICS

For detailed information about running the organization and project applications, see the *IBM DATABASE 2 Administration Guide*.

Starting the DB2 phone application

To start the phone application, clear the screen and type in the transaction code D8PT. You can change the transaction codes when you install DB2. Check with your system administrator to find out if they have been changed from those shown.

Running the EJB "Hello World" sample

You are recommended to include running the EJB "Hello World" sample in your Installation Verification procedures.

For a description of this procedure, see the *Java Applications in CICS* manual.

Part 5. CICSplex SM installation and setup

This part describes the processes and procedures you should follow to install CICSplex SM. It contains the following chapters

- Chapter 36, “CICSplex SM setup checklist and worksheets,” on page 271.
- Chapter 37, “Setting up the MVS environment,” on page 281.
- Chapter 38, “VTAM requirements,” on page 289.
- Chapter 39, “Generating post-installation members,” on page 297.
- Chapter 40, “Creating and managing CICSplex SM data sets,” on page 299.
- Chapter 41, “Upgrading the CSD and macro definitions,” on page 307
- Chapter 42, “Preparing user access to CICSplex SM,” on page 313
- Chapter 43, “Setting up a coordinating address space (CAS),” on page 315.
- Chapter 44, “Setting up a CICSplex SM address space (CMAS),” on page 321.
- Chapter 45, “Setting up a CICS managed application system (MAS),” on page 333.
- Chapter 46, “Setting up a CICSplex SM Web User Interface server,” on page 341.
- Chapter 47, “Configuring the Starter Set,” on page 361.
- Chapter 48, “Applying service to CICSplex SM,” on page 371.
- Chapter 49, “Using the EYUINST EXEC to tailor skeleton jobs,” on page 373.
- Chapter 50, “CICSplex SM system parameters,” on page 383.
- Chapter 51, “CMAS journaling,” on page 397.
- Chapter 52, “Preparing to use the IPCS tools,” on page 401.

Chapter 36. CICSplex SM setup checklist and worksheets

This chapter contains the following aids to your installation and setup procedures:

Checklist

To use as a guide to your progress as you set up or revise the configuration of your IBM CICSplex System manager (CICSplex SM) components. The checklist is for use with a CICS Transaction Server (or a CICS/ESA) system (referred to as an MVS system) and all of the components you can install on it.

Some of the items on the MVS checklist need be performed only once for your CICSplex SM environment, while others must be performed once for each component. See the 'Where to get information' column for a reference to information about how to perform each task.

The order of items in the checklist is a suggested order for performing the installation and setup steps. However, you may find that, particularly if you are modifying your CICSplex SM environment, a different order is more practical.

Worksheets

To use as a record of the names and locations of components and data sets. The worksheets can be copied as you need.

The worksheets contain, in some cases, more than one line for a type of CICSplex SM component. You may have fewer or more than shown of that type of component.

A worksheet is provided for each of the following CICSplex SM system components:

- The CICSplex SM system
- A CAS
- A CMAS
- A local MAS

The checklist and worksheets are also provided on the tape on which CICSplex SM is delivered to you. They are loaded onto your system and available in the library CICSSTS31.CPSM.SEYUINST.

Table 19 lists the members by name and content. You can edit these members, filling in the information specific to your CICSplex SM environment, so that you have an online record of the information you need about that environment.

Table 19. Checklist and worksheets in CICSSTS31.CPSM.SEYUINST

Member name	Contents
EYULSTMV	MVS installation and setup checklist
EYUWKSYS	System worksheet
EYUWKCAS	CAS worksheet
EYUWKCMS	CMAS worksheet
EYUWKLMS	A local MAS worksheet

Installation checklist

MVS installation and setup checklist

Component			What you need to do	Values to note	Where to get information
Note: Components are indicated as follows: C =CAS, CM =CMAS, LM =local MAS					
C	CM	LM	Make note of SYS1.PARMLIB(IEASYSxx) values for this MVS system	APF= CMD= LNK= LNKAUTH= LPA= MAXCAD= MAXUSER= NSYSLX= PROG= RSVNONR= RSVSTRT= SMF= SYSNAME=	"Noting IEASYSxx values" on page 281
C	CM		Update number of common data spaces in IEASYSxx	NSYSLX value	"Updating IEASYSxx (CAS)" on page 282
	CM		Update number of linkage indexes in IEASYSxx	MAXCAD value	"Updating IEASYSxx (CMAS)" on page 282
C	CM	LM	Update IEAAPFxx or PROGxx to authorize index.SEYUAUTH	IEAAPFxx or PROGxx member Library name	"Authorizing libraries" on page 283
		LM	Update IEAAPFxx or PROGxx to authorize index.SEYULPA Optional library. Can be populated below.	IEAAPFxx or PROGxx member Library name	"Authorizing libraries" on page 283
C	CM		Verify index.SEYULINK is authorized	LNKAUTH= value Library name	"Authorizing libraries" on page 283
C	CM		Update linklist with index.SEYULINK	LNKLSTxx member Library name	"Updating the MVS linklist" on page 284
		LM	Update LPA list with index.SEYULPA Optional library. Can be populated below.	LPALSTxx member Library name	"Installing CICSplex SM modules into the LPA" on page 287
C	CM	LM	Create VTAM Mode Table entry	Node name	"Step 1: (Optional) Creating a mode table" on page 289
C	CM	LM	Use your ESM to protect CICSplex SM libraries	As required by your ESM	the <i>CICS RACF Security Guide</i>
C	CM		Define security for the CAS and CMAS startup procedures	Procedure names	the <i>CICS RACF Security Guide</i>
C			Create VTAM application definition for each CAS	SYS1.VTAMLST major node member Application name(s)	"Step 2: Creating a VTAM application definition (CAS)" on page 291
	CM		Create VTAM application definition for each CMAS	SYS1.VTAMLST major node member Application name(s)	"Step 1: Creating a VTAM application definition (CMAS)" on page 294
C			Define cross-domain resources for each CAS	SYS1.VTAMLST members	"Step 3: Defining cross-domain resources (CAS)" on page 292
	CM		Define cross-domain resources for each CMAS	SYS1.VTAMLST members	"Step 2: Defining cross-domain resources (CMAS)" on page 295
C	CM	LM	Add application and cross-domain resource definitions to the VTAM configuration list	SYS1.VTAMLST (ATCCONxx)	"Step 4: Updating the configuration list (CAS)" on page 292

Component			What you need to do	Values to note	Where to get information
C	CM	LM	Activate VTAM definitions	Major node names	"Step 5: Activating the major nodes (CAS)" on page 293
C	CM	LM	Edit EYUISTAR for post-installation members	Edited member	Chapter 39, "Generating post-installation members," on page 297
C	CM	LM	Run edited EYUISTAR member to generate POST install members.	sysproc.XEYUINST output library name	Chapter 39, "Generating post-installation members," on page 297
		LM	(Optional.) Install LPA modules	Installed usermod name	"Installing CICSplex SM modules into the LPA" on page 287
C			(Optional.) Create CICSplex SM parameter repository	dsindex.EYUIPRM	"CAS-related data sets" on page 299
C			(Optional.) Create CICSplex SM screen repository	dsindex.EYUSDEF	"CAS-related data sets" on page 299
	CM		Create CICSplex SM data repository	dsindex.EYUDREP. cmasname	"Creating the CICSplex SM data repository" on page 299
	CM		Update CMAS CSD resource definitions	CSD library name CMAS Group name CMAS Startup list name	"Updating the CSD files using DFHCSDUP (CMAS)" on page 307
		LM	Update MAS CSD resource definitions	CSD library name MAS Group name MAS Startup list name	"Updating CSD files using DFHCSDUP (MVS MAS)" on page 311
	CM		Create CICSplex SM system parameter member for each CMAS	Modified EYUCMS0P parameter member(s)	"Preparing to start a CMAS" on page 323
		LM	Edit CICSplex SM system parameter member for each local MAS	Modified EYULMS0P parameter member(s)	"Preparing to start an MVS MAS" on page 334
	CM		Edit CICS SIT parameters for each CMAS	Modified parameter member(s)	"CMAS-related CICS SIT parameters" on page 326
		LM	Edit CICS SIT parameters for each MAS	Modified parameter member(s)	"MVS MAS-related CICS SIT parameters" on page 336
	CM		Create CICS data sets for each CMAS	Modified EYUDFHDS member	"Preparing to start a CMAS" on page 323
C			Install CAS startup procedure (EYUCAS sample procedure)	Installed procedure member Subsystem Id	"Preparing to start a CAS" on page 315
	CM		Install CMAS startup procedure (EYUCMAS sample procedure)	Installed procedure member	"Preparing to start a CMAS" on page 323
C			Update ISPF signon allocations (EYUTSODS temporary allocation EXEC)	Logon procedure member	Chapter 42, "Preparing user access to CICSplex SM," on page 313
C			Update ISPF panel selection	Updated panel member	Chapter 42, "Preparing user access to CICSplex SM," on page 313
C			Start the CAS	Message BBMZA001 INITIALIZATION COMPLETE	"Preparing to start a CAS" on page 315

Component			What you need to do	Values to note	Where to get information
C			Start the CMAS	Message EYUXL009I CAS Connection established	"Preparing to start a CMAS" on page 323
C			Define CAS-to-CAS links using CASDEF view	Subsystem ids	<i>CICSplex System Manager Administration</i>
	CM		Create CMAS-to-CMAS links using CMTCMDEF view	CMAS names Target APPLID Target CICS SYSID	<i>CICSplex System Manager Administration</i>
	CM		Create CICSplex definition using CPLEXDEF view	CICSplex name	<i>CICSplex System Manager Administration</i>
I		LM	Create all MAS definitions using CICSSYS view	MAS name(s)	<i>CICSplex System Manager Administration</i>
I		LM	Start the MAS	Message EYUXL007I LMAS Phase II initialization complete	"Preparing to start an MVS MAS" on page 334
I		LM	Shut down the MASs using CICSRGN view - terminates CICS	Message EYUXL0016I MAS shutdown complete	"Stopping management of a CICS system" on page 339

System worksheet

System: _____

CAS name: _____

Subsystem ID: _____

VTAM Applid: _____

	Name:	VTAM Applid:	CICS-SYSID:
CMAS:	_____	_____	_____
LMAS:	_____	_____	_____
LMAS:	_____	_____	_____
LMAS:	_____	_____	_____
CMAS:	_____	_____	_____
LMAS:	_____	_____	_____
LMAS:	_____	_____	_____
LMAS:	_____	_____	_____
CMAS:	_____	_____	_____
LMAS:	_____	_____	_____
LMAS:	_____	_____	_____
LMAS:	_____	_____	_____

CAS worksheet

System: _____
 VTAM Applid: _____

CAS name: _____
 Subsystem id: _____

SYS1.PARMLIB(IEASYSxx) values:

APF= _____	CMD= _____	LNK= _____
LNKAUTH= _____	LPA= _____	MAXCAD= _____
MAXUSER= _____	NSYLSX= _____	PROG= _____
RSVNONR= _____	RSVSTRT= _____	SMF= _____
SYSNAME= _____		

Dsn added to member IEAAPFxx or PROGxx: when _____ .SEYUAUTH
 LNKAUTH=APFTAB: (when LNKAUTH=LNKLST, no dsn here) _____ .SEYULINK

Dsn added to member LNKLSTxx: _____ .SEYULINK

VTAM Mode Table Mode Name: _____

SYS1.VTAMLST start list (ATCSTRxx): _____

SYS1.VTAMLST configuration list (ATCCONxx): _____

SYS1.VTAMLST applications member: _____

SYS1.VTAMLST cross-domain member: _____

VTAM definitions; Major Node Names:

1st CAS: _____ 2nd CAS: _____ 3rd CAS: _____

Installation materials library: _____ .SEYUINST

Modified EYUISTAR (post-installation) member: _____

EYUINST exec output library: _____ .XEYUINST

CICSplex SM parameter repository: _____ .EYUIPRM

CICSplex SM screen repository: _____ .EYUSDEF

CAS startup procedure (member): _____

CAS signon procedure (member): _____

ISPF panel selection (member): _____

Links to other CASs: _____

	Subsystem Id:	VTAM Applid:	Link name:
1st CAS:	_____	_____	_____
2nd CAS:	_____	_____	_____
3rd CAS:	_____	_____	_____

CMAS worksheet

System: _____

CMAS name: _____

CAS name: _____

CICS Sysid: _____

VTAM Applid: _____

SYS1.PARMLIB(IEASYSxx) values:

APF= _____
MAXCAD= _____

LNK= _____
NSYLSX= _____

LNKAUTH= _____
PROG= _____

Dsn added to member IEAAPFxx or PROGxx: when _____ .SEYUAUTH
LNKAUTH=APFTAB: (when LNKAUTH=LNKLST, no dsn _____ .SEYULINK
here)

Dsn added to member LNKLSTxx: _____ .SEYULINK

VTAM Mode Table Node Name: _____

SYS1.VTAMLST start list (ATCSTRxx): _____

SYS1.VTAMLST configuration list (ATCCONxx): _____

SYS1.VTAMLST applications member: _____

SYS1.VTAMLST cross-domain member: _____

VTAM definitions; Node Names:

	Name	VTAM Applid	CICS Sysid
LMAS:	_____	_____	_____
LMAS:	_____	_____	_____
LMAS:	_____	_____	_____

Installation materials library: _____ .SEYUINST

Modified EYUISTAR (post-installation) member: _____

EYUINST exec output library: _____ .XEYUINST

CICSplex SM data repository dsn: _____

CICS resource definition tables output dsn: _____

CICS CSD dsn: _____

CMAS group EYU310G0 load module: _____

CMAS startup list EYU310L0 load module: _____

Modified EYUCMSOP member: _____

CICS SIT parameters member: _____

Modified EYUDFHDS member: _____

CMAS startup procedure member: _____

Links to other CMASs:

CMAS name:	VTAM Applid:	CICS Sysid:	Protocol:
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____

Links to LMASs:

LMAS name:	VTAM Applid:	CICS Sysid:	Protocol:
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____
_____	_____	_____	_____

Local MAS worksheet

MVS/ESA System: _____
 CAS Name: _____
 CICSplex Name: _____
 CMAS CPSM Name: _____ MAS CPSM Name: _____
 CMAS CICS Sysid: _____ MAS CICS Sysid: _____
 CMAS VTAM Applid: _____ MAS VTAM Applid: _____
 MAS Type _____ FOR, AOR, TOR

Dsn added to member IEAAPFxx or PROGxx: when _____ .SEYUAUTH
 LNKAUTH=APFTAB: (when LNKAUTH=LNKLST, no dsn _____ .SEYULINK
 here)

Dsn added to member LPALSTxx: _____ .SEYULPA

SYS1.VTAMLST start list (ATCSTRxx): _____

SYS1.VTAMLST configuration list (ATCCONxx): _____

SYS1.VTAMLST applications member: _____

Installation materials library: _____ .SEYUINST

Modified EYUISTAR (post-installation) member: _____

EYUINST exec output library: _____ .XEYUINST

LPA module (usermod) name: _____

CICS resource definition tables output dsn: _____

CICS CSD dsn: _____

MAS group EYU310G1 load module: _____

Modified MAS startup list name: _____

Modified EYULMS0P dsn (member): _____

CICS SIT parameters dsn (member): _____

Link from CMAS:

CMAS name:	VTAM Applid:	CICS Sysid:	Protocol:
_____	_____	_____	_____

Chapter 37. Setting up the MVS environment

This chapter describes the tasks you need to perform to ensure that your MVS environment is correctly defined to support CICSplex SM. These tasks are as follows:

- “Noting IEASYSxx values”
- “Updating IEASYSxx (CMAS)” on page 282
- “Updating IEASYSxx (CAS)” on page 282
- “Updating the MVS linklist” on page 284
- “Preparing to use the CICSplex SM API” on page 284
- “Installing CICSplex SM modules into the LPA” on page 287

Noting IEASYSxx values

Some of the MVS initialization values located in an IEASYSxx member of the SYS1.PARMLIB library are referenced during installation of the CAS and other CICSplex SM address spaces.

Access the IEASYSxx member of the SYS1.PARMLIB library used to initialize your MVS system and make note of the values assigned to the following parameters:

APF=	Completes the name of the parmlib member (IEAAPFxx) that contains authorized library names.
CMD=	Completes the name of the parmlib member (COMMNDxx) that contains commands to be issued internally during master scheduler initialization.
LNK=	Completes the name of one or more parmlib members (LNKLSTxx) that contain names of data sets that are to be concatenated to SYS1.LINKLIB.
LNKAUTH=	Specifies whether all data sets in the LNKLST concatenation are to be treated as APF authorized or whether only those that are named in the APF table are to be treated as APF authorized.
LPA=	Completes the name of one or more parmlib members (LPALSTxx) that are concatenated to SYS1.LPALIB for the purpose of building the pageable LPA (PLPA and extended PLPA).
MAXCAD=	Specifies the maximum number of SCOPE=COMMON data spaces to be allowed during an IPL.
MAXUSER=	Specifies a value that the system uses (along with the RSVSTRT and RSVNONR parameter values) to limit the number of jobs and started tasks that the system can run concurrently during a given IPL.
NSYSLX=	Specifies the number of linkage indexes (LXs), in addition to those in the system function table, to be reserved for system linkage indexes (LXs).
PROG=	Completes the name of the parmlib member (PROGxx) that contains authorized library names when a dynamic APF list is being used.

RSVNONR=	Specifies the number of address space vector table (ASVT) entries to be reserved for replacing those entries marked nonreusable for the duration of an IPL.
RSVSTRT=	Specifies the number of ASVT entries to be reserved for address spaces created in response to a START command.
SMF=	Specifies a parmlib member (SMFPRMxx) from which SMF will obtain its parameters. You should examine the SMFPRMxx member of SYS1.PARMLIB and note the SID() value that identifies the system that will run the CAS.
SYSNAME=	Specifies the name of the system being initialized.

For more information about these parameters, see the *MVS Initialization and Tuning Reference* manual.

Updating IEASYSxx (CAS)

In every MVS/ESA image that contains a CAS, you need to verify that the IEASYSxx member of the SYS1.PARMLIB library that you use for MVS initialization includes the parameters:

NSYSLX=nnn

Set or increase the value to include the minimum number of linkage indexes (LXs) required by CICSplex SM. Because two LXs are required for the CAS and one LX is needed for the ESSS, the minimum number of LXs required for use by CICSplex SM is 3.

If you are also setting up a CMAS, refer to “Updating IEASYSxx (CMAS)” for information about additional parameters.

For additional information about these parameters, see the *MVS Initialization and Tuning Reference* manual.

Updating IEASYSxx (CMAS)

In every MVS/ESA image that contains a CMAS, you need to verify that the IEASYSxx member of the SYS1.PARMLIB library that you use for MVS initialization includes the parameters:

MAXCAD=nnn

Set or increase the value to include the number of common MVS data spaces that are needed for each CMAS. Each CMAS needs a minimum of 6 common MVS data spaces. When setting the MAXCAD limit, allow for 6 common MVS data spaces per CMAS, in addition to any common data spaces that may be in use by other products.

NSYSLX=nnn

Set or increase the value to include the minimum number of linkage indexes (LXs) that are required by CICSplex SM. Because two LXs are required for the CAS and one LX is needed for the Environment Services System Services (ESSS), the minimum number of LXs required for use by CICSplex SM is 3.

Note: This parameter may already have been defined when you set up the CAS. (See “Updating IEASYSxx (CAS)” on page 282.)

For additional information about these parameters, see the *MVS Initialization and Tuning Reference* manual.

Authorizing libraries

In each MVS image containing a CAS and CICSplex SM address space (CMAS), you must change the appropriate IEAAPFxx or PROGxx member of the SYS1.PARMLIB library to authorize CICSplex SM libraries.

The libraries to be authorized in the IEAAPFxx or PROGxx member are:

CICSTS31.CPSM.SEYUAUTH

Needed to run a CAS

SYS1.CICSTS31.CPSM.SEYULINK

The link list data set, needed to run a CMAS (For more information about adding this data set, see “Updating the MVS linklist” on page 284.)

If your operating system uses the parameter

LNKAUTH=LNKLST

(which is the default), you do not need to authorize the SYS1.CICSTS31.CPSM.SEYULINK library now.

SYS1.CICSTS31.CPSM.SEYULPA

The link pack area data set, optionally used for managed application system (MAS) LPA modules.

If you are adding the data set names to the IEAAPFxx member, the format of each entry is:

dsname volser

where dsname is the name of one of the CICSplex SM libraries listed above and volser is the volume serial number of the volume on which the data set is located.

If you are adding the data set names to the PROGxx member, the format of each entry is:

APF ADD DSNAME(dsname) VOLUME(volser)

where dsname is the name of one of the CICSplex SM libraries listed above and volser is the volume serial number of the volume on which the data set is located.

For additional information about adding entries to IEAAPFxx and PROGxx, see the *MVS Initialization and Tuning Reference* manual. If you are running with a static APF list, you must re-IPL MVS in order for authorization to take effect.

You should use RACF (or another external security manager) to protect the CICSTS31.CPSM.SEYUAUTH, SYS1.CICSTS31.CPSM.SEYULPA, and SYS1.CICSTS31.CPSM.SEYULINK libraries, as described in the *CICS RACF Security Guide*.

Updating the MVS linklist

Depending on what components of CICSplex SM you plan to run in an MVS image, ensure that the following required modules reside in an authorized library in the MVS linklist. These modules are supplied in the SYS1.CICSTS31.CPSM.SEYULINK library.

EYU9X310 In each MVS image that contains a CMAS. EYU9X310 is the initialization module for the ESSS.

This CICSplex SM component provides a system address space that is started by the first CMAS to be initialized in the MVS image after an IPL. For additional information about the ESSS, see *CICSplex System Manager Problem Determination* book.

EYU9A310 In each MVS image that contains a CMAS where you wish to run the CICSplex SM API. EYU9A310 is the CICSplex SM API subtask module.

These modules are release specific and are not compatible with earlier versions. If
you plan to run multiple releases of CICSplex SM on the same MVS image, you
must have the equivalent modules specific to the releases you are running.

Note: For information on additional modules that can be placed in the MVS linklist and if you plan to use the CICSplex SM API, see “Preparing to use the CICSplex SM API.”

To add one or more of these modules to an authorized library in the linklist, perform one of the following actions:

- Add the appropriate modules to an authorized library that is already in the linklist.
- Add the SYS1.CICSTS31.CPSM.SEYULINK library to the linklist by identifying the library in a LNKLSTxx member of the SYS1.PARMLIB library.

You should use RACF (or another external security manager) to protect the SYS1.CICSTS31.CPSM.SEYULINK library, as described in the *CICS RACF Security Guide*.

Preparing to use the CICSplex SM API

In each MVS image that contains a CMAS where you plan to run the CICSplex SM API, ensure that the following required modules reside in the proper location. These modules are supplied in the SYS1.CICSTS31.CPSM.SEYUAUTH library.

EYU9AB00 In an authorized library in either the MVS linklist or the STEPLIB concatenation of the application that calls the API. EYU9AB00 is the API batch interface module.

EYU9XESV In an authorized library in either the MVS linklist or the CMAS STEPLIB concatenation. EYU9XESV is the API security exit module.

In addition, any application that calls the API must be link-edited with one of the following stub routine modules, regardless of what programming language is used:

EYU9ABSI

For batch, TSO, or NetView programs. EYU9ABSI is supplied in the SYS1.CICSTS31.CPSM.SEYUAUTH library.

EYU9AMSI

For application programs running in CICS. EYU9AMSI is supplied in the SYS1.CICSTS31.CPSM.SEYULOAD library.

Installing the REXX function package

The REXX run-time interface to the API is supplied as a function package and host command environment. The interface consists of a single load module that contains two entry points:

EYU9AR00	The function package
EYU9AR01	The host command

EYU9AR00 is supplied in the SYS1.CICSTS31.CPSM.SEYUAUTH library with an alias of IRXFLOC.

For a REXX program to access the function package, the module EYU9AR00, along with its alternate entry point, EYU9AR01, and its alias, IRXFLOC, must reside in an authorized library in one of these places:

- The MVS linklist
- The STEPLIB concatenation of the application that calls the API.

For a REXX program to access the function package from NetView, the EYU9AR00 module must also be aliased to DSIRXLFP and placed in an authorized library in either the MVS linklist or the STEPLIB concatenation for the NetView system.

Note: Users of the CICSplex SM run-time interface are subject to the normal CICSplex SM API security checks. See the information in the *CICS RACF Security Guide*.

The following members contain SMP/E user modification control statements that you can use to move the necessary API load modules to the SYS1.CICSTS31.CPSM.SEYULINK library. These members are supplied in CICSTS31.CPSM.SEYUSAMP.

Member	Load module
EYU\$UM11	EYU9AR00
EYU\$UM12	EYU9AB00
EYU\$UM13	EYU9XESV

If you use the IRXFLOC or DSIRXLFP aliases to provide access to the REXX function package, they must be placed ahead of any other IRXFLOC or DSIRXLFP modules in the STEPLIB (or MVS linklist) concatenation.

If you do not want to use the aliases for the REXX function package, you must modify your REXX parameter modules (IRXPARMS, IRXTSPRM, and IRXISPRM). If you do this, the following is recommended:

- The function package supplied by CICSplex SM should be added as a System function package, rather than a Local or User function package.
- A new host command entry like the following should be added:
 - An 8-byte Command Environment name of 'CPSM'
 - An 8-byte Command Routine name of 'EYU9AR01'

- A 16-byte Command Token of blanks

As the last step in installing the REXX function package, you must:

- Increase the number of entries in the appropriate function package table.
- Add an entry to that table for EYU9AR00.

For more information about REXX function packages and host commands, see the *TSO/E Version 2 REXX/MVS Reference* book.

Using CICSplex SM modules in the MVS link pack area

The benefits of using the MVS link pack area (LPA) are:

- **Sharing** – modules in the LPA can be shared by two or more CICS regions in the same MVS image, giving an overall reduction in the total working set.
- **Integrity** – the LPA is page-protected, even against key 0 programs, so all modules placed there are automatically protected against overwriting by other programs such as CICS applications. (This integrity feature applies equally to a single CICS system within the processor.)

Every CICSplex SM module installed in the LPA can be used only by the release of CICSplex SM to which it relates.

CICSplex SM supplies prebuilt SMP/E USERMODs as members in the CICSSTS31.CPSM.SEYUSAMP library. The USERMOD is:

```
# EYU$UM01 - Local MAS modules
#
```

These USERMODs contain ++MOVE statements for each module that is eligible for the extended link pack area (ELPA). A read-only module that may reside above 16MB is eligible for the ELPA.

CICSplex SM allocates an empty library for your use, called SYS1.CICSSTS31.CPSM.SEYULPA. You can use SYS1.CICSSTS31.CPSM.SEYULPA as the LPA library or you can add the modules to another LPA library.

If you are going to use SYS1.CICSSTS31.CPSM.SEYULPA, verify that you have already authorized this library (see “Authorizing libraries” on page 283), and that you have applied appropriate security (see the *CICS RACF Security Guide*.) You can give the SYS1.CICSSTS31.CPSM.SEYULPA library your own high-level index. If you do, you must specify the new index on the LINDEX parameter of the EYUISTAR job.

The following sections provide information about:

- Space requirements
- Installing CICSplex SM modules into the LPA
- Controlling the use of modules from the LPA
- Applying maintenance to LPA modules.

Space requirements

| You must allow enough space in the link pack area for the installation of the
| selected CICSplex SM modules.

| The total space needed depends on how the modules are packaged into the link
| pack area by the operating system and a local MAS requires approximately
| 2 034KB.

Installing CICSplex SM modules into the LPA

The term *install* means move or copy a module into the SYS1.CICSTS31.CPSM.SEYULPA library, by using SMP/E, or by using a copying method that reblocks the copied modules when the target data set has a smaller block size than the data set you are copying from (for example, use the COPYMOD function of the IEBCOPY program). The procedure for installing modules in the LPA by using SMP/E is described in this section.

You should not relink-edit the modules in order to get them into the SYS1.CICSTS31.CPSM.SEYULPA library. CICSplex SM modules, as supplied, have the necessary attributes that cause MVS to load them automatically above 16MB (into the ELPA).

The MVS link pack area has both pageable and fixed areas. Although you can install CICSplex SM modules into the fixed areas, for performance reasons you should use the pageable areas.

Modules to be loaded into the MVS pageable link pack area (PLPA) must have been link-edited with the RENT attribute. The library in which these modules reside must be named in an LPALSTxx member of the SYS1.PARMLIB library.

To install modules in the CICSplex SM LPA library, and to ensure that SMP/E can continue to service them, complete the following steps for one or both of the CICSplex SM-supplied USERMODs:

1. Receive the USERMOD into the CICSplex SM global zone, and apply it to the CICSplex SM target zone.
2. Define the SYS1.CICSTS31.CPSM.SEYULPA library to your MVS.

Note: You must also verify that the CSD referenced by the MAS contains the appropriate CICSplex SM groups for loading modules from the LPA. For information about updating the CSD, see “Updating CSD files using DFHCSDUP (MVS MAS)” on page 311.

Receiving and applying the USERMOD

#

To receive and apply the CICSplex SM-supplied USERMOD, in EYU\$UM01, you can use the sample job EYULPMOD, which is tailored to your CICSplex SM environment and stored in the CICSTS31.CPSM.XEYUINST library when you run the EYUISTAR job. Member EYULPMOD must be edited to receive and apply the desired USERMODs. Ensure that the EYUISTAR settings match the corresponding DFHISTAR settings.

Receive the USERMOD into the CICSplex SM global zone and apply it to the CICSplex SM target zone. This causes SMP/E to move those load modules you have specified from the named CICSplex SM target library (either CICSTS31.CPSM.SEYUAUTH or CICSTS31.CPSM.SEYULOAD) into the SYS1.CICSTS31.CPSM.SEYULPA library.

When the USERMOD is applied, the corresponding LMOD entries within the target zone SMP CSI are updated. Either or both USERMODs may be applied depending on your enterprise’s requirements.

Do not accept the USERMOD into the distribution zone, and, for the time being, do not apply it to any other target zone.

Defining the SYS1.CICSTS31.CPSM.SEYULPA library to your MVS

Add the full name of the SYS1.CICSTS31.CPSM.SEYULPA library to an LPA LSTxx member of SYS1.PARMLIB. This ensures that the library contents are loaded into the PLPA at the next IPL of your system when CLPA is specified.

When you have defined the SYS1.CICSTS31.CPSM.SEYULPA library to MVS, you should re-IPL your MVS with CLPA specified to enable the modules in the SYS1.CICSTS31.CPSM.SEYULPA library to be used from the LPA.

To run DFCSDUP to add the CICSplex SM resource definitions required for MAS execution, use the following SYSIN control statement:

```
//SYSIN DD *  
  UPGRADE USING(EYU9XXGB)  
/*
```

Applying maintenance to LPA modules

Use the SMP/E RESTORE function to back off the USERMOD before modules in the LPA are updated or copied. Afterwards, the USERMOD may be reapplied.

Chapter 38. VTAM requirements

This chapter describes the VTAM requirements for each CAS, CMAS, and MAS used by CICSplex SM.

Defining VTAM requirements (CAS)

ACF/VTAM definitions are required, if you are not using the cross-systems coupling facility (XCF) for CAS-to-CAS communication links, to identify each CAS used by CICSplex SM. This involves creating VTAM application definitions and, optionally, cross-domain resource management definitions.

If you are also setting up a CMAS, see “Defining VTAM requirements (CMAS)” on page 293 for more information about the steps for defining the VTAM requirements for a CMAS.

To create VTAM application definitions and cross-domain resource management definitions for a CAS, you must perform the following steps:

1. Optionally, create a mode table entry.
2. Create a VTAM application definition for each CAS you will be using.
3. Define each CAS as a cross-domain resource.
4. Add the application and cross-domain resource definitions to the VTAM configuration list.
5. Activate the definitions.

Depending on your VTAM conventions, you may need to modify the procedures described in this section. Specifically:

- Change references to the SYS1.VTAMLST library if you do not keep your definitions in the default VTAM list.
- Modify the APPL and CDRSC statements if you want to add these statements to existing members, rather than create new ones.

After you have the CAS running and can access CICSplex SM, you can define VTAM to CICSplex SM. (See “Setting the CAS system communication information” on page 318.)

Step 1: (Optional) Creating a mode table

If you use Network Control Programs (NCPs), you may need to create a mode table with the default entry shown in Figure 49 on page 290 in order to control the VTAM RUSIZES (request unit size) parameter. If you do not create a default entry, VTAM could select a number that is too small, thus resulting in considerable system overhead.

To create a default mode table entry:

1. Define a mode table containing the following entry:

```

        TITLE 'modename - MODE Table - Entries'
modename MODETAB ,
        MODEENT LOGMODE=entryname,                X
            FMPROF=X'13',                          X
            TSPROF=X'07',                          X
            PRIPROT=X'B0',                         X
            SECPROT=X'B0',                         X
            COMPROT=X'50B1',                       X
            SSNDPAC=X'00',                         X
            SRCVPAC=X'00',                         X
            RUSIZES=X'F8F8',                       X
            PSNDPAC=X'00',                         X
            PSERVIC=X'060200000000000000002300',  X
            ENCR=X'00'
        MODEEND ,
    END ,

```

Figure 49. Sample mode table entry

where:

modename Is a mode table name that you supply.

entryname Is a name for an entry that you supply.

For a copy of this mode table entry, see the member EYUSMPMT in CICSTS31.CPSM.SEYUSAMP.

2. Assemble the mode table source and link-edit it into SYS1.VTAMLIB on all systems for which cross-system communication is enabled. As you do so, keep the following in mind:
 - The name you assign to the load module becomes the name of the mode table.
 - You must have access to the macro library used to assemble VTAM applications.

The JCL you use to assemble and link-edit should look like that shown in Figure 50 on page 291. (The member EYUJCLMT in CICSTS31.CPSM.SEYUSAMP contains a copy of this JCL.)

```

/*-----
/*
/* Sample JCL - Assemble and Link Mode Table Entry
/*
/* The following needs to be provided:
/*-----
/* ASM.SYSIN - Input member containing the mode table source.
/* LINK.SYSLMOD - Output member name in SYS1.VTAMLIB
/*
/*-----
//ASM EXEC PGM=ASMA90,
// PARM='OBJECT,NODECK'
//SYSLIB DD DISP=SHR,DSN=SYS1.SISTMAC1
// DD DISP=SHR,DSN=SYS1.MACLIB
//SYSUT1 DD DSN=&&SYSUT1,
// UNIT=VIO,SPACE=(1700,(600,100))
//SYSTEM DD SYSOUT=*
//SYSPRINT DD SYSOUT=*
//SYSLIN DD DISP=(MOD,PASS),
// DSN=&&OBJSET,
// UNIT=VIO,SPACE=(80,(200,50))
//SYSIN DD DISP=SHR,DSN=data_set_name(member_name)
/*
//LINK EXEC PGM=IEWL,
// PARM=(XREF,LET,LIST,NCAL,REUS),
// COND=(8,LT,ASM)
//SYSLIN DD DISP=(OLD,DELETE),DSN=&&OBJSET
// DD DDNAME=SYSIN
//SYSLMOD DD DISP=SHR,DSN=SYS1.VTAMLIB(member_name)
//SYSUT1 DD DSN=&&SYSUT1,
// UNIT=VIO,SPACE=(1024,(50,20))
//SYSPRINT DD SYSOUT=*
/*

```

Figure 50. JCL to assemble a mode table entry

Step 2: Creating a VTAM application definition (CAS)

To establish a VTAM application definition for a CAS, either create a new member (*major node*) or access an existing member in the SYS1.VTAMLST library. To this member, add the following APPL statement:

```

          VBUILD TYPE=APPL
name     APPL ACBNAME=acbname,AUTH=(ACQ),           x
          PARSESS=YES,MODETAB=mode_table

```

where:

name Is a 1- to 8-character unique name.

acbname

Is the node name of this CAS. This name must be unique within the domain. If you omit this parameter, the name of the VTAM APPL statement is used.

mode_table

Is the name of the mode table that is to govern LU 6.2 conversations.

For example, to create a VTAM application definition for the CAS on SYSA, you might create a member named APPLCASA in the SYS1.VTAMLST library that contains the APPL statement:

```

          VBUILD TYPE=APPL
CASA     APPL ACBNAME=CASA,AUTH=(ACQ),          x
          PARSESS=YES,MODETAB=AMODET

```

The same type of definition is needed for each CAS you will be using.

Step 3: Defining cross-domain resources (CAS)

You should define cross-domain resources (CDRSCs) when:

- A CAS that is to communicate with another CAS cannot take advantage of dynamically defined CDRSCs.
- You want to minimize the overhead involved in using dynamically defined CDRSCs.

To establish a CDRSC definition, you must either create a new member or access an existing member in the SYS1.VTAMLST library. In the new or existing member, specify the following CDRSC statement for each CAS with which you want to communicate:

```

          VBUILD TYPE=CDRSC
name     CDRSC CDRM=cdrm

```

where:

name Is the name you assigned to a CAS in Step 1.

cdrm Is the name of the MVS image previously identified as the cross-domain resource manager (CDRM).

For example, to allow the CAS on SYSA to communicate with the CASs on SYSB and SYSC, you might create the member CDRCASA on the SYS1.VTAMLST library, which contains the CDRSC statements:

```

          VBUILD TYPE=CDRSC
CASB     CDRSC CDRM=VTAMB
CASB     CDRSC CDRM=VTAMC

```

where VTAMB and VTAMC are the cross-domain resource manager names assigned to SYSB and SYSC, respectively. The same types of definitions are also needed for the CASs on SYSB and SYSC. That is, for the CAS on SYSB, you might create a member named CDRCASB that contains:

```

          VBUILD TYPE=CDRSC
CASA     CDRSC CDRM=VTAMA
CASC     CDRSC CDRM=VTAMC

```

For additional information about cross-domain resources, see the *VTAM Resource Definition Reference*.

Step 4: Updating the configuration list (CAS)

If, in step 2 or 3, you created new members in the SYS1.VTAMLST library, you must update the VTAM configuration list for each MVS image. This causes the new members to be automatically activated when VTAM starts.

To do this, add the new member names to the end of the configuration list in the appropriate ATCCONxx member of the SYS1.VTAMLST library. To find the suffix of the ATCCONxx member, do the following:

- Get the suffix of the COMMNDxx member from the CMD= parameter in the IEASYSxx member in SYS1.PARMLIB.

- Get the suffix of the ATCSTRxx member from the LIST= parameter on the command used to start VTAM in the COMMNDxx member in SYS1.PARMLIB, or (if you do not start VTAM from the COMMNDxx member) get the suffix from the LIST= parameter of the command that you use to start VTAM.
- Get the suffix of the ATCCONxx member from the CONFIG= parameter in the ATCSTRxx member in SYS1.VTAMLST.

To illustrate, the examples shown in steps 2 and 3 assume the creation of members named APPLCASA and CDRCASA. To add these members to the end of the configuration list in ATCCONxx, you would specify:

```
APPLCASA,                                x
CDRCASA
```

Note: If you added the CAS and cross-domain definitions to existing members, ATCCONxx should already contain these member names.

Step 5: Activating the major nodes (CAS)

You can activate the definitions created in steps 1 and 2 by either restarting VTAM for each system, or manually activating the definitions.

To manually activate a major node, you can issue the following commands, where name identifies a major node created (or modified) in steps 2 and 3:

- Deactivate the major node if it is currently active by issuing the command:

```
VARY NET,INACT,ID=name
```

- Activate (or reactivate) the major node by issuing the command:

```
VARY NET,ACT,ID=name
```

To ensure that the major node has been activated, issue the command:

```
D NET,ID=name
```

For example, to activate the member APPLCASA and then ensure that it has been activated, you would issue the commands:

```
VARY NET,INACT,ID=APPLCASA
VARY NET,ACT,ID=APPLCASA
D NET,ID=APPLCASA
```

To dynamically load a mode table that you have updated, issue the command:

```
F NET,TABLE,OPTION=LOAD,NEWTAB=name
```

If you do not do this after updating and relinking a mode table with a new logmode entry, the entry is unavailable until you have stopped and restarted VTAM. Note that you do not need to issue this command when you create a mode table with a single logmode entry.

The preceding steps need to be performed for each CAS you may be using.

Defining VTAM requirements (CMAS)

ACF/VTAM definitions are required to identify each CMAS used by CICSplex SM. This involves creating VTAM application definitions and, optionally, cross-domain resource management definitions.

Note: You may already have defined the VTAM requirements for a CAS (see “Defining VTAM requirements (CAS)” on page 289). The steps for defining the VTAM requirements for a CMAS are different.

To create VTAM application definitions and cross-domain resource management definitions for a CMAS, you must perform the following steps:

1. Create a VTAM application definition for each CMAS you will be using.
2. Define each CMAS as a cross-domain resource.
3. Add the application and cross-domain resource definitions to the VTAM configuration list.
4. Activate the definitions.

Notes:

1. Before you perform these steps, be sure to specify the size of the VTAM buffers.
 - For the VTAM-to-NCP connection, specify
MAXDATA ≥ 4096
 - For the NCP-to-VTAM connection, specify
MAXBFRU * IOBUF ≥ 4096
MAXBFRU * UNITSZ ≥ 4096
 - For the NCP-to-NCP connection, specify
TRANSFR * BFRS = RUSIZE ≥ 4096

The size specified should be 36 bytes less than the smallest MAXDATA value in any NCP through which the link may pass. The 36 bytes allow for the headers that are required for VTAM. For more information about the requirements for the VTAM-to-NCP connection, refer to the *VTAM Resource Definition Reference* manual for your level of VTAM. For more information about the requirements for the NCP-to-VTAM and the NCP-to-NCP connections, refer to the *NCP Resource Definition Reference* manual for your level of NCP.

If you need help determining or modifying your VTAM buffer specifications, confer with the VTAM system programmer at your enterprise.

2. Depending on your VTAM conventions, you may need to modify the procedures that are described in this section. Specifically:
 - Change references to the SYS1.VTAMLST library if you do not keep your definitions in the default VTAM list.
 - Modify the APPL and CDRSC statements if you want to add these statements to existing members, rather than create new ones.

Once CMAS is running, you can access CICSplex SM and define VTAM to CICSplex SM. (See “Setting the VTAM APPLID for a CMAS” on page 330.)

Step 1: Creating a VTAM application definition (CMAS)

To establish a VTAM application definition for a CMAS, either create a new member (*major node*) or access an existing member in the SYS1.VTAMLST library. Then add the following APPL statement:

```

name          VBUILD TYPE=APPL
              APPL ACBNAME=acbname,AUTH=(VPACE,ACQ,SPO,PASS),           x
              EAS=10,PARSESS=YES,SONSCIP=YES,APPC=NO,                 x
              VPACING=number
  
```

where:

name	Is a 1- to 8-character unique name.
acbname	Is the node name of this CMAS. This name must be unique within the domain. If you omit this parameter, the name of the VTAM APPL statement is used.
vpacing	Is the maximum number of normal-flow requests that another logical unit can send on an intersystem session before waiting to receive a pacing response. Start with a value of 5.

For example, to create a VTAM application definition for the CMAS on SYSA, you might create a member (APCMAS1) in the SYS1.VTAMLST library that contains the APPL statement:

```

          VBUILD TYPE=APPL
CMS1     APPL ACBNAME=CMS1,AUTH=(VPACE,ACQ,SPO,PASS),           x
          EAS=10,PARSESS=YES,SONSCIP=YES,APPC=NO,             x
          VPACING=5

```

The same type of definition is needed for each CMAS you use.

Step 2: Defining cross-domain resources (CMAS)

You should define cross-domain resources (CDRSCs) when:

- A CMAS that is to communicate with another CMAS cannot take advantage of adjacent CDRSCs.
- You want to minimize the overhead involved in using adjacent CDRSCs.

To establish a CDRSC definition, you must either create a new member or access an existing member in the SYS1.VTAMLST library. In the new or existing member, specify the following CDRSC statement for each CMAS that you want to communicate with:

```

          VBUILD TYPE=CDRSC
name     CDRSC CDRM=cdrm

```

where:

name Is the name you assigned to a CMAS in Step 1.

cdrm Is the name of the MVS image previously identified as the cross-domain resource manager (CDRM).

For example, to allow the CMAS on SYSA to communicate with the CMASs on SYSB and SYSC, you might create the member CDRCMS1, in the SYS1.VTAMLST library, which contains the CDRSC statements:

```

          VBUILD TYPE=CDRSC
CMS2     CDRSC CDRM=VTAMB
CMS3     CDRSC CDRM=VTAMC

```

where VTAMB and VTAMC are the cross-domain resource manager names that are assigned to SYSB and SYSC respectively.

The same types of definitions are also needed for the CMASs on SYSB and SYSC. That is, for the CMAS on SYSB, you could create a member (CDRCMS2), which contains the CDRSC statements:

```

          VBUILD TYPE=CDRSC
CMS1     CDRSC CDRM=VTAMA
CMS3     CDRSC CDRM=VTAMC

```

For additional information about cross-domain resources, see the *VTAM Resource Definition Reference* manual.

Step 3: Updating the configuration list (CMAS)

If, in Step 1 or 2, you created new members in the SYS1.VTAMLST library, you must update the VTAM configuration list for each MVS image. When VTAM starts, it automatically activates the new members.

To do this, add the new member names to the end of the configuration list in the appropriate ATCCONxx member of the SYS1.VTAMLST library. To find the suffix of the ATCCONxx member:

- Get the suffix of the COMMNDxx member from the CMD= parameter in the IEASYSxx member in SYS1.PARMLIB.
- Get the suffix of the ATCSTRxx member from the LIST= parameter on the command that is used to start VTAM in the COMMNDxx member in SYS1.PARMLIB. If you do not start VTAM from the COMMNDxx member, get the suffix from the LIST= parameter of the command that you use to start VTAM.
- Get the suffix of the ATCCONxx member from the CONFIG= parameter in the ATCSTRxx member in SYS1.VTAMLST.

To illustrate, the examples shown in Steps 1 and 2 assume that the members APCMAS1 and CDRCMS1 exist. To add these members to the end of the configuration list in ATCCONxx, you would specify:

```
APCMAS1,                               x  
CDRCMS1
```

Note: If you added the CMAS and cross-domain definitions to existing members, ATCCONxx should already contain these member names.

Step 4: Activating the major nodes (CMAS)

You can activate the definitions that are created in Steps 1 and 2 by either restarting VTAM for each system, or manually activating the definitions.

To manually activate a major node, you can issue the following commands, where name identifies a major mode that was created (or modified) in Steps 1 and 2:

- Deactivate the major node if it is currently active by issuing the command:

```
VARY NET,INACT,ID=name
```

- Activate (or reactivate) the major node by issuing the command:

```
VARY NET,ACT,ID=name
```

To ensure that the major node has been activated, issue the command:

```
D NET,ID=name
```

For example, to activate the member APCMAS1 and then ensure that it has been activated, you would issue the commands:

```
VARY NET,INACT,ID=APCMAS1  
VARY NET,ACT,ID=APCMAS1  
D NET,ID=APCMAS1
```

The preceding steps need to be performed for each CMAS you may be using.

Chapter 39. Generating post-installation members

A number of skeleton post-installation members are distributed with CICSplex SM. You can customize and generate these post-installation members.

When you do this, the members identified in Table 20 are produced. These members can be customized, using EYUISTAR, if you perform the actions described in this section.

Table 20. Post-installation members

Job	Use
EYUCAS	A sample JCL procedure that you can use to start a CAS, as described on page 315.
EYUCMAS	A sample JCL procedure that you can use to start a CMAS, as described on page 323.
EYUDEFDS	Sample JCL that you can use to create the data, screen, and parameter repositories. For additional information about creating a: <ul style="list-style-type: none">• Data repository, see page 299.• Screen and parameter repository, see page 299.
EYUDFHDS	Sample JCL that you can use to create the CICS region data sets for the CMAS region.
EYULPMOD	Sample JCL that you can use to apply SMP/E USERMODs that move MAS modules to the SEYULPA library.
EYUTSODS	A REXX EXEC, described on page 313, that you can use to invoke the TSO interface.

Members EYUCAS, EYUDEFDS, and EYUTSODS are used in setting up a CAS. Members EYUCMAS, EYUDFHDS, and EYUDEFDS (for the data repository), are used in setting up a CMAS. Skeleton member, EYULPMOD, is used in setting up a MAS.

To customize and then generate the post-installation members, use the job distributed in the member EYUISTAR of the CICSTS31.CPSM.SEYUINST library.

- Tailor the job in the EYUISTAR member of the CICSTS31.CPSM.SEYUINST library using the parameters identified in Table 21.

Use the SCOPE and ENVIRONMENT parameters to qualify the specific members that are to be generated. That is, use SCOPE to identify the type of members to be generated and ENVIRONMENT to indicate whether those members are to apply to a MAS-only environment or a CMAS environment. For additional information, see “EYUINST EXEC parameters” on page 375.
- Run the EYUISTAR job to produce the post-installation members. The resulting members, listed in Table 20, are stored in the library you specified on the LIB parameter of the EYUISTAR job. See “Sample JCL execution considerations” on page 382 for further information.

For detailed information about the EYUISTAR job, see Chapter 49, “Using the EYUINST EXEC to tailor skeleton jobs,” on page 373.

Table 21. CMAS- and MAS-related EYUINST EXEC parameters

Parameter	CMAS default value	MAS default value
CMASNAME	None	n/a
CINDEXnnn	None	n/a
CRELEASE	None	n/a
DEFVOL	sysprocdd	sysprocdd
DSINFO	index defvol defvol	n/a
ENVIRONMENT	None	None
EYUIPRM	dsinfo.EYUIPRM NEW	n/a
EYUSDEF	dsinfo.EYUSDEF NEW	n/a
GZONECSI	index.GLOBAL OLD smpvol smpvol	index.GLOBAL OLD smpvol smpvol
INDEX	sysprocdsn_levels	sysprocdsn_levels
JOB	//XXXXXXXX JOB	//XXXXXXXX JOB
LIB	sysprocdsn_levels.XEYUINST	sysprocdsn_levels.XEYUINST
OLDDREP	None	n/a
PREFIX	EYU	EYU
SCOPE	ALL	ALL
SELECT	None	None
SYSIDNT	None	n/a
TEMPLIB	sysprocdsn	sysprocdsn
TIMEZONE	None	n/a
TZONE	TZONE	TZONE
UTILITIES	ASMA90 IEWL GIMSMP	ASMA90 IEWL GIMSMP
WORKUNIT	SYSDA	SYSDA

Chapter 40. Creating and managing CICSplex SM data sets

This chapter describes the following:

- “CAS-related data sets”
- “Creating the CICSplex SM data repository”
- “Populating the CICSplex SM data repository” on page 302
- “Converting the CICSplex SM data repository” on page 302
- “Expanding the CICSplex SM data repository” on page 304
- “Taking backups of the CICSplex SM data repository” on page 304

You can use the post-installation job EYUDEFDS to create the CICSplex SM data sets. The EYUDEFDS job is generated when you run the EYUISTAR job, as described in Chapter 39, “Generating post-installation members,” on page 297. The job is stored in the library you specified on the LIB parameter of the EYUISTAR job.

CAS-related data sets

The CAS-related data sets, which may be shared by multiple CASs, are:

- A screen repository. This optional data set contains the screen configuration definitions created by individuals using CICSplex SM. If you do not create this data set, users will not be able to save their CICSplex SM screen configurations. (For additional information about creating and using screen configurations, see the *CICSplex System Manager User Interface Guide*.)
- A parameter repository data set. This required data set contains communications definitions used by the CAS. (See the *CICSplex System Manager Administration* manual for information about creating and maintaining these definitions.)

The EYUDEFDS job includes the following steps related to the CAS data sets:

- SDEFDEL, which deletes any existing screen repository data set having the same name, and SDEFALOC, which creates a new one. These steps are generated only when you specify a disposition of NEW with the EYUSDEF parameter of the EYUISTAR job. If you specified OLD with the EYUSDEF parameter, the existing screen repository data set is referenced by the EYUCAS procedure.
- IPRMDEL, which deletes any existing parameter repository data set having the same name, and IPRMALOC, which creates a new one. These steps are generated only when you specify a disposition of NEW with the EYUIPRM parameter of the EYUISTAR job. If you specified OLD with the EYUIPRM parameter, the existing parameter repository data set is referenced by the EYUCAS procedure.

Creating the CICSplex SM data repository

The CMAS-related data set is the data repository. Each CMAS must have a unique data repository associated with it. The data repository contains the CICSplex SM administration definitions applicable to its associated CMAS.

Note: The data repository is a critical component of CICSplex SM system management. It is imperative that you take regular backups that are associated with each CMAS in your environment.

It is defined to CICS as being a recoverable file which participates in SYNCPOINT and SYNCPOINT ROLLBACK operations. The CMAS must have a CICS system log in order for these operations to operate correctly. Do not, therefore, run a CMAS with a system log that is defined as type DUMMY as this would compromise data integrity on the CICSplex SM data repository.

To create the data set that contains the data repository, you can use the post-installation job EYUDEFDS.

If you will be running multiple CMASs in the same MVS image, you must create a data repository for each CMAS. You can edit and resubmit the EYUISTAR job (as described in Chapter 49, “Using the EYUINST EXEC to tailor skeleton jobs,” on page 373), which generates the EYUDEFDS post-installation job. You may want to use the SELECT parameter to generate *only* the EYUDEFDS post-installation job. Once this job exists, you can edit it to make sure that the names specified with the SYSIDNT and CMASNAME parameters are unique each time you run the job.

Note: If you have already run the EYUDEFDS job (when creating the CAS data sets), be sure to delete the following steps before you rerun EYUDEFDS:

- SDEFDEL
- SDEFALOC
- IPRMDEL
- IPRMALOC

These steps create new screen and parameter repositories, deleting those already in existence. For more information about creating the screen and parameter repository data sets, see “CAS-related data sets” on page 299.

The EYUDEFDS job includes the following steps related to the creation of the data repository:

DREPALOC

This step allocates the VSAM KSDS cluster for the data repository data set:

```
dsindex.EYUDREP.cmasname
```

where:

dsindex

Is defined by the DSINFO parameter of the EYUISTAR job.

cmasname

Is defined by the CMASNAME parameter of the EYUISTAR job.

Note: CICSplex SM does not support VSAM records that span control intervals. Make sure that the IDCAMS job that you use to create a CICSplex SM data repository does not specify the SPANNED parameter. You should accept the IDCAMS default of nonspanned records.

DREPINIT or DREPCNVT

One of these two steps is used to setup the data repository for a CICS Transaction Server for z/OS, Version 3 Release 1 CMAS. The step that is generated in job EYUDEFDS depends on the OLDDREP parameter you specified when you ran the EYUISTAR job.

Step DREPINIT is generated if you did not specify a value with the OLDDREP parameter. This step executes EYU9XDUT to initialize the new data repository that was allocated by step DREPALOC. The new data

repository does not contain any records from a previous version of CICSplex SM. The EYU9XDUT utility uses the following parameters for step DREPINIT:

CMASNAME=xxxxxxx

where:

- You cannot change this name after the data repository is initialized.
- This name must be unique within the CICSplex SM environment. It should not be the same as the name of another CMAS, a CICSplex, a CICS system, or a CICS system group.
- Position 1 must be alphabetic or national, and cannot be numeric.
- Positions 2 through 8 can be alphabetic, national, or numeric.

SYSID=xxxx

where:

- You cannot change this identifier after the data repository is initialized.
- This value must match the SYSIDNT (SIT parameter) for the CMAS; see “CMAS-related CICS SIT parameters” on page 326.
- This value must not be the same as the SYSID for any other CMAS or CICS system that is defined to CICSplex SM.
- Positions 1 through 4 can be alphabetic, national, or numeric.

TIMEZONE=x

where x must be a single alphabetic character (B through Z), representing one of the Greenwich time zone codes (see *CICSplex System Manager Administration*)

ZONEOFFSET=nn

where nn must be a two-digit numeric value (00 through 59), representing an adjustment (offset) to the TIMEZONE.

DAYLIGHT=x

where x must be a single character (Y or N), representing daylight saving time.

For information about defining the TIMEZONE, ZONEOFFSET, and DAYLIGHT parameters, see *CICSplex System Manager Administration*.

Step DREPCNVT is generated if you specified the name of an existing data repository on the OLDDREP parameter. This step executes EYU9XDUT to convert existing data repository records from a previous release of CICSplex SM for use by CICSplex SM for CICS Transaction Server for z/OS, Version 3 Release 1. All the records from the input data repository specified on the OLDDREP parameter are added to the new data repository that was allocated by step DREPALLOC. The input data repository is not modified. The EYU9XDUT utility uses the following parameter for step DREPCNVT:

TARGETVER=0310

where 0310 represents the version of the new output data repository.

Populating the CICSplex SM data repository

You can use the CICSplex SM-supplied extract routine EYU9BCSD to generate CICSplex SM resource definition records for each CSD record identified in your input file.

The output from EYU9BCSD is used to populate the data repository.

For more information about EYU9BCSD see *CICSplex System Manager Managing Business Applications*.

Converting the CICSplex SM data repository

You can run the EYU9XDUT utility to convert the CICSplex SM data repository from any release of CICSplex SM to this release, and back again. That is, you can upgrade the data repository to the current release of CICSplex SM, and you can convert it back to a previous release. For example, after you have upgraded to CICSplex SM for CICS Transaction Server for z/OS, Version 3 Release 1, you can convert the data repository back to CICSplex SM for CICS Transaction Server for z/OS Release 2.3 for use with a CMAS running the that level of CICSplex SM code.

The conversion is controlled by the TARGETVER parameter and the DD statements
you use to execute EYU9XDUT. To convert between a previous release and
CICSplex SM for CICS Transaction Server for z/OS, Version 3 Release 1 requires
the EYUDREP, NEWREP, and BYPASS DD statements in the JCL. The EYUDREP
statement must reference an existing input data repository, and the NEWREP
statement must reference the output data repository.

CRESxxxx is a CICSplex SM Topology Manager object that describes instances of
a resource within a CICS system. All CRESxxxx resource table objects are deleted
during the conversion process. These deleted records are rebuilt the first time the
MAS connects or joins to the CMAS. The following message is then output to the
SYSPRINT DD statement with a count of how many records were not converted:
EYUXD0708I CRESxxxx Resource Table nnnnn records not converted

EYU9XDUT Return codes:

0 execution completed normally. This return code is accompanied by message:
EYUXD0702I Repository successfully converted

indicating the repository was successfully converted. This message may also be
preceded by the message:
EYUXD0708I CRESxxxx Resource Table nnnnn records not converted

4 some records could not be converted. This return code is accompanied by
message:
EYUXD0706W DDNAME NEWREP nnnnn records were bypassed

indicating the repository was successfully converted but some records were
bypassed and not written to the new repository. These records are written to the
BYPASS DD statement. This message can also be preceded by message:
EYUXD0708I CRESxxxx Resource Table nnnnn records not converted

8 EYU9XDUT has failed. Check the joblog for error messages that indicate the
 # cause of the error. For example, DD statement missing, or invalid NEWREP
 # dataset.

Note: Shutdown the CMAS that is using EYUDREP before running EYU9XDUT, otherwise, X'A8' is returned when the dataset is opened.

Use JCL similar to that in Figure 51 to convert from Release 2 of CICSplex SM to CICSplex SM for CICS Transaction Server for z/OS, Version 3 Release 1. This sample JCL assumes that you have already allocated the VSAM cluster that is referenced by the NEWREP DD statement. The file identified by the NEWREP DD statement must be an empty file.

```
# //DREPCNVT EXEC PGM=EYU9XDUT,
# //          PARM=(' TARGETVER=0310' )
# //STEPLIB DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUAUTH
# //EYUDREP DD DISP=SHR,DSN=CPSM310.EYUDREP.cmasname
# //NEWREP DD DISP=OLD,DSN=CICSTS31.CPSM.EYUDREP.cmasname
# //BYPASS DD SYSOUT=*
# //SYSPRINT DD SYSOUT=*
```

Figure 51. Example JCL to run EYU9XDUT

In the JCL, use a value for TARGETVER that indicates the release you are converting to. For example:

To convert to..	Use:
Release 3	TARGETVER=0130
CICSplex SM for CICS TS Release 3	TARGETVER=0140
CICSplex SM for CICS Transaction Server for z/OS Release 2.1	TARGETVER=0210
CICSplex SM for CICS Transaction Server for z/OS Release 2.2	TARGETVER=0220
CICSplex SM for CICS Transaction Server for z/OS Release 2.3	TARGETVER=0230
CICSplex SM for CICS Transaction Server for z/OS Release 3.1	TARGETVER=0310

When the data repository is updated from a previous release to the current release, information stored in the earlier version is carried over to the current version of the data repository. When the data repository reverts back from the current release to a previous release, and the record in which information is changed is identical in both releases, the changes are carried back to the earlier version. Likewise, if a field in a record exists in both releases, later changes to the information in a field are carried back to the earlier version. However, when the data repository is converted from the current release to a previous release and either the record or a field in it did not exist in the previous release, the information contained in the later version is permanently lost.

(For more information about the data repository, see “Creating the CICSplex SM data repository” on page 299 and “Expanding the CICSplex SM data repository” on page 304.)

Expanding the CICSplex SM data repository

The CICSplex SM data repository may fill up and require expansion. To expand the CICSplex SM data repository, use the IDCAMS utility REPRO function. An example of the JCL to do this is in member EYUJXDRP of the CICSTS31.CPSM.SEYUSAMP library.

In that JCL, on the RECORDS(xx,yy) statement. You should specify a primary (xx) and a secondary (yy) value that are appropriate for your environment. The initial values are 500 and 3000.

Taking backups of the CICSplex SM data repository

The CICSplex SM data repository is defined to CICS as a VSAM file called EYUDREP. As the data set is accessed via CICS File Control, all the normal CICS methods of taking backups of VSAM data sets for disaster recovery purposes are available for use with the data repository.

You may use the following techniques for taking copies of the data repository, and for restoring the data repository after a data set failure.

- Use HSM, or DSS, or other utilities to take copies while the associated CMAS is not running, possibly using the Concurrent Copy technique to reduce the time during which the repository must be unavailable.
- Use HSM or DSS to take copies while the associated CMAS is running using the Backup While Open technique, and possibly also using the Concurrent Copy technique, which improves the ease of use of Backup While Open. This requires a forward recovery log (see “Defining a forward recovery log for the data repository”).
- Use HSM or DSS to restore the data set after a data set failure.
- Use a Forward Recovery product, such as CICS VSAM Recovery (CICS/VR), to reapply updates that were made to the data set after the most recent copy was taken. This requires a forward recovery log.
- Use remote site recovery techniques if you need an up-to-date copy of the data set at a remote site for disaster recovery purposes. This requires a forward recovery log.

The *CICS Recovery and Restart Guide* provides information on all the terms referred to above. In particular, it provides information about forward recovery logs, forward recovery, the CICS/VR product, Backup While Open, Concurrent Copy and its associated hardware prerequisites, taking back ups of data sets, restoring data sets from backup copies, and remote site recovery.

Defining a forward recovery log for the data repository

The data repository is defined in the CMAS as a VSAM file called EYUDREP. CICSplex SM provides a default definition that defines this file as not having an associated forward recovery log, and therefore as not being eligible for forward recovery.

If you use forward recovery, you require a journal logstream. Defining CICS log
streams is described in the *CICS System Definition Guide*, and setting up a journal
logstream is described in the *CICS System Definition Guide*.

If you wish to use Forward Recovery, Backup While Open, or Remote Site Recovery, you will need to change the definition of EYUDREP. You will need to specify the following keywords on the definition of EYUDREP to define it as having a forward recovery log:

```
RECOVERY(ALL)
FWDRECOVLOG(nn)
```

where *nn* is a number between 1 and 99.

The default definition of EYUDREP also does not define the repository as being eligible for Backup While Open. To make the repository eligible for Backup While Open, you should specify the following keywords:

```
RECOVERY(ALL)
FWDRECOVLOG(nn)
BACKUPTYPE(DYNAMIC)
```

where *nn* is a number between 1 and 99.

The RECOVERY, FWDRECOVLOG, and BACKUPTYPE parameters of DEFINE FILE are described fully in the *CICS Resource Definition Guide*.

Notes:

1. You should not change any keywords on the EYUDREP definition other than RECOVERY, FWDRECOVLOG and BACKUPTYPE. In addition, you must never set RECOVERY(NONE). Setting RECOVERY(NONE) would cause repository corruption after transaction or CMAS failures.
2. You should not change the recovery options of the EYUDREPN FILE definition. This definition is used when CPSM determines that Data Repository file operations do not require logging. It is normal to receive LSR pool messages for EYUDREPN during CMAS initialization and you should ignore them. There should be no DD statement in the CICS JCL for EYUDREPN and EYUDREPN should not be associated with a data set name.
3. If CPSM Data Repository initialization fails (as reported by message EUIXD0105E) and the cause is due to the EYUDREP data set requiring Batch Backout (for example CICS issues message DFHFC0921), you must recover the EYUDREP data set and then delete and redefine the CMAS Local and Global catalogs in order to reset the CICS backout required status for the data set.
4. Requesting Backup While Open for the CICSplex SM data repository data set via the IDCAMS DEFINE CLUSTER definition within the ICF catalog is not supported.

Chapter 41. Upgrading the CSD and macro definitions

Appropriate resource definitions must be added to the CICS tables and the CICS system definition (CSD) file for each CMAS and MAS you are using.

This chapter describes the following:

- “Creating CICS resource definition tables for CMASs”
- “Updating the CSD files using DFHCSDUP (CMAS)”
- “Journalmodel considerations in a CICS TS z/OS CMAS” on page 308
- “Considerations when upgrading the CSD release (CMAS)” on page 309
- “Considerations when sharing the CSD (CMAS)” on page 309
- “Updating CICS resource definition tables for MASs” on page 310
- “Updating CSD files using DFHCSDUP (MVS MAS)” on page 311
- “Considerations when upgrading the CSD release (MVS MAS)” on page 312
- “Considerations when sharing the CSD (MVS MAS)” on page 312

Creating CICS resource definition tables for CMASs

For each CMAS, you must create resource definition table load modules that are required to run a CMAS. Assemble and link-edit the tables with the CICS procedures for installing resource definition table load modules. The tables need to be link edited into a user-supplied load library, which needs to be specified in the DFHRPL concatenation. Library CICSTS31.CPSM.SEYUSAMP must be included in the SYSLIB concatenation for the Assembler step of the procedure used to assemble and link-edit the CICS tables.

These tables do not need modification for CICSplex SM to function properly.

Note: CICS used to supply sample PLT and SRT tables. APARs modified releases
CICS TS 1.3, CICS TS 2.2 and CICS TS 2.3 so that they no longer need
either a PLTPI program or a special system recovery table.

CICS TS 3.1 does not supply sample PLT and SRT tables.
• Instead of a PLT, specify CPSMCONN=CMAS
• For the SRT specify the default SRT=1\$.

Updating the CSD files using DFHCSDUP (CMAS)

The resource definitions you must add to the CSD file for each CICS CMAS are
distributed in the EYU964G0 modules of the CICSTS31.CPSM.SEYULOAD library,
where nn represents the CICS level.

Sample JCL that you can use to include the definitions is in the member EYUJCLG0 in the CICSTS31.CPSM.SEYUSAMP library. You can edit this JCL, as in Figure 52 on page 308, to:

1. Define the CMAS group of resource definitions to the appropriate CSD file.
2. Add the CMAS group list to the CSD.

```

//CSDUP EXEC PGM=DFHCSDUP
//STEPLIB DD DSN=cics.index.SDFHLOAD,DISP=SHR
// DD DSN=cpsm.index.SEYULOAD,DISP=SHR
//DFHCSD DD DSN=cics.dfhcscd,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
UPGRADE USING(group_load_module)
/*

```

Figure 52. Sample JCL to run DFHCSDUP

Modify the sample JCL to provide the following information:

STEPLIB	Identify: <ul style="list-style-type: none"> • cics.index.SDFHLOAD as the CICS load library that contains the DFHCSDUP module • cpsm.index.SEYULOAD as the CICSplex SM load library that contains the definition modules.
DFHCSD	Identify cics.dfhcscd as the CICS CSD file to be updated.
SYSIN	You must identify the load module (EYU9nnG0) that contains the resource definitions group that is required to run the CMAS (EYU310G0).

A return code of 4 is expected from this run of DFHCSDUP. This is because, before adding the designated group to the CSD, the job attempts to delete any group with the same name.

Note: You should not normally run user transactions in a CMAS. However, if you do choose to define your own transactions to the CMAS, you should be aware that transaction IDs used by CICSplex SM in the CMAS have no specific format. To avoid conflict between your names and those that are used by CICSplex SM, you should review the transactions that are defined in the CSD group EYU310G0. For a list of these transactions, see the *CICS RACF Security Guide*.

Journalmodel considerations in a CICS TS z/OS CMAS

The CMAS grouplists for CICS Transaction Server for z/OS include the CICS-supplied group, DFHLGMOD. If the log stream names used by the DFHLGMOD group are not appropriate for your environment, copy group DFHLGMOD to a new group, where you can make your amendments. Finally, add the new group to the CMAS grouplist.

See Chapter 24, “Defining the logger environment for CICS journaling,” on page 143 for details on how to define log streams.

Note: Do not operate the CMAS with log streams that are defined as DUMMY. This may cause problems when recovering the CSD or CICSplex SM data repository (EYUDREP).

See Chapter 51, “CMAS journaling,” on page 397 for details about the various CMAS journaling options that you can activate.

Considerations when upgrading the CSD release (CMAS)

When the CSD is upgraded to a new CICS release, you must install the CICSplex SM group definitions for the new release into the upgraded CSD. For example, when the CSD is upgraded to CICS Transaction Server for z/OS, use the following SYSIN to install the CICSplex SM CMAS resource definitions for CICS Transaction Server for z/OS Release 3.1.

```
//SYSIN DD *
  UPGRADE USING(EYU964G0)
/*
```

For information about the resource group definitions that are distributed with CICSplex SM, see “Updating the CSD files using DFHCSDUP (CMAS)” on page 307.

Considerations when sharing the CSD (CMAS)

Before the CSD can be shared by multiple releases of CICS, the CSD must be upgraded by installing the CICSplex SM resource definitions for the current CICS release. For information about doing so, see “Considerations when upgrading the CSD release (CMAS).”

If you are running a CMAS under a previous release of CICS that is accessing resource definitions in a CSD that has been upgraded to the current CICS release, you must update the CMAS group list. Because the CMAS group list definitions are secured against updates, you must create a copy of the CMAS group list and update the copy.

For example, to run DFHCSDUP to create a copy of the CMAS group list and add the CICS compatibility groups (DFHCOMP4, DFHCOMP5, DFHCOMP6, DFHCOMP7, DFHCOMP8, DFHCOMP9, and DFHCOMP9A) that are required for a CICS/ESA 4.1 CMAS to access resource definitions in a CICS Transaction Server for z/OS Release 3.1 CMAS; use the following SYSIN control statements:

```
//SYSIN DD *
  UPGRADE USING(EYU964G0)
  APPEND LIST(EYU310L0) TO(EYUE41L0)
  ADD GROUP(DFHCOMP9A) LIST(EYUE41L0)
  ADD GROUP(DFHCOMP9) LIST(EYUE41L0)
  ADD GROUP(DFHCOMP8) LIST(EYUE41L0)
  ADD GROUP(DFHCOMP7) LIST(EYUE41L0)
  ADD GROUP(DFHCOMP6) LIST(EYUE41L0)
  ADD GROUP(DFHCOMP5) LIST(EYUE41L0)
  ADD GROUP(DFHCOMP4) LIST(EYUE41L0)
/*
```

Figure 53. Sample JCL to update CMAS group list

The control statements in Figure 53 perform the following functions:

UPGRADE USING(EYU964G0)

Replaces the previous CICS/ESA, CICS TS for OS/390 or CICS Transaction Server for z/OS release CMAS group definitions with CICS Transaction Server for z/OS Release 3.1 group definitions. The CICS Transaction Server for z/OS Release 3.1 group definitions can be used to run a CICS/ESA 4.1, CICS TS for OS/390 or a CICS Transaction Server for z/OS Version 2 CMAS.

APPEND LIST(EYU310L0) TO(EYUE41L0)

Creates the unprotected copy of list EYU310L0.

ADD GROUP(DFHCOMP A) LIST(EYUE41L0)

Adds CICS Transaction Server for z/OS Release 2.2 compatibility group DFHCOMP A to the list EYUE41L0.

ADD GROUP(DFHCOMP9) LIST(EYUE41L0)

Adds CICS TS for OS/390 Release 3 compatibility group DFHCOMP9 to the list EYUE41L0.

ADD GROUP(DFHCOMP8) LIST(EYUE41L0)

Adds CICS TS for OS/390 Release 3 compatibility group DFHCOMP8 to the list EYUE41L0.

ADD GROUP(DFHCOMP7) LIST(EYUE41L0)

Adds CICS TS for OS/390 Release 2 compatibility group DFHCOMP7 to the list EYUE41L0.

ADD GROUP(DFHCOMP6) LIST(EYUE41L0)

Adds CICS TS for OS/390 Release 1 compatibility group DFHCOMP6 to the list EYUE41L0.

ADD GROUP(DFHCOMP5) LIST(EYUE41L0)

Adds CICS/ESA 4.1 compatibility group DFHCOMP5 to the list EYUE41L0.

This JCL completes with a return code of 04 when group or list that is referenced by the UPGRADE statements is installed for the first time. This occurs because the processing of the UPGRADE statements attempts to delete list EYU310L0 and group EYU310G0 before these resources are defined.

After this job is completed successfully, you can start a CICS/ESA 4.1 CMAS by referencing group list EYUE41L0; you can start a CICS TS for OS/390 Release 3 CMAS by referencing group list EYU310L0.

To start a CICS Transaction Server for z/OS Release 2.3CMAS, you can define an additional group list in a CICS TS for OS/390 CSD. Such a group list will include CICS compatibility group DFHCOMP8.

To start a CICS/ESA 4.1 CMAS, you can define an additional group list in a CICS TS for OS/390 CSD. Such a group list will include CICS compatibility groups DFHCOMP A, DFHCOMP9, DFHCOMP8, DFHCOMP7, DFHCOMP6, and DFHCOMP5, in that order.

For more information about upgrading the CICS CSD with compatibility group definitions, see the “Sharing the CSD between different releases of CICS” topic in the *CICS Transaction Server for z/OS Migration from CICS TS Version 2.3 Guide*,

Updating CICS resource definition tables for MASs

For each MAS, some of your CICS resource definition tables must be updated to reference the CICSplex SM copy books that contain entries for those control tables. When you have updated the tables for each MAS, assemble and link-edit them using the CICS procedures for maintaining resource definition table load modules.

The process used to assemble and link-edit the CICS resource definition table load modules must have library CICSTS31.CPSM.SEYUSAMP in the SYSLIB

concatenation of the assembler step, or the copy book member must be inserted into the table source member in place of the COPY statement.

Updating CSD files using DFHCSDUP (MVS MAS)

The resource definitions you must add to the CSD file for each managed CICS system are distributed in CSD upgrade load modules in CICSTS31.CPSM.SEYULOAD.

The names of the load modules, the environment for which they are used, and the name of the resource group (created using the definitions the load modules contain) are:

Load module	EYU9nnG1, where nn represents the CICS level (for example, 63 refers to the CICS element in CICS TS for z/OS Version 2.3, and 64 refers to the CICS element in CICS TS for z/OS Version 3.1).
Environment	MAS - USELAPCOPY(NO)
Resource group	EYU310G1

Sample JCL that you can use to include the definitions is supplied in the member EYUJCLGN in the CICSTS31.CPSM.SEYUSAMP library. You can edit this JCL, as shown in Figure 54, to:

1. Define a group of resource definitions to the appropriate CSD file.
2. Add the group name to the CSD list referenced by the CICS system initialization table (SIT) parameter GRPLIST.

```
//CSDUP EXEC PGM=DFHCSDUP
//STEPLIB DD DSN=cics.index.SDFHLOAD,DISP=SHR
// DD DSN=cpsm.index.SEYULOAD,DISP=SHR
//DFHCSD DD DSN=cics.dfhcsd,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSIN DD *
UPGRADE USING(group_load_module)
ADD GROUP(EYU310G1) LIST(list_name)
/*
```

Figure 54. Sample JCL to run DFHCSDUP for MVS MAS

Modify the sample JCL to provide the following information:

STEPLIB

Identify:

- cics.index.SDFHLOAD as the CICS load library containing the DFHCSDUP module
- cpsm.index.SEYULOAD as the CICSplex SM load library containing the group definition module.

DFHCSD Identify cics.dfhcsd as the CICS CSD file to be updated.

SYSIN Identify:

- The load module containing the resource definition group
- The group name contained within the load module
- The group list used to start the MAS.

To avoid your transaction names clashing with those used by CICSplex SM, you should review the names of the transactions defined in the appropriate EYU310Gn group in the CSD. The CICSplex SM MAS transaction names are all of the form COxx.

A return code of 4 is expected from this run of DFHCSDUP. This is because, before adding the designated group to the CSD, the job attempts to delete any group with the same name.

To run the MAS using an USELPACOPY(YES) group, the appropriate load modules must be moved to the SYS1.CICSTS31.CPSM.SEYULPA data set. For additional information, see “Using CICSplex SM modules in the MVS link pack area” on page 286.

Considerations when upgrading the CSD release (MVS MAS)

When the CSD is upgraded to a new CICS release, you must install the CICSplex SM group definitions for the new release into the upgraded CSD. For example, when the CSD is upgraded from CICS/ESA 4.1 to the CICS Transaction Server for z/OS, use the following SYSIN statement to install the CICSplex SM local MAS resource definitions for the CICS Transaction Server for z/OS 3.1:

```
//SYSIN DD *  
  UPGRADE USING(EYU964G1)  
/*
```

For information about the resource group definitions distributed with CICSplex SM, see “Updating CSD files using DFHCSDUP (MVS MAS)” on page 311.

Considerations when sharing the CSD (MVS MAS)

Before the CSD can be shared by multiple releases of CICS, the CSD must be upgraded by installing the CICSplex SM resource definitions for the current CICS release. For information about doing so, see “Considerations when upgrading the CSD release (MVS MAS).”

Chapter 42. Preparing user access to CICSplex SM

To permit users to select CICSplex SM as an application from an ISPF menu:

1. If your enterprise uses an external security manager (ESM), which contains a list of TSO command processors that can be executed by users, include the following names in the table:
 - BBM3API
 - BBM9TC20
 - BBM9TC23
2. Insert the following line in the existing list of menu options on one or more of the ISPF menu panels defined as members in the ISPLLIB library:

```
id,'PANEL(EYUDEZZZ) NEWAPPL(EYUD) PASSLIB'
```

where *id* is any appropriate, unique menu option id, such as CP.

3. Add the following libraries to the signon procedure for each individual who might access CICSplex SM during a TSO session:

DD name	Data set name
BBILINK	CICSTS31.CPSM.SEYUAUTH
BBSDEF	CICSTS31.CPSM.EYUSDEF
ISPLLIB	CICSTS31.CPSM.SEYUAUTH
ISPMLIB	CICSTS31.CPSM.SEYUMLIB
ISPLLIB	CICSTS31.CPSM.SEYUPLIB
ISPTLIB	CICSTS31.CPSM.SEYUTLIB

These library names should be placed after the user's data set names and before any other system data set names.

If you are creating a new screen repository, you must run job EYUDEFDS before adding the CICSTS31.CPSM.EYUSDEF data set to a TSO session.

You can also access CICSplex SM by running a REXX EXEC from within ISPF. A sample EXEC, called EYUTSODS, is generated when you run the EYUISTAR job, as described in Chapter 39, "Generating post-installation members," on page 297. EYUTSODS is stored in the library you specified on the LIB parameter of the EYUISTAR job.

The EYUTSODS EXEC performs the following functions:

- Allocates the required CICSplex SM data sets to a user's TSO session. The data sets are concatenated ahead of any data sets already allocated to the referenced DD name.
- Invokes the CICSplex SM ISPF end-user interface via the command:

```
ISPEXEC SELECT PANEL(EYUDEZZZ) NEWAPPL(EYUD) PASSLIB
```
- Restores the original allocation when the user exits CICSplex SM.

Chapter 43. Setting up a coordinating address space (CAS)

This chapter describes the steps you must perform in order to make a coordinating address space (CAS) operational. These steps consist of:

- “Preparing to start a CAS”
- “Setting the CAS system communication information” on page 318
- “Preparing to stop a CAS” on page 318.

For a summary of the CAS setup tasks that you can refer to while performing them, see Chapter 36, “CICSplex SM setup checklist and worksheets,” on page 271.

If you are converting your CICSplex SM system or systems from a previous release to CICSplex SM for CICS Transaction Server for z/OS, Version 3 Release 1, you should read the *CICS Transaction Server for z/OS Migration from CICS TS Version 2.3*.

For details on applying corrective or preventive maintenance to CICSplex SM, see Chapter 48, “Applying service to CICSplex SM,” on page 371.

Preparing to start a CAS

There are several ways you can start a CAS. You can start a CAS:

- At MVS IPL time.

This is the recommended method for starting a CAS. To use this method:

- Verify that the CAS startup procedure is in a system procedure library, such as SYS1.PROCLIB.
- Verify that the CAS startup procedure is in the 'Started Tasks' table of the external security manager (ESM).
- Include the START command, as described on page 316, in the COMMNDaa member of SYS1.PARMLIB that contains the automatic operator commands.

- From the system console.

To start a CAS from the system console:

- Verify that the CAS startup procedure is in a system procedure library, such as SYS1.PROCLIB.
- Verify that the CAS startup procedure is in the 'Started Tasks' table of the external security manager (ESM).
- Have the operator issue the START command, as described on page 316.

- As a batch job.

To start a CAS as a batch job:

- Verify that the CAS startup procedure is in a system procedure library, such as SYS1.PROCLIB.
- Construct a job stream to invoke the CAS procedure.
- Submit the job to invoke a CAS.

A sample procedure that you can use to start a CAS is supplied in the member EYUCAS and is illustrated in Figure 55 on page 316. This member was generated when you ran the EYUISTAR job, as described in Chapter 39, “Generating post-installation members,” on page 297. The member is stored in the library you specified on the LIB parameter of the EYUISTAR job.

```

//EYUCAS  PROC SSID=CPSM,           MVS/ESA Subsystem ID
//          XDM=N,                 Extended diagnostic mode
//          SPCF=N,CONVXCF=N,      SysPlex Coupling Facility
//          COLD=N,                Cold start option
//          DUMP=ALL                Capture all dumps
//*
//CPSMCAS EXEC PGM=BBM9ZA00,
//          PARM=('SSID=&SSID,XDM=&XDM,SPCF=&SPCF,CONVXCF=&CONVXCF'
//              'COLD=&COLD,DUMP=&DUMP'),
//          TIME=1440,
//          REGION=4096K
//*
//STEPLIB DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUAUTH
//BACTDEF DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUDEF
//BBVDEF  DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUDEF
//BBIPARM DD DISP=SHR,DSN=CICSTS31.CPSM.EYUIPRM
//BBSECURE DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUPARM
//*

```

Figure 55. A sample CAS startup job stream

EXEC statement

- Identifies the program that performs basic initialization tasks (PGM=BBM9ZA00).
- Provides unlimited processing time for the CAS (TIME=1440).
- Designates the size of the private region required by the CAS (REGION=4096K). Do not define a region smaller than 4096K.

STEPLIB DD statement

Identifies the CICSTS31.CPSM.SEYUAUTH authorized load library.

BACTDEF DD statement

Defines the library that contains the SMP-installed CICSplex SM action and view tables, that are shared by multiple systems.

BBVDEF DD statement

Defines the library that contains all SMP-installed CICSplex SM views. A CAS is responsible for retrieving the views associated with PlexManager.

BBIPARM DD statement

Defines the library that contains the cross-system definitions created by CICSplex SM users.

BBSECURE DD statement

Defines the library that contains member BBMTSS00, which contains overrides to the CICSplex SM global security parameters. See the *CICS RACF Security Guide*.

START command for a CAS

The syntax of the command you can use to start a CAS is:

```

START procname [,SSID=ssid] [,XDM=Y|N] [,SPCF=Y|N] [,CONVXCF=Y|N]
               [,COLD=Y|N] [,DUMP=Y|N|ALL]

```

where:

procname

Is the 1- to 8-character name of the procedure. (EYUCAS is the name of the distributed sample procedure.)

SSID=ssid

Identifies the 4-character name that uniquely identifies the CAS subsystem. Please note that:

1. Subsystem names must be unique within the MVS image.
2. Subsystems are created without being predefined.

The distributed sample startup JCL uses CPSM as the default subsystem identifier. (EYUX is used as the subsystem identifier for the Environment Services System Services (ESSS) and, therefore, cannot be used as a CAS subsystem ID.)

Make sure that you use this subsystem ID with the CASNAME parameter, described on page “CASNAME(name)” on page 386.

If your enterprise has more than one CAS, make sure your TSO users know the subsystem ID of each CAS. In the Subsystem ID field on the Session Control Parameters panel, they can specify a different CAS than the one they first connect to. (The Session Control Parameters panel is described in the *CICSplex System Manager User Interface Guide*)

XDM=Y|N

Indicates whether the CAS should execute in extended diagnostic mode (XDM).

XDM, which is described in the *CICSplex System Manager Problem Determination* manual, should be activated only when requested by IBM Support Personnel. Specifying XDM=Y disables certain error recovery mechanisms and issues extensive diagnostic messages to the console.

SPCF=Y|N

Indicates whether the sysplex coupling facility (SPCF) should be initialized.

CONVXCF=Y|N

Indicates whether XCF Conversations are to be allocated for CAS-to-CAS connections. If CONVXCF=Y is specified in the startup command for all CASes in a sysplex, it is not necessary to provide a VTAM applid for each CAS in its CASDEF record. If CONVXCF=Y is specified SPCF=Y must also be specified.

COLD=Y|N

Indicates whether the CAS should be cold started.

When the CAS is initialized, several control blocks are built in common storage. Most of these blocks are freed when the CAS terminates. However, some blocks (with a total of less than 4KB of CSA) are retained to permit the reuse of previously allocated system resources—in particular, MVS system linkage indexes (LXs).

When you reinitialize the CAS with COLD=N, the control blocks from the preceding invocation of the CAS are used—rather than building new ones—and, thus, do not consume additional common storage or valuable LXs. By contrast, COLD=Y causes new control blocks to be built. This means that all previously built control blocks continue to occupy common storage until the system is IPLed.

Specify COLD=Y only when requested to do so by IBM Support Personnel in an attempt to clear an error condition.

DUMP=Y|N|ALL

Indicates whether system dumps (SDUMPs) are to be taken when the CAS subsystem recovery manager intercepts an unexpected abend.

When DUMP=ALL is in effect, an SDUMP is attempted for all unexpected abends.

If you specify DUMP=Y, the recovery manager attempts to take an SDUMP only when the failing function is running in supervisor state. If you specify DUMP=N, the recovery manager does not take an SDUMP for any abend, regardless of the PSW state at the time of the failure.

Identifying and connecting to a CAS

The first time a user accesses CICSplex SM, CPSM is used as the default CAS subsystem ID. If this is not the appropriate subsystem ID, the user's profile must be changed. To do this, the user must select option 0 from the CICSplex SM entry panel. Then select suboption 1 and change CPSM to the appropriate subsystem ID.

When the user displays the CICSplex SM entry panel, the names of the context and scope that are to be in effect for the user's CICSplex SM session are shown. When the user selects either option 1 or 2, CICSplex SM establishes connection between the CAS and the CMAS responsible for managing the CICSplex identified as the context.

If, after a CAS connection has been established, the user decides to use option 0.1 to identify a different CAS, the user must use the END command to exit ISPF to FREE the current BBILINK allocations. From the TSO READY prompt, the user must restart the CICSplex SM session in order to establish a connection to the new CAS.

Setting the CAS system communication information

Next, use the PlexManager CASDEF view to specify the CAS system communication information to establish direct CAS-to-CAS communication links. The CASDEF view is described in the *CICSplex SM Administration*.

Note: The CASDEF view will not be available until you have a CAS running and can access the CICSplex SM ISPF end-user interface.

Preparing to stop a CAS

Before you stop a CAS, you should ensure that the MAXUSER, RSVNONR, and RSVSTRT parameters in IEASYSxx contain values that, in combination, will not allow the system to run out of usable ASIDs. To conserve overhead, you may want to limit the value specified for MAXUSER and use values for RSVNONR and RSVSTRT that allow for replacement of nonreusable address spaces when the value at MAXUSER has been exceeded.

The total number specified for MAXUSER and RSVNONR should be greater than zero. The sum of the values specified for MAXUSER, RSVNONR, and RSVSTRT cannot be greater than 32767, which is also the maximum for MAXUSER. For more information about the MAXUSER, RSVNONR, and RSVSTRT parameters, see the *MVS/ESA Initialization and Tuning Reference* manual.

Stopping a CAS

Once a CAS is running, you should not need to stop it unless you want to change its operating parameters.

If you want to stop a CAS, whether it is running as a started task or as a batch job, do the following:

1. Optionally, stop any CMASs that are connected to the CAS.

The CMASs can continue to run without a CAS, but you cannot access them through either the ISPF end-user interface or the application programming interface (API). You may want to leave the CMASs running if either of the following is true:

- You plan to restart the CAS immediately after stopping it.
- The CMAS is involved in workload management for a CICSplex.

Any CMAS that is running when you restart the CAS automatically reconnects to the CAS.

2. From the operator console, issue the MVS purge command:

```
P casname
```

where `casname` identifies the CAS you want to stop.

3. Look for the following console message to verify that the CAS has been stopped:

```
BBMZA999I CAS(ssid) Shutdown Complete - CC=nn
```

where `ssid` identifies the CAS that was stopped and `nn` is the completion code.

Notes:

1. When the CAS is run as a batch job and you CANCEL the job, the initiator is purged.
2. When the CAS is run as a started task and you PURGE the task, the address space is no longer available for other processing.

Chapter 44. Setting up a CICSplex SM address space (CMAS)

This chapter describes the steps you must perform in order to make a CICSplex SM address space (CMAS) operational. These steps consist of:

- “Before you begin”
- “CICSplex SM auxiliary storage usage”
- “Preparing to transmit generic alerts to NetView” on page 322
- “Preparing to start a CMAS” on page 323
- “CMAS-related CICS SIT parameters” on page 326
- “Shutting down a CMAS” on page 330
- “Restarting a CMAS” on page 331.

For a summary of the CMAS setup tasks that you can refer to while performing them, see Chapter 36, “CICSplex SM setup checklist and worksheets,” on page 271.

Before you begin

Before you begin, check the IEASYSxx member of SYS1.PARMLIB that you use for MVS initialization and make note of the initialization values that are referenced during installation. For details about these values, see “Noting IEASYSxx values” on page 281.

If you are converting your CICSplex SM system or systems from a previous release to CICSplex SM for CICS Transaction Server for z/OS, Version 3 Release 1, you should read the *CICS Transaction Server for z/OS Migration from CICS TS Version 2.3*.

In CICS Transaction Server for z/OS, Version 3 Release 1 a CICSplex SM CMAS will run only in a CICS system at the same release level. For example, a CICS TS 3.1 CMAS runs only in a CICS TS 3.1 region. During startup the CMAS checks the CICS release level and terminates with message EYUXL0142 if the releases do not match.

Note: These changes have no effect on the managed CICS systems.

For details on applying corrective or preventive maintenance to CICSplex SM, see Chapter 26, “Applying service to CICS Transaction Server for z/OS,” on page 179.

Take note of the information in *CICSplex System Manager Concepts and Planning* about appropriate uses of a CMAS.

CICSplex SM auxiliary storage usage

When a CMAS is initialized, up to 9 MVS dataspace are created. These dataspace are used by CICSplex SM to allow quick access to data from a CMAS and the MASs attached to it. Although the dataspace are logically owned by the CMAS, they are physically owned by the ESSS address space (EYUX310). The dataspace are deleted when the CMAS (that logically owns the dataspace) and all local MASs that are attached to that CMAS are terminated. The dataspace are recreated when the CMAS is initialized again.

The size of the dataspace is dependent upon the amount of work (end-user interface, workload management, MAS resource monitoring, and real-time analysis

processing) the CMAS is performing and the number of MASs connected to the CMAS. The size may range from 20MB of storage in a relatively idle CICSplex SM configuration to well over 100MB of storage in a configuration that is complex in both the number of MASs and the amount of work requested. If you do not prepare for such an increase in storage usage, you may encounter auxiliary storage shortages when you first start to use CICSplex SM.

As an effort to prevent such auxiliary storage shortages, you should ensure that your auxiliary storage capabilities can handle an increase of 100MB of storage within the environment. Additionally, you can monitor CICSplex SM's dataspace usage by using an external monitor package to determine the amount of storage the EYUX310 job uses.

Note: If you contact IBM support personnel because of auxiliary storage shortages, they may ask you to use the CICSplex SM online debugging transactions (COD0 and CODB) to evaluate the storage use of EYUX310. For information about the COD0 and CODB transactions, refer to the *CICSplex System Manager Problem Determination* manual.

If auxiliary storage shortages do occur, you can alleviate the problem by either dynamically increasing your auxiliary storage capability or by causing CICSplex SM to free the allocated dataspace, as follows:

- To dynamically increase auxiliary storage capacity, allocate an additional page data set, then use the MVS console command PAGEADD to make the new page data set available.

- To cause CICSplex SM to free the allocated dataspace, first terminate the CICSplex SM agent in all local MASs connected to the CMAS. To do this, you must use the MAS view STOP action.

If a local MAS is acting as a CICSplex SM WLM TOR, and the DTR program is specified as EYU9XLOP for that MAS, you must change the DTR program from EYU9XLOP before you can use the MAS view STOP action against that MAS. (For example, you can change it to the IBM default program DFHDYP.)

After the CICSplex SM agent is terminated in all local MASs, terminate the CMAS itself.

After the auxiliary storage capability is increased, you can restart the CMAS. To reconnect any local MASs that remained active after the CICSplex SM agent was stopped, execute the COLM transaction within those CICS regions.

You can execute CORM or COLM using a modify command from the CONSOLE.

Preparing to transmit generic alerts to NetView

You can have the real-time analysis (RTA) component of CICSplex SM transmit generic alerts to an IBM NetView system when one or more user-defined conditions occur during analysis.

For information about how to prepare CICSplex SM to send the generic alerts to NetView, see the discussions of the ACTNDEF view, in *CICSplex System Manager Managing Resource Usage* and the CMASD view, in the *CICSplex System Manager Operations Views Reference* manual.

To be sure that a NetView system is ready to receive the alerts, use the NPDA command

```
DFILTER AREC
```

to verify that the Event Type record IMPD is being passed to the NetView database in the NetView system.

The resulting list should show an ACTION of PASS for ETYPES of IMPD, and RSLV.

If it is necessary to add these record types to the filter, you can issue the following NPDA commands:

```
SRFILTER AREC PASS E IMPD
SRFILTER AREC PASS E RSLV
```

If the name of the NetView Alert Receiver has been changed from the default value (NETVALRT), the CMAS only CICSPlex SM system parameter ALERTRCVR may be used to specify the required name. See Chapter 50, "CICSPlex SM system parameters," on page 383 for details of the ALERTRCVR parameter.

Preparing to start a CMAS

There are several ways to start a CMAS.

You can start a CMAS:

- When an MVS system is IPLed.

To use this method:

- Verify that the CMAS startup procedure is in a system procedure library, such as SYS1.PROCLIB.
- Verify that the CMAS startup procedure is in the 'Started Tasks' table of the external security manager (ESM).
- Change the COMMNDaa member that is referenced by the IEASYSxx member of SYS1.PARMLIB (as in "Noting IEASYSxx values" on page 281). to include a START command for the CMAS.

The START command to be included is described in "START command for a CMAS" on page 330.

- From the system console.

To start a CMAS from the system console:

- Verify that the CMAS startup procedure is in a system procedure library, such as SYS1.PROCLIB.
- Verify that the CMAS startup procedure is in the 'Started Tasks' table of the external security manager (ESM).
- Have the operator issue the START command described on page 330.

- As a batch job.

To start a CMAS as a batch job:

- Verify that the CMAS startup procedure is in a system procedure library, such as SYS1.PROCLIB.
- Construct a job stream to invoke the CMAS procedure.
- Submit the job to invoke a CMAS.

No matter which method you use to start a CMAS, be sure to verify that the procedure references the appropriate:

- CICS SIT parameters, as described on page 326.
- CICSPlex SM startup parameters, as described on page 383.

Notes:

1. Because the job of the CMAS is to manage a MAS, it is important that the CMAS have the ability to process data with a higher priority than the MAS. Therefore, when the MVS image is running in workload management goal mode, the CMAS jobs should be defined to the MVS service class, SYSSTC, for optimal performance. Failure to do so may result in severe performance problems for CICSplex SM.
2. After starting a CMAS for the first time, you must configure the CMAS to your environment. This includes establishing the CICSplexes it is to manage and any communication links that are needed between this CMAS and another CMAS. For additional information about this, see *CICSplex System Manager Administration*.

A sample procedure that you can use to start a CMAS is supplied in the member EYUCMAS. This member was generated when you ran the EYUISTAR job, as described in Chapter 39, “Generating post-installation members,” on page 297. The member is stored in the library you specified on the LIB parameter of the EYUISTAR job.

You must create the data sets for this CICS region. JCL to create the CICS region data sets for the CMAS is supplied in member EYUDFHDS of CICSTS31.CPSM.XEYUINST. This member was generated when you ran the EYUISTAR job.

Figure 56 illustrates segments of the EYUCMAS procedure that are unique to CICSplex SM.

```
//EYUCMAS  PROC DSNCSO=CICSTS31.CPSM.DFHCSO, CSD Data Set name
//          DSNTBL=CICSTS31.CPSM.RGNLOAD, CICS Table Module library
//          RGNHLQ=CICSTS31.CPSM,           CICS Region DSN qualifier
//          CICSPRM=EYUCnnI0,             CICS Parameters
//          CPSMPRM=EYUCMSOP              CPSM Parameters
// *
//CICS     EXEC PGM=EYU9XECS,              CMAS Startup program
//          PARM='SYSIN',                 CICS Parameters location
//          REGION=0K                     Region Size
// *
//STEPLIB DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUAUTH
//          DD DISP=SHR,DSN=CICSTS31.CPSM.CICS.SDFHAUTH
//DFHRPL  DD DISP=SHR,DSN=CICSTS31.CPSM.SEYULOAD
//          DD DISP=SHR,DSN=CICSTS31.CPSM.CICS.SDFHLOAD
//          DD DISP=SHR,DSN=&DSNTBL
:
//EYULOG  DD SYSOUT=*
//DFHJ25A DD DISP=SHR,DSN=CICSTS31.CPSM.SDFHJ25A
//DFHJ25B DD DISP=SHR,DSN=CICSTS31.CPSM.SDFHJ25B
:
//EYUDREP DD DISP=SHR,DSN=CICSTS31.CPSM.EYUDREP.cmasname
//EYUPARM DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUPARM(&CPSMPRM)
//BBACTDEF DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUAEF
//BBVDEF  DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUVDEF
//BBIPARM DD DISP=SHR,DSN=CICSTS31.CPSM.EYUIPRM
```

Figure 56. CMAS-specific JCL requirements

Review the following statements in the sample JCL that are illustrated in Figure 56. Verify that the JCL has been modified so that the:

EXEC PGM=EYU9XECS statement

Starts the CMAS and either verifies the existence of, or creates, the ESSS. EYU9XECS, the CMAS startup program, must be run in order for a CMAS to initialize.

STEPLIB DD statement

Includes the CICSTS31.CPSM.SEYUAUTH authorized load library.

DFHRPL DD statement

Includes the CICSTS31.CPSM.SEYULOAD load library. Include the load library that contains the CICS resource definition table load modules. These need to be link edited into a user-supplied load library, which needs to be specified in the DFHRPL concatenation. See “Creating CICS resource definition tables for CMASs” on page 307 for more information.

You should not include application load libraries in the DFHRPL concatenation.

EYULOG DD statement

Identifies the log to which messages from the CMAS and its associated managed application systems (MASs) are to be directed.

When you are using a sequential data set for the EYULOG, allocate 3 primary cylinders and 1 secondary cylinder.

EYUDREP DD statement

Identifies the library to be used as the data repository by the CMAS, where:

cmasname

Is the name you specified for the CMASNAME parameter on the EYUISTAR job. The CMASNAME value is used by EYU9XDUT in order to create the CICSplex SM data repository. (See “Creating the CICSplex SM data repository” on page 299.)

EYUPARM DD statement

Identifies the library that contains the CICSplex SM system parameters.

BBACTDEF DD statement

Defines the data set that contains the SMP-installed CICSplex SM action and view tables. These tables help the CAS determine which view names and actions are valid within a given context.

BBVDEF DD statement

Defines the library that contains all SMP-installed CICSplex SM views.

BBIPARM DD statement

Identifies the library containing the CICSplex SM system parameters.

Editing CICSplex SM system parameters

Member EYUCMS0P, in the CICSTS31.CPSM.SEYUPARM data set, contains sample parameters for a CMAS; this member must be edited. (See Chapter 50, “CICSplex SM system parameters,” on page 383 for a detailed description of each parameter.)

When the CMAS is to connect to a MAS for which security is active (the CICS SIT parameter for the MAS is SEC=YES), the CMAS must have CICSplex SM security active. When CICSplex SM security is not activated in the CMAS, the connection between the CMAS and the MAS cannot be established. If this is attempted, the following message is issued to the console, the CMAS joblog, and the CMAS EYULOG:

EYUCR0007E Security mismatch between CMAS cmasname and MAS masname. Connection terminating.

To activate CICSplex SM security in the CMAS, you must specify the CICSplex SM system parameter SEC(YES). The default is SEC(NO). (For more information about the SEC parameter, see Chapter 50, “CICSplex SM system parameters,” on page 383.) Specifying SEC=YES in the CICS SIT parameters for the CMAS does not affect CICSplex SM security.

CMAS-related CICS SIT parameters

The CICSTS31.CPSM.SEYUPARM library contains CICS system initialization table (SIT) parameters that should be included in the sequential data set or partitioned data set member EYUC6410 as identified by the CICS SYSIN statement.

Table 22 identifies the CMAS-related CICS SIT parameters.

Notes:

1. When the second column in the table contains an asterisk, before you start a CMAS you should supply your own value for the parameter listed in the first column.
2. When the second column of the table does not contain an asterisk, do not change the value of the parameter in the first column.

Table 22. CICS SIT parameters for a CMAS

Parameter	Your value	Explanation
AIEXIT=DFHZATDX		VTAM terminal autoinstall program.
APPLID=	*	VTAM application ID for this CICS, which is acting as a CMAS. Used as CMAS name when NAME(value) is not specified as a CICSplex SM system parameter.
# AUTORESETTIME=YES # #		Synchronize the CICS and MVS clocks after the local time offset has been changed. You should continue to issue the CEMT PERFORM RESET command.
AUXTR=ON		Auxiliary trace - Exception records.
AUXTRSW=ALL		Continuous auxiliary trace switching.
CICSSVC=216	*	CICS SVC installed in LPA.
CPSMCONN=CMAS		Initialize this region as a CMAS
DFLTUSER=	*	Non-CESN RACF user Id.
DSALIM=4M		Limit of DSA storage below 16MB.
DUMPDS=A	*	Transaction dump data set.
DUMPSW=NEXT	*	Switch to next transaction dump data set.
EDSALIM=100M		Limit of EDSA storage above 16MB. This is a minimum initial value. See “Controlling CICS storage in a CMAS” on page 329 for additional information.
FCT=NO		No File control table.
GMTEXT='CICSplex SM / ESA'	*	Default logon message.
GRPLIST=EYU310L0		CSD group list having group EYU310G0. See “Updating the CSD files using DFHCSDUP (CMAS)” on page 307 for additional information.
ICV=100		Region exit interval.

Table 22. CICS SIT parameters for a CMAS (continued)

Parameter	Your value	Explanation
ICVR=20000		Runaway task interval. Note: For a CMAS running on a small processor and having a large number of resources defined through BAS, this value may need to be increased to about 90000.
ICVTSD=1		Terminal scan delay interval.
INTTR=ON		Activate main storage trace.
IRCSTRT=YES		IRC started at system initialization.
ISC=YES		Load programs required for interregion or intersystem communications during initialization.
MXT=300		Maximum tasks to exist. This is a minimum initial value. See "Controlling CICS storage in a CMAS" on page 329 for additional information.
RENTPGM=PROTECT		Specifies that CICS will allocate ERDSA from readonly key 0 protected storage.
# SEC= {YES NO}		Indicates whether CICS external security checking is performed for this CMAS. The CICS security checking is independent of the CICSplex SM external security checking (which is controlled with the CICSplex SM SEC system parameter) as specified in the EYUPARM DD. For information about the CICSplex SM SEC parameter for the CMAS, see Chapter 50, "CICSplex SM system parameters," on page 383. The CICS external security checking SIT option can be specified in the normal way, along with the other CICS security related options (for example, XTRAN and XCMD). CICS command or resource security is not appropriate in a CMAS. The XTRAN SIT option is typically used to control access to the various CICSplex SM transactions used in a CMAS. For more information, see <i>CICS RACF Security Guide</i> . Note: No CICSplex SM supplied transaction definitions have CMDSEC=YES or RESSEC=YES. If this definition is changed, or the CMDSEC=ALWAYS or RESSEC=ALWAYS SIT parameters are set in a CMAS, and a CICSplex SM transaction receives a NOTAUTH response, results are unpredictable.
SIT=6\$		System initialization table suffix.
SPOOL=YES		System spooling interface. Required when you are going to use the CICSplex SM batched repository-update facility.

Table 22. CICS SIT parameters for a CMAS (continued)

Parameter	Your value	Explanation
START=AUTO		<p>You can normally specify START=AUTO and let CICS initialization decide the type of start to perform.</p> <p>The first time you start a CMAS, ensure the CICS global and local catalog data sets are newly initialized. Use DFHRMUTL and DFHCCUTL respectively, with AUTOINIT on the SET_AUTO_START parameter of DFHRMUTL. This makes sure that the CMAS performs an initial start, which installs the necessary CICS resource definitions and establishes CMAS-to-CMAS connections.</p> <p>Subsequently, you can manipulate the type of start for a CMAS by resetting the global catalog data set, using DFHRMUTL to specify either AUTOINT or AUTOCOLD. For more information, see "Restarting a CMAS" on page 331.</p>
STGPROT=NO		No storage protection.
SUBTSKS=1		Use additional concurrent mode TCB.
SYSIDNT=	*	<p>CICS System Id.</p> <p>Note: The SYSIDNT value must match the EYU9XDUT SYSID parameter value used to initialize the data repository being referenced by the EYUDREP DD statement.</p>
SYSTR=OFF		No system activity trace.
TCT=NO		No TCT needed.
TRANISO=NO		No transaction isolation.
TRTABSZ=2048		Kilobytes for trace table.
TS=COLD		Cold start temporary storage.
TST=NO		No temporary storage table required.
USERTR=ON		Enable user trace facility.
WRKAREA=2048		Bytes for Common Work Area.
XRF=NO		<p>No XRF support.</p> <p>Note: The extended recovery facility (XRF) is not supported because of the way in which a CMAS uses MVS data spaces.</p>

Controlling tasks in a CMAS

Many operations within a CMAS are achieved by multiple asynchronous tasks. This is especially true of operations that are performed between CMASs in a CMAS network, such as data repository synchronisation, workload management state sharing and single system image. Any of these operations, and others, can result in a number of interdependent asynchronous tasks being established or used to execute the request. The number of tasks that can be used is based on other factors, such as the size of a CMAS network, how many MASs are being managed, how many CICSplexes are defined, how much API activity is performed, the scope of EUI/WUI/API/RTA requests and so on for all the major functionality offered by CPSM.

Even though a CMAS can self regulate its tasking model and has tolerance of delayed requests and responses through timeout mechanisms, MXT is a concept

that is not applicable to controlling an interdependent multitasked asynchronous tasking model. Set inappropriately, you may also experience EUI and WUI hang' for long durations if one or more of the asynchronous tasks required to execute the requested function are delayed waiting for an MXT slot. It is therefore strongly recommended that MXT should be set to avoid **any** delays in task attachment.

As task usage within a CMAS grows with the additional requirements that are placed upon it, such as but not limited to, increased use of the API, more CMASs, more MAS's, new function use, and so on, you should set the MXT value to a level that continues to avoid MXT delays.

It is recommended that you monitor any MXT value for its relationship against the task activity within each CMAS at regular intervals. If the CMAS is starting to experience MXT delays, you should adjust the MXT value to avoid these delays.

To monitor the tasking activity within an individual CMAS, it is recommended that you collect and study the statistics generated by the CICS system that underlies the CMAS that it hosts. CICS transaction manager global statistics contain information on the effect the MXT value has on task attachment. For more information and guidance on using CICS statistics see the *CICS Performance Guide*.

Controlling CICS storage in a CMAS

A CMAS is a special application dedicated to the task of managing and controlling MASs. Even though a CMAS does this with an atypical tasking model and with extensive use of MVS dataspace storage, it still has major uses of the storage provided by the CICS system that hosts the CMAS. With an interdependent multitasked asynchronous tasking model there is a reliance on shared storage to perform the communication between the tasks and the functions being performed. Also, according to the requirements that are placed upon a CMAS, there is a large reliance on shared storage to perform the buffering of requests and responses to be transmitted via CMAS to CMAS and CMAS to MAS links. The shared storage to support such operational characteristics is managed by the CICS system that hosts the CMAS.

As CICS storage usage within a CMAS grows with the additional requirements that are placed upon it, such as, increased use of the API, more CMASs, more MASs, increased CMAS to CMAS network traffic and new function use, you should set the EDSALIM value to a level that provides the CMAS with the amount of storage it needs to perform its operations unimpeded. CMAS to CMAS and CMAS to MAS network traffic, in particular, is critical to EUI and WUI response times because large amounts of data may be awaiting shipment on any of the links that a CMAS communicates on

It is recommended that you monitor any EDSALIM value for its effect on the storage usage within each CMAS at regular intervals. If the CMAS is experiencing short on storage (SOS) or storage fragmentation or trending towards such conditions, you should consider increasing the EDSALIM value to meet the storage requirements of the CMAS. Storage fragmentation below a largest free area of 64KB will begin to adversely effect throughput and response times.

To monitor the storage usage within an individual CMAS, it is recommended that you collect and study the statistics generated by the CICS system that underlies the CMAS that it hosts. CICS storage manager global statistics contain information on the overall usage of CICS storage by the CMAS that it hosts. For more information and guidance on using CICS Statistics see the *CICS Performance Guide*.

START command for a CMAS

The syntax of the command you can use to start a CMAS is:

```
START procname [,DSNCSD=dsn] [,DSNTBL=dsn] [,RGNHLQ=idx]  
[,CICSPRM=mem] [,CPSMPRM=mem]
```

where:

procname	Is the 1- to 8-character name of the procedure. (EYUCMAS is the name of the distributed sample procedure.)
DSNCSD=dsn	Specifies the name of the data set that contains the CSD file that has been modified to include the necessary CICSplex SM resource definitions.
DSNTBL=dsn	Specifies the name of the data set that contains the CICS table modules that have been modified for CICSplex SM. These need to be link edited into a user-supplied load library, which needs to be specified in the DFHRPL concatenation. See “Creating CICS resource definition tables for CMASs” on page 307 for more information.
RGNHLQ=idx	Specifies the high-level qualifier that is used with the DFHxxxx data sets that are unique to this CMAS. The EYUINST EXEC parameter CINDEX establishes the high-level qualifier that is used with CICS data sets that are shared between systems.
CICSPRM=mem	Identifies the member in the CICSTS31.CPSM.SEYUPARM library that contains the CICS SIT parameters.
CPSMPRM=mem	Identifies the member in the CICSTS31.CPSM.SEYUPARM library that contains the CICSplex SM system parameters.

Setting the VTAM APPLID for a CMAS

The last step is to use the CMTCMDEF view to set the VTAM APPLID for the target CMAS, to establish direct CMAS-to-CMAS communication links. The CMTCMDEF view is described in the *CICSplex System Manager Administration* manual.

The CMTCMDEF view is not available until you have a CMAS that can access CICSplex SM itself.

Shutting down a CMAS

You can shut down a CMAS using:

- The SHUtdown command
- The COSD transaction.

It is also possible to use the CMASSTOP command of the CODB system-level debugging transaction to shut down the CMAS, but CODB is restricted and should be used only at the request of IBM customer support personnel

Note: You should not attempt to:

- Issue the CEMT PERFORM SHUTDOWN command against a CMAS.
- Cancel the CMAS job from MVS

If you take either of these actions, the CMAS cannot shut itself down properly.

Using the SHUtdown command

You can issue the **SHU**tdown command from either the CMAS view or the CMASD view.

From the CMAS view

Issue the action command:

```
SHUtdown cmas
```

where `cmas` identifies the CMAS to be shut down.

From the CMASD view

Issue the action command:

```
SHUtdown
```

Using the COSD transaction

You can issue from any terminal, including an MVS console, the transaction id:

```
COSD
```

You should see an information message that indicates whether or not the CMAS is shut down. For details of these messages, see *CICSplex System Manager Messages and Codes*.

Restarting a CMAS

A CMAS that was shut down normally (using the CICSplex SM SHUTDOWN action command) can usually be restarted with a SIT parameter of `START=AUTO`. However, you must specify `START=COLD` if you have:

- Modified any of the CICS resource definitions that are used by the CMAS.
- Added or removed CMAS-to-CMAS (CMTCMDEF) connection definitions.

If a CMAS terminates abnormally (that is, through any means other than the CICSplex SM SHUTDOWN action command), you must perform an emergency restart to allow CICS to perform backout processing. You can accomplish an emergency restart of a CMAS in one of two ways:

- If the CMAS is registered with the MVS automatic restart manager (ARM), an emergency restart occurs automatically.
- If the CMAS is not registered with ARM, specify `START=AUTO` in the CMAS startup procedure.

A CMAS should initialize and function properly after an emergency restart, provided you have made no changes to the CICS resource definitions or CICSplex SM connection definitions.

If you have made any such changes since the last run of the CMAS (that is, the one that terminated abnormally), the CMAS may not function properly. In that case, you should shut down the CMAS with the CICSplex SM SHUTDOWN action command and restart it, specifying `START=COLD`. For an illustration of the SHUTDOWN action command, see “Shutting down a CMAS” on page 330.

Chapter 45. Setting up a CICS managed application system (MAS)

This chapter describes the steps you must perform so that a CICS TS system can be known as a managed application system (MAS) to CICSplex SM. (Throughout the rest of this chapter, a CICS TS MAS is referred to as an MVS MAS.) The following levels of CICS under MVS can connect directly to, and be managed by, CICSplex SM:

- CICS Transaction Server for z/OS, Version 2 Release 3
- CICS Transaction Server for z/OS, Version 2 Release 2
- CICS Transaction Server for OS/390, Version 1 Release 3

The information you need is in the following sections:

- “Before you begin”
- “Using CICS global user exits and user-replaceable modules”
- “Controlling the use of modules from the LPA” on page 334
- “Preparing to start an MVS MAS” on page 334
- “Stopping and restarting management of a CICS system” on page 339.

For a summary of the MAS setup tasks that you can refer to while performing them, see Chapter 36, “CICSplex SM setup checklist and worksheets,” on page 271.

Before you begin

Before you begin, check the IEASYSxx member of SYS1.PARMLIB that you use for MVS initialization and make note of the initialization values that are referenced during installation. For details about these values, see “Noting IEASYSxx values” on page 281.

If you are converting your CICSplex SM system or systems from a previous release to CICSplex SM for CICS Transaction Server for z/OS, Version 3 Release 1, you should read the *CICS Transaction Server for z/OS Migration from CICS TS Version 2.3 Guide*.

For details on applying corrective or preventive maintenance to CICSplex SM, see Chapter 26, “Applying service to CICS Transaction Server for z/OS,” on page 179.

Using CICS global user exits and user-replaceable modules

This section describes the CICS global user exits (GLUE) and user replaceable modules that are used by CICSplex SM.

The way these exits are used by CICSplex SM conforms to the standard described in the *CICS Customization Guide*. CICSplex SM uses these exits only to acquire information; the application environment is not altered.

CICSplex SM uses the dynamic routing program user replaceable module (DTRPROG) as part of workload balancing.

The XMNOUT and XSTOUT exits are used when monitoring services are enabled for a managed application system (MAS).

- The XMNOUT exit is used to get task and CICS monitoring data. XMNOUT is used only with a local MAS.
- The XSTOUT exit is used to get statistical data before the data is reset by CICS.

These exits are used to obtain monitoring and statistics information and always return a “continue processing” return code. They are disabled when a shutdown request for the MAS is received.

The XMEOUT, XDUREQ, XDUREQC, XRSINDI and XDUOUT exits are used when topology requests are enabled for a local MAS. The XMEOUT exit is used to detect short on storage sick and well health events.

- The XRSINDI exit is used to detect topology resource changes.
- The XDUREQ exit is used to detect system dump and transaction dump sick health events.
- The XDUREQC exit is used to detect the completion of dump action.
- The XDUOUT exit is used to detect transaction dump well health events.
- The XSNOFF exit is used to detect user signoff events.

Controlling the use of modules from the LPA

You can control whether CICS uses modules from the LPA, by specifying the LPA and PRVMOD CICS system initialization parameters or by including or excluding the SYS1.CICSTS31.CPSM.SEYULPA library (defined to MVS as an LPA library) in the STEPLIB or DFHRPL concatenations.

Notes:

1. A module that is link-edited with the RMODE(ANY) attribute is loaded into the ELPA.
2. It is important to remember that the LPA-resident version of a module usually loaded from STEPLIB is not used from the LPA if it is left in the STEPLIB DD concatenation of libraries. If a module is found in the STEPLIB concatenation, it is loaded into the private area of the address space, and the LPA version ignored. This situation can be avoided by moving the LPA-eligible modules into an LPA library, as described in “Installing CICSplex SM modules into the LPA” on page 287.

For further information about controlling the use of LPA-eligible modules, see Chapter 14, “Installing CICS modules in the MVS link pack area,” on page 107, taking particular note of information concerning:

- The module-not-found warning message (DFHLD0107I)
- CICS SIT parameters related to LPA modules.

Preparing to start an MVS MAS

Note: Because a CICS system is unknown to CICSplex SM until the CMAS with which the CICS system is associated is started, you should start the CMAS before any of the MASs (that is, the CICS systems the CMAS is to manage).

CMAS links can fail if you have high priority jobs running alongside your
CICS regions. For example, if a MAS holding a lock cannot be dispatched
because of a priority conflict, the CMAS links can fail.

In order for a CICS system to be managed by CICSplex SM, you must:

- Define the system to CICSplex SM, as described in the *CICSplex System Manager Administration*
- Change the startup JCL for that system by:

- Modifying the DD statements shown in Figure 57, to include the CICSplex SM data sets
- Verifying that the appropriate CICS SIT parameters are included

```

...
//STEPLIB DD DSN=CICSTS31.CPSM.SEYUAUTH,DISP=SHR
//DFHRPL DD DSN=CICSTS31.CPSM.SEYULOAD,DISP=SHR
//EYUPARM DD DSN=(Any PO or PS data set with LRECL=80)
//EYUHISTA DD DSN=(Optional 1st history dataset)
//EYUHISTB DD DSN=(Optional 2nd history dataset)
//EYUHISTn DD DSN=(Optional nth history dataset)
...

```

Figure 57. MVS MAS-specific JCL requirements

When changing these DD statements in the startup JCL for a CICS system make sure that the:

STEPLIB DD statement

Includes the CICSTS31.CPSM.SEYUAUTH authorized load library.

DFHRPL DD statement

Includes the CICSTS31.CPSM.SEYULOAD load library.

EYUPARM DD statement

Identifies the library containing the CICSplex SM parameters.

Notes:

#

1. Member EYULMS0P in the CICSTS31.CPSM.SEYUPARM data set, contains sample system parameters for a local MAS; this member must be edited. See Chapter 50, “CICSplex SM system parameters,” on page 383 for a detailed description of each parameter.
2. If you want to use Business Application Services to install CICS resources in a MAS, you must specify the CICSplex SM system parameter MASPLTWAIT(YES) for that system. This parameter suspends CICS PLT processing until all CICS resources are installed and the CICSplex SM MAS is fully initialized.

EYUHISTx DD statement

Identifies the history data sets for the MAS. Each MAS must have its own set of CICSplex SM history data sets. The data sets must be allocated to the MAS region by means of DD cards in the JCL with DD names of the form EYUHISTx, where x is a character suffix taking values A through Z. Dynamic allocation is not supported. The data sets must be allocated with a disposition of OLD. The suffix letters must be used in ascending sequence and no letter should be omitted. For example, if four history data sets are required, use DD names EYUHISTA, EYUHISTB, EYUHISTC, and EYUHISTD. See “Preparing the MAS for history recording” on page 338.

Activating DB2 connections during CICS startup

This section applies to CICS Transaction Server for z/OS, Version 3 Release 1 CICS systems with the CICS-DB2 attachment facility.

Special considerations apply when BAS is used to install a DB2 connection defined to CICSplex SM via a DB2CDEF resource definition.

When BAS is used to define and then install a DB2 connection (via a DB2CDEF) the connection starts out in NOTCONNECTED status. You can then issue a

CONNect command on the DB2CONN view against an installed connection, to cause the connection to the DB2 subsystem to be activated.

In a test environment, it might be acceptable to wait for the MAS to start and then install the BAS definition, and issue a CONNECT command against the resulting DB2CONN.

However, in a production system, you might want the connection to be automatically activated when the MAS starts up, as part of the PLT processing sequence, so that the DB2 subsystem can be accessed immediately by programs and users.

Specifying the CICS SIT parameter DB2CONN=YES does not by itself achieve this, because at the time this and other SIT parameters are processed, CICSplex SM has not yet installed any DB2CDEF objects.

The way to activate a DB2 connection during CICS startup is as follows:

1. Ensure there is an appropriate DB2CDEF resource definition for CICSplex SM to install, and that the definition is set up for automatic installation.
2. Specify CICSplex SM parameter MASPLTWAIT(YES). This causes the DB2CDEF resource definition (as well as all other BAS resource definitions) to be installed during PLT processing.
3. Arrange for the appropriate DB2 connect program to be started *after* the MAS startup program (EYU9NXLM for a local MAS).

MQSeries connections

You cannot use BAS to define and install an MQSeries® connection before the CICSplex SM environment has been initialized.

MVS MAS-related CICS SIT parameters

You should verify that the sequential data set or partitioned data set member identified by the CICS SYSIN statement includes the appropriate CICS system initialization table (SIT) parameters, as described in Table 23.

Table 23. CICS SIT parameters for an MVS MAS

Parameter	Explanation
APPLID=	VTAM application ID for this CICS system. Used as MAS name when NAME(value) is not specified as a CICSplex SM system parameter.
# AUTORSETTIME={YES/NO}	This parameter allows for the synchronization of the MVS and the CICS TOD clocks when the local time offset is changed. The default is NO.
CPSMCONN=L/MAS	Initialize the region as a local MAS.
DFLTUSER=userid	Specify the user identifier that is to be used for security checking when a user is not defined to the ESM.
DSALIM=	Limit of DSA storage below 16MB. Should be set to at least 4MB.
# EDSALIM=	Limit of EDSA storage below 16MB. Should be set to at least 50MB.
GRPLIST=	Identify the name of the group list containing the CICSplex SM group added to the CSD file for the MAS. (See “Updating CSD files using DFHCSDUP (MVS MAS)” on page 311 for additional information.)
ISC=YES	Code YES to include the CICS programs required for interregion and intersystem communications.
MCT=	Monitoring control table. If you have CICS performance class monitoring active, then you must specify a value for this parameter. You can use 2\$ (the default) or an existing table. (See Note below.)

Table 23. CICS SIT parameters for an MVS MAS (continued)

Parameter	Explanation
MN=ON	Activates CICS Monitor. (See Note below.)
MNFREQ=001500	Writes performance class data every 15 minutes. Note: Set only for local MAS.
MNPER=ON	Tells CICS to monitor performance classes. (See Note below.)
<p>Note for MCT, MONITOR, MN, and MNPER parameters: To get all data available for the TASK and MLOCTRAN views, MCT must have a value specified, CICS monitoring for performance classes must be activated, and you must be collecting performance class data.</p> <p>If you do not want this data written to an SMF data set, you can suppress the monitor records. See the description of the SUPPRESSCMF parameter in Chapter 50, "CICSplex SM system parameters," on page 383.</p>	
# MXT= # # # # # #	<p>Maximum tasks. Increase by 25 to accommodate the CICSplex SM MAS tasks.</p> <p>Note: CICSplex SM rarely uses all 25 of these additional tasks. If you are using the MXT value alone to control application transactions, increasing this value can allow more application transactions to run concurrently. To prevent this from occurring, you can define a transaction class for the application and set the MAXACTIV task value to limit the number of concurrent transactions.</p>
SEC= {YES NO}	<p>Indicate whether external security checking is to be performed for this CICS system. Specify:</p> <p>YES When READ access is granted:</p> <ul style="list-style-type: none"> • READ is permitted • UPDATE is refused. <p>When UPDATE access is granted:</p> <ul style="list-style-type: none"> • READ is permitted • UPDATE is permitted. <p>NO Security checking is not performed.</p> <p>Notes:</p> <ol style="list-style-type: none"> 1. For CICS security, the value specified with SEC= for a CMAS overrides the value specified with SEC= for a MAS. (For more information about this parameter, see the <i>CICS RACF Security Guide</i>.) 2. For CICSplex SM security to be active, you must set SEC=YES for a MAS, and the CMAS to which it connects must have the CICSplex SM system parameter SEC=YES). When CICSplex SM security is not activated in the CMAS, the connection between the CMAS and the MAS cannot be established. If this is attempted, message EYUCR0007E is issued to the console, the CMAS joblog, and the EYULOG. <p>(For more information about the SEC parameter for the CMAS, see Chapter 50, "CICSplex SM system parameters," on page 383.)</p>
# SECPRFX={YES NO prefix}	Specify whether the user ID is used as the prefix that is added to the beginning of all resource names to distinguish this CICS system from other CICS systems.
SYSIDNT= 	Indicate the id of the CICS system. This name should be unique within a CICSplex.
XCMD= {YES name NO}	Indicate whether EXEC CICS system commands are to be included in security checking. Specify YES or NO. For more information about CICSplex SM transaction security requirements, see the CICS RACF Security Guide.

Table 23. CICS SIT parameters for an MVS MAS (continued)

Parameter	Explanation
XDB2= { <u>No</u> lname}	Indicate whether DB2 resources are to be included in security checking. Specify NO or name.
XFCT= { <u>YES</u> lname NO}	Indicate whether file control entries are to be included in security checking. Specify YES or NO. For more information about CICSplex SM transaction security requirements, see the CICS RACF Security Guide.
XPCT= { <u>YES</u> lname NO}	Indicate whether EXEC-started transactions are to be included in security checking. Specify YES or NO. For more information about CICSplex SM transaction security requirements, see the CICS RACF Security Guide.
XPPT= { <u>YES</u> lname NO}	Indicate whether program entries are to be included in security checking. Specify YES or NO. For more information about CICSplex SM transaction security requirements, see the CICS RACF Security Guide.
XUSER={ <u>YES</u> NO}	Indicates whether CICS is to perform surrogate user checks. If you specify YES, the CICS region userid must be defined as a surrogate of the userid that starts a MAS using the COLM or CORM transaction.

Preparing the MAS for history recording

CICSplex SM provides the ability to save and view data for completed tasks, that is historical task data. When an active task completes, its data is stored in a historical data store. The data store is made up of a number of VSAM KSDS data sets. There must be a minimum of two data sets and a maximum of twenty six data sets.

Each MAS must have its own set of CICSplex SM history data sets. The data sets must be allocated to the MAS region by means of DD cards in the JCL with DD names of the form EYUHISTx, where x is a character suffix taking values A through Z. Dynamic allocation is not supported. The datasets must be allocated with a disposition of OLD. The suffix letters must be used in ascending sequence and no letters should be omitted. For example, if four history data sets are required use DD names EYUHISTA, EYUHISTB, EYUHISTC, and EYUHISTD.

The CICSplex SM history data sets must be defined with the REUSE keyword. Task history recording uses the least recently used data set, or when starting for the first time EYUHISTA. When EYUHISTA becomes full, it switches to use EYUHISTB and so on in sequence. Each full data set remains open with its data available until the history recorder has filled all data sets and needs to start reusing the data sets. At this time EYUHISTA is set closed, emptied, re-opened, and reused first, followed by EYUHISTB and so on in sequence. If a data set is reused its previous contents are destroyed.

Until the history recorder requires to empty a data set in order to reuse it, the historical task data is available for use. The data is maintained across CMAS and MAS restarts. The history data sets need not be defined as recoverable, as unit of work recoverability is not required. However, the CICSplex SM history recorder facility does require files to be defined as non-recoverable to avoid unnecessary logging in the MAS region.

In addition, the history data sets must not be defined to use VSAM compression.
 # The CPSM history function initializes the data sets in order to calculate how many
 # records fit in the data set, so that it can safely use sequential writes to the data set,
 # thereby reducing the I/O overhead. Use of VSAM compression invalidates that
 # calculation and cause data to be lost when the data set becomes full and a data set
 # switch is required.

CICSplex SM provides a tuning aid in the form of a EYUPARM called HISTRECSMSG to determine the optimum size for history data sets. HISTRECSMSG can activate the periodic output of messages detailing how many thousand records have been written to the data set. There is one record for each completed task. Since CICS file control supports extended format KSDS data sets, large history data sets over 4GB in size can be defined. However when considering using very large data sets, take into account that when the CICSplex SM history recorder reuses a data set by emptying it, a large amount of data is lost and not available for subsequent queries. An alternative approach to having a small number of very large data sets, is to spread the data over more data sets. For example, by having twenty five data sets each one capable of holding one hours worth of completed task data, at least one days worth of data can always be maintained. When the oldest data set is reused, only one hours worth of data is lost.

#

CICSplex SM provides a sample job called EYUJHIST in SEYUINST for defining and initializing two history data sets.

Stopping and restarting management of a CICS system

This section tells you how to:

- Stop management of a CICS system
- Restart management of a CICS system
- Terminate a CICS system.

Stopping management of a CICS system

To stop the MAS agent code in an active CICS system, either:

- Issue the STOP action command from the MAS view, or
- Run transaction COSH in the MAS. COSH can be started at a 3270 terminal, at a console, or via ATI.

Stopping the MAS agent prevents CICSplex SM from accessing the MAS until either the CICS system is restarted (see page 334) or the COLM or CORM transaction is issued (see “Restarting management of a CICS system”).

Note: When a MAS is active as a CICSplex SM workload management routing region, and the dynamic routing program is set to EYU9XLOP, the STOP command is not honored. In this situation, before you issue the STOP command you must use the CICSRGND view to change the dynamic routing program from EYU9XLOP to the CICS default dynamic routing program, DFHDYP, or another valid dynamic routing program.

Restarting management of a CICS system

To reactivate a running CICS system as a MAS, issue the CICS transaction:
COLM For a local MAS

|

Note: If you want a local MAS to be recognized as a workload management routing region when CICSplex SM resumes managing the system, make sure the dynamic routing program is set to EYU9XLOP. To change the dynamic routing program, use the CICS CEMT transaction before you reactivate the local MAS.

Terminating a MAS

To verify that the CICSplex SM MAS shutdown processing is properly installed, you can terminate the CICS system and check the log for the following shutdown message:

```
EYUXL0016I MAS shutdown complete
```

To terminate a CICS system running the MAS agent code, use the CICS`SRGN` view to issue the desired shutdown command. For more information about the CICS`SRGN` view, see the *CICSplex System Manager Operations Views Reference* manual.

Controlling the number of long running tasks in a MAS

The MAS agent contains one primary long running task (LRT), which runs under
transaction CONL. By default, this task handles most requests directed to the MAS
through the EUI, API, WUI, and RTA. The CONL task also handles internal requests
for the MAS, including collecting information on dynamically installed resources and
delivering this information to the CMAS. If the LRT becomes busy handling one
request, all subsequent requests directed to the MAS are delayed until the current
request ends.

Alternate LRTs, which run under the CONA transaction, can be requested by
specifying a non-zero value for the MASAL`LRTCNT` EYUPARM. If activated, the
alternate LRTs handle the EUI, API, WUI, and RTA requests normally handled by
the primary LRT. Only one alternate LRT is active at a given time. If the active
alternate LRT becomes busy for longer than the value specified by the
MASAL`LRTTIM` EYUPARM, subsequent EUI, API, WUI, and RTA requests directed
to the MAS are directed to another CONA task.

Using alternate LRTs allows subsequent requests to be processed even though a
previous request has yet to be completed. This also allows the primary LRT to
process internal requests without being delayed by the processing of an EUI, WUI,
API, or RTA request.

The number of alternate long running tasks (MASAL`LRTCNT`) can be tuned using
the EYUNL0911I, EYUNL0912I, and EYUNL0913I messages issued when a MAS
terminates or goes into restart mode. EYUNL0911I displays the number of active
CONA tasks for this execution. EYUNL0912I displays the maximum number of
concurrently busy CONA tasks. If this value is less than the value displayed by
EYUNL0911I, then you might want to lower the MASAL`LRTCNT` so that it equals
the value displayed by EYUNL0912I or is one greater. If the value of EYUNL0912I
is equal to the value displayed by EYUNL0911I, then the value displayed by
EYUNL0913I, the number of times all active CONA tasks were busy at the same
time, is non-zero. Based upon this value you can increase the value of
MASAL`LRTCNT`.

The priority of the alternate LRTs can be controlled by the MASAL`L RTPRI`
EYUPARM. Specifying this less than the default value of 255 can adversely affect
the response time of EUI, API, and WUI users, and might result in RTA `EVENTs` not
being created or resolved in a timely manner.

Note: Specifying different values for MASAL`LRTCNT` for multiple WLM target
regions might result in an uneven distribution of transactions to those regions
because of differing long running task counts.

Chapter 46. Setting up a CICSplex SM Web User Interface server

This chapter describes the steps you must perform to use the CICSplex SM Web User Interface. These steps consist of:

- “Preparing a CICS system to act as the Web User Interface server”
- “Configure CICS Web support” on page 342
- “Review CICS system initialization parameters” on page 343
- “Specify language and codepage” on page 344
- “Prepare codepage conversion table” on page 345
- “Generate the Program Load Table (PLT)” on page 345
- “Create the Web User Interface server repository (EYUWREP)” on page 346
- “Specify the customizable view and menu help data set” on page 346
- “Specify the Web User Interface server initialization parameters” on page 347
- “Update CICS CSD definitions” on page 355
- “Specify the JCL DD statements” on page 356
- “Security considerations” on page 357
- “Additional tasks” on page 359

Preparing a CICS system to act as the Web User Interface server

You should consider the following before you set up your CICS system to act as your Web User Interface server:

- The CICS system that you select to act as your Web User Interface server must be a dedicated CICS Transaction Server for z/OS, Version 3 Release 1 CICSplex SM MAS connected to a CICS Transaction Server for z/OS, Version 3 Release 1 CMAS. For information about how to set up a MAS, see the *CICS Transaction Server for z/OS Installation Guide*.
- Decide how many Web User Interface servers you need. For example:
 - If you intend to support more than one national language you need a Web User Interface server for every language you want to support.
 - You may want to have Web User Interface servers on multiple MVS images.
 - You may want to have more than one Web User Interface server for availability reasons.
 - The Web User Interface server creates and maintains state data when a user signs on via a web browser (or when an application using the data interface DATA/CONNECTs). Because of this state data, an affinity between the web browser (or application using the data interface) and server is created. The use of techniques like dynamic virtual IP addresses (DVIPA) or distributed DVIPA may not be able to honor this affinity. If this affinity is not honored, the usual result is for web browsers to redisplay the sign on screen or for data interface applications to receive a BADSTUB status.
 - If a the Web User Interface server has a different local IP address or name to the one used by users in their web browsers, for example due to a firewall or another reason that causes network address translation (NAT), the TCPIPHTTPhost Web User Interface server initialization parameter may be used to control the way the Web User Interface server generates URLs sent to web browsers. See 348 for details.

To set up your CICS system you should:

1. Create the CICS system and confirm that it is operational using the CICS-supplied installation verification procedures (IVPs). For information about the CICS IVPs, see the *CICS Transaction Server for z/OS Installation Guide*.
2. Configure CICSplexes for your Web User Interface servers. We suggest that you configure a separate CICSplex for your Web User Interface servers. For information, see the *CICS Transaction Server for z/OS Installation Guide*.
3. Ensure that the CMAS to which the Web User Interface connects is managing all CICSplexes that the Web User Interface server needs access to. This is because the Web User Interface server acts as an CICSplex SM API application. However, it is not necessary for the CMAS, to which the Web User Interface connects, to be managing any of the MASs in these CICSplexes. For information, see the *CICS Transaction Server for z/OS Installation Guide*.

If there is more than one CMAS on the MVS image, that the Web User Interface server will run on, you need to consider which CMAS the Web User Interface should connect to depending on which CICSplexes the CMAS is managing. To control this connection you can either:

- Ensure the CICSplex to which the Web User Interface server local MAS belongs is only managed by the CMAS or CMASs that the Web User Interface should connect to, or
 - Ensure that the Web User Interface server connects to a specific CMAS by specifying the CMASYSID EYUPARM for the server local MAS.
4. Define the Web User Interface server CICS system to CICSplex SM as a local MAS (for information, see the *CICS Transaction Server for z/OS Installation Guide*) and ensure that the CICS system has been set up correctly using the CICSplex SM installation verification procedures (IVPs).
 5. Consider basic monitoring of your Web User Interface servers. You can use standard CICSplex SM monitoring because the Web User Interface server is defined as a MAS.

Configure CICS Web support

You should always use a CICS Transaction Server for z/OS, Version 3 Release 1 system to act as your Web User Interface server. In order to configure CICS web support you should:

- Include the CICS resource definition group, DFHWEB, in the group list referenced by the GRPLIST system initialization parameter of your CICS system.
- Run the CICS Web support sample application, DFH\$WB1A, to ensure that CICS Web support has been set up correctly.

For more information about specifying CICS system initialization parameters and defining resources to CICS for CICS Web support, see the *CICS Internet Guide*.

If you wish to use the secure sockets layer (SSL) you should also:

- Create a key database containing a certificate
- Specify the appropriate system initialization parameters
- Install the appropriate resource definitions

For more information about SSL, see the *CICS Internet Guide*.

Notes:

1. You do not need to write your own Analyzer or Converter programs as these are provided with the Web User Interface.

2. On the Web User Interface initialization the TCPIP SERVICE is created and opened for you by the Web User Interface. You do, however, need to create a temporary TCPIP SERVICE definition to run the CICS Web support sample application. This temporary TCPIP SERVICE definition should be discarded after CICS Web support has been tested and before Web User Interface initialization has begun.
3. The Web User Interface can either use the default certificate in the key database or a named certificate. However, it can only use a named certificate provided that the label contains only alphanumeric characters and is a maximum of 32 characters.
4. The use of pre-CICS Transaction Server for z/OS, Version 3 Release 1 systems as Web User Interface servers is not supported.

Review CICS system initialization parameters

You need to specify the storage key for the CICS common work area (CWA), and the amount of storage required for the CWA on the CWAKEY and WRKAREA CICS system initialization parameters as follows:

```
CWAKEY=CICS  
WRKAREA=2048
```

To ensure that Web User Interface exception trace entries are written to the CICS auxtrace data set, as required to achieve first failure data capture, you should specify the USERTR, SYSTR, and AUXTR CICS system initialization parameters as follows:

```
USERTR=ON  
SYSTR=OFF  
AUXTR=ON
```

Note: If you set AUXTR=OFF, this is overridden at startup. The Web User Interface sets auxiliary trace on in order to record exception trace entries in the event of a problem that does not result in a SVCDUMP.

You should specify the CPSMCONN CICS system initialization parameter to invoke CICSplex SM code automatically during CICS initialization and initialize the region as a CICSplex SM Web User Interface server. This is the recommended alternative to specifying the CICSplex SM WUI initialization and shutdown programs in initialization and shutdown program list tables (PLTPI and PLTSD):

```
CPSMCONN=WUI
```

You should specify the action CICS should take if, at the next local midnight, the CICS time-of-day differs from the system time-of-day by more than 30 minutes (for example, after setting clocks forward or back to adjust for Summer and Winter time) as follows:

```
AUTORESETTIME=YES
```

Clients should continue to issue the CEMT PERFORM RESET command.

In addition to specifying the necessary CICS system initialization parameters for CICSplex SM local MAS execution, specify the appropriate CICS system initialization parameters to enable CICS Web Interface support, for your release of CICS. For example, TCPIP=YES for CICS Transaction Server for OS/390 version 1.3 or later.

For information about these parameters see the *CICS System Definition Guide*.

Specify language and codepage

In addition to specifying CICS system initialization parameters for the CICS Web Interface and CICSplex SM local MAS execution, the Web User Interface requires an INITPARM system initialization parameter to specify the server language and the client codepage. You need to code EYU9VKEC to represent the language of the Web User Interface server and EYU9VWAN to represent the codepage of the client on the INITPARM parameter.

You can select the server language and the client codepage from Table 24 and specify them on the INITPARM parameter as follows:

```
INITPARM=(EYU9VKEC='xxx',EYU9VWAN='yyy')
```

where xxx is the language identifier of the Web User Interface server and yyy is the codepage identifier of the client.

Table 24. Language and codepage identifiers for INITPARM

Language	Language identifier (EYU9VKEC)	Client codepage	Default client codepage identifier (EYU9VWAN)
US English	ENU	ISO-8859-1 (819)	ENU1
Japanese	JPN	Shift-JIS (943)	JPN1
Simplified Chinese	CHS	GB2312 (1381)	CHS1
Simplified Chinese	CHS	GB18030 (05488)	CHS2

For example, if your chosen language was English you would code the INITPARM parameter as follows:

```
INITPARM=(EYU9VKEC='ENU',EYU9VWAN='ENU1')
```

Notes:

1. The codepage identifier can be overridden for individual user requests by placing it in the URL used to access the Web User Interface. For example:

```
http://hostname:port/CICSplexSM/codepage
```

where *hostname* is the name specified on the TCPIPHOSTNAME Web User Interface server initialization parameter and *port* is the value specified on the TCPIPPORT Web User Interface server initialization parameter. For information about the Web User Interface server initialization parameters see “Specify the Web User Interface server initialization parameters” on page 347.

2. If the INITPARM system initialization parameter is not specified or if a value is not specified for EYU9VKEC or EYU9VWAN, the default values are ENU for the language and ENU1 for the codepage. However, operator messages are issued every time default values are used.
3. A simplified Chinese web user interface server can support client browsers using either GB2312 (CHS1) or GB18030 (CHS2). For GB2312 clients, the server uses the EBCDIC codepage, 935. For GB18030 clients, the server assumes a second EBCDIC codepage, 1388, which is a superset of codepage 935. View sets and menus edited using a GB2312 client browser are stored in 935 and can be used in either client codepage. However, if a view set or menu is edited using a GB18030 client and characters not available in 935 are used, the resulting views set or menu are not displayed correctly on GB2312 clients. Note that all supplied messages and starter set views and menus, and view

sets and menus customized using CICS TS 2.2 or earlier, use the 935 codepage and can be displayed on either client codepage.

4. Some web browsers do not support all the available client code pages. For example, many older browsers do not support GB18030.

Prepare codepage conversion table

You need to create or modify the DFHCNV table for data conversion to allow the Web User Interface to deal with incoming requests.

A sample copybook is provided in CICSTS31.CPSM.SEYUSAMP called EYU\$CNV1. This contains an entry for every language and client codepage combination that is supported as follows:

EYUENU1

Entry for English

EYUJPN1

Entry for Japanese

EYUCHS1

Entry for simplified Chinese (GB2312 clients).

EYUCHS2

Entry for simplified Chinese (GB18030 clients)

You should include a copy statement for EYU\$CNV1 in the DFHCNV source, for example, the CICS Web Interface sample, DFHCNVW\$. For information about the definitions required for the CICS Web Interface, see the *CICS Internet Guide*.

Once you have updated your DFHCNV source module, you should assemble and link-edit it using the CICS procedures for maintaining conversion table load modules.

The process used to assemble and link-edit the CICS conversion table load modules must have library CICSTS31.CPSM.SEYUSAMP in the SYSLIB concatenation of the assembler step, or the copy book member must be inserted into the table source member in place of the COPY statement.

Generate the Program Load Table (PLT)

The following paragraphs contain instructions for generating the PLT. However for CICS TS systems there is no need to specify the WUI initialization and shutdown programs in initialization and shutdown program list tables (PLTPI and PLTSD). The recommended alternative is to specify the CPSMCONN=WUI CICS system initialization parameter which will invoke CICSplex SM code automatically during CICS initialization to initialize the region as a CICSplex SM Web User Interface server.

Update your WUI PLTPI and PLTSD initialization and shutdown program list tables
with the following:

```
# DFHPLT TYPE=ENTRY,PROGRAM=EYU9VKIT
```

Note: This should be placed after the DFHDELIM for PLTPI and before the
DFHDELIM for the PLTSD. An example of the DFHDELIM for PLTPI is as
follows:

```
# DFHPLT TYPE=ENTRY,PROGRAM=DFHDELIM
# DFHPLT TYPE=ENTRY,PROGRAM=EYU9VKIT
```

When you have updated your PLT CICS resource definition table, assemble and link-edit it using the CICS procedures for maintaining resource definition table load modules.

Create the Web User Interface server repository (EYUWREP)

The Web User Interface server repository (EYUWREP) contains the Web User Interface server's view and menu definitions. You can use the IDCAMS utility to create a VSAM file for these definitions as follows:

```
DEFINE CLUSTER (                               -
          NAME( dsname )                       -
          VOLUMES( dsvol )                     -
          RECORDS( 5000 5000 )                 -
          RECORDSIZE( 8192 32000 )            -
          CONTROLINTERVALSIZE( 8192 )        -
          SPANNED                               -
          INDEXED                               -
          KEYS( 20 20 )                         -
          SHAREOPTIONS( 2 )                    -
        )
```

Figure 58. Sample definition to create Web User Interface repository

Each Web User Interface server must have its own Web User Interface server repository that cannot be shared with any other Web User Interface server.

You can copy the Web User Interface server repository from one Web User Interface server to another using IDCAMS, DFSMSdss or equivalent utility. For example, you may wish to copy the Web User Interface server repository from your test system to your production system.

You should migrate definitions using the import and export functions. For information, see the *CICSplex System Manager Web User Interface Guide*.

It is recommend that you back up the Web User Interface server repository data as the repository is updated whenever changes are made using the View Editor or when definitions are imported using the COVC transaction. You can back up the Web User Interface repository by using IDCAMS, DFSMSdss or equivalent utility.

Sample JCL to create the Web User Interface repository is provided, called EYUJWREP, in SEYUINST.

Specify the customizable view and menu help data set

The Web User Interface allows a site to provide customized help for individual views and menus. This help takes the form of HTML documents that can be served by the Web User Interface server or by an external server. If the Web User Interface is to serve the HTML documents, you must provide a partitioned data set to contain the HTML documents.

You can use the View Editor to customize your views and menus to include a link to the customizable view and menu help data set. The View Editor gives you the option of specifying:

- No help to be available for this view or menu

- Member name of a help page to be served by the Web User Interface from DFHHTML
- URL of an external help page to be served by another HTTP server

For information about the View Editor, see the *CICSplex System Manager Web User Interface Guide*.

The Web User Interface server uses the CICS Web Interface template manager to serve the customized view and menu help. For more information, see the *CICS Internet Guide*.

Note: The customizable view and menu help data set (DFHHTML) must be a single data set and should not be concatenated with any other data set.

Specify the Web User Interface server initialization parameters

You can specify the Web User Interface server initialization parameters in the start-up job or in a fixed block 80 data set. See “Specify the JCL DD statements” on page 356 for the DDname. All of these parameters are subject to the following conditions unless otherwise stated:

- Lines with an asterisk in column 1 are comments and are ignored.
- Values must not contain lower case characters.
- Values must be specified in parenthesis immediately following the parameter.
- Values must not be greater than 32 characters.

For example:

```
* An EYUWUI parameter data set
DEFAULTMENU(OURHOME)
TCPIPHOSTNAME(MVSXX.COMPANY.COM)
TCPIPPORT(4445)
```

A description of the Web User Interface server initialization parameters follows with default values for the parameters underlined>.

Required parameters

The Web User Interface server has some required initialization parameters. If you do not specify a required parameter the Web User Interface server initialization fails. The Web User Interface server initialization also fails if any of the specified parameters are invalid.

The required Web User Interface server initialization parameters are:

TCPIPHOSTNAME(name)

Specify the TCP/IP host name of this Web User Interface server. This is normally the host name and domain name of the MVS system (that is, a fully-qualified name). This host name is normally used by the Web User Interface to construct URLs, depending on the client's HTTP version and the value of the TCPIPHTTPhost Web User Interface server parameter.

This value is always returned in the TCPIPHOSTNAME header of a DATA/CONNECT Web User Interface Data Interface request.

The Web User Interface does not support names longer than 32 characters. If required, you may use the address of the server using the dotted decimal notation. For example, '127.0.0.1'.

TCPIPPORT(value)

Specify the TCP/IP port number of the port that you have allocated for the Web User Interface to run on.

The value specified in this parameter must correspond to the port number given on the CWBC transaction, if you are using a pre-CICS Transaction for OS/390 version 1.3 CICS system.

Optional parameters

You might also want to consider the following Web User Interface server initialization parameters:

AUTOREFRESH(YES|NO)

Disable the automatic refresh option for a WUI server. When YES is specified (the default), the automatic refresh control is displayed, based on the view definition. When NO is specified, the automatic refresh control is not displayed, even if automatic refresh is set on the view definition. For additional information on the automatic refresh option, see the CICSplex SM Web User Interface Guide (SC34-6841).

RESOURCELIMIT(WARNING|FAIL)

Specifies the action when the default warning count threshold is reached. When WARNING is specified (the default), message EYUVC1258W is issued and the user can select OK to ignore the warning threshold. When FAIL is specified, message EYUVC1267E is issued and the resource request is denied. The filter can be changed, but users of the WUI server will not be able to click OK to bypass a warning count.

Additional TCP/IP parameters

You can specify the following TCP/IP parameters only if you are using a CICS Transaction Server for OS/390 version 1.3 or later CICS system.

TCPIPADDRESS(name | INADDR_ANY)

Specify the dotted decimal IP address on which the Web User Interface will listen for incoming requests. If name is specified, it must be of the form nnn.nnn.nnn.nnn where nnn is 0 through 255. If INADDR_ANY is specified (the default), the Web User Interface will listen on any of the addresses known to the TCP/IP for OS/390 host.

You do not normally need to specify the TCPIPADDRESS option unless the OS/390 host has multiple TCP/IP addresses.

TCPIPHTTPHOST(NO|YES)

Indicate whether you require the TCP/IP host name used to construct URLs to be generated based on the incoming HTTP request for HTTP version 1.1 requests or later.

This option has no effect on pre HTTP 1.1 requests sent to the Web User Interface server. The Web User Interface server will always construct URLs using the host name specified in the TCPIPHOSTNAME Web User Interface server parameter for HTTP 1.0 (and earlier) requests.

NO For HTTP 1.1 (or later) requests, the host name used in URLs constructed by the Web User Interface server is based on the value specified in the TCPIPHOSTNAME Web User Interface server parameter.

YES For HTTP 1.1 (or later) requests, the host name used in URLs constructed by the Web User Interface server is based on the incoming URI or HTTP 'Host' header according to the HTTP 1.1 specification.

When HTTP 1.1 clients are used with a Web User Interface server running
TCPIPHTTPHOST(YES), the IP address or name used on the server, does not
need to be the same as that used by the HTTP 1.1 client. This can allow the
Web User Interface to be used when name address translation (NAT) is
performed (for example due to a firewall).

If TCPIPSSL(YES) is used with TCPIPHTTPHOST(YES) and HTTP 1.1 clients
are used along with different IP address names, you may receive SSL certificate
warnings due to host name mismatches.

TCPIPSSL(YES | NO)

| Indicate whether you require data encryption between your Web User Interface
| server and web browser. If you select YES, you must have specified the
| appropriate system initialization parameters to enable SSL support in the CICS
| Web Interface. For information see the *CICS Internet Guide*.

TCPIPSSLCERT(name)

| Specify (in upper case characters) the label for the SSL certificate that is to be
| used for the connection between the Web User Interface and the web browser.
| If you specify an explicit certificate, the label must be no longer than 32
| characters.

| The default is the default certificate in the key database or key ring, as
| applicable.

| **Note:** The names of all SSL certificates to be used with the WUI server must
| be upper case.

Import option

| You can specify the following parameter if you want the Web User Interface server
| to import automatically menus and view sets from a specified TD queue. This is an
| alternative to using the import function of the COVC transaction.

AUTOIMPORTTDQ(*tdq_name*)

| Specifies the name of the CICS extrapartition transient data queue from which
| you want the server to import menu and view sets automatically during server
| initialization. In order to use this option, you need to enter a value explicitly.
| There is no automatic default, however, queue name COVI (DD name
| EYUCOVI) is defined in the CICSplex SM CSD group EYU nnn GW.

| **Note:** Include this parameter in the Web User Interface initialization parameters
| for the following occasions only:

- When starting the Web User Interface server for the first time.
- When starting the Web User Interface server after the view sets have been replaced or modified as a result of service (by a PTF).
- If you are already a CICSplex SM user and want to import other view sets into your existing EYUWREP data set.

| Avoid using this parameter at other times because of the overhead
| involved in performing the import operation.

Data formatting options

| These options determine how data will appear on Web User Interface displays.

CVDASTYLE(MIXED | UPPER)

| Indicate whether the CVDAs, EYUDAs, and so on should be displayed in upper
| case or mixed case characters.

| **MIXED**

| Mixed case text, that is, the first character upper case and the rest
| lower case, for example, 'Enabled'.

| **UPPER**

| Text is displayed in upper case only.

| **DATEFORMAT (format)**

| Specify the format to be used to display the date on Web User Interface
| displays as follows:

| **YYMMDD**

| **DDMMYY**

| **MMDDYY**

| **YYYYMMDD**

| **DDMMYYYY**

| **MMDDYYYY**

| where:

| **DD** is the day.

| **MM** is the month.

| **YY and YYYY** are the year in two-digit or four-digit format, respectively.

| **DATESEPARATOR(character | /)**

| Specify the character to be used to separate the date elements on Web User
| Interface displays.

| **DECIMALSEPARATOR(character | .)**

| Specify the character to be used to denote the decimal point on Web User
| Interface displays.

| **GMMTEXTMSG(NO | YES | BEFORE | AFTER)**

| Specify how the CICS "good morning" message is handled.

| **NO** The message is not issued

| **YES** The message is issued before and after signon.

| **BEFORE**

| The message is issued before signon only.

| **AFTER**

| The message is issued after signon only.

| **MSGCASE (MIXED | UPPER)**

| Indicate whether messages destined for the operator or EYULOGs should be
| displayed in mixed case or upper case characters.

| **MIXED**

| Mixed case text is displayed.

| If you specify MIXED, output may be displayed incorrectly on Katakana
| display terminals, where lower case characters are displayed as
| Katakana symbols.

| **UPPER**

| Text is displayed in upper case only.

| **THOUSNDSEPARATOR(character | ,)**

| Specify the character to be used to separate thousands on Web User Interface
| displays, when required. For example, 100000 is displayed as 100,000 if the
| default is used.

| **Notes:**

- | 1. The space character (hex 40) is a valid THOUSNDSEPARATOR value,
| allowing digits to be grouped by a space.
| 2. Use 0 (zero) to suppress the THOUSNDSEPARATOR value.
| 3. The THOUSNDSEPARATOR value is used only when required by the
| individual view definition.

| **TIMESEPARATOR(character | :)**

| Specify the character to be used to separate hours, minutes, and seconds on
| Web User Interface displays.

| **Environment options**

| These specify the context and scope values, and the home menu and navigation
| frame, used by the Web User Interface unless overridden.

AUTOREFRESH(YES | NO)

Disable the automatic refresh option for a WUI server. The default setting, YES,
displays automatic refresh control, based on the view definition. When NO is
specified, automatic refresh control is not displayed, even if automatic refresh
control is set on the view definition. See the CICSPlx SM Web User Interface
Guide for more information on the automatic refresh option.

| **DEFAULTCMASCTXT(name | EYUCMS1A)**

| Specify the CMAS context that is set when the user signs onto the Web User
| Interface.

| **DEFAULTCONTEXT(name | EYUPLX01)**

| Specify the context that is set when the user signs onto the Web User Interface.

DEFAULTMAPCOLL(value | 0)

Specify the number of rows in a generated map below which a map opens in
the expanded state. If the number of rows to be displayed is above this number,
the map opens in a fully collapsed state. The default value of 0 means that in
every generated map all of the rows are visible when opened.

| **DEFAULTMENU(name | EYUSTARTMENU)**

| Specify the name of the menu that is be presented to users after sign onto the
| Web User Interface.

| **DEFAULTNAVIGATE(name | EYUSTARTNAVIGATE)**

| Specify the name of the navigation frame that is presented to users after sign
| onto the Web User Interface.

| **DEFAULTSCOPE(name | EYUPLX01)**

| Specify the scope that is set when the user signs onto the Web User Interface.

| **DEFAULTWARNCNT(value)**

| Specify the number of records required to trigger the record count warning
| mechanism before opening a view. This can take an integer value in the range
| of 0 to 99999999. The default value is 0 meaning no warnings are issued.

| **Note:** You can also set a record count warning value applying to a group of
| users when setting up a WUI user group (this applies only if the WUI is

running with security switched on). A value set in a user group takes precedence over a value set in the DEFAULTWARNCNT parameter for the users in that group.

GLOBALPREFILTER(YES | NO)

Specify whether to filter parameters the first time a view is displayed (before data is collected).

Note: You can also specify this parameter when setting up a WUI user group (this applies only if the WUI is running with security switched on). A value set in a user group takes precedence (for users in that group) over the value set in the GLOBALPREFILTER parameter.

RESOURCELIMIT(WARNING | FAIL)

Specify whether a warning or failure is issued when the resource limit is reached. The default setting, WARNING, issues message EYUVC1258W and the user can select OK to bypass the warning threshold. Specify FAIL to issue message EYUVC1267E and to deny the new resource request. The WUI server can be used to change the RESOURCELIMIT filter, however the WUI server cannot be used to bypass the warning threshold.

Operation options

These options name the default view set to be used if the Web User Interface receives an external request that does not specify a view set name but specifies an object name. The view sets that you name in these options must represent the objects that may be specified. For more information see the *CICSplex System Manager Web User Interface Guide*.

These parameters can be ignored if you do not intend to launch Web User Interface displays in this manner.

DEFAULTCICSplex(name | EYUSTARTCICSplex)

Specify the name of the default CICSplex view set.

DEFAULTCICSrgn(name | EYUSTARTCICSrgn)

Specify the name of the default CICS region view set.

DEFAULTCONNECT(name | EYUSTARTCONNECT)

Specify the name of the default connection view set.

DEFAULTCSysgrp(name | EYUSTARTCSysgrp)

Specify the name of the default CICS system group view set.

DEFAULTDB2SS(name | EYUSTARTDB2SS)

Specify the name of the default DB2 subsystem view set.

DEFAULTEJCObean(name | EYUSTARTEJCObean)

Specify the name of the default Enterprise Bean in a CorbaServer view set.

DEFAULTEJDJbean(name | EYUSTARTEJDJbean)

Specify the name of the default Enterprise Bean in a CICS-deployed JAR file view set.

DEFAULTEVENT(name | EYUSTARTEVENT)

Specify the name of the default event view set.

DEFAULTLOCfile(name | EYUSTARTLOCfile)

Specify the name of the default local file view set.

DEFAULTLOctran(name | EYUSTARTLOctran)

Specify the name of the default local transaction view set.

| **DEFAULTPROGRAM(name | EYUSTARTPROGRAM)**
 | Specify the name of the default program view set.

| **DEFAULTREMFIL(name | EYUSTARTREMFIL)**
 | Specify the name of the default remote file view set.

| **DEFAULTREMTRAN(name | EYUSTARTREMTRAN)**
 | Specify the name of the default remote transaction view set.

| **DEFAULTTASK(name | EYUSTARTTASK)**
 | Specify the name of the default task view set.

User options

| **INACTIVETIMEOUT(value | 30)**
 | Specify the period, in minutes, after which inactive user sessions are
 | terminated. The maximum period allowed is 10080 minutes (7 days).

| **MAXUSERS(value | 20)**
 | Specify the maximum number of concurrent users of the Web User Interface.
 | The maximum number of concurrent users allowed is 50.

SIGNONPANEL(BASIC | ENHANCED)
 # Specifies, if the Web user Interface server has CICS security active (SEC=YES
 # in the system initialization parameter), whether the Web User Interface sign on
 # panel takes one of the following actions:
 #
 # • Displays a GROUP option
 # • Saves previously used USER and GROUP values
 # • Positions the cursor in the sign on field requiring input

When the default value, BASIC, is specified, the GROUP option is not displayed
 # on the sign on screen and the user group profile is set to the default group of
 # the user. Values are not saved and the cursor is not positioned on the sign on
 # panel.

When the value, ENHANCED, is specified, the GROUP option is displayed on
 # the sign on screen and the following events occur:
 #
 # • If the user enters a value, sign on proceeds and if:
 # – The user ID is connected to the specified group, the group is used for the
 # WUI user group profile
 # – The user ID is not connected to the specified group or the group name is
 # not valid, sign on continues, but the WUI group profile is set to the default
 # group of the user, and message EYUVC1227W is issued to the WUI user
 # after sign on is complete. Message EYUVS0024W is written to the WUI
 # server's EYULOG.
 # • If the user does not enter a value, the user group profile is set to the default
 # group of the user

The GROUP option does not change the current connect group of the user
 # being signed on. The security environment built by the WUI is always based on
 # the default group of the user. The group option on the WUI signon screen
 # specifies which WUI user group profile the user should be associated with and
 # does not change any security decisions that might be made by the External
 # Security Manager.

When the SIGNONPANEL(ENHANCED) option is set and JavaScript is enabled
 # in the web browser, the sign on process performs the following actions:
 #
 # • Saves the user ID and group values in a cookie, so that when the signon
 # process next runs, the form is filled with previously entered values

• Positions the cursor to the sign on field requiring input

Whether the Web User Interface user group profile is set based on the default

group, or specified on the GROUP option, if no matching Web User Interface

group profile is found, the values usually set using a user group profile are set

to the system default.

The SIGNONPANEL option is ignored if the Web User Interface server is

running with CICS Security inactive (SEC=NO in the system initialization

parameter).

Accessibility options

These parameters specify the default colors for the Web User Interface displays.

These parameters should not normally be changed as they effect all users of the Web User Interface server. If you want to change these parameters for reasons of accessibility, take care to ensure that the Web User Interface displays do not become unreadable.

Each parameter specifies a color as six hexadecimal digits. Each pair of digits describes the red, green and blue components of the color, respectively. For example, FFFFFFFF represents white, 000000 represents black, FF0000 represents bright red, 00FF00 represents bright green, and 0000FF represents bright blue.

COLORPAPER(color)

Main work frame background color.

COLORPAPERHEAVY(color)

Navigation and assistance frame background color.

COLORPAPERLIGHT(color)

Background color used for many interface items (for example, information messages, table column headings, detail view labels, view selection and refresh area).

COLORPAPERWARN(color)

Background color for warning messages.

COLORPAPERERROR(color)

Background color for error messages.

COLORPAPERALT(color)

Background color for alternate rows on tabular displays.

COLORPAPERRULE(color)

Background color for assistance frame bar containing the navigation and help icons.

COLORINK(color)

Main work frame text color.

COLORINKBANNER(color)

Navigation and assistance frame text color.

COLORINKLINK(color)

Unvisited link text color.

COLORINKVLINK(color)

Visited link text color.

Problem determination option

WUITRACE(trace levels)

Specifies the level of tracing for the Web User Interface server.

The trace levels that you specify must be separated by a comma. For example:

```
WUITRACE(8,11,13,15,18)
```

You can define a range of trace levels, for example:

```
WUITRACE(1:5)
    activates trace levels 1 through 5
```

```
WUITRACE(1:5,13,28:31)
    activates trace levels 1 through 5, 13, and 28 through 31
```

Attention: It is recommended that you only activate trace at the request of IBM Support Center personnel.

Update CICS CSD definitions

The resource definitions that you must add to the CSD file for the Web User Interface are distributed in CSD upgrade load modules in CICSTS31.CPSM.SEYULOAD.

The names of the load modules are EYU9nnG1, where nn represents the CICS level (for example, 64 refers to CICS Transaction Server for z/OS Version 3 Release 1, and 63 refers to the CICS element of CICS Transaction Server for z/OS Version 2 Release 3). The name of the resource group (created using the definitions the load modules contain) is EYU310GW.

Note: EYU9nnG1 also contains LMAS group EYU310G1.

You can use the sample JCL shown in Figure 59 to:

- Define a group of resource definitions to the appropriate CSD file
- Add the group name to the CSD list referenced by the CICS system initialization parameter GRPLIST

```
//CSDUP   EXEC PGM=DFHCSDUP
//STEPLIB DD DSN=cics.index.SDFHLOAD,DISP=SHR
//        DD DSN=cpsm.index.SEYULOAD,DISP=SHR
//DFHCSD  DD DSN=cics.dfhcscd,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSIN   DD *
          UPGRADE USING(group_load_module)
          ADD GROUP(EYU310GW) LIST(list_name)
/*
```

Figure 59. Sample JCL to upgrade CSD to include Web User Interface group

Modify the sample JCL to provide the following information:

cics.index.SDFHLOAD

Is the CICS load library that contains the DFHCSDUP module.

cpsm.index.SEYULOAD

Is the CICSplex SM load library that contains the group definition modules EYU9nnG1.

cics.dfhcscd

Is the CICS CSD file that is to be updated.

| **group_load_module**

| Is the load module, EYU9nnG1, that contains the resource definition group,
| EYU310GW, appropriate for the level of CICS being used.

| **list_name**

| Is the group list that is used to start the Web User Interface server.

| **Transient data queue definitions**

| You need definitions for the following transient data queues (TDQs):

| **COVP** The Web User Interface server initialization parameters data set, EYUWUI.
| This is a fixed block 80 input data set.

| **COLG** The CICSplex SM output log, EYULOG. This is a variable length output
| data set.

| **COVI** Sample definition for the Web User Interface import data set, EYUCOVI.
| This is a variable length input data set.

| **COVE** Sample definition for the Web User Interface export data set, EYUCOVE.
| This is a variable length output data set.

| **CICS Transaction Server definitions**

| If you are using the CICS element of CICS Transaction Server for z/OS, the
| transient data queue (TDQ) definitions are provided in resource group EYU310GW.

| COVI and COVE are provided as samples that can be used to create additional
| import and export transient data queues.

| For more information about the COVI and COVE TDQs see the *CICSplex System*
Manager Web User Interface Guide.

Temporary storage models

TSMODELs and TSMDEFs should not be installed into a Web User Interface (WUI)
server.

| **Specify the JCL DD statements**

| Additional DD statements should be added to the Web User Interface server for the
| following data sets:

| **EYUWUI**

| The Web User Interface server initialization parameters data set. See
| “Specify the Web User Interface server initialization parameters” on page
| 347.

| **EYUWREP**

| The Web User Interface server repository data set. See “Create the Web
| User Interface server repository (EYUWREP)” on page 346.

| **EYULOG**

| The CICSplex SM output log.

| **DFHHTML**

| The customizable view and menu help data set. See “Specify the
| customizable view and menu help data set” on page 346. This is optional.

EYUCOVI

The Web User Interface server import data set. For more information see “Transient data queue definitions” on page 356 and the *CICSplex System Manager Web User Interface Guide*. This is optional.

EYUCOVE

The Web User Interface server export data set. For more information see “Transient data queue definitions” on page 356 and the *CICSplex System Manager Web User Interface Guide*. This is optional.

For example,

```
/*  
//DFHHTML DD DISP=SHR,DSN=data set name  
//EYUWREP DD DISP=SHR,DSN=data set name  
//EYUCOVI DD DISP=SHR,DSN=CICSTS31.CPSM.SEYUVIEW(EYUEVX01)  
//EYULOG DD SYSOUT=*  
//EYUWUI DD *  
DEFAULTMENU(OURHOME)  
TCPHOSTNAME(MVSXX.COMPANY>COM)  
TCPPIPORT(4445)  
/*
```

Security considerations

This section describes the Web User Interface security requirements for CICS security, Secure Sockets Layer (SSL) support, and access to MVS data sets.

CICS security considerations

If your Web User Interface server region is running with CICS security active, you need to define the security access required:

- For the CICS Web Interface
- By the administrator
- By the end-user and users of the View Editor

Table 25 on page 358 summarizes the access required by the various userids.

You may wish to use CICS transaction security (see the *CICS RACF Security Guide*) to limit the users who are allowed to control the Web User Interface server via the COVC transaction.

See the *CICSplex System Manager Web User Interface Guide* for information about how to control users of the Web User Interface and to limit what resources they are allowed to access.

Security access for the CICS Web Interface

If CICS transaction security is in use the CICS DFLTUSER (for a CICS Transaction Server for OS/390 version 1.3 or later system) or the CWBM transaction userid (for a pre-CICS Transaction Server for OS/390 version 1.3 system) must be given access to the COVP, COVU, and COVE transactions.

Security access for the administrator

The userid that starts the Web User Interface (terminal user of COVC or PLTPIUSR, if started automatically via PLTPI) must have access to the COVC and COVG transactions.

If CICS surrogate user security checking is active in the Web User Interface server region, the userid that started the Web User Interface (terminal user of COVC or

PLTPIUSR, if started automatically via PLTPI) must have READ access to wui-userid.DFHSTART in the SURROGAT class for all Web User Interface users.

Security access for the end-user and users of the View Editor

The Web User Interface end-user needs access to the COVA transaction and CICSplex SM.

Users of the View Editor need access to the COVA transaction, CICSplex SM and the View Editor profile. For more information about access to the View Editor, see the *CICSplex System Manager Web User Interface Guide*.

All users who are successfully signed onto the Web User Interface have access to all of the customizable view and menu help pages, if the customizable view and menu help is served by the Web User Interface.

Summary

Table 25 summarizes the security accesses required by users of the Web User Interface.

Table 25. Security accesses required by users of the Web User Interface

User Roles	CICS Web Interface	Administrator	End-user	View Editor
Transactions	COVP COVE COVU	COVG COVC	COVA	COVA
CICS surrogate user security		Yes		
View Editor profile				Yes
CICSplex SM and CICS security			As appropriate for individual users	As appropriate for individual users

Secure Sockets Layer support

If you are using a CICS Transaction Server for OS/390 version 1.3 or later system, you can provide secure connections by using the Secure Sockets Layer (SSL) support to provide encryption on the connection. For information about SSL support, see the *CICS Internet Guide*. Also, see “Specify the Web User Interface server initialization parameters” on page 347 for information about the TCPIPSSL and TCPIPSSLCERT, Web User Interface server initialization parameters, that you need to specify for SSL support.

Note: Web User Interface SSL support uses server authentication only. User authentication is by the external security manager (ESM) user ID and password.

Authorizing access to MVS data sets

In addition to standard CICS and CICSplex SM requirements, the CICS region userid must have the authority to access the data sets associated with the DDnames described in Table 26.

Table 26. Security access required for MVS data sets

DDnames	Access required
EYUWUI	READ

Table 26. Security access required for MVS data sets (continued)

DFHHTML	READ
EYUCOVI (and clones)	READ
EYUWREP	UPDATE
EYULOG	UPDATE
EYUCOVE (and clones)	UPDATE

Additional tasks

After you have set up the Web User Interface you need to:

Submit start-up JCL

You should submit the start-up JCL for the Web User Interface server to start it for the first time. To confirm that the Web User Interface server has started successfully, you should ensure that the following messages are displayed on the job log:

```
08.52.33 JOB03331 +EYUVS0001I IYCQCTA5 CICSplex SM Web User Interface
                                initialization started.
08.52.37 JOB03331 +EYUVS0002I IYCQCTA5 CICSplex SM Web User Interface
                                initialization complete.
```

If you chose not to start the Web User Interface server during PLTPI processing, you can start it using the COVC transaction Start command.

Check browser connection

You should check the connection between the Web User Interface and the web browser by typing in the following URL:

```
http://hostname:port/CICSplexSM
```

where *hostname* is the name specified on the TCPIPHOSTNAME Web User Interface server initialization parameter and *port* is the value specified on the TCPIPSPORT Web User Interface server initialization parameter. For information about the Web User Interface server initialization parameters see “Specify the Web User Interface server initialization parameters” on page 347. You should be presented with the Web User Interface server Welcome panel containing a Begin Signon button.

Obtain view and menu definitions

Once the Web User Interface has been started, you should obtain some view and menu definitions. You can do this by either:

- Logging onto the CICS terminal and running the COVC transaction. The Import option of the COVC transaction enables you to import the starter set views and menus. The starter set views and menus are provided in CICSTS31.CPSM.SEYUVIEW. For information about the COVC transaction, see the *CICSplex System Manager Web User Interface Guide*.
- Using the View Editor. For information about the View Editor see the *CICSplex System Manager Web User Interface Guide*.

Shutdown the Web User Interface server

You can shutdown the Web User Interface server by:

- Shutting down the CICS system in which the Web User Interface server is running.
- Using the COVC transaction. For more information about the COVC transaction see the *CICSplex System Manager Web User Interface Guide*.

Chapter 47. Configuring the Starter Set

The CICSplex SM Starter Set establishes a sample CICSplex SM environment of eight managed CICS systems (MASs) across two MVS images, which are referred to as system A and system B. This chapter describes:

- “The Starter Set samples libraries”
- “Creating the Starter Set environment” on page 364
- “Deleting the Starter Set” on page 368
- “Using the Starter Set as a model” on page 368.

For a description of the structure and purpose of the Starter Set, see the *CICSplex System Manager Concepts and Planning* manual.

The Starter Set samples libraries

The Starter Set is in two samples libraries that are installed automatically when CICSplex SM itself is installed. The libraries are:

- CICSSTS31.CPSM.SEYUJCL, which contains sample JCL for creating, starting, and deleting the Starter Set components
- CICSSTS31.CPSM.SEYUDEF, which contains definitions, such as CICS tables and VTAM definitions, required by the Starter Set

The contents of the data sets CICSSTS31.CPSM.SEYUJCL and CICSSTS31.CPSM.SEYUDEF are described in the remainder of this section.

JCL in CICSSTS31.CPSM.SEYUJCL for creating the Starter Set

Table 27, and Table 28 identify the JCL supplied in CICSSTS31.CPSM.SEYUJCL for creating the Starter Set.

Table 27. JCL for creating the system A components of the Starter Set

Sample name	Description
EYUJBBIA	Creates the CAS data sets EYUSDEF and EYUIPRM
EYUJCICA	Creates all data sets for MASs EYUMAS1A, EYUMAS2A, EYUMAS3A, and EYUMAS4A
EYUJCMSA	Creates all data sets for CMAS EYUCMS1A
EYUJDRPA	Creates the data repository for CMAS EYUCMS1A
EYUJCSDA	Creates DFHCSD data set for MASs and CMAS

Table 28. JCL for creating the system B components of the Starter Set

Sample name	Description
EYUJBBIB	Creates the CAS data sets EYUSDEF and EYUIPRM
EYUJCICB	Creates all data sets for MASs EYUMAS1B, EYUMAS2B, EYUMAS3B, and EYUMAS4B
EYUJCMSB	Creates all data sets for CMAS EYUCMS1B
EYUJDRPB	Creates the data repository for CMAS EYUCMS1B
EYUJCSDB	Creates DFHCSD data set for MASs and CMAS

To create those components of the Starter Set belonging to CICSplex EYUPLX01 only, you must run both the system A JCL and the system B JCL.

To create those components of the Starter Set belonging to CICSplex EYUPLX02 only, you must run the system B JCL.

JCL in CICSTS31.CPSM.SEYUJCL for running the Starter Set

Table 29 and Table 30 list and describe the JCL supplied in CICSTS31.CPSM.SEYUJCL for running the Starter Set.

Table 29. JCL for running the system A components of the Starter Set

Sample name	Description
EYUJCS1A	Starts CAS EYUCAS1A
EYUJCSSA	Starts CAS EYUCAS1A as a started task
EYUJCM1A	Starts CMAS EYUCMS1A
EYUJMS1A	Starts MAS EYUMAS1A
EYUJMS2A	Starts MAS EYUMAS2A
EYUJMS3A	Starts MAS EYUMAS3A
EYUJMS4A	Starts MAS EYUMAS4A

Table 30. JCL for running the system B components of the Starter Set

Sample name	Description
EYUJCS1B	Starts CAS EYUCAS1B
EYUJCSSB	Starts CAS EYUCAS1B as a started task
EYUJCM1B	Starts CMAS EYUCMS1B
EYUJMS1B	Starts MAS EYUMAS1B
EYUJMS2B	Starts MAS EYUMAS2B
EYUJMS3B	Starts MAS EYUMAS3B
EYUJMS4B	Starts MAS EYUMAS4B

To run those components belonging to CICSplex EYUPLX01 only, you use both the system A JCL and the system B JCL.

To run those components belonging to CICSplex EYUPLX02 only, you use only the system B JCL.

Definitions in CICSTS31.CPSM.SEYUDEF for the Starter Set environment

Table 31 and Table 32 on page 363 identify the supplied Starter Set definitions that are required on system A and system B.

Table 31. Starter Set definitions in CICSTS31.CPSM.SEYUDEF for system A

Sample name	Description
EYUDVTMA	VTAM definitions
EYUDCSDX	CICS TS for OS/390 1.3 DFHCSDUP definitions for Starter Set
EYUDCSDZ	CICS Transaction Server for z/OS 2.2, 2.3 and 3.1 DFHCSDUP definitions for Starter Set
EYUDCDMA	CDRM definitions
EYUDCDSA	CDRSC definitions
EYUMDTAB	Modetable for CAS EYUCAS1A
EYUTPLTC	DFHPLT for CMAS EYUCMS1A
EYUTPLTL	DFHPLT for local MASs
EYUTSRTS	DFHSRT for CMAS EYUCMS1A and for MASs

Table 31. Starter Set definitions in CICSTS31.CPSM.SEYUDEF for system A (continued)

Sample name	Description
EYU@ISPF	ISPF logon procedure
EYU@PRIM	ISPF primary option panel

Table 32. Starter Set definitions in CICSTS31.CPSM.SEYUDEF for system B

Sample name	Description
EYUDVTMB	VTAM definitions
EYUDCDMB	CDRM definitions
EYUDCDSB	CDRSC definitions
EYUMDTAB	Modetable for CAS EYUCAS1B
EYUTPLTC	DFHPLT for CMAS EYUCMS1B
EYUTPLTL	DFHPLT for local MASs
EYUTSRTS	DFHSRT for CMAS EYUCMS1B and for MASs
EYU@ISPF	ISPF logon procedure
EYU@PRIM	ISPF primary option panel

CICSplex EYUPLX01 uses both the system A and the system B definitions.

CICSplex EYUPLX02 uses the system B definitions.

The Starter Set naming convention

The CICSplex SM components of the Starter Set are named according to the following convention:

Table 33. Starter Set naming convention: CICSplex SM resources

CICSplex SM resource	Convention
Coordinating address space (CAS)	EYUCASxx
CICS system group	EYUCSGxx
CICSplex	EYUPLXxx
CICSplex SM address space (CMAS)	EYUCMSxx
Managed address space (MAS)	EYUMASxx
Monitor definition	EYUMODxx
Monitor group	EYUMOGxx
Monitor specification	EYUMOSxx
Workload definition	EYUWLDxx
Workload group	EYUWLGxx
Workload specification	EYUWLSxx
Transaction group	EYUTRGxx
Analysis definition	EYURTDxx
Evaluation definition	EYURTExx
Analysis group	EYURTGxx
Analysis specification	EYURTSxx
Analysis point specification	EYURAPxx
Action definition	EYURTAxx

Table 33. Starter Set naming convention: CICSplex SM resources (continued)

CICSplex SM resource	Convention
Status definition	EYURSTxx
Time Period definitions	EYUPDFxx
Resource group	EYUBAGxx
Resource description	EYUBADxx
Resource assignment	EYUBAxx

CICS resource definitions used by the Starter Set are named according to the following convention:

Table 34. Starter Set naming convention: CICS resources

CICS resource definition type	Convention
Connections	xxxx
Files	EYUFILxx
Journals	EYUJNLxx
Modenames	EYUMDNxx
Programs	EYUPRGxx
Terminals	Exxx
Transactions	ETxx
Transient data queues	EQxx

Creating the Starter Set environment

To configure the Starter Set on any MVS image, you must have access on that MVS image to:

- The Starter Set data sets CICSTS31.CPSM.SEYUDEF and CICSTS31.CPSM.SEYUJCL
- CICS load libraries
- CICS table-assembly JCL
- SYS1.PARMLIB and SYS1.VTAMLST (or be able to add definitions to SYS1.PARMLIB and SYS1.VTAMLST)
- The MVS console log via TSO SDSF.

Selecting the Starter Set configuration

The complete Starter Set is installed across two MVS images and comprises two CICSplexes, EYUPLX01 and EYUPLX02. You can install the complete Starter Set, or you can install a specific subset of it. That is, you can install:

- The system A components only
- The system B components only
- EYUPLX01 only (which comprises the system A components and the system B components)
- EYUPLX02 only (which comprises the system B components).

When you have identified those parts of the Starter Set you want to install, locate the appropriate tables of JCL and definitions in this chapter. For example, to define and start the system A components only, you will:

- Run the JCL described in Table 27 on page 361
- Run the JCL described in Table 29 on page 362
- Use the definitions described in Table 31 on page 362.

When you have identified the JCL and sample definitions you will be using, follow the procedure described in “Defining the Starter Set environment.”

Defining the Starter Set environment

This section describes the tasks you must perform to incorporate the Starter Set in your MVS environment.

Notes:

1. If you have already run an IVP (as described in Chapter 53, “CICSplex SM installation verification procedures,” on page 407) on the MVS image on which you are planning to configure the Starter Set, you will already have performed most of the steps described below. You do not need to repeat those steps, unless the Starter Set components created during the IVP have been deleted.
2. The Starter Set MAS JCL and the CSD update job do not support languages other than assembler. If you require support for other languages, please make appropriate changes to DFHRPL (for the MAS JCL) and to DFHCSDUP.

Carry out the following steps as appropriate:

1. Versions of CICS in CICS Transaction Server for OS/390 and CICS Transaction Server for z/OS use MVS log streams for their system logs and require appropriate MVS and CICS definitions to be in place. If you already have CICS TS levels of CICS installed, and if you use the default naming convention of userid.applid.DFHLOG and userid.applid.DFHSHUNT for the system log streams, you can proceed to the next step without taking any further action. However, you might want to review the coupling facility space implications of creating new CICS system logs.

If you do not use the default naming convention for your system logs, or you have never previously brought up a CICS Transaction Server level of CICS, you should seek assistance from your CICS and MVS system programmers to set up the logger definitions for the sets of system logs that you require. For a full description of how to create the required MVS and CICS definitions for MVS log streams, see Chapter 24, “Defining the logger environment for CICS journaling,” on page 143 and the *CICS System Definition Guide*.

Whichever naming convention you adopt, do not define the CICS system log as type DUMMY, as this would compromise data integrity on the CICSplex SM data repository.

2. Run the EYUISTRT job to tailor the Starter Set JCL for your environment. EYUISTRT runs the EYUINST EXEC to tailor the Starter Set members. For more information about using EYUISTRT, see Chapter 49, “Using the EYUINST EXEC to tailor skeleton jobs,” on page 373. Table 35 identifies those EYUINST EXEC parameters that are applicable to the Starter Set.

Table 35. EYUINST EXEC parameters required for the Starter Set

Parameter	CMAS	MAS	Default
BLKU	Yes	Yes	6144
CINDEXnnn	Yes	Yes	None
CMASNAME	Yes		None
CRELEASE	Yes	Yes	6.4.0

Table 35. EYUINST EXEC parameters required for the Starter Set (continued)

Parameter	CMAS	MAS	Default
DSINFO	Yes	Yes	index dsvlsr dsunit
ENVIRONMENT	Yes	Yes	None
INDEX	Yes	Yes	CICSTS31.CPSM
JOB	Yes	Yes	//XXXXXXXXX JOB
LIB	Yes	Yes	index.XEYUINST
PREFIX	Yes	Yes	EYU
SCEESAMP	Yes		SYS1.SCEESAMP
SCOPE	Yes	Yes	POST
Note: The SCOPE value must be set to STARTER.			
SELECT	Yes		None
TEMPLIB	Yes	Yes	index.SEYUJCL
Note: For more information about TEMPLIB, see “EYUINST EXEC parameters” on page 375			
WORKUNIT	Yes	Yes	SYSDA
WORKVOL	Yes	Yes	•

3. Add VTAM definitions for the CAS, CMAS, and MASs (as appropriate) to the VTAM table. For example, for the system A Starter Set components, the relevant VTAM definitions are in members EYUDVTMA, EYUDCDMA, and EYUDCDSA of CICSTS31.CPSM.SEYUDEF.

Note: If you use Advanced Communications Function (ACF) Network Control Programs (NCPs), you may need to create a mode table, using the sample entry shown in EYUMDTAB, in order to control the VTAM RUSIZE (request unit size) parameter.

4. Run the JCL EYUJBB1x to define the CAS data sets.
5. Run the JCL EYUJCMSx to define the CMAS data sets.
6. Run the JCL EYUJCICx to define the MAS data sets.
7. Run the JCL EYUJDRPx to define the CMAS data repository.
8. Run the JCL EYUJCSDx to define, initialize, and load the CSD.
9. Make any necessary site-specific changes to the CSD. For example, you might need to add TYPETERMs, TERMINALs, or AUTOINSTALL MODELs.
10. Assemble the sample CICS tables (EYUTxxxx) into a load library.
11. Update ISPF to reflect the addition of CICSplex SM. A sample of the changes required is in EYU@ISPF and EYU@PRIM in CICSTS31.CPSM.SEYUDEF.

Starting the Starter Set components

Before you can use the Starter Set, you must:

- Start the CAS
- Start the CMAS
- Add definitions to the CMAS data repository
- Start the MASs.

These steps must be performed on system A or system B (or both).

Start EYUCAS1A or EYUCAS1B

To start the CAS, you submit JCL EYUJCSx or EYUJCSSx (to start the CAS as a started task). For example, to start EYUCAS1B as a started task, you use JCL EYUJCSS2.

Start EYUCMS1A or EYUCMS1B

Check the SIT parameters in JCL EYUJCM1A or EYUJCM1B (as appropriate), in particular the SVC numbers and the default user, to ensure that they are suitable for your environment. To start the CMAS, submit JCL EYUJCM1x. For example, to start CMAS EYUCMS1B, you submit JCL EYUJCM1B.

Add definitions to the data repository

You define CICSplex EYUPLX01 or EYUPLX02, or both, via the CICSplex SM user interface. Then you use the batched repository update facility to load the remaining Starter Set definitions.

Note: If you have run an IVP on the target MVS image (system A or system B), and have not deleted the IVP components from that image, you must run step 4 and step 7 in the section “Defining the Starter Set environment” on page 365 before continuing with steps 1 through 4 below.

1. On system A, define CICSplex EYUPLX01, specifying EYUCMS1A as the maintenance point CMAS. Also on system A, identify EYUCMS1B as a secondary CMAS for EYUPLX01 if you are planning to define the system B components of the Starter Set. For more information about defining CICSplexes, see the *CICSplex System Manager Administration* manual. (Alternatively, you can follow the instructions in “Starting up and verifying CICSplex SM components on system A” on page 413.)
2. If you are installing the system B components, define EYUPLX02 on system B; EYUCMS1B is the maintenance point CMAS.
3. If you have defined both EYUCAS1A and EYUCAS1B, you must define a link from EYUCAS1A to EYUCAS1B, and from EYUCAS1B to EYUCAS1A. For information about defining CAS-to-CAS links, see the *CICSplex System Manager Administration* manual. (Alternatively, you can follow the instructions in “3: Checking CAS-to-CAS connections” on page 433.)
4. To add the Starter Set CICSplex SM definitions to the data repository on system A or system B (or both), you run the batched repository update facility. Definitions to be added to the data repository on system A are in member EYUDDRPA of CICSTS31.CPSM.SEYUDEF, and those to be added to the data repository on system B are in member EYUDDRPA of CICSTS31.CPSM.SEYUDEF. For information about the batched repository update facility, see the *CICSplex System Manager Administration* manual. (Alternatively, see the instructions for using the batched repository update facility during the IVPs in Chapter 53, “CICSplex SM installation verification procedures,” on page 407.)

Start the MASs

To start the MASs, submit the JCL EYUJMSnx. For example, to start MAS EYUMNS2B, submit the JCL EYUJMS2B. JCL for starting the MASs is identified in Table 29 on page 362 and Table 30 on page 362. The CICSplex SM Starter Set is now ready to use.

If errors occur while defining or using the Starter Set

If errors occur while you are setting up the Starter Set or while you are using it, one or more error messages might be issued. Please refer to the the *CICSplex System Manager Messages and Codes* manual for a detailed description of any CICSplex SM error message.

Deleting the Starter Set

CICSplex SM provides sample JCL (in data set CICSTS31.CPSM.SEYUJCL) that you can run to delete the Starter Set components from one or more of the MVS images on which it is installed. Table 36, and Table 37 list the supplied deletion JCL and identify, for each sample, the components that it deletes. For example, if you want to delete the Starter Set components on system B only, you run the deletion samples EYUJBBDB, EYUJCIDB, EYUJDRDB, EYUJCDDB, and EYUJCMDB on system B. When you have deleted the Starter Set components, you must also remove the relevant VTAM definitions.

Table 36. JCL in CICSTS31.CPSM.SEYUJCL for deleting the Starter Set from system A

Sample name	Description
EYUJBBDA	Deletes the CAS data sets EYUSDEF and EYUIPRM
EYUJCIDA	Deletes the MAS data sets
EYUJDRDA	Deletes the data repository
EYUJCDDA	Deletes the DFHCSD dataset
EYUJCMDA	Deletes the CMAS data sets

Table 37. JCL in CICSTS31.CPSM.SEYUJCL for deleting the Starter Set from system B

Sample name	Description
EYUJBBDB	Deletes the CAS data sets EYUSDEF and EYUIPRM
EYUJCIDB	Deletes the MAS data sets
EYUJDRDB	Deletes the data repository
EYUJCDDB	Deletes the DFHCSD data set
EYUJCMDB	Deletes the CMAS data sets

To delete those components belonging to CICSplex EYUPLX01, you must run both the system A deletion JCL and the system B deletion JCL.

To delete those components belonging to CICSplex EYUPLX02, you must run the system B deletion JCL.

Using the Starter Set as a model

The CICSplex SM Starter Set is provided primarily as instructional material. However, you can copy many of the Starter Set definitions, and use them as a basis for your own configuration, as follows:

1. Examine the Starter Set definitions and identify candidates for inclusion in your own configuration.
2. In the CICSTS31.CPSM.SEYUDEF members EYUDDRPA and EYUDDRPB (as appropriate), locate the statements that the batched repository update facility uses to create the definitions you want to use.
3. Copy those statements into your own PDS member and provide a valid CONTEXT statement.

4. Load those definitions into your own data repository by running the batched repository update facility and specifying the maintenance point CMAS as the context.

For more information about the batched repository update facility, see the *CICSplex System Manager Administration* manual.

Chapter 48. Applying service to CICSplex SM

This section contains information about the service material for CICSplex SM that is distributed as corrective or preventive service. Both types of changes are called system modifications (SYSMODs). SYSMODs are processed using SMP/E control statements.

For background information on SMP/E operations, see the *System Modification Program Extended: General Information* book. For more detailed information, see the *System Modification Program Extended: Reference* book. For information about how to apply corrective service using SMP/E, see the *System Modification Program Extended: User's Guide*.

CICS Transaction Server for z/OS-supplied SMP/E procedure

For all CICS/ESA and CICS Transaction Server systems, the procedure for applying service is called DFHSMPE. This procedure is customized by the DFHISTAR job stored in the CICSTS31.CICS.XDFHINST library.

For full details about applying service to the CICSplex SM component of CICS TS, see Chapter 26, "Applying service to CICS Transaction Server for z/OS," on page 179.

Applying PTFs to CICSplexes running CICS Transaction Server for z/OS, Version 3 Release 1 and later

Only use the procedure described below if all CMASs in your CICSplex are running CICS Transaction Server for z/OS, Version 3 Release 1 or a later release of CICSplex SM. If any CMAS in your CICSplex is running CICS TS or an earlier release of CICSplex SM, please consult the documentation that comes with the PTF for advice on how to proceed.

Some PTFs modify CICSplex SM resource tables. The documentation will tell you if this is the case. Use the procedure described below if the PTF modifies a CICSplex SM resource table:

- First apply the PTF to the maintenance point for the CICSplex.
- If the PTF modifies a repository record, upgrade the repository at the maintenance point before restarting the maintenance point CMAS.
- After the maintenance point CMAS has been restarted, apply the PTF to any local MASs connected to the maintenance point CMAS. You can restart these local MASs one at a time. There is no need to restart them all together.
- After the maintenance point CMAS has been restarted, apply the PTF to any other CMASs in the CICSplex. You can do this at the same time as the MASs connected to the maintenance point are being updated. You can update the non-maintenance point CMASs one at a time and there is no need to restart them all together.
- If the PTF modifies a repository record, upgrade the repository for the non-maintenance point CMAS before restarting it.
- Once a non-maintenance point CMAS has been restarted, you can apply the PTF to any local MASs connected to that CMAS and restart them. You can restart these local MASs one at a time. There is no need to restart them all together.

In other words, update the maintenance point CMAS first, then the other CMASs, and only update an LMAS after its owning CMAS has been updated.

A PTF might contain additional documentation, giving further instructions specific to that PTF.

Chapter 49. Using the EYUINST EXEC to tailor skeleton jobs

This section describes how you can use the sample JCL members to execute the EYUINST EXEC that customizes skeleton jobs provided by CICSplex SM.

The following sample members are provided to execute the EYUINST EXEC:

- Member EYUISTRT, in the library CICSTS31.CPSM.SEYUJCL, is provided to customize the Starter Set jobs.
- Member EYUISTAR, in the library CICSTS31.CPSM.SEYUINST, is provided to customize the post-installation jobs.

For a description of the Starter Set jobs, see Chapter 47, “Configuring the Starter Set,” on page 361.

You can edit and run the sample JCL members multiple times. For example, the EYUISTAR job can be used to select and edit skeleton member EYUDEFDS to create a unique data repository for each CMAS. In addition, you can subsequently change the skeleton jobs when, for example, you have to apply service to any of those jobs. This allows you to tailor the skeleton jobs to your environment after you have loaded the CICSplex SM software into the SMP/E-supported CICSplex SM libraries.

The following sections provide information about:

- “Sample JCL editing considerations”
- “EYUINST EXEC parameters” on page 375
- “Sample JCL execution considerations” on page 382.

Sample JCL editing considerations

To tailor the sample EYUISTAR or EYUISTRT members, you can either directly modify the contents of the member in the SMP/E target library or copy the member (to preserve the CICSplex SM-supplied values) and then change the copy.

When you edit the EYUISTAR member, do the following:

- Set the SCOPE parameter to indicate that post-installation jobs are to be generated.
- Set the TEMPLIB parameter to identify the installation library CICSTS31.CPSM.SEYUINST, which contains the skeleton jobs.
- In the SYSPROC DD statement, identify the library that contains the EYUINST EXEC. To ensure that you are using the most current version of these jobs, identify the library as CICSTS31.CPSM.SEYUINST.

When you edit the EYUISTRT member, do the following:

- Set the TEMPLIB parameter to identify the Starter Set library CICSTS31.CPSM.SEYUJCL, which contains the skeleton jobs.
- In the SYSPROC DD statement, identify the library which contains the EYUINST EXEC. To ensure that you are using the most current version of these jobs, identify the library as CICSTS31.CPSM.SEYUINST.

If the sample JCL members are serviced, you must perform one of the following actions:

- To preserve your current installation parameters, add the service changes to the previously edited sample JCL member.

- Respecify your current installation parameters in the serviced sample JCL members in the SMP/E target library. These members are EYUISTAR in the library CICSTS31.CPSM.SEYUINST and EYUISTRT in the library CICSTS31.CPSM.SEYUJCL.

The CICSPlex SM installation libraries are identified in Table 38.

When a parameter has a default value, as indicated in Table 39 on page 375, you can use the default value by:

- Omitting the parameter.
- Omitting the last value with a parameter supporting multiple values.
- Using a period in place of a value, where either of the following:

```
UTILITIES . LKED .
```

```
UTILITIES . LKED
```

is the same as specifying:

```
UTILITIES ASMA90 LKED GIMSMP
```

If your disk space is managed by the storage management subsystem (SMS) component of MVS/DFP, the unit and volume parameters may be omitted from the generated JCL by specifying the value SMS for any of the UNIT or VOLUME operands of the EYUINST EXEC parameters. For example, to omit UNIT and VOLUME values from the JCL generated by EYUINST EXEC parameters which obtain their default value from the DEFVOL parameter, specify:

```
DEFVOL SMS SMS
```

For the other parameters that have unit and volume specifications and that are to obtain the default from DEFVOL, use a period (which represents the default to SMS).

Table 38. Installation libraries for CICSPlex SM

Library	Function
SEYUINST	The SMP/E-supported target installation library. After you have installed the CICSPlex SM software into this and other SMP/E-supported libraries (named SEYUxxxx and AEYUxxxx), this library stores the skeleton jobs you should use on any later runs of the EYUISTAR job.
XEYUINST	To store the tailored, executable, copies of the skeleton jobs that are to be run.
AEYUINST	The SMP/E-supported distribution installation library.
AEYUJCL	The SMP/E-supported distribution library that contains the Starter Set JCL members.
SEYUJCL	The SMP/E-supported target library that contains EYUISTRT and the other Starter Set members.

Note: The name of the XEYUINST library and the high-level index for the other CICSPlex SM libraries are determined by the EYUINST EXEC parameters used in the EYUISTAR and EYUISTRT jobs. These parameters are described in “EYUINST EXEC parameters” on page 375.

EYUINST EXEC parameters

Table 39 identifies all of the EYUINST EXEC parameters (supplied in the EYUISTAR and EYUISTRT members) and, when appropriate, their default values. The term None indicates that the parameter has no default. Lowercase characters indicate the source of the default value. Except as noted with the following parameter descriptions, you may specify your own values for any of these parameters.

The headings POST and STARTER, which also represent values you can specify with the SCOPE parameter, indicate the type of skeleton jobs you can tailor and generate, where:

- POST identifies parameters used to generate customized post-installation jobs.
- STARTER identifies parameters used to generate customized Starter Set jobs.

The subheadings of CMAS and MAS indicate the environment to which the parameter applies.

Table 39. EYUINST EXEC parameters, when they are used, and their default values

Parameter	POST		STARTER		Default value
	CMAS	MAS	CMAS	MAS	
BLKU	--	--	Yes	Yes	6144
CINDEXnnn	Yes	--	Yes	Yes	None
CMASNAME	Yes	--	Yes	--	None
CRELEASE	Yes	--	Yes	Yes	6.4.0
DEFVOL	Yes	--	--	--	CPS310 3390
DSINFO	Yes	--	Yes	Yes	index defvol
ENVIRONMENT	Yes	Yes	Yes	Yes	None
EYUIPRM	Yes	--	--	--	index.EYUIPRM NEW
EYUSDEF	Yes	--	--	--	index.EYUSDEF NEW
GZONECSI	Yes	Yes	--	--	CICSTS31.GZONE NEW CPS310 3390
INDEX	Yes	Yes	Yes	Yes	CICSTS31.CPSM
JOB	Yes	Yes	Yes	Yes	//XXXXXXXXX JOB
LIB	Yes	Yes	Yes	Yes	index.XEYUINST
OLDDREP	Yes	--	--	--	None
PREFIX	Yes	Yes	Yes	Yes	EYU
SCEESAMP	--	--	Yes	--	SYS1.SCEESAMP
SCOPE	Yes	Yes	Yes	Yes	POST
SELECT	Yes	Yes	Yes	Yes	None
SMPWORK	Yes	Yes	--	--	SYSDA
SYSIDNT	Yes	--	--	--	None
TEMPLIB	Yes	Yes	Yes	Yes	index.SEYUINST
TIMEZONE	Yes	--	--	--	None
TZONE	Yes	Yes	--	--	TZONE
UTILITIES	Yes	Yes	--	--	ASMA90 IEWL GIMSMP
# WORKUNIT	Yes	Yes	Yes	Yes	SYSDA
# WORKVOL	Yes	Yes	Yes	Yes	-

The EYUINST EXEC parameters are:

BLKU blocksize

Indicates the block size to be used when allocating data sets that have an UNDEFINED record length.

The default is 6144.

CINDEXnnn library_prefix

Where nnn represents a CICS Transaction Server for z/OS release

(Required.) The value of nnn must correspond to the release level specified for the CRELEASE parameter. That is:

- CINDEX620 library_prefix specifies the high-level indexes assigned to the CICS TS for z/OS Release 2.2 libraries.
- CINDEX630 library_prefix specifies the high-level indexes assigned to the CICS TS for z/OS Release 2.3 libraries.
- CINDEX640 library_prefix specifies the high-level indexes assigned to the CICS TS for z/OS Release 3.1 libraries.

The index value must not exceed 26 characters in length, and the leading character must be alphabetic. If you specify more than one level of index, the names must be separated by a period (as in CINDEX CICS.TEST) The index is used for the following data sets:

cindex.SDFHAUTH
cindex.SDFHLOAD

One or more CINDEXnnn parameters must be specified as required by the CRELEASE parameter values.

No default is assumed.

CMASNAME name

(Required when you specify CMAS with the ENVIRONMENT parameter.)

For POST, identifies a 1- to 8-character name that is to be assigned to a CMAS.

For STARTER, designates the Starter Set environment to be created so that the appropriate subset of members are selected from the library you identify via the TEMPLIB parameter.

The name of a CMAS must be unique within the CICSplex SM environment. It should not be the same as the name of another CMAS, a CICSplex, a CICS system, or a CICS system group.

EYUCMS1A

Indicates that all of the Starter Set jobs associated with System A are to be created.

EYUCMS1B

Indicates that all of the Starter Set jobs associated with System B are to be created.

No default is assumed.

CRELEASE value1 value2 value3 value4 value5

Identifies the CICS release level for each CICS region referenced by this run of EYUINST. From one to five values may be defined.

When SCOPE=STARTER, this identifies the CICS release level for each CICS region installed for one of the three MVS/ESA images associated with the Starter Set. When the SCOPE parameter is not equal to STARTER, only the first value is used. Valid values are 5.3.0, 6.2.0, 6.3.0 and 6.4.0..

The default is 6.4.0 for all five regions.

Table 40 on page 377 shows the Starter Set CICS region that is assigned the values entered for the CRELEASE parameter. The EYUINST EXEC must be run three times in order to edit the Starter Set members for the three MVS images. For example, when the EYUINST EXEC is run to edit

the Starter Set members for System B, the second value entered on the CRELEASE parameter determines the CICS release level assigned to the MAS1B CICS region.

Table 40. Starter Set CICS regions assigned values by the CRELEASE parameter

MVS Image	CRELEASE value for each CICS region					
	6.4.0	6.4.0	6.4.0	6.4.0	6.4.0	6.4.0
System A	CMS1A	MAS1A	MAS2A	MAS3A	MAS4A	MAS5A
System B	CMS1B	MAS1B	MAS2B	MAS3B	MAS4B	MAS5B

DEFVOL volume disktype

Defines the default disk on which the CICSplex SM libraries are to reside if the appropriate parameter is not coded in the job used to run the EYUINST EXEC. For example, if you do not code the DISTVOL parameter, the CICSplex SM distribution libraries will reside on the disk defined using the DEFVOL parameter.

volume

Is the volume serial identifier (volser) of the volume.

Use a period to specify the volser allocated in the SYSPROC DD statement of the job used to run the EYUINST EXEC.

disktype

Is the UNIT parameter of the volume.

Use a period to specify the UNIT parameter of the volume allocated in the SYSPROC DD statement.

If both DEFVOL parameters are defined as SMS, then other statements including VOLUME and DISK values specified with a period, default also to SMS.

The defaults are the volser and unit specified with the SYSPROC DD statement.

DSINFO dsindex volume disktype

Defines details of the data sets to be created when you run either the post installation jobs or the Starter Set jobs.

dsindex

Is a high-level index that is to be assigned to all CICSplex SM data sets defined by either the post-installation jobs or Starter Set jobs.

You can specify a multilevel index, where the leading character is alphabetic, each level does not exceed eight characters in length, and the total length of the data set name does not exceed 17 characters. If you specify more than one level of index, the names must be separated by a period (for example, data.set.index).

Use a period to specify the high level index associated with the INDEX parameter.

volume

Is the volser of the data sets to be created

Use a period to specify the volser associated with the DEFVOL parameter.

disktype

Is the UNIT parameter for the volume.

Use a period to specify the UNIT parameter associated with both DEFVOL parameters.

The defaults are the high-level index specified with the INDEX parameter and the volser and unit specified with the DEFVOL parameter. If you are using SMS, and values other than the DFHVOL defaults, you must code SMS for each of these values.

ENVIRONMENT CMASIMAS

(Required.) Identifies the type of environment that is to be supported in the MVS image into which CICSplex SM is installed.

CMAS Indicates that the MVS image is to have one or more CMASs and MASs.

MAS Indicates that the MVS image is to have only one or more MASs, and no CMASs.

No default is assumed.

EYUIPRM dsname NEWIOLD

Defines details of the CICSplex SM cross-system definitions repository.

dsname

Is the data set name of the parameter repository.

Use a period to specify dsinfo.EYUIPRM, where dsinfo is the index specified with the DSINFO parameter.

NEWIOLD

Indicates whether an existing parameter repository is to be used. With NEW, any existing file with the specified name is deleted and a new parameter repository is allocated. With OLD, an existing parameter repository is used.

The default is NEW.

The defaults are index.EYUIPRM NEW.

EYUSDEF dsname NEWIOLD

Defines details of the CICSplex SM screen repository.

dsname

Is the data set name of the screen repository.

Use a period to specify dsinfo.EYUSDEF, where dsinfo is the index specified with the DSINFO parameter.

NEWIOLD

Indicates whether an existing screen repository is to be used. With NEW, any existing file with the specified name is deleted and a new screen repository is allocated. With OLD, an existing screen repository is used.

The default is NEW.

The defaults are index.EYUSDEF NEW.

GZONECSI cluster NEWIOLD volume disktype

Specifies details of the global zone CSI. Ensure that the values specified correspond to the values used for GZONECSI for DFHISTAR.

cluster

Is the VSAM cluster name, minus the qualifier .CSI.

Use a period to specify index.GLOBAL, where index is the value associated with the INDEX parameter.

NEWIOLD

Specifies whether an existing global zone CSI is to be used. With NEW, any existing global zone CSI with the specified cluster name is deleted and a new global zone CSI is allocated. With OLD, an existing global zone CSI is used.

Use a period to specify OLD.

volume

Is the volser identifier for the volume on which the global zone CSI is to be allocated.

Use a period to specify the volser associated with the SMPVOL parameter.

disktype

Is the UNIT parameter for the volume.

Use a period to specify the UNIT parameter associated with the SMPVOL parameter.

The disposition, volume, and unit values are ignored when the SCOPE is POST.

INDEX library_prefix

Assigns a high-level index to the CICSplex SM distribution, target and SMP/E libraries.

The index value must not exceed 26 characters in length, and the leading character must be alphabetic. If you specify more than one level of index, the names must be separated by a period (as in INDEX CICS31.CPSM.LEVEL2).

The default is the data set name, without the lowest level qualifier, specified with the SYSPROC DD statement in the EYUISTAR job.

JOB accounting_information

Specifies the JOB statement and JES information that you want substituted into the jobs generated by the job used to run the EYUINST EXEC. To do this, edit the sample JOB statement in the job used to run the EYUINST EXEC to specify the appropriate information, as in:

```
JOB //XXXXXXXX JOB 1,userid,MSGCLASS=A,MSGLEVEL=(1,1),
JOB // CLASS=A,NOTIFY=userid
JOB /*JOBPARM SYSAFF=node1,LINES=99
JOB /*ROUTE PRINT node2.userid
```

Normal JCL rules for coding JOB statements apply to the JOB parameter.

The default is //XXXXXXXX JOB.

The job name is ignored. The name is the input member name after it is altered by the PREFIX parameter.

LIB library_name

Specifies the 1- to 44-character name of the library to which the customized members generated by the EYUISTAR program are to be added.

The default is the data set name specified with the SYSPROC DD statement in the job used to run the EYUINST EXEC, where the lowest level qualifier is replaced with XEYUINST, as in

CICSTS31.CPSM.XEYUINST. (If necessary, the job used to run the EYUINST EXEC creates the library specified on the LIB parameter.)

OLDDREP dsname

Identifies an existing data repository that is being used by a previous release of CICSplex SM. The records in the existing data repository are migrated to a new data repository for CICS TS for z/OS, Version 3.1. The existing data repository is not modified.

dsname

Is the VSAM cluster name of the existing data repository.

The new CICS TS for z/OS, Version 3.1 data repository will have the name:

```
dsinfo.EYUDREP.cmasname
```

where:

dsinfo Is the index specified with the DSINFO parameter.

cmasname

Is the name specified with the CMASNAME parameter.

Use a period to have an empty data repository created for CICS TS for z/OS, Version 3.1.

PREFIX prefix

Defines the 1- to 7-character prefix that is to be added to the jobs generated by the job used to run the EYUINST EXEC. This prefix overwrites up to seven characters of the job name. For example, PREFIX XYZ changes the name of the job EYUDEFDS to XYZDEFDS.

The default is EYU.

SCEESAMP data set name

Specifies the name of the Language Environment library that contains the CEECCSD and CEECCSDX members. The default is SYS1.SCEESAMP.

SCOPE POSTSTARTER

Indicates which group of jobs you want to generate. Specify:

POST Generates only the post-installation jobs.

STARTER

Generates only the Starter Set jobs.

The SELECT parameter overrides the SCOPE parameter; that is, if you use both SCOPE and SELECT in the job used to run the EYUINST EXEC, only the job identified by SELECT is generated.

The default is for EYUISTAR is POST.

SELECT jobname1 [newname1]

Identifies the member containing the post-installation or Starter Set job you want to generate. To generate multiple jobs, specify a separate SELECT parameter for each.

jobname

Is the name of the member containing the job to be generated.

newname

Is a new 1- to 8-character name that is to be assigned to the member containing the job.

The SELECT parameter overrides the SCOPE parameter; that is, if you use both SCOPE and SELECT in the job used to run the EYUINST EXEC, only the job identified by SELECT is generated.

No default is assumed.

SYSIDNT value

(Required when you specify CMAS with the ENVIRONMENT parameter.) Specifies the 4-character system identifier used with the CICS TS for z/OS system initialization table (SIT) parameter SYSIDNT for the CMAS. This value is assigned to the data repository created by the EYUDEFDS post-installation job.

If you are setting up more than one CMAS, you must create a separate data repository for each CMAS.

No default is assumed.

TEMPLIB library_name

Identifies the 1- to 44-character name of the library containing the input members to be edited, when SCOPE is set to:

- POST - this is the name of the library from which the post-installation skeleton jobs can be obtained. You should specify CICS31.CPSM.SEYUINST.
- STARTER - this is the name of the library from which the Starter Set skeleton jobs can be obtained. You should specify CICS31.CPSM.SEYUJCL.

Using the suggested SMP/E target data sets of CICS31.CPSM.SEYUINST or CICS31.CPSM.SEYUJCL ensure that subsequent runs of the job used to run the EYUINST EXEC will use the updated version of the input members after maintenance is applied.

The default is the data set name specified with the SYSPROC DD statement in the job used to run the EYUINST EXEC.

TIMEZONE code

Required when you specify CMAS with the ENVIRONMENT parameter.

Specifies the time zone assigned to the data repository initialized by post-installation job EYUDEFDS for use by the CMAS named using the CMASNAME parameter.

For additional information about how CICSplex SM uses the time zone codes, see the *CICSplex System Manager Administration* manual.

TZONE zonename

Specifies the name of the target zone to be used by SMP/E. This name must be unique to the target zone. It must not be longer than seven characters and the leading character must be alphabetic.

Use the same name as that specified for TZONE for DFHISTAR.

The default is TZONE.

UTILITIES asmprog lkedprog smpeprog

Specifies the names of the utility programs to be used when installing CICSplex SM and programs that it uses.

asmprog

Is the program name of the assembler.

Use a period to specify ASMA90.

lkedprog

Is the program name of the linkage editor.

Use a period to specify IEWL.

smpeprog

Is the program name of the SMP/E program.

Use a period to specify GIMSMP.

The defaults are ASMA90 IEWL GIMSMP.

WORKUNIT

Specifies the UNIT parameter for the disk or disks on which work data sets are stored. If SMS is active, a value of NO may be used to prevent EYUINST from specifying a UNIT on the allocation of the work data sets.

The default is SYSDA.

WORKVOL

Optionally specifies the VOLUME parameter to be used by the work data sets allocated on the WORKUNIT unit.

- If WORKUNIT is set to NO, WORKVOL has no effect.
- If WORKVOL is a period, the VOLUME parameter is not used for the allocation.

The default is a period.

#

Sample JCL execution considerations

After you have edited the EYUISTAR or EYUISTRT job, submit the job.

The job log produced by the EYUINST EXEC lists the parameter values used for the job.

Should the EYUINST EXEC end with a return code of 04, review the warning message to ensure that the job ran as you intended.

When the EYUINST EXEC ends with a return code of 08 or 12, the skeleton jobs are not tailored or copied. To resolve the cause of either of these errors, examine the output job log, correct the problem, and submit the EYUINST EXEC again.

The output from the EYUINST EXEC depends on the ENVIRONMENT and SCOPE you set, and consists of the customized jobs identified in Table 20 on page 297. These jobs are added to the library used to run the EYUINST EXEC.

Chapter 50. CICSplex SM system parameters

This chapter describes the system parameters that you can use to identify or alter CICSplex SM attributes.

These parameters are specified by means of an extrapartition transient data queue. The transient data queue name is COPR. The parameters may be assigned to a DD * file, sequential data set or a partitioned data set member. The DD name for the extrapartition transient data queue is EYUPARM.

The system parameters are coded as 80-byte records. Multiple system parameters may be specified on a single record as long as they are separated by commas and do not exceed a total of 71 characters in length. The format of the system parameters is:

keyword(v)

where:

keyword

is the name of a CICSplex SM system parameter.

v is an alphanumeric data value that may be specified with the system parameter.

Table 41 identifies the CICSplex SM parameters used in the CMAS and MAS and indicates whether these parameters are required or optional.

For CMASs and CICS/ESA, CICS Transaction Server for OS/390, and CICS Transaction Server for z/OS MASs, members of the CICSTS31.CPSM.SEYUPARM library containing samples of these parameters are:

EYUCMS0P

CMAS parameters

EYULMS0P

Local MAS parameters

Note: Before using these members to start a CMAS or MAS, remove the comments from the samples and supply the appropriate values.

Table 41. CICSplex SM parameters used in CMAS and MAS

Parameter	CMAS	Local MAS	Default
ALERTRCVR	Optional	n/a	NETVALRT
ALERTVER	Optional	n/a	0
APISIGNMSG	Optional	n/a	YES
BASASSOCBLK	Optional	n/a	14301
BASLOGMSG	n/a	Optional	NO
CASNAME	Optional	n/a	
CICSplex	n/a	Required	
CMASYSID	n/a	Optional	
CMTMLNKACQ	n/a	Optional	RECONN
COHTTASKPRI	n/a	Optional	200
COIRTASKPRI	n/a	Optional	200
COMMTSBLOCKS	Optional	Optional	128 (MAS) 128 (MAS)
HISTORYONLY	n/a	Optional	NO

Table 41. CICSplex SM parameters used in CMAS and MAS (continued)

	Parameter	CMAS	Local MAS	Default
	HISTRECSMSG	n/a	Optional	0
	HISTSECS	n/a	Optional	30
	JRNLEDFCH	Optional	n/a	NO
	JRNLOPACT	Optional	n/a	NO
	JRNLRTEV	Optional	n/a	NO
#	MASALRLRCNT	n/a	Optional	0
#	MASALRLRTPRI	n/a	Optional	255
#	MASALRLRTTIM	n/a	Optional	10
#	MASINITTIME	n/a	Optional	10
#	MASPLTWAIT	n/a	Optional	NO
	MAXAUXCPSM	Optional	n/a	50
	MAXAUXTOTL	Optional	n/a	70
	MAXHISTRECS	n/a	Optional	1
#	MSGBUCKETS	n/a	Optional	1024
	MSGCASE	Optional	Optional	MIXED
	NAME	Optional	Optional	
	RESSTATUS	Optional	n/a	NOTIFY
	SEC	Optional	n/a	NO
#	SECLOGMSG	Optional	n/a	NO
	SECPRFX	n/a	n/a	NO
#	SECTIMEOUT	Optional	n/a	30
	SPOOLCLASS	Optional	Optional	P
	STALLDBCTSK	n/a	Optional	4
	STALLDBCCNT	n/a	Optional	4
	STALLDB2TSK	n/a	Optional	4
	STALLDB2CNT	n/a	Optional	4
	STALLDLITSK	n/a	Optional	4
	STALLDLICNT	n/a	Optional	4
	STALLDSPTSK	n/a	Optional	4
	STALLDSPCNT	n/a	Optional	2
	STALLENQTSK	n/a	Optional	4
	STALLENQCNT	n/a	Optional	4
	STALLFLETSK	n/a	Optional	3
	STALLFLECNT	n/a	Optional	4
	STALLILKTSK	n/a	Optional	2
	STALLILKCNT	n/a	Optional	3
	STALLLCKTSK	n/a	Optional	4
	STALLLCKCNT	n/a	Optional	4
	STALLITVTSK	n/a	Optional	0
	STALLITVCNT	n/a	Optional	0
	STALLJNLTSK	n/a	Optional	1
	STALLJNLCNT	n/a	Optional	3
	STALLPGMTSK	n/a	Optional	2
	STALLPGMCNT	n/a	Optional	4
	STALLSESTSK	n/a	Optional	2
	STALLSESCNT	n/a	Optional	3
	STALLSTGTSK	n/a	Optional	1
	STALLSTGCNT	n/a	Optional	2
	STALLTDQTSK	n/a	Optional	3
	STALLTDQCNT	n/a	Optional	4
	STALLTRMTSK	n/a	Optional	0
	STALLTRMCNT	n/a	Optional	0
	STALLTSKTSK	n/a	Optional	0

Table 41. CICSplex SM parameters used in CMAS and MAS (continued)

Parameter	CMAS	Local MAS	Default
STALLTSKCNT	n/a	Optional	0
STALLTSQTSK	n/a	Optional	3
STALLTSQCNT	n/a	Optional	4
STALLXMGTSK	n/a	Optional	4
STALLXMGCNT	n/a	Optional	2
STALLXRFTSK	n/a	Optional	1
STALLXRFCNT	n/a	Optional	2
SUPPRESSCMF	n/a	Optional	NO

APAR

PK05183 added
TOBATCHREQ,
TOONLINEREQ, and
TOPOLLINT

TOBATCHREQ	Optional	n/a	0
TOONLINEREQ	Optional	n/a	0
TOPOLLINT	Optional	n/a	300
WLMLOADCOUNT	n/a	Optional	ALLQUEUED
WLMLOADTHRS	n/a	Optional	65

ALERTRCVR(NETVALRT | name)

Identifies the 1-8 character name of the NetView Alert Receiver to be used by the CMAS if NetView Generic Alerts are to be sent by the CMAS to NetView.

ALERTVER(0 | 1)

Identifies the version of the CPSM generic alert record that the CMAS will send to NetView. See Appendix B of the *CICSplex System Manager Managing Resource Usage* manual for details on the generic alert Records CPSM may send to NetView.

ALERTVER is only relevant for a CMAS which is named in an ACTNDEF as sending generic alerts to NetView.

APISIGNMSG(YES | NO)

Indicate whether the successful signon / signoff message, EYUXD0807I, is to be issued when a CICSplex SM API user CONNECTs to, or DISCONNECTs (TERMINATEs) from, the CICSplex SM API.

BASASSOCBLK(value | 14301)

Specify the number of BAS association blocks that can be acquired from a single association element. The default EYUPARM value creates an association segment size requiring approximately 1.2 mB of storage. If the maximum value of 114597 blocks-per-segment is specified, then the resultant segment size will be just over 8 mB.

BASLOGMSG(YES | NO)

Indicate whether CICS resources defined using BAS should have their definitions logged to the CSDL Transient Data Queue of the MAS when they are installed.

If the CICS version used by the MAS does not support the LOGMESSAGE option of the EXEC CICS CREATE command, BASLOGMSG will have no effect.

CASNAME(name)

Identify the 4-character name of the CAS subsystem with which the CMAS
is to be associated.

This name must match the CAS subsystem ID identified in the CAS startup
JCL and also specified with the SSID parameter of the START command.

If this parameter is omitted, the CMAS does not attempt to connect with a
CAS. It is not necessary to start a CAS on the MVS system on which the
CMAS runs.

Note: You should ensure that every CMAS connects to a CAS. The
connection allows a TSO user signed on to any MVS image to
access the CPSM EUI. It also provides Single System Image (SSI)
function for requests directed at resources accessed under a CMAS
context. If you start a CMAS without a CASNAME, you need not
start a CAS on that MVS image. However, if it later becomes
necessary to connect to the EUI with the context set to that CMAS,
you must bring down the CMAS and restart it with the CASNAME
parameter identifying the SSID of a CAS running on the same MVS
image.

CICSPLEX(name)

| Identify the 1- to 8-character name of the CICSplex to which the local MAS
| is to be associated.

| The name of a CICSplex should not be the same as the name of a CMAS,
| a CICS system, or a CICS system group.

CMASYSID(name)

| Identify the 1- to 4-character name of the CMAS to which a MAS is to be
| attached.

| You can also use this parameter when a local MAS is to attach to a specific
| CMAS in the same MVS image.

CMTMMLNKACQ(ALWAYS | RECONN)

Specify whether you want the CMAS to attempt to reacquire LU6.2
CMAS-to-CMAS links (CMTMMLNKs) if the initial acquire attempt made by
CICS fails. The initial acquire attempt is made by CICS at CMAS startup,
VTAM ACB open, or CMTMMLNDEF (CMAS-to-CMAS definition) install.

If the initial acquire attempts fail, CICSplex SM network surveillance may
attempt to reacquire the LU6.2 CMAS-to-CMAS links, depending on the
value of CMTMMLNKACQ:

ALWAYS

The CMAS will attempt to acquire CMTMMLNKs even if they have
never been established in the current CMAS run.

RECONN

The CMAS will attempt to reacquire only those CMTMMLNKs that were
previously established in the current CMAS run. Note that if the
CMTMMLNKs were not previously used in the current CMAS run and
the initial acquire attempts fail, you must acquire the CMTMMLNK
manually, using one of the following methods:

#

- using the ACQUIRE action in the EYUSTARTCMTMLNK Web User Interface view.
- using the ACQUIRE action of the CMTMLNK resource table in a user-written CICSplex SM API program.
- using CEMT to manually acquire the CICS connection used by the CMTMLNK.

Note: Depending on the CMTMLNKACQ option in use, the repeated acquire attempts may cause multiple error messages from CICS (DFH3C3437, DFH3C3462 and DFH3C2405) and VTAM (IST663, and IST664) logging the connection ACQUIRE attempt if the requests continue to fail.

CMTMLNKACQ can be dynamically changed in a CMAS via the COD0 SET command. See the *Problem Determination Guide* for details.

COHTTASKPRI(value | 200)

Specify the CICS task priority for the MAS COHT task. COHT is invoked in a MAS when an API or web user interface query for completed task history records (HTASK records) is directed to the MAS. Use this parameter to tune the priority of HTASK requests so that a resource intensive query does not impact the performance of other tasks in the MAS.

COIRTASKPRI(value | 200)

Specify the task priority of COIR, in the range 0 to 255. COIR is a CICSplex SM task that can be used to process evaluation definitions (EVALDEFs) independent of the MAS.

For each EVALDEF that requests a separate task, an instance of COIR is started at the specified priority. If you specify a priority of 0, no separate COIR tasks are started; all EVALDEFs are processed by the MAS long running task (LRT).

Note: This parameter does not apply to CICS for Windows.

COMMTSLOCKS(value | 512/128)

This is the number of sets of control blocks allocated at CMAS or MAS startup for CPSM Communications Transport Services. These control blocks are used when data must be shipped between a CMAS or MAS and other CMASs or MASs.

The default and minimum values for this parm are 512 in a CMAS and 128 in a MAS. The maximum value is 8192 in either a CMAS or MAS.

Each set requires 1204 bytes of storage allocated in ESDSA in the CMAS or MAS. If the defaults are used, the following total storage is allocated:

CMAS - $512 * 1204 = 616,448$ bytes
MAS - $128 * 1204 = 154,112$ bytes

If the maximum value is specified, the following total storage is allocated:

CMAS - $8192 * 1204 = 9,863,168$ bytes
MAS - $8192 * 1204 = 9,863,168$ bytes

If a shortage occurs during the execution of a CMAS or MAS, message EYUCT0105E is issued. At termination of the CMAS or MAS, message EYUCT0106W is issued. The later message will include a value equal to the highest concurrent shortage of sets (High water mark). It is

recommended that the COMMTSBLOCKS parm for the CMAS or MAS be increased by at least the amount specified by the EYUCT0106W message before restarting the CMAS or MAS.

HISTORYONLY(YES | NO)

Specify whether history data should be collected without collecting normal CICSplex SM monitoring data as well. For example, if MLOCTRAN and MREMTRAN data is not required set HISTORYONLY(YES) to prevent this data from being collected.

HISTRECSMSG(value | 0)

Specify that message EYUNL0179I 'Task History Recorder dataset EYUHISTx has accrued nnnn records' should be output each time 'value' thousand records are written to the history data sets. The maximum allowed value is 1000 which means output a message every time 1 million records are written to the history data sets.

The message can be used as an aid to determining the optimum size of the history data sets. A value of 0 means no EYUNL0179I messages are to be produced.

HISTSECS(value | 30)

Specify the number of seconds to use as the default when API or web user interface users specify a parameter of RECENT(HISTSECS) when requesting completed task (HTASK) resource table records. The maximum allowed value is 86400 seconds (24 hours).

JRNLDEFCH(YES | NO)

Causes a journal record to be written for each data repository add, delete, and update operation.

JRNLOPACT(YES | NO)

Causes a journal record to be written for each successful action command issued against a MAS or CMAS.

JRNLRTAEV(YES | NO)

Causes a journal record to be written each time an real-time analysis (RTA) event is generated.

MASALTLRTCNT(0 - 5 | 0)

The number of alternate long running tasks (CONA) started in the MAS during MAS agent initialization. These tasks remain active until the MAS agent terminates or goes into restart mode, and handles all EUI/API/WUI/RTA normally handled by the CONL task, allowing the CONL task to perform other processing in the MAS. At any time, only one of the CONA tasks processes requests. If the CONA task that is currently processing requests becomes busy (as determined by the value of the MASALTLRTTIM EYUPARM), subsequent requests are directed to another CONA task.

If zero (0) is specified, no CONA tasks are started and the CONL task services the EUI/API/WUI/RTA requests that are normally directed to the long running task.

Note: Specifying different values for MASALTLRTCNT for multiple WLM target regions might result in an uneven distribution of transactions to those regions because of differing long running task counts.

MASALTLRTPRI(0 - 255 | 255)

The priority given to the CONA transaction for the current execution of the MAS.

#

Note: Specifying this value less than 255 can adversely affect the
response time of EUI, API, and WUI users, and might result in RTA
EVENTS not being created or resolved in a timely manner

MASALTLRTTIM(1 - 3600 | 10)

The amount of time in seconds for which a CONA task can be busy before
subsequent requests are directed to another active CONA task.

MASINITTIME(value | 10)

Specifies the number of minutes, from 5 to 59, that CICSplex SM should
wait for the MAS to initialize.

- # • If you specify MASPLTWAIT(YES), the MASINITTIME value is the
maximum length of time that PLT processing can be suspended for MAS
initialization. (By suspending PLT processing the chance of completing
MAS initialization within a specified time is increased, because you are
asking for less work to be done in a given time interval, and reducing the
scope for contention, during that time).
- # • If you specify MASPLTWAIT(NO), the MASINITTIME value is the
maximum length of time that can elapse before MAS initialization is
aborted if it does not complete.

MASPLTWAIT(YES | NO)

Indicates whether CICSplex SM should suspend all PLT processing until
the MAS is fully initialized and connected to the CMAS.

- # • When you specify MASPLTWAIT(YES), no CICS applications can be
started and no users can sign on to the system until CICSplex SM
completes the installation of resources and resumes PLT processing. If
CICSplex SM does complete the installation of resources and resume
PLT processing within the time interval specified by MASINITTIME,
message EYUTS0003I is issued. If it does not complete within the time
interval specified by MASINITTIME, message EYUNL0090W is issued,
the MAS initialization is aborted and the PLT processing resumes to
allow the region to function as a CICS region without CICSplex SM
control. MAS Initialization can be retried by entering the COLM
transaction manually.
- # • When you specify MASPLTWAIT(NO), CICSplex SM still observes the
MASINITTIME value waiting for the MAS agent to complete the topology
connect. If CICSplex SM does not complete the topology connect within
the time interval specified by MASINITTIME (or its default value),
message EYUNL0090W is issued, the MAS initialization is aborted and
the PLT processing resumes to allow the region to function as a CICS
region without CICSplex SM control. MAS Initialization can be retried by
entering the COLM transaction manually.

If you are using Business Application Services (BAS) to automatically install
resources at CICS system initialization, you should specify
MASPLTWAIT(YES) for that system.

Note: If you are using Business Application Services (BAS) to automatically
install a DB2 connection, and you want the connection to be
activated during CICS startup, see the information on page 335

MAXAUXCPSTM(value | 50)

Specify the percent of total auxiliary storage which may be committed to
each CMAS, in the range of 1 to 99. Note that each CMAS will require
24,160 4kB pages (94 mB) of cache storage at initialization. If a request for
additional cache storage would cause the CMAS to exceed this threshold,

an SDUMP is taken and the CMAS is terminated. If this occurs during CMAS initialization, it means that the CMAS was unable to acquire the initial allocations for all required component data cache areas. Either the value of MAXAUXCPSM must be increased, or the total amount of auxiliary storage must be increased by adding or expanding external page data sets. If this threshold is reached during an attempt to create or extend a data cache after CMAS initialization has completed, ARM is invoked to attempt to restart the CMAS.

MAXAUXTOTL(value | 70)

This value is the maximum total auxiliary storage usage at which the CMAS allows a request for additional cache storage to be made, in the range of 1 to 99. This prevents the CMAS from requesting an amount of cache storage which would cause the MVS system to enter a state of auxiliary storage shortage. If a request for additional cache storage would cause the CMAS to exceed this threshold, an SDUMP is taken and the CMAS is terminated. This parameter can cause a CMAS to shut down even though the CMAS is not the largest user of auxiliary storage. If this occurs during CMAS initialization, it means that the CMAS was unable to acquire the initial allocations for all required component data cache areas. The total amount of auxiliary storage available must be increased by adding or expanding external page data sets. If this threshold is reached during an attempt to create or extend a data cache after CMAS initialization has completed, ARM is invoked to attempt to restart the CMAS.

MAXHISTRECS(value | 1)

Specify a limit, in the range 1 to 50, on the number of records returned on a completed task query from the MAS to 'value' thousand records. This can be used to limit the amount of data in a request for completed task (HTASK) resource table records. When this limit is reached, the CICSplex SM API GET request will receive a WARNING response and MAXRECORDS reason.

MSGBUCKETS(value | 1024)

Specify a value in the range 1 to 32768. This value specifies the number of buffers to be allocated for Topology data collection in the MAS. Each buffer is 64 bytes long. The buffer pool, allocated in the MAS cache data space, is used by CPSM's XMEOUT and XRSINDI Global User Exits and by the MAS Heartbeat task. The number of buffers must equal or exceed the total number of connections, DSNAMEs, GLUEs, TRUEs, and FEPI connections defined in the MAS. If the number of buffers is not sufficient for the Topology mapped resources in the MAS, a trace record with debug text XDATLOST is written at every other heartbeat interval when MAS Topology resource data is collected. If this occurs, resources will be missing from Topology Resource Maps for the MAS in all CMASes in the CICSplex, and query or action requests entered from the EUI or API for specific resources may fail because the target resources are not known to Topology.

MSGCASE(MIXED | UPPER)

Indicate whether the following types of output should be displayed in mixed case or upper case:

- Messages issued by Message Services to the console, joblog, and EYULOG
- Batched repository-update facility output
- Diagnostic output from the CODB, COD0, and COLU transactions.

You can specify:

#

MIXED

Mixed case text is displayed as is.

If you specify MIXED, output may be displayed incorrectly on Katakana display terminals, where lower case characters are displayed as Katakana symbols.

UPPER

Mixed case text is displayed in upper case only.

NAME(name)

Identify the 1- to 8-character name of the CMAS or local MAS that is to be started. If you do not specify this parameter, the default is the VTAM application ID.

RESSTATUS(NOTIFY | MSG | CONMSG)

Indicate how the CMAS is to respond when a CICS resource that is being reported to the resource status facility has a change in operational state:

NOTIFY

Issues event notifications in the form of ERESSTAT resource table records.

These event notifications can be monitored by using the LISTEN command of the CICSplex SM API. For more information, see the *CICSplex System Manager Application Programming Guide*.

MSG Writes external messages to EYULOG.

If you specify MSG, event notifications are produced in addition to the messages.

CONMSG

Writes external messages to the job log, console, and EYULOG.

If you specify CONMSG, event notifications are produced in addition to the messages.

Note: Use this option with care. It could cause a large number of messages to be sent to the console.

SEC(YES | NO)

For a CMAS, indicate whether the CMAS is to perform security checking of CICSplex SM requests directed to the CICS systems it manages.

When NO all security-related parameters are ignored.

If a CMAS manages any CICS regions that are running with security active (SEC=YES specified as a system initialization parameter), the CMAS must include SEC(YES) in EYUPARM. If you do not activate CICSplex SM security in the CMAS, a connection cannot be established to a CICS system that specifies SEC=YES. If a connection is attempted, the following message is issued to the console, the CMAS job log, and the CMAS EYULOG:

EYUCR0007E Security mismatch between CMAS cmasname and
MAS masname. Connection terminating.

Note: If a CMAS started with SEC(NO) connects directly or indirectly to a CMAS started with SEC(YES), any request sent to the SEC(YES) CMAS will fail.

- If the request originates from the TSO EUI, the TSO user will receive message: EYUEI0586E

- If the request originates from the CICSplex SM API connected to the SEC(NO) CMAS, the API request will receive: RESPONSE 1031 NOTPERMIT REASON 1345 USRID
- If the request originates from the CICSplex SM Web User Interface server connected to a SEC(NO) CMAS, the browser will receive message: EYUVC1220E

```

#          SECLOGMSG(NO | YES | ALL)
#          Controls whether CICSplex SM should issue message EYUCR0009I to the
#          CMAS EYULOG, to record security failures.
#
#          When NO is specified, the default, message EYUCR0009I is not issued.
#
#          Specify YES, or ALL, to cause message EYUCR0009I to be issued.
#
#          SECLOGMSG(YES) can be useful if the External Security Manager (ESM)
#          does not issue messages when it cannot make a decision, or when a failure
#          occurs.
#
#          Note: When SECLOGMSG(YES) is specified, EYUCR0009I will be issued
#          only for requests which are to be logged to the ESM.
#
#          SECLOGMSG(ALL) causes EYUCR0009I to be issued even when the ESM
#          permits access to the resource. The ALL operand can produce a large
#          number of EYUCR0009I messages and should normally be used only under
#          the direction of IBM Support.
#
#          SECLOGMSG can be dynamically changed in a CMAS with the COD0 SET
#          command. See the CICS Problem Determination Guide for details.
|
|          SECPRFX(YES6 |prefix userid
|          Indicate whether the user ID is used as the prefix that is added to the
|          beginning of all resource names to distinguish this CICS system from other
|          CICS systems.
#
#          SECTIMEOUT(value|30)
#          Specifies the time in minutes, in the range of 1 through 1440 (1 day), that
#          idle userids are to remain signed on within the CMAS before being
#          considered for timeout.
#
#          The value is also used to control how often the CMAS checks for idle users
#          to timeout. For example, with the default value of 30, the CMAS will check
#          every 30 minutes for users who have not used the CMAS for 30 minutes.
#          However, as the times are not synchronized it may mean that the userid will
#          not be timed out for up to double the SECTIMEOUT value. Setting this
#          value low will increase the number of calls to the External Security Manager
#          (ESM). Setting this value high means that users may have to wait a long
#          time before automatically picking up security changes that affect the userid
#          (for example, adding the user to a new group).
#
#          The CMAS or CMASLIST PURGE request (available from the EUI, API and
#          WUI) can be used to force a CMAS to check for users to timeout
#          immediately.
#
#          The CMAS or CMASLIST RESET USERID request (available from the API
#          and WUI) can be used to force the CMAS to rebuild the user's security
#          information the next time it is used. This request would typically be used
#          after adding or removing a userid to, or from, a group, and the user does
#          not want to wait to be timed out to pick up the change.

```

6. For a CMAS or local MAS only

SPOOLCLASS(class | P)

Specify a SYSOUT class value, from A to Z, that identifies where CICSplex SM spool output is to be sent.

Spool output can be generated by these CICSplex SM functions:

- The online utility transaction (COLU)
- The PRINT and CAPTURE commands of the interactive debugging transaction (COD0).

STALLxxxTSK

Where xxx represents a CICSplex SM suspend class. The values for xxx are shown in Table 42.

#

Identify the minimum number of concurrent tasks required to enter the suspend class. The value may be between 0 and 999. The default value for each task is shown in Table 41 on page 383. Use 0 to indicate STALL detection for the xxx suspend class is not active.

STALLxxxCNT

Where xxx represents a CICSplex SM suspend class. The values for xxx are shown in Table 42.

#

Identify the number of consecutive occurrences of an entry in the suspend class required for CICSplex SM to report a STALL. The value may be between 0 and 999. The default value for each task is shown in Table 41 on page 383. Use 0 to indicate STALL detection for the xxx suspend class is not active.

Table 42. CICSplex SM Suspend Classes

Suspend Class	CICS Suspend Types	Value in STALLxxx Parameters	Text in EYUPNxxxx Messages
DBCTL	DBCTL	DBC	DBCTRL
DB2	CDB2RDYQ CDB2TCB DB2_INIT DB2 CDB2CONN DB2CDISC DB2EDISA	DB2	DB2
DLI	DLI	DLI	DLI
Dispatcher	DS_HELD DISPATCH	DSP	DISP
Enqueue	KC_ENQ ENQUEUE	ENQ	ENQUEUE
File	FCxxxxxx CFDTxxxx	FLE	FILE
Interval Control	ICxxxxxx	ITV	INTV
Journal	JASUBTAS JCxxxxxx	JNL	JOURNAL
Lock Manager	LMQUEUE	LCK	LOCK
Program Loader	PROGRAM	PGM	PROGRAM
Allocate Session	ALLOCATE	SES	ALLCSESS
Storage	xDSA ExDSA	STG	STORAGE
Transient Data	MBCB_xxx MRCB_xxx TDEPLOCK TDIPLOCK TD_INIT TD_READ	TDQ	TSDATA
Terminal Control	ZCxxxxxx	TRM	TERM
Task Wait	EKCWAIT KCCOMPAT	TSK	TASKWAIT
Temporary Storage	TSxxxxxx	TSQ	TEMPSTOR

#

Table 42. CICSplex SM Suspend Classes (continued)

Suspend Class	CICS Suspend Types	Value in STALLxxx Parameters	Text in EYUPNxxxx Messages
Terminal	IRLINK	ILK	IRLINK
Transaction Manager	XM_HELD MXT TCLASS	XMG	TRANSACT
XRF	XRxxxxxx	XRF	XRF
Note: EYUPNxxxx messages are issued when a stall condition occurs that generates a real-time analysis system availability monitoring (SAM) event.			

SUPPRESSCMF(YES | NO)

For a local MAS, indicates whether the records collected by the CICS Monitor Facility are written to SMF.

The parameter only suppresses CICS type 3 performance class records. Type 4 exception records and type 5 transaction resource records are not suppressed. The type 3 performance records are only suppressed if the CICS region has an active CICSplex SM monitor definition installed for the MTRAN monitoring class. You can verify which CICS regions have active monitoring for the MTRAN class by issuing the MONACTV view from the TSO End User Interface.

TOBATCHREQ(value | 0)

APAR

PK05183 added TOBATCHREQ, TOONLINEREQ, and TOPOLLINT

The time in seconds before a batch request directed to a MAS is timed out. This includes RTA requests and API requests initiated from non-CICS programs. Specify zero, or a value in the range 10 to 1800.

- If you specify zero, the default value of 240 seconds (4 minutes) is applied. This value is then doubled when the request is transmitted to the MAS.
- If you specify a non-zero value in the range 10 to 1800, that value is used.
- If you specify a non-zero value less than 10, TOBATCHREQ is set to 10.

Depending upon the value specified for TOBATCHREQ more time outs may be received. This may be noticed in the following ways:

RTA requests

No data will be processed for any MAS that times out and no external message will be displayed. This may cause an event to not be created, or lead to premature termination of existing events.

API requests initiated from non-CICS programs

All API requests initiated from non-CICS programs will receive a REPSONSE of ENVIRONERROR (1030) and REASON of REQTIMEOUT (1342) and no data records will be returned, regardless of the CONTEXT and SCOPE of the request.

TOONLINEREQ(value | 0)

The time in seconds before an online request directed to a MAS is timed

```

# out. This includes EUI and WUI requests and API requests initiated from
# CICS programs. Specify zero, or a value in the range 10 to 1800.
#
# • If you specify zero, the default value of 240 seconds (4 minutes) is
# applied. This value is then doubled when the request is transmitted to the
# MAS.
#
# • If you specify a non-zero value in the range 10 to 1800, that value is
# used.
#
# • If you specify a non-zero value less than 10, TOONLINEREQ is set to
# 10.
#
# Depending upon the value specified for TOONLINEREQ more time outs
# may be received. This may be noticed in the following ways:
#
# EUI requests
# If all systems that are part of the CONTEXT and SCOPE time out,
# the following messages are returned to the EUI display:
# EYUEI0591E
# Communications to <masname> timed out
# BBMXBD15I
# There is no data that satisfies your request
# BBMXBD23I
# 0 records presented by the product
#
# If at least one of the systems that are part of the CONTEXT and
# SCOPE do not time out, the records for that system (or those
# systems) will be displayed and no error messages will be displayed.
#
# WUI requests
# All WUI requests will receive the following message and no data
# records will be displayed, regardless of the CONTEXT and SCOPE
# of the request.
# EYUVC1220E
# CICSplex SM API command (GET) failed. (Environerror,
# Reptimeout)
#
# API requests initiated from CICS programs
# All API requests initiated from CICS programs will receive a
# REPSONSE of ENVIRONERROR (1030) and REASON of
# REQTIMEOUT (1342) and no data records will be returned,
# regardless of the CONTEXT and SCOPE of the request.
#
# TOPOLLINT(value | 300)
# The time in seconds that a CMAS delays between checking all requests to
# determine if they exceed their time out time. Since polling is used to
# determine when to time out a request, more reliable time outs will occur if
# this value is set less than or equal to both TOBATCHREQ and
# TOONLINEREQ.
#
# When a request is directed to a MAS that is not connected to the
# originating CMAS, it is transmitted from the originating CMAS to the remote
# CMAS to which the MAS is connected. When this occurs, the remote
# CMAS performs the time out processing, based upon the TOBATCHREQ
# and TOONLINEREQ values specified in the originating CMAS and the
# TOPOLLINT value specified in the remote CMAS. For this reason, time out
# processing will be more consistent if all CMASes in the network have the
# same TOPOLLINT value.
#

```

WMLLOADCOUNT(ALLQUEUED | MXTQUEUED)
For a local MAS, indicates which queued tasks should be included in the
WLM task load count for the MAS.

Specify ALLQUEUED to include tasks queued for both maxtask and
tranclass.

Specify MXTQUEUED to include tasks queued only for maxtask.
WMLLOADTHRS(65 | 1 - 100)
For a local MAS that is defined as a CPSM WLM routing region, indicates
what task load percentage ((active tasks/maxtask) *100) should be used as
part of the determination as to when the routing region should route to
target regions on other CECs.

For example, if the default value of 65 is used, then all target regions on
the CEC where this routing region resides must have a task load of 65% or
higher before the routing region routes to target regions on other CECs, if
all other health factors (for example, short-on-storage) for the routing
regions are similar. As soon as all target regions on other CECs achieve a
task load of 65% or higher, the routing region resumes routing to the target
regions on the local CEC again. When a local target region's task load
drops below 65%, the routing region resumes routing to that target region
regardless of the task load in target regions on remote CECs.

Specifying this value lower than the default probably decreases the delay in
routing to target regions on remote CECs. Take care not to set this value so
low that the threshold is met by long-running tasks in the target regions.

Specifying this value higher than the default probably increases the delay in
routing to target regions on remote CECs.

Note that the effectiveness of this parameter is increased as the
characteristics (for example, maxtask value or number of long-running
tasks) of the target regions become similar.

Chapter 51. CMAS journaling

A CICSplex SM address space (CMAS) is capable of producing CICS journal records to track a variety of activities in the CICSplex. These journal records provide an audit trail that can aid in the recovery of data or the reconstruction of events that affected the CICSplex. A journal record can be written when:

- A definition in the data repository is added, removed, or updated
- An operations action is issued against a MAS
- A real-time analysis event is generated.

For example, when a CMAS serves as the temporary maintenance point, it temporarily stores in its data repository any definitions that you add, update, or remove. When the maintenance point CMAS resumes operation, the temporary information is removed. You can obtain journal records of what is added to and deleted from the data repository for the temporary maintenance point.

The journal records are stored in a 32KB buffer and are flushed to the corresponding log streams when the buffer becomes full or when a normal shutdown of the CICS region is initiated.

To force the buffer to be flushed to a log stream when the CICS region is still active, you could specify the `WAIT` option on the `WRITE JOURNALNAME` command using `EXEC CICS` or the `CECI` transaction.

To request one or more of the record types, specify the appropriate CICSplex SM system parameters in the startup JCL of a CMAS:

JRNDEFCH(YES)	For data repository definition changes
JRNLOPACT(YES)	For operations actions
JRNLRRTAEV(YES)	For real-time analysis events

For more information on these parameters, see Chapter 50, “CICSplex SM system parameters,” on page 383.

If you do not want to use the CICSplex SM default log stream name of `EYUJRNL`, you must define a `JOURNALMODEL` resource in the CSD that has the desired log stream name. The distributed CMAS resource definition group and group list are protected from modification. Thus, to make the `JOURNALMODEL` resource definition available during CMAS initialization, you must create a new CMAS group list that includes the group containing the `JOURNALMODEL` resource definition. To add the `JOURNALMODEL` resource to the CSD, either edit and run the JCL contained in sample member `CICSTS31.CPSM.SEYUSAMP(EYUJRNE$)` to execute batch utility `DFHCSDUP` or use the CICS `CEDA` transaction. Performing either of these steps does the following:

- Appends the protected `EYU310L0` group list to a new unprotected group list.
- Defines the desired `JOURNALMODEL` for `EYUJRNL` in an unprotected group.
- Adds the unprotected group to the new, unprotected group list.

You must also update the CICS system initialization (SIT) parameters used to start the CMAS by setting the `GRPLIST` parameter to reference the new group list.

The journal records produced by a CMAS contain data mapped by a DSECT called `EYUBCPJR`. Each record consists of a standard prefix and a variable data area. The contents of the data area are specific to the type of journal record being written.

Figure 60 shows the format of EYUBCPJR.

* EYUBCPJR DSECT Prefix *			

EYUBCPJR	DSECT		
EYUBCPJR	DS	0D	
CPJR_PREFIX	DS	0D	Prefix of record
CPJR_CMASNAME	DS	CL8	CMAS Name which produced record
CPJR_CONTEXT	DS	CL8	Plex Name
CPJR_SCOPE	DS	CL8	Scope Name
CPJR_USER	DS	CL8	User Name
CPJR_STCK	DS	D	Store clock
CPJR_VERSION	DS	H	Current record version
CPJR_VER_ZERO	EQU	0000	Version 0
CPJR_VER_ONE	EQU	0001	Version 1
CPJR_VER_CURR	EQU	CPJR_VER_ONE	Current Version
CPJR_TYPE	DS	H	Record type
CPJR_TYPE_DEFCH	EQU	0001	Definition Add/Change/Delete
CPJR_TYPE_RTAEV	EQU	0002	Rta Event
CPJR_TYPE_OPACT	EQU	0003	Operation action
CPJR_LENGTH	DS	F	Length of entire record plus x prefix area
	DS	FL8	Available for use
CPJR_LEN	EQU	*-CPJR_PREFIX	Length of Prefix area
CPJR_DATA_AREA	DS	0H	Data area

* Data record for RTA Events *			

CPJR_RTA_DATA	DS	0H	
CPJR_RTA_TYPE	DS	X	Record type
CPJR_RTATYPE_CRT	EQU	0001	Event Created
CPJR_RTATYPE_REM	EQU	0002	Event Removed
CPJR_RTATYPE_UPD	EQU	0003	Event Updated
CPJR_RTATYPE_RES	EQU	0004	Event Resolved
CPJR_RTA_GTYPE	DS	X	Generated by type
CPJR_RTAGTYPE_SAM	EQU	0001	Event produced by Sam
CPJR_RTAGTYPE_APM	EQU	0002	Event produced by Apm
CPJR_RTAGTYPE_MRM	EQU	0003	Event produced by Mrm
CPJR_RTA_EVENT	DS	CL8	Event Name
CPJR_RTA_MSGSTRT	DS	CL30	External Entry Message
CPJR_RTA_MSGEND	DS	CL30	External Exit Message
CPJR_RTA_EVENTXT	DS	CL30	Event Text
CPJR_RTA_SEVERITY	DS	CL3	Severity Level
CPJR_RTA_DATA_L	EQU	*-CPJR_RTA_DATA	Length of the record

Figure 60. The EYUBCPJR DSECT (Part 1 of 2)

```

*-----*
*                               Data record for Definition changes                               *
*-----*

CPJR_DEF_DATA      DS  0H
CPJR_DEF_TYPE      DS  X          Record type
CPJR_DEFTYPE_ADD   EQU 0001      Definition Added
CPJR_DEFTYPE_DEL   EQU 0002      Definition Deleted
CPJR_DEFTYPE_UPD   EQU 0003      Definition Update
CPJR_DEF_TYPE      DS  X          Reserved
CPJR_DEF_MAJORNM   DS  CL8       Major Name
CPJR_DEF_MAJORID   DS  CL8       ADMIN Restype
# CPJR_DEF_MAJORVR   DS  XL4       Major Version
# CPJR_DEF_MAJORVR_NONE EQU -1    Major Version None
CPJR_DEF_MINORNM   DS  CL8       Minor Name
CPJR_DEF_MINORID   DS  CL8       ADMIN Restype
# CPJR_DEF_MINORVR   DS  XL4       Minor Version
# CPJR_DEF_MINORVR_NONE EQU -1    Minor Version None
# CPJR_DEF_SYSID    DS  CL8       System Id where change was originated x
CPJR_DEF_DATA_L    EQU *-CPJR_DEF_DATA Length of the record

*-----*
*                               Data record for Operation commands                               *
*-----*

CPJR_OPS_DATA      DS  0H
CPJR_OPS_LENGTH    DS  H          Length of fixed and variable x
                                portion of data area
CPJR_OPS_NUMFLDS   DS  H          Number of fields
CPJR_ACTION        DS  CL12       Name of action

CPJR_RESNAME       DS  CL8       Resource Name
CPJR_OPS_STRTENT   DS  0C        Start of data entries
CPJR_OPS_DATA_L    EQU *-CPJR_OPS_DATA Length of the record
*
CPJR_OPS_ENTRY     DS  0C
CPJR_OPS_FIELD     DS  CL12      Field Name
CPJR_OPS_DATALEN   DS  X          Length of the Data
CPJR_OPS_ENTLEN    DS  X          Length of entire entry
CPJR_OPS_FLDDATA   DS  0C        Start of the Data
CPJR_OPS_ENT_L     EQU *-CPJR_OPS_ENTRY Fixed portion length

```

Figure 60. The EYUBCPJR DSECT (Part 2 of 2)

For information on writing a program to access and format CICS journal records, refer to the *CICS Customization Guide*.

Chapter 52. Preparing to use the IPCS tools

The interactive problem control system (IPCS) provides MVS users with an interactive facility for diagnosing software failures. You can use IPCS to format and analyze SDUMPs produced by CICSplex SM or stand-alone dumps obtained while CICSplex SM was active in the system being dumped. You can either view the dumps at your terminal or print them.

Note: The CICSplex SM IPCS tools are available only for CASs, CMASs, or MASs running in an MVS image.

CICSplex SM provides two types of IPCS tools:

- A set of panels (driven by a corresponding set of CLISTs) that allow you to display:
 - The data in a coordinating address space (CAS) dump
 - The names and locations of control blocks and areas of a CAS dump
 - Subsystem information
 - Address space-related control blocks
 - Modules loaded by CICSplex SM
 - Tasks created by CICSplex SM
 - Storage subpools managed by CICSplex SM
 - BBC LU 6.2 communication information
- A dump formatting routine that can be used with the VERBEXIT subcommand to format CMAS or MAS dumps

For more information about:

- IPCS, see the *MVS Interactive Problem Control System: User's Guide*.
- Using IPCS to format CICSplex SM system dumps, see the *CICS Operations and Utilities Guide*.
- Displaying and formatting dumps with IPCS, see the *CICSplex System Manager Problem Determination* manual.

Before you can use the CICSplex SM IPCS tools, you must make the preparations described in:

- "Updating BLSCECT"
- "Updating library allocations" on page 402
- "SDUMP options" on page 402.

Updating BLSCECT

IPCS provides an exit control table called BLSCECT; it normally resides in SYS1.PARMLIB. This table contains imbed statements to enable other products to supply exit control information. You must perform the following steps:

1. Update the BLSCECT table for either a MAS-only environment or for a CMAS environment.
 - When the EYUINST ENVIRONMENT parameter of MAS was used to install CICSplex SM, then the following IMBED statement is required:
`IMBED MEMBER(EYUIPCSP) ENVIRONMENT(ALL)`
 - When the EYUINST ENVIRONMENT parameter of CMAS was used to install CICSplex SM, then the following IMBED statements are required:
`IMBED MEMBER(EYUIPCSP) ENVIRONMENT(ALL)`
`IMBED MEMBER(BBM3IPCS) ENVIRONMENT(ALL)`

Updating BLSCECT

BBM3IPCS defines the CICSPlex SM main panel as CPSMSSDA, and adds an entry for the panel to the IPCS MVS component menu. EYUIPCSP identifies the CICSPlex SM formatting routine as EYU9D310 with a VERB name of CPSM310.

2. Make sure the required parameter member(s) can be found by your IPCS job by doing one of the following:
 - Copy the required parameter member(s) from the CICSTS31.CPSM.SEYUPARM library into the same library as BLSCECT (usually SYS1.PARMLIB).
 - Provide an IPCSPARM DD statement to specify the library that contains the IPCS control tables. For example, the DD statement for a batch TSO session might look like this:

```
//IPCS Parm DD DSN=SYS1.PARMLIB,DISP=SHR          for BLSCECT
//          DD DSN=CICSTS31.CPSM.SEYUPARM,DISP=SHR for BBM3IPCS/EYUIPCSP
```

For more information about SYS1.PARMLIB library members related to IPCS, see the *MVS Interactive Problem Control System (IPCS): Customization* manual.

Updating library allocations

To update the library allocations, you must do the following:

- Update the CLIST or REXX EXEC that invokes IPCS at your enterprise to include the following data set allocations:

ISPPLIB CICSTS31.CPSM.SEYUPLIB

Contains panels that allow you to view data structures.

SYSPROC CICSTS31.CPSM.SEYUCLIB

Contains CLISTs that obtain information from a dump and display it. These CLISTs also create a set of IPCS symbol equates to help you locate data while browsing a dump outside of the panels.

ISPMLIB CICSTS31.CPSM.SEYUMLIB

Contains messages issued by the CLISTs.

- Make sure that the EYU9D310 IPCS user exit routine is in a library in the linklist or a library that is accessed by the JOBLIB, STEPLIB, or TASKLIB option of the IPCS command, during IPCS session. To accomplish this, do one of the following:
 - Allocate CICSTS31.CPSM.SEYULINK to the desired DD statement.
 - Copy CICSTS31.CPSM.SEYULINK (EYU9D310) to an appropriate library.
 - Invoke IPCS, using the TASKLIB keyword to allocate CICSTS31.CPSM.SEYULINK .

For example, issue the TSO COMMAND:

```
IPCS NOPARM TASKLIB('CICSTS31.CPSM.SEYULINK ')
```

SDUMP options

Make sure the following SDUMP options are in effect at the time the dump is taken:

CSA Common service area

LPA Link pack area modules

LSQA Local system queue area

NUC Non-page-protected areas of the DAT-on nucleus

PSA	Prefixed storage area for all processors
RGN	Private area of address space being dumped
SQA	System queue area
SUM	Summary dump
SWA	Scheduler work area
TRT	GTF, system trace, and master trace data

SDUMP options

Part 6. CICSplex SM verification

This part describes the processes and procedures you should follow to run the installation verification procedures for CICSplex SM. It contains the following chapters

- Chapter 53, “CICSplex SM installation verification procedures,” on page 407
- Chapter 54, “Installation verification procedure 1 (IVP1),” on page 411
- Chapter 55, “Installation verification procedure 2 (IVP2),” on page 425

Chapter 53. CICSplex SM installation verification procedures

This chapter describes how to run the CICSplex SM installation verification procedures (IVPs) to confirm that CICSplex SM has been installed successfully. It is recommended that you run the IVPs before you complete the setup and configuration tasks for your environment.

There are two IVPs for the installation of CICSplex SM on MVS, IVP1 and IVP2:

- IVP1 verifies the installation of CICSplex SM on the first or only MVS image.
- IVP2 verifies the installation of CICSplex SM on the second and subsequent MVS images.

IVP1 and IVP2 are largely the same, except that IVP2 incorporates tests of links to and from the CICSplex SM components established by IVP1.

Please note the following:

- While you are running the IVPs, you will encounter the CICSplex SM term *view*. A view is simply a formatted display of data relating to one or more CICS resources or CICSplex SM definitions.
- You enter commands throughout the IVPs by typing the command name in the COMMAND field of the current view and pressing Enter. However, if any particular command is assigned to a PF key, you may use the PF key instead of typing the command name.

For general information about the CICSplex SM ISPF user interface, see the *CICSplex System Manager User Interface Guide*.

If the IVPs do not work as described

You run the IVPs to verify that CICSplex SM has been installed successfully. Therefore, the failure of an IVP is likely to mean that either the installation of CICSplex SM has not succeeded, or preceding steps of the IVP have failed. Error messages may be issued at any stage of the IVPs: please refer to the *CICSplex System Manager Messages and Codes* manual for detailed descriptions of CICSplex SM error messages.

The stages of IVP1 and IVP2

During the course of performing the tasks of IVP1 and IVP2, you install a subset of the CICSplex SM Starter Set that is sufficient to test all major components and functions of CICSplex SM. The structure and purpose of the Starter Set are described in the *CICSplex System Manager Concepts and Planning* manual. How to configure the Starter Set for use in your enterprise is described in Chapter 47, “Configuring the Starter Set,” on page 361.

The main stages of IVP1 and IVP2 are:

1. Setting up the CICSplex SM environment
2. Starting the CICSplex SM components
 - a. Starting the CAS
 - b. Starting the CMAS
 - c. Defining a CICSplex
 - d. Loading definitions using the batched repository update facility
 - e. Starting the MAS

3. Testing the CICSPlex SM operations functions

When you have defined your own CICSPlex SM configuration, you might want to rerun IVP1 and IVP2 using your own CASs, CMASs, and MASs rather than those of the Starter Set. Instructions for running IVP1 and IVP2 with your own configuration are supplied in “Customizing the installation verification procedures” on page 443.

The IVP samples libraries

The JCL and sample definitions you need to run IVP1 and IVP2 are in the Starter Set samples libraries CICSTS31.CPSM.SEYUJCL and CICSTS31.CPSM.SEYUDEF. The library CICSTS31.CPSM.SEYUJCL includes sample JCL for creating, running, and deleting the Starter Set components created during IVP1 and IVP2. The library CICSTS31.CPSM.SEYUDEF includes samples such as VTAM definitions and CICS tables. Table 43, Table 44, Table 45, and Table 46 on page 409 identify the JCL and definitions used during IVP1 and IVP2.

Table 43. JCL in CICSTS31.CPSM.SEYUJCL for creating the IVP components

Sample name	IVP1	IVP2	Description
EYUIBBIA	✓	✓	Creates CAS data sets EYUSDEF and EYUIPRM on system A
EYUIBBIB		✓	Creates CAS data sets EYUSDEF and EYUIPRM on system B
EYUICICA	✓	✓	Creates MAS data sets on system A
EYUICICB		✓	Creates MAS data sets on system B
EYUICMSA	✓	✓	Creates CMAS data sets on system A
EYUICMSB		✓	Creates CMAS data sets on system B
EYUIDRPA	✓	✓	Creates data repository on system A
EYUIDRPB		✓	Creates data repository on system B
EYUICSDA	✓	✓	Creates DFHCSD data set on system A
EYUICSDB		✓	Creates DFHCSD data set on system B

Table 44. JCL in CICSTS31.CPSM.SEYUJCL for running the IVPs

Sample name	IVP1	IVP2	Description
EYUICM1A	✓	✓	Starts CMAS EYUCMS1A on system A
EYUICM1B		✓	Starts CMAS EYUCMS1B on system B
EYUIMS1A	✓	✓	Starts MAS EYUMAS1A on system A
EYUIMS1B		✓	Starts MAS EYUMAS1B on system B
EYUICS1A	✓	✓	Starts CAS EYUCAS1A on system A
EYUICS1B		✓	Starts CAS EYUCAS1B on system B
EYUICSSA	✓	✓	Starts CAS EYUCAS1A on system A as a started task
EYUICSSB		✓	Starts CAS EYUCAS1B on system B as a started task

Table 45. Starter Set definitions in CICSTS31.CPSM.SEYUDEF used by the IVPs

Sample name	IVP1	IVP2	Description
EYUDVTIA	✓	✓	VTAM definitions for system A
EYUDVTIB		✓	VTAM definitions for system B
EYUDCDMA		✓	CDRM definitions for system A
EYUDCDMB		✓	CDRM definitions for system B

Table 45. Starter Set definitions in CICSTS31.CPSM.SEYUDEF used by the IVPs (continued)

Sample name	IVP1	IVP2	Description
EYUMDTAB	✓	✓	Modetable for CASs
EYUTPLTC	✓	✓	DFHPLT for CMASs
EYUTPLTL	✓	✓	DFHPLT for local MAS
EYUTSRTS	✓	✓	DFHSRT for CMASs and MASs
EYU@ISPF	✓	✓	ISPF logon procedure
EYU@PRIM	✓	✓	ISPF primary option panel

Table 46. JCL in CICSTS31.CPSM.SEYUJCL for deleting components created by the IVPs

Sample name	IVP1	IVP2	Description
EYUIBBDA	✓	✓	Deletes CAS data sets on system A
EYUIBBDB		✓	Deletes CAS data sets on system B
EYUICIDA	✓	✓	Deletes MAS data sets on system A
EYUICIDB		✓	Deletes MAS data sets on system B
EYUIDRDA	✓	✓	Deletes the data repository on system A
EYUIDRDB		✓	Deletes the data repository on system B
EYUICDDA	✓	✓	Deletes the DFHCSD data set on system A
EYUICDDB		✓	Deletes the DFHCSD data set on system B
EYUICMDA	✓	✓	Deletes the CMAS data sets on system A
EYUICMDB		✓	Deletes the CMAS data sets on system B

Note: When you have run IVP1 and IVP2, you might want to use the JCL listed in Table 46 to delete the Starter Set components you have created. However, if you are planning to configure the Starter Set for use on an MVS image on which you have run an IVP, keeping the IVP components might save you some effort at a later stage. See Chapter 47, “Configuring the Starter Set,” on page 361 for more information.

Chapter 54. Installation verification procedure 1 (IVP1)

It is recommended that you run IVP1 on the first or only MVS image on which you install CICSplex SM. Before you begin, ensure that the CICSplex SM data sets are authorized as described in “Authorizing libraries” on page 283. On the MVS image on which you run IVP1 (which is referred to in the remainder of this section as “system A”) you must have access to:

- The CICSplex SM samples data sets CICSTS31.CPSM.SEYUDEF and CICSTS31.CPSM.SEYUJCL
- CICS load libraries
- CICS table-assembly JCL
- The CEDA transaction on MAS EYUMAS1A
- The MVS console log via TSO SDSF.

Figure 61 shows those components of the CICSplex SM Starter Set that are defined during IVP1.




Figure 61. Starter Set components for IVP1. Shaded components—EYUCAS1A, EYUCMS1A, and EYUMAS1A—are used during IVP1

Setting up the CICSplex SM environment on system A

Perform the following steps to prepare the MVS environment on system A for CICSplex SM:

1. Run EYUISTRT on system A to tailor the skeleton jobs for the Starter Set (and thereby for the IVPs). EYUISTRT runs the EYUINST EXEC to tailor the Starter Set members. For more information about EYUISTRT, see Chapter 49, “Using the EYUINST EXEC to tailor skeleton jobs,” on page 373. Table 47 identifies those EYUINST EXEC parameters that are applicable to the Starter Set.

Table 47. EYUINST EXEC parameters required for the Starter Set

Parameter	CMAS	MAS	Default
CINDEXnnn	Yes	Yes	None
CMASNAME	Yes		None
CRELEASE	Yes	Yes	None
DSINFO	Yes		index dsvlsr dsunit
ENVIRONMENT	Yes	Yes	None
INDEX	Yes	Yes	CICSTS31.CPSM
JOB	Yes	Yes	//XXXXXXXX JOB
LIB	Yes	Yes	CICSTS31.CPSM.XEYUINST
PREFIX	Yes	Yes	EYU
SCEESAMP	Yes		SYS1.SCEESAMP
SCOPE	Yes	Yes	STARTER
Note: The SCOPE value should be set to STARTER.			
SELECT	Yes		None
TEMPLIB	Yes	Yes	CICSTS31.CPSM.SEYUJCL
Note: For more information about TEMPLIB, see “EYUINST EXEC parameters” on page 375.			

2. Add VTAM definitions for EYUCAS1A, EYUCMS1A, and EYUMAS1A to the VTAM table on system A. An example of the VTAM definitions for these three CICSPlex SM components is provided in sample EYUDVTIA.

You need not add the VTAM definitions now to system B if you plan to not run IVP2. (Remember that IVP2 should be run when you will have CMAS-to-CMAS communication links.)

EYUDVTIA is a subset of the VTAM definitions required on system A for the complete Starter Set. It holds the basic definitions required to run IVP1.

Note: The sample VTAM definitions use MODETAB(EYUMDTAB). The source of this is in CICSTS31.CPSM.SEYUDEF, member EYUMDTAB. If you use the starter set VTAM definitions, you must assemble this table and put it into the VTAMLST library.

If you use Network Control Programs (NCP), you may need to create a mode table, using the sample entry shown in EYUMDTAB, in order to control the VTAM RUSIZE (request unit size) parameter.

3. Run the JCL EYUIBBIA, which defines the BBIPARM data set for CAS EYUCAS1A.
4. Run the JCL EYUICMSA, which defines all data sets required by CMAS EYUCMS1A.
5. Run the JCL EYUICICA, which defines all data sets required by MAS EYUMAS1A.

6. Run the JCL EYUIDRPA, which defines the CICSplex SM data repository on system A.

Note: This data repository can be used with the Starter Set on system A: it does not need to be recreated after the IVPs have been run.)

7. Run the JCL EYUICSDA, which defines, initializes, and loads the CSD to be used by both EYUCMS1A and EYUMAS1A.
8. Make any necessary site-specific changes to the CSD created in step 7. For example, you might need to add TYPETERMS, TERMINALS or AUTOINSTALL MODELS.
9. Assemble the following sample CICS tables into a load library:
 - EYUTPLTC (PLT for EYUCMS1A)
 - EYUTPLTL (PLT for EYUMAS1A)
 - EYUTSRTS (SRT)

Notes:

- a. Ensure that you have a model installed for the system log stream. The default naming convention is userid.applid.DFHLOG and userid.applid.DFHSHUNT for a system log stream, and userid.applid.DFHJnn (where nn is 01 through 99) for a user journal. See Chapter 24, “Defining the logger environment for CICS journaling,” on page 143 and the *CICS System Definition Guide* for more information about creating log streams.
 - b. TDQ definitions are added to the CSD when the CSD is created or upgraded.
 - c. For details on assembling CICS control tables, see the *CICS/ESA System Definition Guide*.
10. Update ISPF on system A to reflect the addition of CICSplex SM. You can find an example of the required changes in EYU@ISPF and EYU@PRIM. Note that any changes you make to ISPF are generally applicable on system A and are not confined to IVP1 only. Therefore, you should try to make a permanent change at this stage so that you don’t have to repeat this step later. For more information, see Chapter 42, “Preparing user access to CICSplex SM,” on page 313.

Starting up and verifying CICSplex SM components on system A

When the system A environment for CICSplex SM is established, you are ready to:

1. Start the CAS EYUCAS1A
2. Start the CMAS EYUCMS1A
3. Define a CICSplex
4. Run the batched repository update facility
5. Start the MAS EYUMAS1A

1: Start the CAS EYUCAS1A

1. Log on to system A and start the CAS using either JCL EYUICS1A or (to start the CAS as a started task) JCL EYUICSSA. When you start the CAS, output similar to this appears in the JES2 job log:

```

COMMAND INPUT ==>
                                                                    SCROLL ==> PAGE
***** TOP OF DATA *****
                J E S 2  J O B  L O G  --  S Y S T E M  M V 2 6  --

BBMYAB62I Default system values used for CAS definition
BBMXCL41I Default system values used for target definition
BBMXBI17I Default security parameters used
BBMXBI26I Default security resource properties used
BBMXCL36I Default security resource definition used for COMMON resources
BBMSS001I Security - ESMTYPE(RACF) SUBSYS(EYUA) REQSTOR(<asis>) APPL(EYUA)
BBMZA001I CAS(MV26) SSID(EYUA) INITIALIZATION COMPLETE - R3.3.8 (HPC2300)
BBMXCL36I Default security resource definition used for PLEXMGR resources

```

2. Look for message number BBMZA001I in the output to confirm that the CAS EYUCAS1A is started.

2: Start the CMAS EYUCMS1A

1. Check the CICS Transaction Server for z/OS system initialization table (SIT) parameters in JCL EYUICM1A, in particular the SVC numbers and the default user, to ensure that they are suitable for your environment.
2. Submit JCL EYUICM1A. The output from EYUICM1A is similar to this:

```

COMMAND INPUT ==>                                SCROLL ==> PAGE
11.12.45 JOB13455 +DFHCP0102I EYUCMS1A CPI initialization has ended.
11.12.45 JOB13455 +DFHPR0105I EYUCMS1A Partner resource manager initialization has ended.
11.12.45 JOB13455 +DFHAI0102I EYUCMS1A AITM initialization has ended.
11.12.46 JOB13455 +DFHSI1511I EYUCMS1A Installing group list CMSIAGPL.
11.12.48 JOB13455 +DFHLG0103I EYUCMS1A System log (DFHLOG) initialization has started.
11.12.49 JOB13455 +DFHLG0104I EYUCMS1A 759
759 System log (DFHLOG) initialization has ended. Log stream
759 CICINST.EYUCMS1A.DFHLOG is connected to structure LOG_GENERAL_002.
11.12.49 JOB13455 +DFHLG0103I EYUCMS1A System log (DFHSHUNT) initialization has started.
11.12.50 JOB13455 +DFHLG0104I EYUCMS1A 761
761 System log (DFHSHUNT) initialization has ended. Log stream
761 CICINST.EYUCMS1A.DFHSHUNT is connected to structure LOG_GENERAL_002.
11.12.50 JOB13455 +DFHLG0745I EYUCMS1A System log full scan has started.
11.12.50 JOB13455 +DFHLG0748I EYUCMS1A System log selective scan has started.
11.12.50 JOB13455 +DFHLG0749I EYUCMS1A System log scan has completed.
11.12.50 JOB13455 +DFHRM0156 EYUCMS1A This COLD start will NOT cause any damage to local resources.
11.12.50 JOB13455 +DFHRX0106I EYUCMS1A Restart processing with Resource Recovery Services (RRS) is beginning.
11.12.50 JOB13455 +DFHRX0107I EYUCMS1A Restart processing with Resource Recovery Services (RRS) has ended.
11.12.51 JOB13455 +DFHSI1519I EYUCMS1A The interregion communication session was successfully started.
11.12.51 JOB13455 +DFHAP1203I EYUCMS1A Language Environment is being initialized.
11.12.52 JOB13455 +DFHAP1211I EYUCMS1A Language Environment initialization completed.
11.12.53 JOB13455 +DFHWB1007 EYUCMS1A Initializing CICS Web environment.
11.12.53 JOB13455 +DFHWB1008 EYUCMS1A CICS Web environment initialization is complete.
11.12.53 JOB13455 +DFHSI8440I EYUCMS1A Initiating connection to CICSplex SM.
11.12.53 JOB13455 +EYUXL0001I EYUCMS1A CMAS PLTPI program starting
11.12.53 JOB13455 +EYUXL0002I EYUCMS1A CICS TRACE active
11.12.54 JOB13455 +EYUXL0017I EYUCMS1A CMAS PLTPI program terminating
11.12.54 JOB13455 +DFHSI1517 EYUCMS1A Control is being given to CICS.
11.12.54 JOB13455 +DFHEJ0102 EYUCMS1A Enterprise Java domain initialization has ended.
11.12.54 JOB13455 +EYUXL0003I EYUCMS1A CPSM Version 0310 CMAS startup in progress
11.12.55 JOB13455 +DFHFC0208I EYUCMS1A 794
794 LSR pool 1 is being built dynamically by CICS because all of the
794 necessary parameters have not been supplied. Either there is no
794 LSRPOOL definition or it is incomplete. The following are not
794 defined: 'CI SIZE' 'STRINGS' 'MAXKEYLENGTH'. A delay is possible.
11.12.55 JOB13455 +DFHFC0961 EYUCMS1A 799
799 01/26/2005 11:12:55 EYUCMS1A Calculation of LSR pool 1 parameters
799 incomplete. Filename EYUDREPN has no DSNNAME.
11.12.57 JOB13455 +EYUXL0022I EYUCMS1A CMAS Phase I initialization complete
11.12.57 JOB13455 +EYUXL0211I EYUCMS1A CPSM Start Up Parameters
11.12.57 JOB13455 +EYUXL0212I EYUCMS1A CASNAME(EYUA)
11.12.57 JOB13455 +EYUXL0212I EYUCMS1A NAME(EYUCMS1A)
11.12.57 JOB13455 +EYUXL0020I EYUCMS1A ESSS connection in progress
11.12.57 JOB13455 +EYUXL0004I EYUCMS1A ESSS connection complete
11.12.58 JOB13455 +EYUCR0006W EYUCMS1A Security checking disabled per SEC(NO) EYUPARM parameter specification
11.12.58 JOB13455 +EYUCW0108I EYUCMS1A Time zone offset from GMT computed based on CMAS time zone attributes
11.12.59 JOB13455 +EYUXL0007I EYUCMS1A CMAS Phase II initialization complete
11.12.59 JOB13455 +EYUXL0007I EYUCMS1A CMAS Phase III initialization complete
11.12.59 JOB13455 +EYUXL0007I EYUCMS1A CMAS Phase IV initialization complete
11.13.00 JOB13455 +EYUXL0009I EYUCMS1A CAS connection established
11.13.30 JOB13455 +EYUXL0010I EYUCMS1A CMAS initialization complete
11.13.30 JOB13455 +EYUXL0008I EYUCMS1A CICSplex registration complete

```

3. In the output from EYUICM1A, look for messages EYUXL0009I and EYUXL0008I to confirm that the CMAS EYUCMS1A is started.

3: Define a CICSplex to CICSplex SM

During this stage, you define a CICSplex to CICSplex SM via the CICSplex SM end-user interface.

1. Log on to TSO on system A and select the CICSplex SM option from the main ISPF panel; the CICSplex SM option is CP if you are using the supplied samples. Ensure that "EYUA" is specified as the subsystem ID. (This can be changed using option 0.1 from the main ISPF panel.) The CICSplex System Manager entry panel is displayed:

```

----- CICSPlex System Manager -----
OPTION ==>

0 PROFILE      - User Session Parameters
1 PLEXMGR     - List of Service Points
2 CPSM        - CICSPlex SM

      Default Criteria for CPSM:

Context          ==> EYUCMS1A
Scope           ==> EYUCMS1A
Warning Record Count ==> 0          0 for no checking
Require Set      ==> YES          YES, NO

      Licensed Materials - Property of IBM
      5697-E93 (C) Copyright IBM Corp. 1994, 2010.
      All Rights Reserved. U.S. Government Users
      Restricted Rights - Use, Duplication or Disclosure
      restricted by GSA ADP Schedule Contract with IBM Corp.

```

2. Select CICSPlex SM by typing the value “2” in the OPTION field. Before pressing Enter, ensure that both the Context field and the Scope field contain the name of the CMAS, which is EYUCMS1A. The MENU menu is displayed:

```

27FEB2005 13:38:17 ----- INFORMATION DISPLAY -----
COMMAND ==>                                     SCROLL ==> PAGE
CURR WIN ==> 1          ALT WIN ==>
W1 =MENU=====EYUCMS1A=EYUCMS1A=27FEB2005==13:38:17=CPSM=====14==
CMD Name          Description
-----
ANALYSIS  Real Time Analysis Operations Views
CONFIG    CMAS Configuration Operations Views
MONITOR   Monitoring Views
OPERATE   Operations Views
TOPOLOGY  Topology Operations Views
WORKLOAD  Workload Operations Views
=====
ADMSAM    RTA System Availability Monitoring Administration Views
ADMRRM    RTA MAS Resource Monitoring Administration Views
ADMMPM    RTA Analysis Point Monitoring Administration Views
ADMCONFG  CMAS Configuration Administration Views
ADMMON    Monitor Administration Views
ADMTOPOL  Topology Administration Views
ADMWLM    Workload Manager Administration Views
ADMBAS    Business Application Services Administration Views
ADMRES    Business Application Services Resource Views

```

3. From the MENU menu, select ADMCONFG. You can select ADMCONFG in one of three ways. You can:
 - Type ADMCONFG in the COMMAND field and press Enter.
 - Move the cursor down to the ADMCONFG line, type S (for select) in the C column, and press Enter.
 - Move the cursor to the ADMCONFG value or its description and press Enter.

Note: You can select any view from a menu of views using any of these methods.

The ADMCONFIG menu is displayed:

```

27FEB2005 13:38:28 ----- INFORMATION DISPLAY -----
COMMAND ===>                                SCROLL ===> PAGE
CURR WIN ===> 1          ALT WIN ===>
W1 =MENU=====EYUCMS1A=EYUCMS1A=27FEB2005==13:38:28=CPSM=====6===
CMD Name          Description
-----
ADMCONFIG  CMAS Configuration Administration Views
BATCHREP   Batched Repository Updates
CPLEXDEF   CICSplex Definitions
CPLXCMAS   CMAS in CICSplex Definitions
CMTCMDEF   CMAS-to-CMAS Link Definitions
CMTPMDEF   CMAS-to-RMAS Link Definitions
  
```

- From the ADMCONFIG menu, select CPLEXDEF. The CPLEXDEF view is displayed:

```

27FEB2005 13:39:00 ----- INFORMATION DISPLAY -----
COMMAND ===>                                SCROLL ===> PAGE
CURR WIN ===> 1          ALT WIN ===>
W1 =CPLEXDEF=====EYUCMS1A=EYUCMS1A=27FEB2005==13:38:28=CPSM=====
BBMXBD15I There is no data which satisfies your request
  
```

The CPLEXDEF view contains message BBMXBD15I because, at this stage, there are no CICSplexes defined to CMAS EYUCMS1A.

- To create a CICSplex definition, type CRE in the COMMAND field of the CPLEXDEF view and press Enter. The Create CICSplex input panel is displayed:

```

----- Create CICSplex for EYUCMS1A -----
COMMAND ===>

CICSplex name      ===>
Description        ===>
Monitor Interval   ===> 480   Performance interval duration (15-1440 min)
Daylight Savings Time ===> NO   YES or NO
Time Zone          ===> B     Time zone for interval (B-Z)
Time Zone Adjustment ===> 0     Offset from time zone (0-59)
Populate in Resource
  Status Facility  ===> NO     Monitored by the resource
                                     status facility
CICS Command Checking ===> NO   Simulated CICS Command Checks
CICS Resource Checking ===> NO   Simulated CICS Resource Checks
Exemption Checking  ===> NO     Check for Exempt Users

Press ENTER to create CICSplex.
Type END or CANCEL to cancel without creating.
  
```

In the CICSplex Name field, type the value EYUPLX01, and supply a brief description (for example, "IVP 1 CICSplex") in the Description field. Leave all other fields to default and press Enter. The CPLEXDEF view is redisplayed:

```

27FEB2005 13:39:25 ----- INFORMATION DISPLAY -----
COMMAND ===>                                SCROLL ===> PAGE
CURR WIN ===> 1          ALT WIN ===>
W1 =CPLEXDEF=====EYUCMS1A=EYUCMS1A=27FEB2005==13:39:25=CPSM=====1===
CMD Name      Mon Time Zone Day  Cmd Res Xmp Res Description
---          - Intv Zone Adj  Save Chk Chk Chk Sta -----
EYUPLX01  480 B          0 NO   NO   NO   NO   IVP 1 CICSplex

```

The CPLEXDEF view now contains an entry for CICSplex EYUPLX01.

- Return to the CICSplex SM MENU menu by typing MENU in the COMMAND field of the CPLEXDEF view and pressing Enter.

4: Run the batched repository update facility on system A

During this stage you load several definitions into the data repository of CMAS EYUCMS1A using the batched repository update facility.

- From the CICSplex SM MENU menu, select ADMCONFIG. From the ADMCONFIG menu, select BATCHREP. The BATCHREP view is displayed:

```

27FEB2005 13:39:36 ----- INFORMATION DISPLAY -----
COMMAND ===>                                SCROLL ===> PAGE
CURR WIN ===> 1          ALT WIN ===>
W1 =BATCHREP=====EYUCMS1A=EYUCMS1A=27FEB2005==13:39:36=CPSM=====
BBMXBD15I There is no data which satisfies your request

```

- To submit a job to update the data repository, type the value SUB in the COMMAND field of the BATCHREP view and press Enter. The Start Batch Run input panel is displayed:

```

COMMAND ===>

Data Set Name  ===> 'CICSTS31.CPSM.SEYUDEF'

Data Set Member ===> EYUDDRIA

Print Class    ===> H

Print Node     ===> *

Output Userid  ===> *

Run Type       ===> EXECUTE                      (CHECK or EXECUTE)

Press ENTER to Run the Job.
Type END or CANCEL to cancel without Running.

```

Complete the Start Batch Run screen as shown above and press Enter. The supplied sample data repository definitions are loaded into the data repository of EYUCMS1A.

Note: The Print Class, Print Node, and Output Userid values are site specific. Consult your MVS administrator for valid values for these fields. Be

aware, however, that the Print Class value should identify a HELD output class so that the results of the batch run may be validated.

3. Verify that the batched repository update facility has created the definitions by examining the JOBLOG of EYUICM1A, which is in the HELD output queue. Look for message EYUXU0218I to verify this.

```
COMMAND INPUT ==>                                SCROLL ==> PAGE
***** TOP OF DATA *****
CREATE LNKSMSG  SPEC(EYUMOS03)
                GROUP(EYUCSG04)
                FORCE
                ;
EYUXU0218I EYUCMS1A BATCH CREATE REQUEST COMPLETE - STATUS(OK)
CREATE LNKSMSG  SPEC(EYUMOS03)
                GROUP(EYUCSG05)
                FORCE
                ;
EYUXU0218I EYUCMS1A BATCH CREATE REQUEST COMPLETE - STATUS(OK)
CREATE LNKSRS  SPEC(EYURTS01)
                SYSTEM(EYUMAS1A)
                ;
EYUXU0218I EYUCMS1A BATCH CREATE REQUEST COMPLETE - STATUS(OK)
CREATE LNKSRS  SPEC(EYURTS01)
                SYSTEM(EYUMAS4A)
                ;
EYUXU0218I EYUCMS1A BATCH CREATE REQUEST COMPLETE - STATUS(OK)
```

4. Return to the CICSplex SM MENU menu by typing MENU in the COMMAND field of the BATCHREP view and pressing Enter.

5: Start the MAS EYUMAS1A

1. Check the SIT parameters in JCL EYUIMS1A, in particular the SVC numbers and the default user, to ensure that they are suitable for your environment.
2. Submit JCL EYUIMS1A from TSO. Output similar to this appears in the job log:

COMMAND INPUT ==>

SCROLL ==> PAGE

```
13.06.30 JOB13676 +DFHSI1511I EYUMAS1A Installing group list MAS1AGPL.
13.06.33 JOB13676 +DFHLG0103I EYUMAS1A System log (DFHLOG) initialization has started.
13.06.34 JOB13676 +DFHLG0104I EYUMAS1A 983
983 System log (DFHLOG) initialization has ended. Log stream
983 CICINST.EYUMAS1A.DFHLOG is connected to structure LOG_GENERAL_002.
13.06.34 JOB13676 +DFHLG0103I EYUMAS1A System log (DFHSHUNT) initialization has started.
13.06.34 JOB13676 +DFHLG0104I EYUMAS1A 997
997 System log (DFHSHUNT) initialization has ended. Log stream
997 CICINST.EYUMAS1A.DFHSHUNT is connected to structure LOG_GENERAL_002.
13.06.34 JOB13676 +DFHRX0106I EYUMAS1A Restart processing with Resource Recovery Services (RRS) is beginning.
13.06.35 JOB13676 +DFHRX0107I EYUMAS1A Restart processing with Resource Recovery Services (RRS) has ended.
13.06.35 JOB13676 +DFHSI1519I EYUMAS1A The interregion communication session was successfully started.
13.06.35 JOB13676 +DFHSZ4001 I 01/26/2005 13:06:35 EYUMAS1A FEPI initialization has started.
13.06.35 JOB13676 +DFHAP1203I EYUMAS1A Language Environment is being initialized.
13.06.35 JOB13676 +DFHSZ4002 I 01/26/2005 13:06:35 EYUMAS1A FEPI initialization has ended.
13.06.37 JOB13676 +DFHAP1211I EYUMAS1A Language Environment initialization completed.
13.06.37 JOB13676 +DFHWB1007 EYUMAS1A Initializing CICS Web environment.
13.06.37 JOB13676 +DFHWB1008 EYUMAS1A CICS Web environment initialization is complete.
13.06.37 JOB13676 +DFHSI8440I EYUMAS1A Initiating connection to CICSplex SM.
13.06.37 JOB13676 +EYUNX0001I EYUMAS1A LMAS PLTPI program starting
13.06.38 JOB13676 +EYUXL0003I EYUMAS1A CPSM Version 0310 LMAS startup in progress
13.06.39 JOB13676 +EYUXL0022I EYUMAS1A LMAS Phase I initialization complete
13.06.39 JOB13676 +EYUXL0211I EYUMAS1A CPSM Start Up Parameters
13.06.39 JOB13676 +EYUXL0212I EYUMAS1A NAME(EYUMAS1A)
13.06.39 JOB13676 +EYUXL0212I EYUMAS1A CICSplex(EYUPLX01)
13.06.39 JOB13676 +EYUXL0212I EYUMAS1A CMASYSID(CM1A)
13.06.39 JOB13676 +DFHEJ0102 EYUMAS1A Enterprise Java domain initialization has ended.
13.06.39 JOB13676 +DFHSI1517 EYUMAS1A Control is being given to CICS.
13.06.41 JOB13676 +EYUXL0020I EYUMAS1A ESSS connection in progress to CICSplex(EYUPLX01) for SYSID(CM1A)
13.06.41 JOB13676 +EYUXL0004I EYUMAS1A ESSS connection complete
13.06.41 JOB13676 +EYUCL0006I EYUMAS1A ESSS link to EYUCMS1A established
13.06.41 JOB13676 +EYUXL0007I EYUMAS1A LMAS Phase II initialization complete
13.06.42 JOB13676 +EYUNL0099I EYUMAS1A LMAS LRT initialization complete
```

3. Look for messages EYUXL0004I and EYUXL0007I to confirm that MAS EYUMAS1A is started.

Testing CICSplex SM functions

During this part of IVP1, you test the operations function of CICSplex SM on system A.

Test the operations functions on system A

During this stage of IVP1 you:

- Change the value of a CICS resource via CICSplex SM
 - Test the CICSplex SM help facility.
1. From the CICSplex SM MENU menu, check that the context and scope are still set to EYUPLX01 by looking at the window information line, which is the fourth line down from the top of the display. Following the two occurrences of the menu name (MENU) are the context (EYUPLX01) and scope (EYUPLX01) values.

From the MENU menu, select OPERATE. The OPERATE menu is displayed:

```

27FEB2005 13:48:12 ----- INFORMATION DISPLAY -----
COMMAND ==> SCROLL ==> PAGE
CURR WIN ==> 1 ALT WIN ==>
W1 =OPERATE=====EYUPLX01=EYUPLX01=27FEB2005==13:48:12=CPSM=====15===
CMD Name Description
-----
OPERATE Operations Views
CICSBTS CICS BTS Views
CONNECT Connection Views
DOCTEMP Document Template Views
DB2 DB2 and DBCTL Views
ENQUEUE Global Enqueue Views
ENTJAVA Enterprise Java component views
EXIT Exit Views
FEPI FEPI Views
FILE File Views
JOURNAL Journal Views
PROGRAM Program Views
REGION CICS Region Views
TASK Task Views
TCPIPS TCP/IP Service Views
TCPIPGBL TCP/IP Global Views
TDQ Transient Data Queue Views
TEMPSTOR Temporary Storage Queue Views
TERMINAL Terminal Views
TRANS Transaction Views
UOW Unit of Work Views

```

- From the OPERATE menu, enter CICSRGN to display details of CICS systems belonging to EYUPLX01. From the CICSRGN view, display a detailed view of data for region EYUMAS1A by moving the cursor to the entry for EYUMAS1A and pressing Enter.

Note: It is not sufficient to tab to the desired line on the display, the cursor must be placed under one of the letters of the name of the region, for example EYUMAS1A.

- The CICSRGND view for EYUMAS1A is displayed. Move the cursor to the Current Tasks field and press Enter. The CICSRGN3 view is displayed.
- Verify that the CICSplex SM help function is working by typing HEL in the COMMAND field of the CICSRGN3 view, moving the cursor to the MAXtasks field, and pressing Enter. A pop-up panel⁷ in which the MAXtasks field is described, overwrites the CICSRGN3 view.
- Type END in the COMMAND field of the help panel and press Enter to return to the CICSRGN3 view.
- From a second display, and following your local procedure, log on to CICS system EYUMAS1A. Type CEMT INQUIRE SYSTEM and press Enter. A summary of current values for CICS system EYUMAS1A is displayed:

7. If you are using a version of ISPF prior to Version 3 Release 1, all help information is provided in full-screen panels.

```

STATUS: RESULTS - OVERTYPE TO MODIFY
Aging( 00500 )                Progautoexit( DFHPGADX )
Akp( 04000 )                  Progautoinst( Autoinactive )
Cicstslevel(030100)           Reentprotect(Noreentprot)
Cmdprotect(Cmdprot)           Release(0640)
Db2conn( )                    Runaway( 0020000 )
Debugtool(Nodebug)            Scandelay( 5000 )
Dfltuser(CPSM)                Sdtran(CESD)
Dsalimit( 05242880 )          Sosstatus(Notsos)
Dsrtprogram( NONE )           Storeprotect(Inactive)
Dtrprogram( EYU9XLOP )        Time( 0005000 )
Dumping( Nosysdump )          Transolate(Inactive)
Edsalimit( 0033554432 )
Forceqr( Force )
Logdefer ( 00005 )
Maxtasks( 080 )
Mrobatch( 001 )
Oslevel(010400)
Progautoctlg( Ctlgmodify )

                                SYSID=MS1A APPLID=EYUMAS1A
RESPONSE: NORMAL                TIME: 13.49.16 DATE: 27.02.05
PF 1 HELP          3 END          5 VAR          7 SBH 8 SFH 9 MSG 10 SB 11 SF

```

Take a note of the current MAxtasks value.

- Return to the CICSplex SM session where the CICS RGN3 view is displayed. Tab the cursor to the left of the first field in the first row of data, type the word SET, then move the cursor to the MAxtasks field, change the current value to 60, and press Enter. The MAxtasks value changes to 60:

```

27FEB2005 13:49:39 ----- INFORMATION DISPLAY -----
COMMAND ==>
CURR WIN ==> 1          ALT WIN ==>
>W1 =CICSRGN==CICSRGN3=EYUMAS1A==EYUPLX01===27FEB2005==15:37:31===CPSM=====1
CICS System.. EYUMAS1A Tot Pgrm Use.      11 Cur LU Sess      0
Current Tasks      3 Pgrm Compress      0 HWM LU Sess      0
Peak Tasks...     13 Cur Act UTrn.        3
Current Amax.     N/A Cur Que UTrn.          0
Peak Amaxtask     N/A Peak Act UTrn          4
Total Tasks..    107 Peak Que UTrn          0
Interval task      6 Totl Act UTrn          6
Times at MAXT      0 Totl Que UTrn          0
Act Max Tasks     N/A Tot Que Time. 00:00:00
Maxtasks.....    60 Cur Que Time. 00:00:00
Pgrm AIn Attm      0 PRSS Inq Cnt.      0
Pgrm AIn Xrej      0 PRSS NIB Cnt.     0
Pgrm AIn Fail      0 PRSS Opn Cnt.     0
Pgrm Load NIU      26 PRSS UbndCnt.    0
Tot NIU Qtime 00:00:00 PRSS Err Cnt.    0
NIU Reclaims.      9

```

- To verify that the value has been changed in the CICS system itself, return to the CICS (EYUMAS1A) session and enter the CEMT INQUIRE SYSTEM command again. The MAxtasks value is 60:

STATUS: RESULTS - OVERTYPE TO MODIFY

```
Aging( 00500 )           Progautoexit( DFHPGADX )
Akp( 04000 )             Progautoinst( Autoinactive )
Cicstslevel(030100)      Reentprotect(Noreentprot)
Cmdprotect(Cmdprot)      Release(0640)
Db2conn( )               Runaway( 0020000 )
Debugtool(Nodebug)       Scandelay( 5000 )
Dfltuser(CPSM)           Sdtran(CESD)
Dsalimit( 05242880 )     Sosstatus(Notsos)
Dsrtprogram( NONE )      Storeprotect(Inactive)
Dtrprogram( EYU9XLOP )   Time( 0005000 )
Dumping( Nosysdump )     Transolate(Inactive)
Edsalimit( 0033554432 )
Forceqr( Force )
Logdefer ( 00005 )
Maxtasks( 060 )
Mrobatch( 001 )
Oslevel(010400)
Progautoctlg( Ctlgmodify )
```

SYSID=MS1A APPLID=EYUMAS1A

RESPONSE: NORMAL

TIME: 13.49.19 DATE: 27.02.05

PF 1 HELP 3 END 5 VAR 7 SBH 8 SFH 9 MSG 10 SB 11 SF

End the CICS session using CESF LOGOFF and return to the CICSplex SM session.

9. Type TRAN in the COMMAND field of the CICS RGN3 view and press Enter. The TRAN view, showing general information about transactions within EYUPLX01, is displayed. Move the cursor to the Tran ID CONL and press Enter. The LOCTRAN view, showing details of local transaction CONL in EYUMAS1A, is displayed.
10. Return to the CICSplex SM MENU menu by typing MENU in the COMMAND field of the LOCTRAN view and pressing Enter.

IVP1 is complete

If you are planning to run CICSplex SM on multiple MVS images, you should now run IVP2. However, before you begin IVP2, you must stop EYUCAS1A, EYUCMS1A, and EYUMAS1A on system A. If you do not stop these system A components, you will have difficulty running IVP2.

Chapter 55. Installation verification procedure 2 (IVP2)

It is recommended that you run IVP2 on the second and subsequent MVS images on which you install CICSplex SM. Throughout this chapter, the MVS image on which you are running IVP2 is referred to as “system B”.

In order to run IVP2, you must have:

- Two physically connected MVS/ESA images (system A and system B) on which CICSplex SM has been installed
- On both systems, access to:
 - The CICSplex SM samples data sets, CICSTS31.CPSM.SEYUDEF and CICSTS31.CPSM.SEYUJCL
 - CICS load libraries
 - CICS table-assembly JCL
 - SYS1.PARMLIB and SYS1.VTAMLST (or be able to add definitions to SYS1.PARMLIB and SYS1.VTAMLST)
- Access to the CEDA transaction on EYUMAS1B
- Access to the MVS console log via TSO SDSF.

Before you can run IVP2, you must have run IVP1 successfully and stopped EYUCAS1A, EYUCMS1A, and EYUMAS1A.

Figure 62 on page 426 shows those components of the CICSplex SM Starter Set that are defined during IVP2.




Figure 62. Starter Set components for IVP2. Shaded components—EYUCAS1A, EYUCAS1B, EYUCMS1A, EYUCMS1B, EYUMAS1A, and EYUMAS1B—are used during IVP2.

Setting up the CICSplex SM environment on system B

Perform the following tasks to prepare the MVS environment on system B for CICSplex SM.

1. Run EYUISTRT on system B to tailor the skeleton jobs for the Starter Set (and thereby for the IVPs). EYUISTRT runs the EYUINST EXEC to tailor the Starter Set members. For more information about EYUISTRT, see Chapter 49, “Using the EYUINST EXEC to tailor skeleton jobs,” on page 373.
2. Add VTAM definitions for EYUCAS1B, EYUCMS1B, and EYUMAS1B to the VTAM table on system B. An example of the VTAM definitions for these three CICSplex SM components is provided in sample EYUDVTIB.

Notes:

- a. EYUDVTIB is a subset of the VTAM definitions required on system B for the complete Starter Set.
- b. If you use Network Control Programs (NCP), you may need to create a mode table, using the sample entry shown in EYUMDTAB, in order to control the VTAM RUSIZE (request unit size) parameter.

3. Run the JCL EYUIBBIB, which defines the EYUIPRM data set for CAS EYUCAS1B. If you are using shared DASD, this will already have been defined during IVP1.
4. Run the JCL EYUICMSB, which defines all data sets required by CMAS EYUCMS1B.
5. Run the JCL EYUICICB, which defines all data sets required by MAS EYUMAS1B.
6. Run the JCL EYUIDRPB, which defines the CICSplex SM data repository on system B.

Note: This data repository can be used with the Starter Set on system B: it does not need to be recreated after the IVPs have been run.

7. Run the JCL EYUICSD, which defines, initializes, and loads the CSD to be used by both EYUCMS1B and EYUMAS1B.
8. Make any necessary site-specific changes to the CSD created in step 7. For example, you might need to add TYPETERMS, TERMINALS or AUTOINSTALL MODELS.
9. Assemble the following sample CICS tables into a load library:
 - EYUTPLTC (PLT for EYUCMS1B)
 - EYUTPLTL (PLT for EYUMAS1B)
 - EYUTSRTS (SRT)

Notes:

- a. Ensure that you have a model installed for the system log stream. The default naming convention is userid.applid.DFHLOG and userid.applid.DFHSHUNT for a system log stream, and userid.applid.DFHJnn (where nn is 01 through 99) for a user journal. See Chapter 24, “Defining the logger environment for CICS journaling,” on page 143 and the *CICS System Definition Guide* for more information about creating log streams.
 - b. When using CICS TS releases, TDQ definitions are added to the CSD when the CSD is created or upgraded.
 - c. For details on assembling CICS control tables, see the *CICS/ESA System Definition Guide*.
10. Update ISPF on system B to reflect the addition of CICSplex SM. You can find an example of the required changes in EYU@ISPF and EYU@PRIM. Note that any changes you make to ISPF are generally applicable on system B and are not confined to IVP2 only. Therefore, you should try to make a permanent change at this stage so that you don't have to repeat this step later. For more information, see Chapter 42, “Preparing user access to CICSplex SM,” on page 313.

Starting up and verifying CICSplex SM components on system B

When the system B environment for CICSplex SM is established, you are ready to:

1. Create CAS definitions
2. Start the CAS EYUCAS1B
3. Checking CAS-to-CAS connections
4. Start the CMAS EYUCMS1B
5. Run the batched repository update facility
6. Enable EYUCMS1B to manage EYUPLX01
7. Start the MAS EYUMAS1B

1: Create CAS definitions

1. Before you can start the CAS on system B, you must restart the CAS on system A (EYUCAS1A) and create CAS definitions for CAS EYUA and EYUB. For information about starting EYUCAS1A, see “1: Start the CAS EYUCAS1A” on page 413.
2. Log on to TSO on system A and select the CICSplex SM option from the main ISPF panel. (This is option CP if you are using the supplied samples.) The CICSplex System Manager entry panel is displayed:

```

----- CICSplex System Manager -----
OPTION ==>

  0 PROFILE      - User Session Parameters
  1 PLEXMGR      - List of Service Points
  2 CPSM         - CICSplex SM

      Default Criteria for CPSM:

Context          ==> EYUCMS1A
Scope           ==> EYUCMS1A
Warning Record Count ==> 0          0 for no checking
Require Set      ==> YES           YES, NO

      Licensed Materials - Property of IBM
      5997-E93 (C) Copyright IBM Corp. 1994, 2010.
      All Rights Reserved. U.S. Government Users
      Restricted Rights - Use, Duplication or Disclosure
      restricted by GSA ADP Schedule Contract with IBM Corp.
  
```

3. Type 1 in the OPTION field of the CICSplex System Manager entry panel and press Enter. (The values in the Context and Scope fields are ignored.) The PLEXOVER view is displayed.

The remainder of this stage varies according to whether you are using the same EYUIPRM data set on shared DASD for both CASs. If you are using shared DASD, follow the steps in “CAS data set EYUIPRM on shared DASD” If you are not using shared DASD, follow the steps in “CAS data set EYUIPRM not on shared DASD” on page 429.

CAS data set EYUIPRM on shared DASD

1. In the COMMAND field of the PLEXOVER view, type CASDEF and press Enter. The CASDEF view is displayed:

Figure 63. CASDEF view

```

27FEB2005 14:17:33 ----- INFORMATION DISPLAY -----
COMMAND ==>                                SCROLL ==> PAGE
CURR WIN ==> 1          ALT WIN ==>
>W1 =CASDEF=====EYUA===== (00 BROWSE      )=PLEXMGR=====1====
CMD CAS      Cur Description                Status          VTAM
--- Name---- Sys -----                    ----- App1Name
      MV26     Yes Use CASDEF to update      INSTALLED       *NONE*
  
```

The first time you display the CASDEF view (that is, before you have added any CAS definitions), information for a default definition is displayed (MV26 in the

- CASDEF view shown in Figure 63 on page 428). Throughout this example CAS name EYUA and EYUB are used. We will now create the definitions.
- In the COMMAND field of the CASDEF view, type EDIT and press Enter.
 - In the COMMAND field, type ADD EYUA and press Enter. Alternatively, move the cursor to the CMD field, type ADD and press Enter. The ADD CAS SYSTEM DEFINITION input panel is displayed:

Figure 64. ADD CAS system definition panel

```

----- ADD CAS SYSTEM DEFINITION -----
COMMAND ==>

CAS System Name   ==> EYUA   (Recommended same as MVS System Name)
Description       ==> SYSTEM A CAS

System Identification Information:
MVS System Name  ==> EYUA           SMF ID           ==> *
SysPlex Name    ==> *             Subsystem ID    ==> *

System Communication Information:
VTAM Appl Name  ==> EYUCAS1A
XCF Group Name  ==> EYUGR310

Enter END to add the CAS System Definition.
Enter CANCEL to leave without adding.

```

- Complete the ADD CAS SYSTEM DEFINITION input panel (displayed in Figure 64) then press Enter. (See the *CICSplex System Manager Administration* for a description of the fields on this panel). If the panel is displayed as a result of typing ADD in the CMD field, the System Identification Information is already completed with your own system defaults.
Enter END in the COMMAND field to add the definition. The CASDEF view is displayed again, this time showing an entry for CAS EYUA.
Repeat Steps 3 and 4 for CAS EYUB (subsystem ID EYUB and VTAM Application name EYUCAS1B).
Enter DEL in the CMD field next to the default entry (MV26 in this example) to schedule this entry for deletion the next time the CAS is recycled.
- Enter SAVE in the COMMAND field to save the definitions.
- Return to the CICSplex System Manager entry panel by typing RETURN in the COMMAND field of the CASDEF view and pressing Enter. If you do not return to the CICSplex System Manager entry panel, system A will have the shared file locked.
- Shut down the CAS on system A.

CAS data set EYUIPRM not on shared DASD

- In the COMMAND field of the PLEXOVER view, type CASDEF and press Enter. The CASDEF view is displayed:

Figure 65. CASDEF view

```

27FEB2005 14:17:33 ----- INFORMATION DISPLAY -----
COMMAND ==>
CURR WIN ==> 1          ALT WIN ==>
>W1 =CASDEF=====EYUA=====*(00 BROWSE          )=PLEXMGR=====1===
CMD CAS      Cur Description                      Status          VTAM
--- Name--- Sys -----                          ----- App1Name
MV26      YES Use CASDEF to update                INSTALLED      *NONE*

```

The first time you display the CASDEF view (that is, before you have added any CAS definitions) information for a default definition is displayed (MV26 in the CASDEF view shown in Figure 65 on page 429. Throughout this example CAS name EYUA and EYUB are used. We will now create the definitions.

2. In the COMMAND field of the CASDEF view, type EDIT and press Enter.
3. In the COMMAND field, type ADD EYUA and press Enter. Alternatively, move the cursor to the CMD field, type ADD and press Enter. The ADD CAS SYSTEM DEFINITION input panel is displayed:

Figure 66. ADD CAS system definition input panel

```

----- ADD CAS SYSTEM DEFINITION -----
COMMAND ==>

CAS System Name   ==> EYUA      (Recommended same as MVS System Name)
Description       ==> SYSTEM A CAS

System Identification Information:
MVS System Name  ==> EYUA          SMF ID           ==> *
SysPlex Name     ==> *           Subsystem ID     ==> *

System Communication Information:
VTAM App1 Name   ==> EYUCAS1A
XCF Group Name   ==> EYUGROUP

Enter END to add the CAS System Definition.
Enter CANCEL to leave without adding.

```

4. Complete the ADD CAS SYSTEM DEFINITION input panel (displayed in the example above) then press Enter. (See the *CICSplex System Manager Administration* for a description of the fields on this panel). If the panel is displayed as a result of typing ADD in the CMD field, the System Identification Information is already completed with your own system defaults. Enter END in the COMMAND field to add the definition. The CASDEF view is displayed again, this time showing an entry for CAS EYUA. Repeat Steps 3 and 4 for CAS EYUB (subsystem ID EYUB and VTAM Application name EYUCAS1B). Enter DEL in the CMD field next to the default entry (MV26 in this example) to schedule this entry for deletion the next time the CAS is recycled. The CASDEF view is displayed again, this time showing entries for CAS EYUA and CAS EYUB:

```

27FEB2005 14:17:33 ----- INFORMATION DISPLAY -----
COMMAND ==>
CURR WIN ==> 1          ALT WIN ==>
>W1 =CASDEF=====EYUA=====*(00 EDIT MOD      )=PLEXMGR=====2===
CMD CAS      Cur Description                               Status          VTAM
--- Name---- Sys -----
EYUA        YES SYSTEM A CAS                               UNINSTALLED     EYUCAS1A
EYUB        NO  SYSTEM B CAS                               UNINSTALLED     EYUCAS1B

```

5. In the COMMAND field of the CASDEF view, type SAVE and press Enter.
6. Return to the CICSplex System Manager entry panel by typing RETURN in the COMMAND field of the CASDEF view and pressing Enter.
7. Shut down the CAS on system A.
8. Start CAS EYUCAS1B on system B using JCL EYUICS1B or JCL EYUICSSB (to start the CAS as a started task). Look for message number BBMZA001I in the output to confirm that the CAS EYUCAS1B is started.
9. Log on to TSO on System B and select the CICSplex SM option from the main ISPF panel. (The CICSplex SM option is CP if you are using the supplied samples.) The CICSplex System Manager entry panel is displayed:

```

----- CICSplex System Manager -----
OPTION ==>

0 PROFILE      - User Session Parameters
1 PLEXMGR      - List of Service Points
2 CPSM         - CICSplex SM

      Default Criteria for CPSM:

Context                ==> EYUCMS1B
Scope                  ==> EYUCMS1B
Warning Record Count  ==> 0          0 for no checking
Require Set            ==> YES        YES, NO

      Licensed Materials - Property of IBM
      5697-E93 (C) Copyright IBM Corp. 1994, 2010.
      All Rights Reserved. U.S. Government Users
      Restricted Rights - Use, Duplication or Disclosure
      restricted by GSA ADP Schedule Contract with IBM Corp.

```

10. Type 1 in the OPTION field of the CICSplex SM entry field and press Enter. The PLEXOVER view is displayed.
11. In the COMMAND field of the PLEXOVER view, type CASDEF and press Enter. The CASDEF view is displayed:

```

27FEB2005 14:17:33 ----- INFORMATION DISPLAY -----
COMMAND ==>
CURR WIN ==> 1          ALT WIN ==>
>W1 =CASDEF=====EYUB=====*(00 BROWSE      )=PLEXMGR=====1===
CMD CAS      Cur Description                               Status          VTAM
--- Name---- Sys -----
MV29        YES Use CASDEF to update                       INSTALLED        *NONE*

```

The default definition for system B in this example is MV29. You now need to add definitions for EYUA and EYUB and delete the default definition on system B.

- In the COMMAND field, type ADD EYUB and press Enter. Alternatively, move the cursor to the CMD field, type ADD and press Enter. The ADD CAS SYSTEM DEFINITION input panel is displayed:

Figure 67. ADD CAS system definition input panel

```

----- ADD CAS SYSTEM DEFINITION -----
COMMAND ==>

CAS System Name   ==> EYUB      (Recommended same as MVS System Name)
Description       ==>

System Identification Information:
MVS System Name   ==> EYUB      SMF ID           ==> *
SysPlex Name      ==> *        Subsystem ID      ==> *

System Communication Information:
VTAM App1 Name    ==> EYUCAS1B
XCF Group Name    ==> EYUGROUP

Enter END to add the CAS System Definition.
Enter CANCEL to leave without adding.

```

- Complete the ADD CAS SYSTEM DEFINITION input panel (displayed in Figure 67) then press Enter. (See the *CICSplex System Manager Administration* for a description of the fields on this panel). If the panel is displayed as a result of typing ADD in the CMD field, the System Identification Information is already completed with your own system defaults. Enter END in the COMMAND field to add the definition. The CASDEF view is displayed again, this time showing an entry for CAS EYUB. Repeat Steps 3 and 4 for CAS EYUA (subsystem ID EYUA and VTAM Application name EYUCAS1A). Enter DEL in the CMD field next to the default entry (MV29 in this example) to schedule this entry for deletion the next time the CAS is recycled. The CASDEF view is displayed again, this time showing entries for CAS EYUB and CAS EYUA.

```

27FEB2005 14:17:33 ----- INFORMATION DISPLAY -----
COMMAND ==>                                SCROLL ==> PAGE
CURR WIN ==> 1          ALT WIN ==>
>W1 =CASDEF=====EYUB=====*(00 EDIT MOD      )=PLEXMGR=====2===
CMD CAS      Cur Description                Status          VTAM
--- Name---- Sys -----                  ----- App1Name
EYUA        NO SYSTEM A CAS                UNINSTALLED    EYUCAS1A
EYUB        YES SYSTEM B CAS                UNINSTALLED    EYUCAS1B

```

- In the COMMAND field of the CASDEF view, type SAVE and press Enter.
- Return to the CICSplex System Manager entry panel by typing RETURN in the COMMAND field of the CASDEF view and pressing Enter.
- Shut down the CAS on system B.

2: Start the CAS EYUCAS1B

- Before you can start the CAS on system B, you must restart the CAS on system A (EYUCAS1A). For information about starting EYUCAS1A, see “1: Start the CAS EYUCAS1A” on page 413.

- You can start CAS EYUCAS1B using JCL EYUICS1B or (to start the CAS as a started task) JCL EYUICSSB. When you start the CAS, output similar to this appears in the JES2 job log.

```

COMMAND INPUT ==>                                SCROLL ==> PAGE
***** TOP OF DATA *****
                J E S 2  J O B  L O G  --  S Y S T E M  M V 2 9  --

BBMYAB62I Default system values used for CAS definition
BBMXCL41I Default system values used for target definition
BBMXCL40W SSI Context Definition member 00 not found in BBIPARM
BBMXBI17I Default security parameters used
BBMXBI26I Default security resource properties used
BBMXCL36I Default security resource definition used for COMMON resources
BBMSS001I Security - ESMTYPE(RACF) SUBSYS(EYUB) REQSTOR(asis) APPL(EYUB)
BBMZA001I CAS(EYUB) SSID(EYUB) INITIALIZATION COMPLETE - R3.3.8 (BPY3621)
BBMXCL36I Default security resource definition used for PLEXMGR resources

```

- Look for message number BBMZA001I in the output to confirm that the CAS EYUCAS1B is started.

3: Checking CAS-to-CAS connections

During this stage of IVP2, you check to confirm that the connection from the CAS on system A to the CAS on system B, and from the CAS on system B to the CAS on system A were installed when the CAS was started.

- Log on to TSO on system A and select the CICSPlex SM option from the main ISPF panel. (This is option CP if you are using the supplied samples.) The CICSPlex System Manager entry panel is displayed:

```

----- CICSPlex System Manager -----
OPTION ==>

0 PROFILE      - User Session Parameters
1 PLEXMGR      - List of Service Points
2 CPSM         - CICSPlex SM

          Default Criteria for CPSM:

Context              ==> EYUCMS1A
Scope                ==> EYUCMS1A
Warning Record Count ==> 0           0 for no checking
Require Set          ==> YES         YES, NO

          Licensed Materials - Property of IBM
          5697-E93 (C) Copyright IBM Corp. 1994, 2010.
          All Rights Reserved. U.S. Government Users
          Restricted Rights - Use, Duplication or Disclosure
          restricted by GSA ADP Schedule Contract with IBM Corp.

```

- Type 1 in the OPTION field of the CICSPlex System Manager entry panel and press Enter. (The values in the Context and Scope fields are ignored.) The PLEXOVER view is displayed.

- In the COMMAND field of the PLEXOVER view, type CASDEF and press Enter. The CASDEF view is displayed:

```

27FEB2005 14:17:33 ----- INFORMATION DISPLAY -----
COMMAND ==>
CURR WIN ==> 1          ALT WIN ==>
>W1 =CASDEF=====EYUA=====*(00 BROWSE          )=PLEXMGR=====2===
CMD CAS      Cur Description              Status      VTAM
--- Name---- Sys -----
EYUA        YES SYSTEM A CAS              INSTALLED   EYUCAS1A
EYUB        NO  SYSTEM B CAS              INSTALLED   EYUCAS1B

```

Both CAS entries should be installed. If they are not then place the cursor in the CMD field next to the entry and type INS.

- Return to the CICSplex System Manager entry panel by typing RETURN in the COMMAND field of the CASDEF view and pressing Enter.
- If the same EYUIPRM on shared DASD is not being used, repeat Steps 1 through 4 for CAS EYUB on system B.

4: Start the CMAS EYUCMS1B

- Before you can start the CMAS on system B, you must restart the CMAS on system A (EYUCMS1A). For information about starting EYUCMS1A, see “2: Start the CMAS EYUCMS1A” on page 414.
- Check the CICS Transaction Server for z/OS system initialization table (SIT) parameters in JCL EYUICM1B, in particular the SVC parameters and the default user, to ensure that they are suitable for your environment.
- Submit JCL EYUICM1B. The output from JCL EYUICM1B is similar to this:

```

COMMAND INPUT ==>
11.59.23 JOB17758 +DFHSI1511I EYUCMS1B Installing group list CMS1BGPL.
11.59.26 JOB17758 +DFHLG0103I EYUCMS1B System log (DFHLOG) initialization has started.
11.59.27 JOB17758 +DFHLG0104I EYUCMS1B 054
054 System log (DFHLOG) initialization has ended. Log stream
054 DOBROWN.EYUCMS1B.DFHLOG is connected to structure LOG_GENERAL_002.
11.59.27 JOB17758 +DFHLG0103I EYUCMS1B System log (DFHSHUNT) initialization has started.
11.59.27 JOB17758 +DFHLG0104I EYUCMS1B 056
056 System log (DFHSHUNT) initialization has ended. Log stream
056 DOBROWN.EYUCMS1B.DFHSHUNT is connected to structure LOG_GENERAL_002.
11.59.27 JOB17758 +DFHRX0106I EYUCMS1B Restart processing with Resource Recovery Services (RRS) is beginning.
11.59.28 JOB17758 +DFHRX0107I EYUCMS1B Restart processing with Resource Recovery Services (RRS) has ended.
11.59.28 JOB17758 +DFHSI1519I EYUCMS1B The interregion communication session was successfully started.
11.59.28 JOB17758 +DFHAP1203I EYUCMS1B Language Environment is being initialized.
11.59.30 JOB17758 +DFHAP1211I EYUCMS1B Language Environment initialization completed.
11.59.30 JOB17758 +DFHWB1007 EYUCMS1B Initializing CICS Web environment.
11.59.30 JOB17758 +DFHWB1008 EYUCMS1B CICS Web environment initialization is complete.
11.59.31 JOB17758 +DFHSI8440I EYUCMS1B Initiating connection to CICSplex SM.
11.59.31 JOB17758 +EYUXL0001I EYUCMS1B CMAS PLTPI program starting
11.59.31 JOB17758 +EYUXL0002I EYUCMS1B CICS TRACE active
11.59.31 JOB17758 +EYUXL0017I EYUCMS1B CMAS PLTPI program terminating
11.59.31 JOB17758 +DFHSI1517 EYUCMS1B Control is being given to CICS.
11.59.31 JOB17758 +DFHEJ0102 EYUCMS1B Enterprise Java domain initialization has ended.
11.59.32 JOB17758 +EYUXL0003I EYUCMS1B CPSM Version 310 CMAS startup in progress
11.59.32 JOB17758 +DFHFC0208I EYUCMS1B 090
090 LSR pool 1 is being built dynamically by CICS because all of the
090 necessary parameters have not been supplied. Either there is no
090 LSRPOOL definition or it is incomplete. The following are not
090 defined: 'CI SIZE' 'STRINGS' 'MAXKEYLENGTH'. A delay is possible.
11.59.32 JOB17758 +DFHFC0961 EYUCMS1B 091
091 01/27/2005 11:59:32 EYUCMS1B Calculation of LSR pool 1 parameters
091 incomplete. Filename EYUDREPN has no DSNAME.
11.59.33 JOB17758 +EYUXL0022I EYUCMS1B CMAS Phase I initialization complete
11.59.33 JOB17758 +EYUXL0211I EYUCMS1B CPSM Start Up Parameters
11.59.33 JOB17758 +EYUXL0212I EYUCMS1B CASNAME(EYUB)
11.59.33 JOB17758 +EYUXL0212I EYUCMS1B NAME(EYUCMS1B)
11.59.33 JOB17758 +EYUXL0020I EYUCMS1B ESSS connection in progress
11.59.33 JOB17758 +EYUXL0004I EYUCMS1B ESSS connection complete
11.59.34 JOB17758 +EYUCR0006W EYUCMS1B Security checking disabled per SEC(NO) EYUPARM parameter specification
11.59.34 JOB17758 +EYUCW0108I EYUCMS1B Time zone offset from GMT computed based on CMAS time zone attributes
11.59.35 JOB17758 +EYUXL0007I EYUCMS1B CMAS Phase II initialization complete
11.59.35 JOB17758 +EYUXL0007I EYUCMS1B CMAS Phase III initialization complete
11.59.35 JOB17758 +EYUXL0007I EYUCMS1B CMAS Phase IV initialization complete
11.59.36 JOB17758 +EYUXL0009I EYUCMS1B CAS connection established
12.00.05 JOB17758 +EYUXL0010I EYUCMS1B CMAS initialization complete
12.00.05 JOB17758 +EYUXL0008I EYUCMS1B CICSplex registration complete

```

4. In the output from EYUICM1B, look for messages EYUXL0009I and EYUXL0008I to confirm that CMAS EYUCMS1B is started.

5: Run the batched repository update facility on system B

During this stage of IVP2, you load several definitions into the data repository of CMAS EYUCMS1B using the batched repository update facility.

1. Log on to TSO on system B. Select the CICSplex SM option from the main ISPF panel; the CICSplex SM option is CP if you are using the supplied samples. Ensure that "EYUB" is specified as the subsystem ID. (This can be changed using option 0.1 from the main ISPF panel.) The CICSplex System Manager entry panel is displayed.
2. Set the context and scope fields of the CICSplex System Manager entry panel to EYUCMS1B, then type 2 in the OPTION field and press Enter. The MENU menu is displayed.
3. From the CICSplex SM MENU menu, select ADMCONFIG. The ADMCONFIG menu is displayed. From the ADMCONFIG menu, select BATCHREP. The

BATCHREP view is displayed:

```
27FEB2005 14:40:58 ----- INFORMATION DISPLAY -----  
COMMAND ==> SCROLL ==> PAGE  
CURR WIN ==> 1 ALT WIN ==>  
W1 =BATCHREP=====EYUCMS1B=EYUCMS1B=27FEB2005==14:40:45=CPSM=====  
BBMXBD15I There is no data which satisfies your request
```

4. To submit a job to update the data repository of CMAS EYUCMS1B, type SUB in the COMMAND field of the BATCHREP view and press Enter. The Start Batch Run input panel is displayed:

```
COMMAND ==>  
  
Data Set Name ==> 'CICSTS31.CPSM.SEYUDEF'  
Data Set Member ==> EYUDDRIB  
Print Class ==> H  
Print Node ==> *  
Output Userid ==> *  
Run Type ==> EXECUTE (CHECK or EXECUTE)  
  
Press ENTER to Run the Job.  
Type END or CANCEL to cancel without Running.
```

5. Complete the Start Batch Run screen as shown in the example above and press Enter. Verify that the batched repository update facility has created the definitions by examining the JOBLOG of EYUICM1B, which is in the HELD output queue.
6. Return to the CICSplex SM MENU menu by typing MENU in the COMMAND field of the BATCHREP view and pressing Enter.

6: Enable EYUCMS1B to manage EYUPLX01

During this stage of IVP2, you define EYUCMS1B as a secondary CMAS for CICSplex EYUPLX01. (CMAS EYUCMS1A is the primary CMAS for EYUPLX01.)

1. Log on to TSO on system A and select the CICSplex SM option from the main ISPF panel. (The CICSplex SM option is CP if you are using the supplied samples.) The CICSplex System Manager entry panel is displayed:

```

----- CICSPlex System Manager -----
OPTION ==>

0 PROFILE      - User Session Parameters
1 PLEXMGR     - List of Service Points
2 CPSM        - CICSPlex SM

      Default Criteria for CPSM:

Context          ==> EYUCMS1A
Scope           ==> EYUCMS1A
Warning Record Count ==> 0          0 for no checking
Require Set      ==> YES          YES, NO

      Licensed Materials - Property of IBM
      5697-E93 (C) Copyright IBM Corp. 1994, 2010.
      All Rights Reserved. U.S. Government Users
      Restricted Rights - Use, Duplication or Disclosure
      restricted by GSA ADP Schedule Contract with IBM Corp.

```

2. Ensure that both the Context and the Scope fields on the CICSPlex System Manager entry panel are set to EYUCMS1A. Type 2 in the OPTION field and press Enter. The MENU menu is displayed:

```

27FEB2005 14:42:11 ----- INFORMATION DISPLAY -----
COMMAND ==>                                SCROLL ==> PAGE
CURR WIN ==> 1          ALT WIN ==>
W1 =MENU=====EYUCMS1A=EYUCMS1A=27FEB2005==14:42:11=CPSM=====14==
CMD Name          Description
-----
ANALYSIS  Real Time Analysis Operations Views
CONFIG    CMAS Configuration Operations Views
MONITOR   Monitoring Views
OPERATE   Operations Views
TOPOLOGY  Topology Operations Views
WORKLOAD  Workload Operations Views
=====
ADMSAM    RTA System Availability Monitoring Administration Views
ADMMRM    RTA MAS Resource Monitoring Administration Views
ADMMPM    RTA Analysis Point Monitoring Administration Views
ADMCONFG  CMAS Configuration Administration Views
ADMMON    Monitor Administration Views
ADMTOPOL  Topology Administration Views
ADMWLM    Workload Manager Administration Views
ADMBAS    Business Application Services Administration Views
ADMRES    Business Application Services Resource Views

```

3. Select ADMCONFG from the MENU menu. The ADMCONFG menu is displayed:

```

27FEB2005 14:42:18 ----- INFORMATION DISPLAY -----
COMMAND ===>                                SCROLL ===> PAGE
CURR WIN ===> 1          ALT WIN ===>
W1 =MENU=====EYUCMS1A=EYUCMS1A=27FEB2005==14:42:18=CPSM=====6===
CMD Name          Description
-----
ADMCONFG    CMAS Configuration Administration Views
  BATCHREP    Batched Repository Updates
  CPLEXDEF    CICSplex Definitions
  CPLXCMAS    CMAS in CICSplex Definitions
  CMTCMDEF    CMAS-to-CMAS Link Definitions
  CMTPMDEF    CMAS-to-RMAS Link Definitions

```

- From the ADMCONFG menu, select CPLEXDEF. The CPLEXDEF view is displayed:

```

27FEB2005 14:42:27 ----- INFORMATION DISPLAY -----
COMMAND ===>                                SCROLL ===> PAGE
CURR WIN ===> 1          ALT WIN ===>
W1 =CPLEXDEF=====EYUCMS1A=EYUCMS1A=27FEB2005==14:42:27=CPSM=====1===
CMD Name      Mon Time Zone Day  Cmd Res Xmp ROD Description
-----
EYUPLX01     480 B          0 NO  NO  NO  NO  IVP 1 CICSplex

```

- Move the cursor to the EYUPLX01 entry, type ADD in the CMD field, and press Enter. The Add CMAS to CICSplex input panel is displayed:

```

COMMAND ===>

CICSplex Name      EYUPLX01
Description        IVP 1 CICSplex

CMAS Name          ===>          Name of CMAS or Generic

Press ENTER to add CMAS to CICSplex.
Type END or CANCEL to cancel without adding.

```

- In the CMAS Name field of the Add CMAS to CICSplex input panel, type EYUCMS1B and press Enter. The CPLEXDEF view is redisplayed.
- To verify that the data repository on system B has been updated with the definition of EYUPLX01, you must change the current context and scope to EYUCMS1B. To change the context and scope, type SET in the COMMAND field of the CPLEXDEF view and press Enter. Complete the SET WINDOW, CONTEXT, PRODUCT, SCOPE, AND VIEW panel and press Enter.
- Enter CMASPLEX in the COMMAND field of the CPLEXDEF view. The CMASPLEX view, showing CICSplexes managed by EYUCMS1B, is displayed:

```

27FEB2005 14:43:38 ----- INFORMATION DISPLAY -----
COMMAND ===>
CURR WIN ===> 1          ALT WIN ===>
W1 =CMASPLEX=====EYUCMS1B=EYUCMS1B=27FEB2005==14:43:38=CPSM=====1===
CMD CICSPlex MP
-----
EYUPLX01 NO

```

An entry for EYUPLX01 appears in the CMASPLEX view.

9. Return to the CICSPlex SM MENU menu by typing MENU in the COMMAND field of the CMASPLEX view and pressing Enter.

7: Start the MAS EYUMAS1B

1. Before you can start the MAS on system B, you must restart the MAS on system A (EYUMAS1A). For information about starting EYUMAS1A, see “5: Start the MAS EYUMAS1A” on page 419.
2. Check the SIT parameters in JCL EYUIMS1B, in particular the SVC numbers and the default user, to ensure that they are suitable for your environment.
3. Submit JCL EYUIMS1B from TSO. Output similar to this appears in the job log:

COMMAND INPUT ==>

SCROLL ==> PAGE

```
13.58.49 JOB21350 +DFHSI1511I EYUMAS1B Installing group list MAS1BGPL.
13.58.51 JOB21350 +DFHLG0103I EYUMAS1B System log (DFHLOG) initialization has started.
13.58.52 JOB21350 +DFHLG0104I EYUMAS1B 171
171 System log (DFHLOG) initialization has ended. Log stream
171 DOBROWN.EYUMAS1B.DFHLOG is connected to structure LOG_GENERAL_002.
13.58.52 JOB21350 +DFHLG0103I EYUMAS1B System log (DFHSHUNT) initialization has started.
13.58.52 JOB21350 +DFHLG0104I EYUMAS1B 185
185 System log (DFHSHUNT) initialization has ended. Log stream
185 DOBROWN.EYUMAS1B.DFHSHUNT is connected to structure LOG_GENERAL_002.
13.58.52 JOB21350 +DFHLG0745I EYUMAS1B System log full scan has started.
13.58.52 JOB21350 +DFHLG0748I EYUMAS1B System log selective scan has started.
13.58.52 JOB21350 +DFHLG0749I EYUMAS1B System log scan has completed.
13.58.52 JOB21350 +DFHRM0156 EYUMAS1B This COLD start will NOT cause any damage to local resources.
13.58.53 JOB21350 +DFHRX0106I EYUMAS1B Restart processing with Resource Recovery Services (RRS) is beginning.
13.58.53 JOB21350 +DFHRX0107I EYUMAS1B Restart processing with Resource Recovery Services (RRS) has ended.
13.58.53 JOB21350 +DFHSI1519I EYUMAS1B The interregion communication session was successfully started.
13.58.53 JOB21350 +DFHSZ4001 I 01/27/2005 13:58:53 EYUMAS1B FEPI initialization has started.
13.58.53 JOB21350 +DFHAP1203I EYUMAS1B Language Environment is being initialized.
13.58.53 JOB21350 +DFHSZ4002 I 01/27/2005 13:58:53 EYUMAS1B FEPI initialization has ended.
13.58.54 JOB21350 +DFHAP1211I EYUMAS1B Language Environment initialization completed.
13.58.54 JOB21350 +DFHWP1007 EYUMAS1B Initializing CICS Web environment.
13.58.55 JOB21350 +DFHWP1008 EYUMAS1B CICS Web environment initialization is complete.
13.58.55 JOB21350 +DFHSI8440I EYUMAS1B Initiating connection to CICSplex SM.
13.58.55 JOB21350 +EYUNX0001I EYUMAS1B LMAS PLTPI program starting
13.58.55 JOB21350 +EYUXL0003I EYUMAS1B CPSM Version 310 LMAS startup in progress
13.58.56 JOB21350 +EYUXL0022I EYUMAS1B LMAS Phase I initialization complete
13.58.57 JOB21350 +EYUXL0211I EYUMAS1B CPSM Start Up Parameters
13.58.57 JOB21350 +EYUXL0212I EYUMAS1B NAME(EYUMAS1B)
13.58.57 JOB21350 +EYUXL0212I EYUMAS1B CICSplex(EYUPLX01)
13.58.57 JOB21350 +EYUXL0212I EYUMAS1B CMASYSID(CM1B)
13.58.57 JOB21350 +DFHEJ0102 EYUMAS1B Enterprise Java domain initialization has ended.
13.58.57 JOB21350 +DFHSI1517 EYUMAS1B Control is being given to CICS.
13.58.57 JOB21350 +DFHSM0133 EYUMAS1B CICS is under stress (short on storage above 16MB).
13.58.57 JOB21350 +DFHSM0134 EYUMAS1B CICS is no longer short on storage above 16MB.
13.58.59 JOB21350 +EYUXL0020I EYUMAS1B ESSS connection in progress to CICSplex(EYUPLX01) for SYSID(CM1B)
13.58.59 JOB21350 +EYUXL0004I EYUMAS1B ESSS connection complete
13.58.59 JOB21350 +EYUCL0006I EYUMAS1B ESSS link to EYUCMS1B established
13.58.59 JOB21350 +EYUXL0007I EYUMAS1B LMAS Phase II initialization complete
13.58.59 JOB21350 +EYUNL0099I EYUMAS1B LMAS LRT initialization complete
```

4. Look for messages EYUXL0004I and EYUXL0007I in the output to confirm that the MAS is active.

Testing CICSplex SM functions

During this part of IVP2, you test the operations and functions of CICSplex SM on system B.

Test the operations functions on system B

During this stage of IVP2 you:

- Change the value of a CICS resource via CICSplex SM
- Test the CICSplex SM help facility
- Test the CMAS-CMAS links.

1. From the CICSplex SM MENU menu on system A, change the context and scope to EYUPLX01 then select the OPERATE option. The OPERATE menu is displayed:


```

27FEB2005 13:48:12 ----- INFORMATION DISPLAY -----
COMMAND ==>                                     SCROLL ==> PAGE
CURR WIN ==> 1           ALT WIN ==>
W1 =OPERATE=====EYUPLX01=EYUPLX01=27FEB2005==13:48:12=CPSM=====15===
CMD Name           Description
-----
OPERATE           Operations Views
CICSBTS           CICS BTS Views
CONNECT           Connection Views
DB2               DB2 and DBCTL Views
DOCTEMP           Document Template Views
ENQUEUE           Global Enqueue Views
EXIT              Exit Views
FEPI              FEPI Views
FILE              File Views
JOURNAL           Journal Views
PROGRAM           Program Views
REGION            CICS Region Views
TASK              Task Views
TCPIPS            TCP/IP Service Views
TCPIPGBL          TCP/IP Global Views
TDQ               Transient Data Queue Views
TEMPSTOR          Temporary Storage Queue Views
TERMINAL          Terminal Views
TRANS             Transaction Views
UOW               Unit of Work Views

```

2. From the OPERATE menu, enter CICSRGN to display details of CICS regions in EYUPLX01. From the CICSRGN view, display a detailed view of data for region EYUMAS1B by moving the cursor to the entry for EYUMAS1B and pressing Enter. The CICSRGND view for EYUMAS1B is displayed.
3. Move the cursor to the Current Tasks field and press Enter. The CICSRGN3 view is displayed. Verify that the help function is working by typing HEL in the COMMAND field of the CICSRGN3 view, moving the cursor to the MAxtasks field, and pressing Enter. A pop-up panel,⁸ in which the MAxtasks field is described, overwrites the CICSRGN3 view.
Type END in the COMMAND field of the help panel and press Enter to return to the CICSRGN3 view.
4. From a second display screen, and following your local procedure, log on to CICS system EYUMAS1B. Type CEMT INQUIRE SYSTEM and press Enter. A summary of current values for CICS system EYUMAS1B is displayed:

8. If you are using a version of ISPF prior to Version 3 Release 1, all help information is provided in full-screen panels.

```

STATUS: RESULTS - OVERTYPE TO MODIFY
Aging( 00500 )          Progautoexit( DFHPGADX )
Akp( 04000 )           Progautoinst( Autoinactive )
Cicstslvl(030100)      Reentprotect(Noreentprot)
Cmdprotect(Cmdprot)    Release(0640)
Db2conn( )            Runaway( 0020000 )
Debugtool(Nodebug)     Scandelay( 5000 )
Dfltuser(CPSM)        Sdtran(CESD)
Dsalimit( 05242880 )   Sosstatus(Notsos)
Dsrtprogram( NONE )    Storeprotect(Inactive)
Dtrprogram( EYU9XLOP ) Time( 0005000 )
Dumping( Nosysdump )   Transolate(Inactive)
Edsalimit( 0033554432 )
Forceqr( Force )
Logdefer ( 00005 )
Maxtasks( 080 )
Mrobatch( 001 )
Oslevel(010400)
Progautoctlg( Ctlgmodify )

                                SYSID=MS1B APPLID=EYUMAS1B
RESPONSE: NORMAL                TIME: 13.49.24 DATE: 27.02.05
PF 1 HELP          3 END          5 VAR          7 SBH 8 SFH 9 MSG 10 SB 11 SF

```

Take a note of the current MAxtasks value.

- Return to the CICSplex SM terminal session, move the cursor to any field to the left of the first column of data and type the word SET, then move the cursor to the MAxtasks field, change the current value to 60, and press Enter. The MAxtasks value changes to 60:

```

27FEB2005 13:49:39 ----- INFORMATION DISPLAY -----
COMMAND ==>                                SCROLL ==> PAGE
CURR WIN ==> 1          ALT WIN ==>
>W1 =CICSRGN==CICSRGN3=EYUPLX01===EYUPLX01===27FEB2005==15:37:31====CPSM=====1
CICS System..      EYUMAS1B Tot Pgrm Use.      11 Cur LU Sess      0
Current Tasks      3 Pgrm Compress      0 HWM LU Sess      0
Peak Tasks...      13 Cur Act UTrn.      3
Current Amax.      N/A Cur Que UTrn.      0
Peak Amaxtask      N/A Peak Act UTrn      4
Total Tasks..      107 Peak Que UTrn      0
Interval task      6 Totl Act UTrn      6
Times at MAXT      0 Totl Que UTrn      0
Act Max Tasks      N/A Tot Que Time.      00:00:00
Maxtasks.....      60 Cur Que Time.      00:00:00
Pgrm AIn Attm      0 PRSS Inq Cnt.      0
Pgrm AIn Xrej      0 PRSS NIB Cnt.      0
Pgrm AIn Fail      0 PRSS Opn Cnt.      0
Pgrm Load NIU      26 PRSS UbndCnt.      0
Tot NIU Qtime      00:00:00 PRSS Err Cnt. 0
NIU Reclams.      9

```

- To verify that the value has been changed in the CICS system itself, return to the CICS (EYUMAS1B) session and enter the CEMT INQUIRE SYSTEM command again. The MAxtasks value is 60:

```

STATUS: RESULTS - OVERTYPE TO MODIFY
Aging( 00500 )                      Progautoexit( DFHPGADX )
Akp( 04000 )                          Progautoinst( Autoinactive )
Cicstslevel(030100)                  Reentprotect(Noreentprot)
Cmdprotect(Cmdprot)                  Release(0640)
Db2conn( )                            Runaway( 0020000 )
Debugtool(Nodebug)                   Scandelay( 5000 )
Dfltuser(CPSM)                       Sdtran(CESD)
Dsalimit( 05242880 )                 Sosstatus(Notsos)
Dsrtprogram( NONE )                  Storeprotect(Inactive)
Dtrprogram( EYU9XLOP )                Time( 0005000 )
Dumping( Nosysdump )                 Transolate(Inactive)
Edsalimit( 0033554432 )
Forceqr( Force )
Logdefer ( 00005 )
Maxtasks( 060 )
Mrobatch( 001 )
Oslevel(010400)
Progautoctlg( Ctlgmodify )

                                SYSID=MS1B APPLID=EYUMAS1B
RESPONSE: NORMAL                                TIME: 13.49.28 DATE: 27.02.05
PF 1 HELP          3 END          5 VAR          7 SBH 8 SFH 9 MSG 10 SB 11 SF

```

End the CICS terminal session using CESF LOGOFF and return to the CICSplex SM terminal session.

7. Type the command TRAN in the COMMAND field of the CICS RGN3 view and press Enter. The TRAN view, which shows all transactions currently installed in the CICSplex, is displayed. Scroll down and move the cursor to the CONL entry for EYUMAS1B, then press Enter. The LOCTRAN view, which shows details of local transaction CONL in EYUMAS1B, is displayed.
8. Return to the CICSplex SM MENU menu by typing MENU in the COMMAND field of the LOCTRAN view and pressing Enter.

IVP2 is complete

It is recommended that you repeat IVP2 on the third and subsequent MVS images on which you install CICSplex SM.

Customizing the installation verification procedures

When you have finished configuring CICSplex SM to manage your CICS systems, you can run IVP1 and IVP2 again, but using your own CASs, CMASs, and MASs, to ensure that your configuration is working.

To run IVP1 and IVP2 with your own CICSplex SM components, you need to change the supplied IVP definitions:

1. Ensure that your CMAS uses the IVP1 data repository (CICSTS31.CPSM.SAMPLES.SYSTEMA.EYUDREP) on system A.
2. Ensure that your CMAS uses the IVP2 data repository (CICSTS31.CPSM.SAMPLES.SYSTEMB.EYUDREP) on system B.
3. Delete and redefine the data repositories using the supplied JCL EYUIDRPA and EYUIDRPB.
4. Throughout the IVP definitions, change all references to EYUA and EYUB to the two subsystem IDs of your CASs.

5. Your CMAS EYUPARM NAME(xxxxxxx) must refer to EYUCMS1A on system A and EYUCMS1B on system B.
6. Your MAS EYUPARM NAME(xxxxxxx) must refer to EYUMAS1A on system A and EYUMAS1B on system B.

When you run IVP1 and IVP2 with your own configuration, you can omit the steps described in “Setting up the CICSplex SM environment on system A” on page 411 and in “Setting up the CICSplex SM environment on system B” on page 426.

Part 7. Appendixes

Appendix. CICS modules eligible for the MVS link pack area

This topic provides information about the CICS modules that are required in the MVS link pack area, and other CICS modules that are eligible for the MVS link pack area. This information is intended to help you plan for and install CICS modules in the MVS link pack area, for the functions that your CICS regions use.

The following terms are used in this appendix:

Term	Meaning
MVS link pack area	The MVS link pack area generally.
LPA	The area of the MVS link pack area below 16MB.
ELPA	The area of the MVS link pack area above 16MB.

For further information about installing CICS modules into the MVS link pack area, and about controlling their use from the MVS link pack area, see “Default message-formatting initialization parameters” on page 88.

CICS modules required in the MVS link pack area

CICS modules that are required in the MVS link pack area are loaded into the *hlq.SDFHLPA* library when you install CICS. Details of these modules is given in Table 48 on page 451. These modules are not affected by any CICS parameters or options, and CICS does not use the standard MVS search order for them. For further information about these modules, see “The IEASYSxx MVS initialization member” on page 83.

CICS modules eligible for the MVS link pack area

Other CICS modules that are eligible for installation in the MVS link pack area are specified in the CICS-supplied USERMODs: DFH\$UMOD (for base CICS modules). Details of these modules is given in Table 49 on page 451.

Information about modules eligible for the MVS link pack area

The following information is provided in Table 48 on page 451 and Table 49 on page 451. Some of the information applies only to the modules listed in Table 49.

Name	The name of the module.
Description	A brief description of the module. This gives some clues to the associated function, useful if the module does not have a controlling CICS option.

Library	(Table 49 only.) The library in which the module is installed:
----------------	--

Library	DS name
AUTH	<i>hlq.SDFHAUTH</i>
LOAD	<i>hlq.SDFHLOAD</i>
LINK	<i>SYS1.hlq.SDFHLINK</i>

You can use the CICS-supplied usermods to move the modules from these libraries to the *hlq.SDFHLPA* library.

LPA/ELPA	(Table 49 only.) In this column, the terms LPA and ELPA are used
-----------------	--

to indicate whether a module is loaded into the part of the MVS link pack area that is below (LPA) or above (ELPA) 16MB.

Priority	(Table 49 only.) A nominal “priority” to help you decide whether a module should be in the MVS link pack area and to choose between modules if your MVS link pack area is short on space.
Size	The size of the module.
Option/Note	Identifies one or more notes about the use of the module from the MVS link pack area and any associated CICS options to be specified for the function that uses the module.

Some of these information categories are described in more detail in the following sections.

Priority

The priority of the modules eligible for the LPA are as follows:

1. Must be in the MVS link pack area. Information about these modules, installed in the *hlq.SDFHLPA* library, is given in Table 48 on page 451.
2. Generally a good candidate for inclusion in the MVS link pack area. You should include these modules in the LPA to support the associated option.
3. A good candidate for inclusion in the MVS link pack area. You should include these modules in the MVS link pack area if you are a heavy user of the associated function.

Size

The module sizes were taken from the latest information available at the time of publishing, but may be different in your CICS environment depending on the options selected and if any PTFs applied affect the modules. The sizes are given here to help you plan the amount of storage that you need for the modules that you want to install in the MVS link pack area. You can get the actual sizes for these modules from a directory listing of the modules or from the module index provided at the back of a formatted SDUMP taken with the LPA=NO system initialization parameter specified.

Option/Note

This column identifies any CICS options associated with the use of the module from the MVS link pack area, or refers to a note in the following list for additional information, or both.

Notes:

1. The program is used from the MVS link pack area only if you set the USELPACOPY option of its program resource definition to YES.
2. You must always install the latest service level of the CICS SVC module, DFHCSVC. You should install the DFHCSVC module into the MVS link pack area before you run the CICS installation verification procedures.

You must define the DFHCSVC module in an IEASVCxx member of the SYS1.PARMLIB library, using SVC Parm statements. You select the required IEASVCxx member by coding the SVC parameter (SVC=xx) in a SYS1.PARMLIB member (IEASYSyy), which you use to IPL your MVS.

You can run several CICS regions, at different release levels, in the same MVS image, with each region using its own version of the DFHCSVC module. However, if some of those regions use MRO, then all regions that use MRO must use the latest DFHCSVC module and the latest DFHIRP module.

If you have some regions that are to use the DFHCSVC module, and you give the SVC a number different from the SVC number used by the regions, you must generate a new version of the DFHCRC program on the regions.

For information about defining and using the DFHCSVC module, see the *CICS Transaction Server for z/OS Program Directory*.

3. If your batch region is sharing the database with a CICS/OS/VS 1.7 region or a CICS/MVS Version 2 region, you can continue to use the batch region controller program, DFHDRP, from before CICS/ESA Version 3. (The CICS/ESA Version 3 DFHIRP program supports earlier levels of the DFHDRP program.) However, if your batch region is sharing the database with a CICS TS for z/OS, Version 3.1 region, you are recommended to install the CICS TS for z/OS, Version 3.1 DFHDRP module in SYS1.LINKLIB, or another suitable APF-authorized library in the MVS linklist.
4. All LPA-required modules are downward-compatible with earlier releases of CICS. If you are running earlier releases of CICS, you must ensure that the correct version is installed in the LPA. The module must be in the LPA for integrity reasons, but the post exit routine itself can reside either in the LPA, or in the CICS address space. This enables you to use different versions of the DFHDSAUT module in different CICS regions running in the same MVS image, because the DFHDSAUT module may not be compatible from release to release.
5. The use of this pre-CICS/ESA Version 3 programmable interface to the master terminal program, DFHEMTA, is supported for compatibility reasons only. You are strongly recommended to use the equivalent EXEC CICS INQUIRE and ISET commands instead. The documentation for this interface is available only in the CICS libraries for the releases prior to CICS/ESA Version 3.
6. You can set the system tracing status by coding appropriate system initialization parameters, and you can also set it dynamically by using the CETR transaction.

The system initialization parameters that you can use are:

Parameter	Use
AUXTR	Activate auxiliary trace.
AUXTRSW	Define the auxiliary switch status.
GTFTR	Enable CICS to use MVS GTF tracing.
INTTR	Activate CICS internal tracing.
TRTABSZ	Specify the size of the internal trace table.
USERTR	Set the master user trace flag on or off.

For information about using CICS trace, and using the CETR transaction to control the tracing status, see the *CICS Problem Determination Guide*.

7. The DFHIRP module needs to be in the MVS link pack area only if you are using MRO, CICS shared database, or the console message-handling facility. If you install the DFHIRP module in the MVS link pack area, you must also install DFHSSSEN if you are using the console message-handling facility. You must always install the latest service level of the DFHIRP (if needed) and DFHSSSEN. If you are running CICS with MRO at different release levels, all regions in the same MVS-image must use the latest DFHIRP module.
8. To use the console message formatting facility of the MVS subsystem interface, you must install the modules DFHSSGC and DFHSSWT either in the MVS link pack area or in an APF-authorized library in the MVS linklist. These

#

modules are used by the subsystem interface and not directly by CICS. Therefore, the use of these modules from the MVS link pack area is not controlled by CICS parameters or options.

For information about enabling the console message-formatting facility, and about the other modules it requires, see “Modules needed to use the console message-handling facilities” on page 89.

9. CICS needs the following load modules, supplied with CICS, to use data table services:

- DFHDTINT
- DFHDTOC
- DFHDTLD
- DFHDTRD
- DFHDTES

The modules are all eligible for the MVS link pack area, but DFHDTRD and DFHDTES are probably the only ones which are used sufficiently frequently to be worth considering.

10. The following modules, used by the Shared Data Tables facility, are eligible for the MVS link pack area:

- DFHDTAM
- DFHDTAOR
- DFHDTCV
- DFHDTFOR
- DFHDTSVC
- DFHDTXS
- DFHMVRMS

All these modules, except for DFHMVRMS, are listed in the usermod, DFH\$UMOD, supplied with CICS. Only DFHDTAM, DFHDTAOR, DFHDTFOR, and possibly DFHDTCV are used sufficiently frequently to be worth considering for the MVS link pack area.

The following modules, installed in the *hlq*.SDFHLINK library, must be installed in the MVS linklist, or in the MVS link pack area:

- DFHDTSVC
- DFHDTCV
- DFHMVRMS

11. BMS=STANDARD
12. BMS=FULL
13. BMS=MINIMUM
14. DTRPGM=DFHDYP
15. SPOOL=YES
16. FCT=YES/xx
17. ISC=YES/xx
18. VTAM=YES
19. XRF=YES/xx
20. AUXTR=ON
21. TST=YES/xx
22. TCP=YES/xx

#

23. This module is installed into SDFJAUTH and is copied to SDFJLPA.

This column also gives any associated options that you must specify to use the function associated with the LPA-eligible module. Unless otherwise stated, the options are specified by system initialization parameters as defined in the *CICS*

System Definition Guide . Any special information about a particular module is given in a note in the list starting on page "Option/Note" on page 448.

Table 48. LPA-required modules, supplied in hlq.SDFHLPA

Name	Description	LPA/ ELPA	Size	Option/ Note
# DFHCSVC	CICS SVC startup	ELPA	2280	CICSSVC (2) (4 on page 449)
# DFHDSPEX	DS domain - MVS POST exit stub	ELPA	168	(4)
# DFHDUMPX	SDUMPX IEASDUMP QUERY exit	ELPA	152	(4 on page 449)
# DFHIRP	Interregion communication program	ELPA	49416	(7) (4 on page 449)
# DFHSSEN	Subsystem interface end-of-memory / end-of-task clean up routine	ELPA	472	(4 on page 449)
# DFHSSGC	Subsystem interface generic connect	ELPA	936	(8) (4 on page 449)
# DFHSSWT	Subsystem interface WTO router	ELPA	4512	(8) (4 on page 449)
# DFH99SVC	Dyn alloc - SVC services	ELPA	8	(4 on page 449)

Table 49. LPA-eligible modules

Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
AXMSC	Server connection routines	LINK	ELPA	2	21856	-
# EYUMCT1C		AUTH	ELPA	2		-
# EYUMCT1E		AUTH	ELPA	2		-
# EYUMCT1K		AUTH	ELPA	2		-
# DFHADWWM0		LOAD	ELPA	2		-
# DFHADWWM1		LOAD	ELPA	2		-
# DFHADWWM2		LOAD	ELPA	2		-
# DFHADWWM3		LOAD	ELPA	2		-
# DFHADWWM4		LOAD	ELPA	2		-
# DFHADWWM5		LOAD	ELPA	2		-
# DFHADWWM6		LOAD	ELPA	2		-
# DFHADWWT0		LOAD	ELPA	2		-
# DFHADWWT1		LOAD	ELPA	2		-
# DFHADWWT2		LOAD	ELPA	2		-
# DFHADWWT3		LOAD	ELPA	2		-
# DFHADWWT4		LOAD	ELPA	2		-
# DFHADWWT5		LOAD	ELPA	2		-
DFHAIIN	AITM Manager initialization	LOAD	ELPA	3	2048	AIEXIT
DFHAIIQ	AITMM - locate/unlock/inquire/browse	LOAD	ELPA	2	1384	AIEXIT
DFHAIP	Application Interface program	LOAD	LPA	2	11560	-
DFHAIRP	AITMM - initialization/recovery	LOAD	ELPA	3	1592	-
DFHAITM	AITMM - add replace/delete	LOAD	ELPA	3	3216	AIEXIT
DFHALP	Terminal allocation	LOAD	ELPA	2	21784	AIEXIT
# DFHALRC		LOAD	ELPA	2		-
# DFHALXM		LOAD	ELPA	2		-
DFHAPAC	AP domain - abnormal condition reporting interface module	LOAD	ELPA	3	1928	-

Table 49. LPA-eligible modules (continued)

	Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
#	DFHAPATT	AP domain - entrypoint attach	LOAD	ELPA	2	728	-
	DFHAPCR		LOAD	ELPA	3		-
	DFHAPDM	AP domain - initialization/ termination	LOAD	ELPA	3	5416	-
	DFHAPDN	AP domain - transaction definition notify	LOAD	ELPA	3	2904	-
#	DFHAPEP	AP domain - user exit service	LOAD	ELPA	2	11128	-
	DFHAPID		LOAD	ELPA	3		-
	DFHAPIN	AP domain - special initialization for programs and user-replaceable modules	LOAD	ELPA	2	184	-
	DFHAPIQ	AP domain - user exit data access service	LOAD	ELPA	3	1232	-
	DFHAPJC	AP domain - journaling gate service	LOAD	ELPA	3	2528	-
	DFHAPLI	AP domain - language interface program	LOAD	ELPA	2	27528	-
#	DFHAPLJ		LOAD	ELPA	2		-
	DFHAPLX	AP domain - manage execution under X8/X9 TCB	LOAD	ELPA	2		-
	DFHAPNT	AP domain - MXT notify gate	LOAD	ELPA	3	1096	-
	DFHAPPG	AP domain - optimize initial_link for	LOAD	ELPA	2	1808	-
	DFHAPRDR	AP domain gate APRD	LOAD	ELPA	2	22176	-
	DFHAPRT	AP Domain - route transaction gate	LOAD	ELPA	3	9104	-
	DFHAPSTL	AP domain - statistics collection program	LOAD	ELPA	2	35248	-
#	DFHAPTC		LOAD	ELPA	3		-
	DFHAPTI	AP domain - timer notify gate	LOAD	ELPA	2	1096	-
	DFHAPTIX	AP domain - expiry analysis task	LOAD	ELPA	2	1096	-
	DFHAPXM	AP domain - transaction initialization and termination services	LOAD	LPA	2	3744	-
	DFHAPXME	AP domain - XM exception handler	LOAD	ELPA	3	2720	-
#	DFHASV	Authorized services interface	AUTH	LPA	2	2504	-
	DFHBADML		LOAD	ELPA	2		-
	DFHBRAI	Bridge Functions	LOAD	ELPA	3		-
	DFHBRAT	Bridge BRAT gate Functions	LOAD	ELPA	3	AA0	-
	DFHBRFM	Bridge Facility Management	LOAD	ELPA	3	3620	-
	DFHBRFR	Bridge Functions	LOAD	ELPA	3		-
	DFHBRIC	IC Bridge Exit Interface	LOAD	ELPA	2	1570	-
	DFHBRIQ	Bridge BRIQ gate Functions	LOAD	ELPA	3	580	-
	DFHBRLK	Bridge Functions	LOAD	ELPA	3		-
	DFHBRME	Bridge Functions	LOAD	ELPA	3		-
	DFHBRMF	Bridge Functions	LOAD	ELPA	3		-
	DFHBRMG	Bridge Functions	LOAD	ELPA	3		-
	DFHBRMR	Bridge Functions	LOAD	ELPA	3		-
	DFHBRMS	BMS Bridge Exit Interface	LOAD	ELPA	2	49B0	-
	DFHBRNS	Bridge Functions	LOAD	ELPA	3		-
	DFHBRRM	Bridge Recovery Manager Functions	LOAD	ELPA	3	8D0	-

Table 49. LPA-eligible modules (continued)

Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
DFHBRSP	SP Bridge Exit Interface	LOAD	ELPA	2	D60	-
DFHBRTB	Bridge terminal buffer management program	LOAD	ELPA	2	3F90	-
DFHBRTC	Bridge support for Terminal Control requests	LOAD	ELPA	2	3D08	-
DFHBRTQ	Bridge terminal buffer query program	LOAD	ELPA	2	2AC0	-
DFHBRXM	Bridge XM Attach Client	LOAD	ELPA	3	21E0	-
DFHCCNV	Data conversion for CICS OS/2 ISC users	LOAD	ELPA	2	806096	(1)
# DFHCCNVG		LOAD	ELPA	3		-
# DFHCDKRN		LOAD	ELPA	3		-
DFHCEGN	Goodnight transaction stub	LOAD	ELPA	3	2400	(1)
DFHCESD	Shutdown transaction	LOAD	ELPA	3	4088	(1)
DFHCHS	CICS/ESA mirror for CICS OS/2 and CICS/VM	LOAD	ELPA	2	8368	(1)
DFHCMAC	ME domain - CICS messages and codes transaction (CMAC)	LOAD	ELPA	2	7576	(1)
DFHCMP	CICS monitoring compatibility interface	LOAD	ELPA	2	496	-
# DFHCNV		LOAD	ELPA	3		-
DFHCPIC	SAA communications interface program	LOAD	ELPA	2	175952	-
DFHCPIN	CPI initialization program	LOAD	ELPA	3	2744	-
DFHCPIRR	SAA resource recovery interface program	LOAD	ELPA	2	1176	-
DFHCPSM	Translator for CICSplex SM commands	LOAD	LPA	3	3184	-
# DFHCQCQ		LOAD	ELPA	3		-
DFHCRLB	Subroutine entry to process logging requests for MRO and LU6.1 links from assembler callers	LOAD	ELPA	2	1360	-
DFHCRNP	Interregion connection manager	LOAD	ELPA	2	10696	(1)
DFHCRQ	ATI purge program	LOAD	ELPA	2	872	(1)
DFHCRR	Interregion session recovery program	LOAD	ELPA	3	4840	(1)
DFHCRS	Remote scheduler program	LOAD	ELPA	2	6800	(1)
DFHCRSP	CICS IRC startup module	LOAD	ELPA	3	3528	(1)
DFHCRT	Transaction routing relay program for APPC devices	LOAD	ELPA	2	648	(1)
DFHCRU	Performs initialization of AP gates for various resource managers and facilities	LOAD	ELPA	2	34448	-
DFHDBAT	CICS-DBCTL adapter/transformer	LOAD	ELPA	2	7960	(1)
DFHDBCT	CICS-DBCTL control program	LOAD	ELPA	3	16968	(1)
DFHDBMOX	CICS-DBCTL monitoring exit	LOAD	ELPA	2	488	-
DFHDBREX	CICS-DBCTL resume exit	LOAD	ELPA	2	472	-
DFHDBSPX	CICS-DBCTL suspend exit	LOAD	ELPA	2	1000	-
DFHDBSSX	CICS-DBCTL status exit	LOAD	ELPA	3	672	-
DFHDBSTX	CICS-DBCTL statistics exit	LOAD	ELPA	3	656	-
# DFHDBTI	EXEC DLI LD table	LOAD	ELPA	3	9024	(1)
DFHDBTOX	CICS-DBCTL token exit	LOAD	ELPA	3	488	-
DFHDPC	Dump control program	LOAD	ELPA	3	848	-

Table 49. LPA-eligible modules (continued)

	Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
#	DFHDHML		LOAD	ELPA	2		-
#	DFHDHRP		LOAD	ELPA	3		-
	DFHDIP	Data interchange program	LOAD	ELPA	2	3936	DIP=YES
	DFHDIPDY	Data interchange program (dummy)	LOAD	ELPA	2	168	DIP=NO
	DFHDLI	DL/I call router	LOAD	LPA	2	4504	-
	DFHDLIDP	DBCTL call processor	LOAD	ELPA	2	7032	-
#	DFHLLD		LOAD	ELPA	2		-
	DFHDMRM	CSD open/close program	LOAD	ELPA	3	888	-
#	DFHDPML		LOAD	ELPA	3		-
#	DFHDPWM0		LOAD	ELPA	2		-
#	DFHDPWM1		LOAD	ELPA	2		-
#	DFHDPWM2		LOAD	ELPA	2		-
#	DFHDPWM3		LOAD	ELPA	2		-
#	DFHDPWM4		LOAD	ELPA	2		-
#	DFHDPWM5		LOAD	ELPA	2		-
#	DFHDPWM6		LOAD	ELPA	2		-
#	DFHDPWT0		LOAD	ELPA	2		-
#	DFHDPWT1		LOAD	ELPA	2		-
#	DFHDPWT2		LOAD	ELPA	2		-
#	DFHDPWT3		LOAD	ELPA	2		-
#	DFHDPWT4		LOAD	ELPA	2		-
#	DFHDPWT5		LOAD	ELPA	2		-
#	DFHDPWT6		LOAD	ELPA	2		-
	DFHDSAUT	DS domain - authorized services	AUTH	ELPA	2	2280	-
	DFHDSBA\$	BMS data stream build (standard)	LOAD	ELPA	2	1592	(11)
	DFHDSB1\$	BMS data stream build (full)	LOAD	ELPA	2	1592	(12)
#	DFHDSRP		LOAD	ELPA	2		-
	DFHDTAM	Shared data tables: access manager	AUTH	ELPA	2	11680	(10)
	DFHDTAOR	Shared data tables: AOR module	AUTH	ELPA	2	3264	(10)
	DFHDTCV	Shared data tables connection validation	LINK	ELPA	2	288	(10)
	DFHDTFOR	Shared data tables: FOR module	AUTH	ELPA	2	13400	(10)
#	DFHDTLX		LOAD	ELPA	2		-
	DFHDT SVC	Shared data tables: SVC services	LINK	ELPA	3	10944	(10)
	DFHDTXS	Shared data tables connection security	AUTH	ELPA	3	1616	(10)
	DFHDUIO	DU domain - open/close/switch/ write	LOAD	LPA	2	5016	-
	DFHDUSVC	DU domain - SVC processing routine	AUTH	ELPA	2	4160	-
	DFHDYP	Dynamic routing program	LOAD	ELPA	2	320	(14) (1)
#	DFHD2CC		LOAD	ELPA	3		-
#	DFHD2CM0		LOAD	ELPA	3		-
#	DFHD2CM1		LOAD	ELPA	3		-
#	DFHD2CM2		LOAD	ELPA	3		-
#	DFHD2CM3		LOAD	ELPA	3		-
#	DFHD2CO		LOAD	ELPA	3		-
#	DFHD2D2		LOAD	ELPA	3		-
#	DFHD2EDF		LOAD	ELPA	3		-
#	DFHD2EX1		LOAD	ELPA	3		-

Table 49. LPA-eligible modules (continued)

	Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
#	DFHD2EX2		LOAD	ELPA	3		-
#	DFHD2EX3		AUTH	ELPA	3		-
#	DFHD2IN		LOAD	ELPA	3		-
#	DFHD2INI		LOAD	ELPA	3		-
#	DFHD2MSB		AUTH	ELPA	3		-
#	DFHD2RP		LOAD	ELPA	3		-
#	DFHD2STP		LOAD	ELPA	3		-
#	DFHD2STR		LOAD	ELPA	3		-
#	DFHD2TM		LOAD	ELPA	3		-
	DFHEBU	EXEC FMH construction	LOAD	ELPA	2	432	(17)
#	DFHECBAM		LOAD	ELPA	3		-
	DFHECID	CECI service program	LOAD	ELPA	3	77424	(1)
	DFHECIP	Command interpreter (CECI) program	LOAD	ELPA	3	3008	(1)
	DFHECSP	Command syntax check (CECS) program	LOAD	ELPA	3	3008	(1)
	DFHEDAD	RDO (CEDA) service program	LOAD	ELPA	3	127688	(1)
	DFHEDAP	RDO (CEDA) program	LOAD	ELPA	3	3144	(1)
	DFHEDC	EXEC interface for dump control	LOAD	ELPA	2	152	-
	DFHEDCP	EXEC interface for dump system/transaction	LOAD	ELPA	3	3776	-
	DFHEDFBR	Temporary-storage browse transaction, CEBR	LOAD	ELPA	3	12024	(1)
	DFHEDFD	EDF display program	LOAD	ELPA	3	63552	(1)
	DFHEDFE	EDF attach error handler	LOAD	ELPA	3	1360	(1)
	DFHEDFP	EDF control program	LOAD	ELPA	3	7512	(1)
	DFHEDFR	EDF response table	LOAD	ELPA	3	576	(1)
	DFHEDFX	EDF task switch program	LOAD	ELPA	3	4296	(1)
	DFHEDI	EXEC interface for data interchange	LOAD	ELPA	2	1352	DIP=YES
#	DFHEDP	EXEC DLI command stub	LOAD	ELPA	2	7128	(1)
	DFHEEI	EXEC interface for HANDLE, ADDRESS, ASSIGN	LOAD	ELPA	2	6536	-
	DFHEEX	EXEC FMH extraction	LOAD	ELPA	2	752	-
	DFHEGL	EXEC interface for unmapped LU6.2 commands	LOAD	ELPA	2	3664	(18)
	DFHEIACQ	EXEC ACQUIRE TERMINAL	LOAD	ELPA	3	1464	-
#	DFHEIBAM		LOAD	ELPA	2		-
	DFHEICRE	EXEC CICS CREATE commands	LOAD	ELPA	3	86880	-
#	DFHEIDEF		LOAD	ELPA	2		-
#	DFHEIDEL		LOAD	ELPA	3		-
#	DFHEIDH		LOAD	ELPA	2		-
	DFHEIDLI	DL/I load table	LOAD	LPA	3	9248	DLI
	DFHEIDTI	EXEC ask-time, format-time program	LOAD	ELPA	2	3048	-
#	DFHEIEM		LOAD	ELPA	2		-
	DFHEIFC	File control: EXEC interface module	LOAD	ELPA	2	11800	-
#	DFHEIGDS	Translator table (GDS commands)	LOAD	ELPA	3	2752	(1)
	DFHEIGDX	EXEC interface load table	LOAD	LPA	3	3024	-
	DFHEIIC	EXEC interface IC module	LOAD	ELPA	2	7824	-
#	DFHEIINS		LOAD	ELPA	3		-

Table 49. LPA-eligible modules (continued)

	Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
#	DFHEIPI		LOAD	ELPA	2		-
	DFHEIPRT	EXEC interface for perform resetime	LOAD	ELPA	3	680	-
	DFHEIPSE	EXEC interface for perform security	LOAD	ELPA	3	896	SEC=YES
	DFHEIPSH	EXEC interface for perform shutdown	LOAD	ELPA	3	2800	-
#	DFHEIQBA		LOAD	ELPA	2		-
#	DFHEIQBR	EXEC bridge inquire facility	LOAD	ELPA	3	5848	-
#	DFHEIQCF		LOAD	ELPA	3		-
#	DFHEIQDH		LOAD	ELPA	3		-
#	DFHEIQDI		LOAD	ELPA	3		-
	DFHEIQDN	EXEC inquire/set for external data sets	LOAD	ELPA	3	7576	-
	DFHEIQDS	EXEC inquire/set/discard for files	LOAD	ELPA	3	14344	-
	DFHEIQDU	EXEC inquire/set for dump data sets and dump codes	LOAD	ELPA	3	8584	-
#	DFHEIQD2		LOAD	ELPA	3		-
#	DFHEIQEJ	EXEC inquire EJB commands	LOAD	ELPA	3	12824	-
	DFHEIQIR	EXEC inquire/set for IRC	LOAD	ELPA	3	1976	-
	DFHEIQMS	EXEC inquire/set for monitor and stats	LOAD	ELPA	3	13944	-
	DFHEIQMT	EXEC inquire/set for CEMT-only commands	LOAD	ELPA	3	3408	-
#	DFHEIQOP	EXEC inquire requestmodel	LOAD	ELPA	3	2608	-
#	DFHEIQPI		LOAD	ELPA	3		-
	DFHEIQRQ	EXEC inquire for queued requests (REQIDs)	LOAD	ELPA	3	3152	-
#	DFHEIQRR		LOAD	ELPA	3		-
	DFHEIQSA	EXEC inquire/set for system attributes	LOAD	ELPA	3	8928	-
	DFHEIQSC	EXEC inquire/set for connections	LOAD	ELPA	3	16616	-
	DFHEIQSJ	EXEC inquire/set for journals	LOAD	ELPA	3	3480	-
	DFHEIQSK	EXEC inquire/set for tasks	LOAD	ELPA	3	15248	-
	DFHEIQSL	EXEC inquire/discard for journalmodel	LOAD	ELPA	3	3144	-
	DFHEIQSM	EXEC inquire/set for modenames	LOAD	ELPA	3	4048	-
#	DFHEIQSO		LOAD	ELPA	3		-
	DFHEIQSP	EXEC inquire/set/discard for programs	LOAD	ELPA	3	6272	-
	DFHEIQSQ	EXEC inquire/set for TD queues	LOAD	ELPA	3	9096	-
	DFHEIQST	EXEC inquire/set for terminals	LOAD	ELPA	3	22480	-
	DFHEIQSV	EXEC inquire/set for volumes	LOAD	ELPA	3	400	-
	DFHEIQSX	EXEC inquire/set/discard for transactions	LOAD	ELPA	3	7144	-
#	DFHEIQSY		LOAD	ELPA	3		-
	DFHEIQSZ	EXEC CICS SPI commands for FEPI	LOAD	ELPA	3	3784	-
	DFHEIQTR	EXEC inquire/set for trace	LOAD	ELPA	3	10392	-
	DFHEIQUE	EXEC inquire for exit programs	LOAD	ELPA	3	6288	-
	DFHEIQVT	EXEC inquire/set for VTAM and autoinstall	LOAD	ELPA	3	5968	-
#	DFHEIQWB		LOAD	ELPA	3		-

Table 49. LPA-eligible modules (continued)

Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
# DFHEIQWR		LOAD	ELPA	3		-
# DFHEISO		LOAD	ELPA	3		-
DFHEISP	EXEC interface syncpoint processor	LOAD	ELPA	2	1576	-
# DFHEITAB	Translator table (basic commands)	LOAD	ELPA	3	46272	(1)
# DFHEITBS	Translator table (special	LOAD	ELPA	3	47984	(1)
#	commands)					
DFHEITHG	EXEC interface hired gun lookup table	LOAD	LPA	2	13800	-
DFHEITMT	Command language table for CEMT	LOAD	ELPA	3	34432	(1)
DFHEITOT	Command language table for CEOT	LOAD	ELPA	3	1192	(1)
DFHEITS	EXEC TS request handler	LOAD	ELPA	2	7096	-
DFHEITST	CEST language definition table	LOAD	ELPA	3	4984	(1)
# DFHEITSZ	EXEC CICS language definition table	LOAD	ELPA	3	8592	(1)
#						
# DFHEIWB		LOAD	ELPA	2		-
DFHEJC	EXEC interface for journaling	LOAD	ELPA	2	984	-
# DFHEJDML		LOAD	ELPA	3		-
# DFHEJITL		LOAD	ELPA	2		-
DFHEKC	EXEC interface for task control	LOAD	ELPA	2	1448	-
# DFHEMDML		LOAD	ELPA	2		-
DFHEMEX	EXEC interface for ME domain	LOAD	ELPA	3	2792	-
DFHEMS	EXEC interface for BMS	LOAD	ELPA	2	4264	BMS
DFHEMTA	Programmable interface to Master terminal program	LOAD	ELPA	3	3232	(1,5)
DFHEMTD	Master terminal (CEMT) service program	LOAD	ELPA	3	98120	(1)
DFHEMTP	Master terminal (CEMT) program	LOAD	ELPA	3	3232	(1)
DFHEOP	EXEC interface for write operator	LOAD	ELPA	3	2752	-
DFHEOTP	CEOT service program	LOAD	ELPA	3	3232	(1)
DFHEPC	EXEC interface for program control	LOAD	ELPA	2	8280	-
DFHEPS	System spooling interface stub	LOAD	ELPA	2	2856	(15)
DFHERM	Resource manager interface (RMI) module	LOAD	LPA	2	14056	-
DFHERMRS	External resource manager resync processor	LOAD	ELPA	3	4312	-
DFHERMSP	External resource manager syncpoint processor	LOAD	ELPA	3	4400	-
DFHESC	EXEC interface for storage control	LOAD	ELPA	2	1320	-
DFHESE	EXEC interface for query security	LOAD	ELPA	2	4664	-
DFHESN	EXEC interface for signon and sign-off	LOAD	ELPA	2	4992	-
DFHESTP	CEST service program	LOAD	ELPA	3	3232	(1)
DFHESZ	EXEC CICS API commands for FEPI	LOAD	ELPA	3	1136	-
DFHETC	EXEC interface for terminal control	LOAD	ELPA	2	7376	-
DFHETD	EXEC interface for transient data	LOAD	ELPA	2	2728	-
DFHETL	LU6.2 EXEC interface stub	LOAD	ELPA	2	7944	-
DFHETR	EXEC interface for trace control	LOAD	ELPA	2	792	(6)
DFHETRX	EXEC interface for enter tracenum, monitor	LOAD	ELPA	2	1232	USERTR

Table 49. LPA-eligible modules (continued)

Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
DFHFCAT	File control catalog manager	LOAD	ELPA	2	7328	-
DFHFCBD	File control BDAM request processor	LOAD	LPA	2	5192	(16)
DFHFCCA	File Control RLS Control ACB Manager	LOAD	ELPA	2	14984	-
# DFHFCDL		LOAD	ELPA	2		-
DFHFCDN	File control DSN block manager	LOAD	ELPA	3	9856	(16)
# DFHFCDO		LOAD	ELPA	2		-
# DFHFCDR		LOAD	ELPA	2		-
# DFHFCDUW		LOAD	ELPA	2		-
DFHFCD2	File control shared data tables record request handler	LOAD	ELPA	2	16120	(16) (10)
DFHF CFL	File Control FRAB/FLAB processor	LOAD	ELPA	2	6896	-
DFHF CFR	File Control request handler	LOAD	ELPA	2	10760	(16)
DFHF CFS	File Control state program	LOAD	ELPA	2	54632	(16)
DFHF CIN	File control initialization program	LOAD	ELPA	3	1448	(16)
DFHF CLJ	File control logging and journaling	LOAD	ELPA	2	16968	-
DFHF CMT	File control table manager	LOAD	ELPA	3	11864	(16)
DFHF CNQ	File control lock name interpreter	LOAD	ELPA	2	3088	-
DFHF CQI	File control VSAM RLS Quiesce - Initiation	LOAD	ELPA	2	5408	-
DFHF CQT	File control VSAM RLS Quiesce - Common System Transaction	LOAD	ELPA	2	14376	-
DFHF CQU	File control VSAM RLS Quiesce - Process	LOAD	ELPA	2	8304	-
DFHF CQX	File control VSAM RLS Quiesce - CICS RLS Quiesce Exit	LOAD	ELPA	2	2440	-
DFHF CRC	File control recovery control	LOAD	ELPA	2	20792	-
# DFHF CRF		LOAD	ELPA	2		-
DFHF CRL	File control VSAM SHRCTL block manager	LOAD	ELPA	3	3320	(16)
DFHF CRO		LOAD	ELPA	2	31384	-
DFHF CRP	File control restart program	LOAD	ELPA	3	24040	(16)
DFHF CRS	File control VSAM RLS record management module	LOAD	ELPA	2	24192	-
DFHF CRV	File control VSAM RLS interface module	LOAD	ELPA	2	3576	-
DFHF CSD	File control shutdown program	LOAD	ELPA	2	1792	(16)
DFHF CST	File control statistics program	LOAD	ELPA	3	7352	(16)
DFHF CU	File open utility program	LOAD	LPA	3	552	(16) (1)
DFHF CVS	File access VSAM request processor	LOAD	ELPA	2	30504	(16)
DFHGMM	VTAM LU startup message	LOAD	ELPA	2	2096	(1)
DFHGTCNV	Subroutine used by the LOGR subsystem interface	LINK	ELPA	3	11736	-
DFHICP	Interval control program	LOAD	ELPA	2	11440	-
DFHICRC	Interval Control Recovery module	LOAD	ELPA	2	7616	-
DFHICXM	AP domain - bind, inquire, and release facility IC functions	LOAD	ELPA	2	4952	-
# DFHIEDML		LOAD	ELPA	3		-
# DFHIEP		LOAD	ELPA	3		-
# DFHIEXM		LOAD	ELPA	2		-

Table 49. LPA-eligible modules (continued)

	Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
#	DFHIIDML		LOAD	ELPA	3		-
	DFHIIPA\$	BMS non-3270 input mapping (standard)	LOAD	ELPA	3	2048	(11)
	DFHIIP1\$	BMS non-3270 input mapping (full)	LOAD	ELPA	3	2048	(12)
#	DFHIIXM		LOAD	ELPA	2		-
	DFHINDAP	Indoubt tool	LOAD	ELPA	3	1912	(1)
	DFHINDSP	Indoubt tool syncpoint processor	LOAD	ELPA	3	1688	-
	DFHINDT	Indoubt tool	LOAD	ELPA	3	6464	(1)
	DFHINTRU	Indoubt tool task-related user exit	LOAD	ELPA	3	2224	(1)
	DFHIRW10	IRC work delivery exit program	AUTH	ELPA	2	1328	-
	DFHISP	Intersystem communication program	LOAD	ELPA	2	3512	ISC=YES
	DFHJCP	Journaling component	LOAD	LPA	2	2288	-
#	DFHJVMAT		AUTH	ELPA	2		-
	DFHKCP	Transaction manager startup routine	LOAD	ELPA	2	8936	-
	DFHKCSC	DFHKCQ chain scanning for discard	LOAD	ELPA	3	1072	-
	DFHKESVC	KE domain - authorized service routine	AUTH	ELPA	2	1768	-
	DFHLDDMI	LD domain - secondary initialization	LOAD	ELPA	3	18480	-
	DFHLDNT	LD domain - storage notify handler	LOAD	ELPA	2	2464	-
	DFHLDST	LD domain - statistics collection	LOAD	ELPA	3	3592	-
	DFHLD SVC	LD domain - authorized service routine	AUTH	LPA	2	2256	-
	DFHLEDT	Transaction dump service	LOAD	ELPA	2	330	-
	DFHLGCNV	Exit routine used by the LOGR subsystem interface	LINK	ELPA	3	20088	-
	DFHLGDM	Log manager domain initialization	LOAD	ELPA	3	346736	-
	DFHLIRET	Language interface return program	LOAD	LPA	2	136	-
	DFHMCPA\$	BMS mapping control program (standard)	LOAD	ELPA	2	8248	(11)
	DFHMCPE\$	BMS mapping control program (minimum)	LOAD	ELPA	2	7064	(13)
	DFHMCP1\$	BMS mapping control program (full)	LOAD	ELPA	2	12920	(12)
	DFHMCX	BMS fast path module	LOAD	ELPA	2	7136	BMS
#	DFHMCY	Process MAPPINGEV Requests	LOAD	ELPA	2	7192	BMS
#	DFHMET1C		AUTH	ELPA	2		-
	DFHMET1E	DFHMEU base messages link-edit module	AUTH	ELPA	2	340872	NATLANG
#	DFHMET1K		AUTH	ELPA	2		-
#	DFHMET5C		AUTH	ELPA	2		-
	DFHMET5E	DFHMEU ONC RPS messages link-edit module	AUTH	ELPA	2	67512	-
#	DFHMET5K		AUTH	ELPA	2		-
#	DFHMET9C		AUTH	ELPA	2		-
	DFHMET9E	DFHMEU user messages link-edit module	AUTH	ELPA	2	360	-
#	DFHMET9K		AUTH	ELPA	2		-
	DFHMGP	Message writer program	LOAD	ELPA	3	14560	-

Table 49. LPA-eligible modules (continued)

Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
DFHMGT	Message generation table	LOAD	ELPA	3	23272	-
DFHMIRS	DFHMIRS	LOAD	ELPA	2	4816	ISC=YES (1)
DFHML1	BMS LU1 printer mapping program	LOAD	ELPA	2	5144	BMS
DFHMNDML	MN domain - initialization/ termination	LOAD	ELPA	2	74936	-
DFHMNSVC	MN domain - authorized service routine	AUTH	ELPA	2	4600	-
DFHMRXM						-
DFHMSP	Message switching program	LOAD	ELPA	2	11440	(1)
DFHMXP	Local queuing shipper	LOAD	ELPA	2	1176	(1)
DFHM32A\$	BMS 3270 mapping (standard)	LOAD	ELPA	2	6520	(11)
DFHM321\$	BMS 3270 mapping (full)	LOAD	ELPA	2	6520	(12)
# DFHNCIF		LINK	ELPA	3		-
DFHNQDM	NQ domain initialize, quiesce and terminate domain functions	LOAD	ELPA	2	34760	-
# DFHOTDML		LOAD	ELPA	2		-
DFHPBPA\$	BMS page and text build (standard)	LOAD	ELPA	2	8552	(11)
DFHPBP1\$	BMS page and text build (full)	LOAD	ELPA	2	9352	(12)
DFHPCP	Program control program	LOAD	ELPA	2	2488	-
DFHPGADX	Program autoinstall exit - Assembler	LOAD	ELPA	2	200	(1)
DFHPGDM	PG domain - initialize, quiesce, and terminate domain functions	LOAD	ELPA	2	153328	-
DFHPGRP	PG domain - recovery program	LOAD	ELPA	2	12888	-
DFHPHP	Partition handling program	LOAD	ELPA	2	2248	BMS
# DFHPIAP		LOAD	ELPA	2		-
# DFHPIDML		LOAD	ELPA	2		-
# DFHPIDSH		LOAD	ELPA	3		-
# DFHPIDSQ		LOAD	ELPA	3		-
# DFHPIITL		LOAD	ELPA	2		-
# DFHPILSQ		LOAD	ELPA	3		-
# DFHPIRS		LOAD	ELPA	3		-
# DFHPIRT		LOAD	ELPA	3		-
# DFHPISN1		LOAD	ELPA	2		-
# DFHPISN2		LOAD	ELPA	2		-
# DFHPITP		LOAD	ELPA	3		-
# DFHPITQ1		LOAD	ELPA	3		-
DFHPRCM	Partner resource manager command interface	LOAD	ELPA	3	1360	-
DFHPRFS	Partner resource manager interface to SAA communications interface	LOAD	ELPA	2	632	-
DFHPRIN	Partner initialization load program	LOAD	ELPA	3	3336	-
DFHPRPT	Partner resource table (PRT) manager	LOAD	ELPA	3	3040	-
DFHPSP	System spooling interface program	LOAD	LPA	2	14424	(15)
DFHPSSVC	System spooling interface, retrieve a data set name	AUTH	ELPA	2	1472	(15)
# DFHPTDML		LOAD	ELPA	3		-

Table 49. LPA-eligible modules (continued)

Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
DFHQRY	Query transaction	LOAD	ELPA	2	3824	(1)
DFHRLRA\$	BMS route list resolution (standard)	LOAD	ELPA	2	2040	(11)
DFHRLR1\$	BMS route list resolution (full)	LOAD	ELPA	2	3832	(12)
DFHRMSY	Resource manager resync program	LOAD	ELPA	3	4160	(1)
DFHRPAL	ONC RPC feature alias list	LOAD	ELPA	3	2384	(1)
DFHRTC	CRTE cancel command processor	LOAD	ELPA	2	864	(1)
DFHRTE	Transaction routing program	LOAD	ELPA	2	2600	(1)
DFHRTSU	Surrogate terminal interface program	LOAD	ELPA	3	2736	-
# DFHRXDML		LOAD	ELPA	2		-
# DFHRZDML		LOAD	ELPA	2		-
# DFHRZJN		LOAD	ELPA	2		-
DFHSAIQ	AP domain - system data inquire & set	LOAD	ELPA	2	2224	-
DFHSFP	Sign-off program	LOAD	ELPA	2	4144	(1)
# DFHSHDML		LOAD	ELPA	2		-
# DFHSHRRP		LOAD	ELPA	2		-
# DFHSHRSP		LOAD	ELPA	2		-
# DFHSHSY		LOAD	ELPA	2		-
# DFHJCSL		AUTH	ELPA	3		-
# DFHSJDML		LOAD	ELPA	3		-
# DFHSJJLL		AUTH	ELPA	3		-
# DFHSJJML		LOAD	ELPA	3		-
DFHSKP	Subtask management program	LOAD	ELPA	2	6448	-
DFHSTSK	General purpose subtask entry point	AUTH	ELPA	3	40	-
DFHSMSVC	SM domain - authorized service routine	AUTH	ELPA	3	11336	-
# DFHSMTAB	CICSplex SM commands language table	LOAD	ELPA	3	632	-
# DFHSNP	Signon program	LOAD	ELPA	2	13184	(1)
DFHSNUS	US domain - local and remote signon	LOAD	ELPA	2	52984	-
# DFHSODML	SO domain	LOAD	ELPA	2	263768	-
# DFHSOSE	SO domain	LOAD	ELPA	2	23480	-
DFHSPP	Syncpoint program	LOAD	ELPA	2	1744	-
DFHSTDML	ST domain - initialization/ termination	LOAD	ELPA	3	30520	-
DFHSUSX	XRF signon	LOAD	ELPA	2	9240	(19)
DFHSUWT	WTO/WTOR interface subroutine	LOAD	ELPA	3	7152	-
DFHSUZX	ZC trace controller	LOAD	ELPA	3	6808	-
DFHSZATR	FEPI adaptor program	LOAD	ELPA	3	17328	-
DFHTBSS	Builder syncpoint processor	LOAD	ELPA	2	19168	-
DFHTCRP	Terminal control recovery program	LOAD	ELPA	3	25392	-
DFHTDP	Transient data program	LOAD	LPA	2	25448	-
DFHTDQ	Transient data program	LOAD	ELPA	2	30280	-
DFHTDRM	Transient data recovery manager processor	LOAD	ELPA	2	31080	-
DFHTDRP	Transient data recovery program	LOAD	ELPA	3	6432	-
DFHTDTM	TD table management gate	LOAD	ELPA	2	17656	-

Table 49. LPA-eligible modules (continued)

Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
DFHTDXM	XM domain - TD facility management services	LOAD	ELPA	2	3696	-
DFHTFBB	Terminal facility manager bind facility functions	LOAD	ELPA	2	14528	-
DFHTFIQ	Terminal facility manager inquire/set functions	LOAD	ELPA	2	5632	-
DFHTFRF	Terminal facility manager release function	LOAD	ELPA	2	4176	-
# DFHTFXM		LOAD	ELPA	2		-
DFHTIDM	TI domain - initialization/termination	LOAD	ELPA	3	9264	-
DFHTMP	Table manager program	LOAD	ELPA	2	21088	-
DFHTON	Terminal object resolution module	LOAD	ELPA	2	816	-
DFHTONR	Terminal object resolution recovery	LOAD	ELPA	2	2248	-
DFHTPPA\$	BMS terminal page processor (standard)	LOAD	ELPA	2	3344	(11)
DFHTPP1\$	BMS terminal page processor (full)	LOAD	ELPA	2	4336	(12)
DFHTPQ	BMS terminal page cleanup program	LOAD	ELPA	2	4040	BMS (1)
DFHTPR	BMS terminal page retrieval program	LOAD	ELPA	2	21688	BMS (1)
DFHTPS	BMS terminal page scheduling program	LOAD	ELPA	2	4632	BMS (1)
DFHTRAO	TR domain - auxiliary trace output	LOAD	LPA	3	1480	(20)
DFHTSDML	Temporary storage domain	LOAD	ELPA	2	123248	-
# DFHTSDQ		LOAD	ELPA	2		-
DFHTSP	Temporary-storage control program	LOAD	ELPA	2	3928	(21)
DFHUEH	User exit handler (AP domain)	LOAD	ELPA	2	7960	-
DFHUEM	User exit manager	LOAD	ELPA	3	7864	-
DFHUSDM	US domain - initialize, quiesce, and terminate domain functions	LOAD	ELPA	3	58640	-
# DFHWBAAX		LOAD	ELPA	2		-
# DFHWBADX		LOAD	ELPA	2		-
# DFHWBDML		LOAD	ELPA	2		-
# DFHWBENV		LOAD	ELPA	3		-
# DFHWBERX		LOAD	ELPA	2		-
# DFHWBIMG		LOAD	ELPA	3		-
# DFHWBPA		LOAD	ELPA	3		-
# DFHWBUN		LOAD	ELPA	3		-
DFHWSMS	DFHWSMS	AUTH	ELPA	2	38456	(19)
DFHWSSON	CAVM state management signon request handler	AUTH	ELPA	2	14280	(19)
DFHWTI	XRF takeover initiation program	AUTH	ELPA	3	11648	(19)
# DFHXCEIX		EXCI	ELPA	2		-
DFHXCI	External CICS interface (EXCI) program	LOAD	LPA	3	3152	-
# DFHXCPRX		EXCI	ELPA	2		-
DFHXCSVC	EXCI SVC services	LINK	ELPA	3	512	-
# DFHXCTAB	EXCI language table	LOAD	ELPA	3	504	-
# DFHXFP	Online data transformation program	LOAD	ELPA	2	31744	ISC=YES
#						

Table 49. LPA-eligible modules (continued)

Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
DFHXFRM	Function shipping storage recovery	LOAD	ELPA	2	1744	-
DFHXFX	Optimized data transformation program	LOAD	ELPA	2	8024	ISC=YES
DFHXRP	XRF request program	LOAD	ELPA	2	9272	(19)
DFHXRSP	XRF surveillance program	LOAD	ELPA	2	4800	(19)
DFHXSS	XS domain - supervisor request services	AUTH	ELPA	3	30576	SEC=NO
DFHXSWM	XRF message manager for security manager	LOAD	ELPA	2	1744	(19)
DFHXTP	Terminal sharing transformation program	LOAD	ELPA	2	11656	ISC=YES
DFHZATA	Autoinstall program	LOAD	ELPA	2	18648	(1)
DFHZATD	Autoinstall delete program	LOAD	ELPA	2	6584	(1)
DFHZATDX	User-replaceable autoinstall exit	LOAD	ELPA	2	392	AIEXIT (1)
DFHZATDY	User-replaceable autoinstall exit with APPC	LOAD	ELPA	2	560	AIEXIT (1)
# DFHZBAN	Terminal control bind analysis	LOAD	LPA	2	10288	-
DFHZCA	VTAM working set module	LOAD	ELPA	2	9888	(18)
DFHZCB	VTAM working set module	LOAD	ELPA	2	39496	(18)
DFHZCC	VTAM working set module	LOAD	ELPA	2	63160	(18)
DFHZCN1	CICS Client CCIN transaction	LOAD	ELPA	3	4472	(1)
DFHZCN2	CICS Client CCIN transaction	LOAD	ELPA	3	4464	-
DFHZCP	Terminal management program	LOAD	ELPA	2	33528	(18)
DFHZCT1	CICS Client CTIN transaction	LOAD	ELPA	3	103046	(1)
DFHZCUT	Persistent verification signed-on-from list management program	LOAD	ELPA	2	5376	(18)
DFHZCW	VTAM nonworking set module	LOAD	ELPA	3	7072	(18)
DFHZCX	LOCATE, ISC/IRC request	LOAD	ELPA	2	34728	ISC=YES
DFHZCXR	Transaction routing module address list	LOAD	ELPA	2	28984	ISC=YES
DFHZCY	VTAM nonworking set module	LOAD	ELPA	3	82976	(18)
DFHZCZ	VTAM nonworking set module	LOAD	ELPA	3	25712	(18)
DFHZGAI	APPC autoinstall - create APPC clones	LOAD	ELPA	2	9288	AIEXIT
DFHZGBM	APPC manipulate bitmap	LOAD	ELPA	2	4776	(18)
DFHZGCA	LU6.2 CNOS actioning	LOAD	ELPA	3	6168	(18)
DFHZGCC	Catalog CNOS services	LOAD	ELPA	3	2440	(18)
DFHZGCH	ZC VTAM change macro domain function	LOAD	ELPA	3	4056	-
DFHZGCN	LU6.2 CNOS negotiation	LOAD	ELPA	3	12272	(18)
DFHZGIN	ZC VTAM issue inquire	LOAD	ELPA	3	3544	-
DFHZGPR	VTAM persistent sessions resource handler	LOAD	ELPA	3	2848	(18)
DFHZGTA	ZC table alter	LOAD	ELPA	2	23312	-
DFHZGTI	ZC table inquire gate	LOAD	ELPA	2	14744	-
DFHZHPRX	Authorized path SRB mode VTAM EXECRPL	AUTH	ELPA	2	712	HPO=YES
DFHZLS1	LU6.2 CNOS request transaction program	LOAD	ELPA	3	2160	(18) (1)
DFHZRSP	Resync send program	LOAD	ELPA	2	248	(22) (1)
# DFH62XM		LOAD	ELPA	2		-

Table 49. LPA-eligible modules (continued)

	Name	Description	Library	LPA/ ELPA	Pri	Size	Option/ Note
#	ICCFCTAB		LOAD	ELPA	3		-
#	ICCFCTBH		LOAD	ELPA	3		-

Glossary of SMP/E terms used in this book

ACCEPT (function of SMP/E) . SMP/E control statement that controls the placement (installing) of SYSMODs into the distribution libraries. Processing is similar to that during APPLY except that the distribution zone is updated, not the target zone, and JCLIN data is not processed by ACCEPT.

If the installing is successful, any entries in the SCDS created by APPLY are deleted, as are temporary libraries created by RECEIVE. Therefore, after a SYSMOD is accepted, it can no longer be removed by SMP/E.

APAR (authorized program analysis report) . IBM-supplied fixes of a temporary corrective nature to elements of IBM-supplied function SYSMODs. APAR fixes are intended to cure problems currently being experienced by an installation. The APAR fix is usually in the form of either a modification to a load module or an update to card-image data. It is intended as a temporary arrangement until a PTF is issued to fix the problem permanently. This PTF will supersede the APAR fix, and indeed specifies this relationship on its ++VER statement.

To get an APAR SYSMOD accepted into the distribution libraries, the APARS keyword must be specified in the ACCEPT control statement, which protects against inadvertent updating of distribution libraries that are to be kept free of temporary fixes.

The ++VER statement in the APAR SYSMOD must specify the FMID of the function that “owns” the elements being updated.

```
++APAR(AP12345)
++VER(C150) FMID(HCI6400)
```

You should not accept APARs into the distribution library, however, because the relevant PTF will become available in due course as a more permanent form of service.

APPLY (function of SMP/E) . SMP/E control statement that applies SYSMODs to the CICS target libraries, where they can be tested. If the tests are not satisfactory, you can remove all or selected SYSMODs using the RESTORE function. If the test is successful, you can use the ACCEPT function to store the elements from the SYSMOD into the distribution libraries.

During JCLIN processing, every affected entry in the target zone is saved in the SCDS, in case the target system libraries and the target zone have to be restored to their original status.

CSI (consolidated software inventory) . A keyed VSAM data set, logically divided by SMP/E into **zones**. For further information on the CSI and the logical structure of zones, see the *System Modification Program Extended: User's Guide*.

Distribution zone . Describes the structure and contents of a set of distribution libraries.

Function SYSMOD . An IBM-supplied product that can be installed with SMP/E. CICS Transaction Server for z/OS, Version 3 Release 1 is packaged as a function SYSMOD on a distribution tape. This contains distribution libraries and JCLIN data which SMP/E uses to create the target libraries.

FMID (keyword of CICS SYSMODs) . Keyword identifying the release and option to which a SYSMOD is applicable. For CICS Transaction Server for z/OS, Version 3 Release 1, it is always HCI6400.

Global zone . Logical division of the SMP/E consolidated software inventory (CSI), containing such information as:

- Definitions of all other related zones
- Descriptions of the SYSMODs present in the PTS
- Descriptions of the system utilities to be invoked during SMP/E processing
- DD definition entries for use by dynamic allocation

load module . In the context of SMP/E, an executable load module in a target library (such as *hlq.SDFHLOAD*). The standard SMP/E abbreviation for a load module is LMOD.

PTF (program temporary fix) . IBM-supplied fixes to elements of IBM-supplied function SYSMODs. PTFs are intended for installation by all users to avoid possible problems.

A PTF may contain fixes for several different problems. This means that several APAR fixes reported in RETAIN may all be superseded by the more permanent PTF, which:

- Provides card-image changes that are identical to those in the APAR fix
- Contains object-module replacements for preassembled CICS programs

Every PTF is introduced by a ++PTF header statement, and contains the FMID keyword on its ++VER modification control statement, identifying CICS (HCI6400) as the owner of the modules being serviced.

For example:

```
++PTF(UP12345)
++VER(C150) FMID(HCI6400)
```

PTS (PTF temporary store) . SMP/E primary data set used to store temporarily SYSMODs that are in RECEIVE or APPLY status; that is, they have not been rejected or accepted.

RECEIVE (function of SMP/E) . SMP/E control statement that initiates processing of a SYSMOD.

RECEIVE reads the SYSMODs from the SMPPTFIN data set. Each SYSMOD must have been received before any other function can be executed.

RECEIVE updates the SMPPTS data set and performs syntax checking on input. Before any SYSMOD for CICS can be received, the global zone must have been initialized with a global zone entry.

Service SYSMODs can be received into the (PTS) before the function to which it applies has been received, and can be maintained there until the function is received. This allows all service for a product such as CICS to be installed with the base product.

REJECT (function of SMP/E) . SMP/E control statement that removes SYSMODs from the PTS data set and deletes any temporary libraries that SMP/E may have allocated when the SYSMOD was received (RELfiles). If the SELECT or EXCLUDE option is not coded on the REJECT control statement, all SYSMODs not applied or accepted are removed from the PTS. This is called a **mass rejection**. All other SYSMOD processing functions (RECEIVE, APPLY, RESTORE, and ACCEPT) can have SELECT or EXCLUDE specified, or may default to mass-processing mode.

RESTORE (function of SMP/E) . SMP/E control statement that removes SYSMODs from the target system libraries after they have been applied, and restores the target libraries to their status prior to application of the SYSMODs. If necessary, RESTORE reconstructs the target zone entries from the SCDS. If you select “mass restore”, **all** SYSMODs that have been applied but not accepted are removed from the target libraries.

SYSMOD (system modification) . An IBM-supplied product (function SYSMOD). An IBM-supplied preventive service (PTF). An IBM-supplied corrective service (APAR). A user-supplied modification (USERMOD).

Target zone . Describes the structure and contents of a set of target system libraries.

UCLIN (function of SMP/E) . SMP/E control statement that can be used to manipulate the various data sets that make up the SMP/E data base. The most common use of this function is to initialize the SMP/E database before the first attempt to use it. For CICS, this initialization is performed during installation, when DFHINST4 is run.

USERMOD (user modification) . User-supplied modifications to elements of IBM-supplied function SYSMODs. USERMODs are similar to APAR fixes, but are supplied by the user and not by IBM. They may be:

- A local fix to bypass a problem until an official IBM fix is available
- A user modification to add or alter function within CICS

The decision to modify CICS, either to add or to alter function, should be taken with caution, because it greatly increases the amount of research you must do before installing PTFs, and may also increase the installation time for PTFs. Furthermore, USERMODS will cause difficulty when you want to install future release of CICS.

Bibliography

The CICS Transaction Server for z/OS library

The published information for CICS Transaction Server for z/OS is delivered in the following forms:

The CICS Transaction Server for z/OS Information Center

The CICS Transaction Server for z/OS Information Center is the primary source of user information for CICS Transaction Server. The Information Center contains:

- Information for CICS Transaction Server in HTML format.
- Licensed and unlicensed CICS Transaction Server books provided as Adobe Portable Document Format (PDF) files. You can use these files to print hardcopy of the books. For more information, see “PDF-only books.”
- Information for related products in HTML format and PDF files.

One copy of the CICS Information Center, on a CD-ROM, is provided automatically with the product. Further copies can be ordered, at no additional charge, by specifying the Information Center feature number, 7014.

Licensed documentation is available only to licensees of the product. A version of the Information Center that contains only unlicensed information is available through the publications ordering system, order number SK3T-6945.

Entitlement hardcopy books

The following essential publications, in hardcopy form, are provided automatically with the product. For more information, see “The entitlement set.”

The entitlement set

The entitlement set comprises the following hardcopy books, which are provided automatically when you order CICS Transaction Server for z/OS, Version 3 Release 1:

Memo to Licensees, GI10-2559
CICS Transaction Server for z/OS Program Directory, GI10-2586
CICS Transaction Server for z/OS Release Guide, GC34-6421
CICS Transaction Server for z/OS Installation Guide, GC34-6426
CICS Transaction Server for z/OS Licensed Program Specification, GC34-6608

You can order further copies of the following books in the entitlement set, using the order number quoted above:

CICS Transaction Server for z/OS Release Guide
CICS Transaction Server for z/OS Installation Guide
CICS Transaction Server for z/OS Licensed Program Specification

PDF-only books

The following books are available in the CICS Information Center as Adobe Portable Document Format (PDF) files:

CICS books for CICS Transaction Server for z/OS

General

CICS Transaction Server for z/OS Program Directory, GI10-2586
CICS Transaction Server for z/OS Release Guide, GC34-6421
CICS Transaction Server for z/OS Migration from CICS TS Version 2.3, GC34-6425

CICS Transaction Server for z/OS Migration from CICS TS Version 1.3,
GC34-6423

CICS Transaction Server for z/OS Migration from CICS TS Version 2.2,
GC34-6424

CICS Transaction Server for z/OS Installation Guide, GC34-6426

Administration

CICS System Definition Guide, SC34-6428

CICS Customization Guide, SC34-6429

CICS Resource Definition Guide, SC34-6430

CICS Operations and Utilities Guide, SC34-6431

CICS Supplied Transactions, SC34-6432

Programming

CICS Application Programming Guide, SC34-6433

CICS Application Programming Reference, SC34-6434

CICS System Programming Reference, SC34-6435

CICS Front End Programming Interface User's Guide, SC34-6436

CICS C++ OO Class Libraries, SC34-6437

CICS Distributed Transaction Programming Guide, SC34-6438

CICS Business Transaction Services, SC34-6439

Java Applications in CICS, SC34-6440

JCICS Class Reference, SC34-6001

Diagnosis

CICS Problem Determination Guide, SC34-6441

CICS Messages and Codes, GC34-6442

CICS Diagnosis Reference, GC34-6899

CICS Data Areas, GC34-6902

CICS Trace Entries, SC34-6443

CICS Supplementary Data Areas, GC34-6905

Communication

CICS Intercommunication Guide, SC34-6448

CICS External Interfaces Guide, SC34-6449

CICS Internet Guide, SC34-6450

Special topics

CICS Recovery and Restart Guide, SC34-6451

CICS Performance Guide, SC34-6452

CICS IMS Database Control Guide, SC34-6453

CICS RACF Security Guide, SC34-6454

CICS Shared Data Tables Guide, SC34-6455

CICS DB2 Guide, SC34-6457

CICS Debugging Tools Interfaces Reference, GC34-6908

CICSplex SM books for CICS Transaction Server for z/OS

General

CICSplex SM Concepts and Planning, SC34-6459

CICSplex SM User Interface Guide, SC34-6460

CICSplex SM Web User Interface Guide, SC34-6461

Administration and Management

CICSplex SM Administration, SC34-6462

CICSplex SM Operations Views Reference, SC34-6463

CICSplex SM Monitor Views Reference, SC34-6464

CICSplex SM Managing Workloads, SC34-6465

CICSplex SM Managing Resource Usage, SC34-6466

CICSplex SM Managing Business Applications, SC34-6467

Programming

CICSplex SM Application Programming Guide, SC34-6468

CICSplex SM Application Programming Reference, SC34-6469

Diagnosis

CICSplex SM Resource Tables Reference, SC34-6470
CICSplex SM Messages and Codes, GC34-6471
CICSplex SM Problem Determination, GC34-6472

CICS family books

Communication

CICS Family: Interproduct Communication, SC34-6473
CICS Family: Communicating from CICS on System/390, SC34-6474

Licensed publications

The following licensed publications are not included in the unlicensed version of the Information Center:

CICS Diagnosis Reference, GC34-6899
CICS Data Areas, GC34-6902
CICS Supplementary Data Areas, GC34-6905
CICS Debugging Tools Interfaces Reference, GC34-6908

Other CICS books

The following publications contain further information about CICS, but are not provided as part of CICS Transaction Server for z/OS, Version 3 Release 1.

<i>Designing and Programming CICS Applications</i>	SR23-9692
<i>CICS Application Migration Aid Guide</i>	SC33-0768
<i>CICS Family: API Structure</i>	SC33-1007
<i>CICS Family: Client/Server Programming</i>	SC33-1435
<i>CICS Transaction Gateway for z/OS Administration</i>	SC34-5528
<i>CICS Family: General Information</i>	GC33-0155
<i>CICS 4.1 Sample Applications Guide</i>	SC33-1173
<i>CICS/ESA 3.3 XRF Guide</i>	SC33-0661

Books from related libraries

Systems Network Architecture (SNA)

- *z/OS Communications Server: SNA Network Implementation*, SC31-8777
- *z/OS Communications Server: SNA Resource Definition Reference*, SC31-8778
- *Systems Network Architecture - Function Description of Logical Unit Types*, GC20-1868
- *Systems Network Architecture - Types of Logical Unit to Logical Unit Sessions*, GC20-1869.

Advanced communications function for VTAM (ACF/VTAM)

- *Network Program Products General Information*, GC30-3350
- *Advanced Communications Function for VTAM Installation and Resource Definition*, SC23-0111
- *Advanced Communications Function for VTAM Customization*, SC23-0112
- *Advanced Communications Function for VTAM Operation*, SC23-0113
- *Advanced Communications Function for VTAM Messages and Codes*, SC23-0114
- *Advanced Communications Function for VTAM Diagnosis Guide*, SC23-0116
- *Advanced Communications Function for VTAM Diagnosis Reference*, LY30-5582

- *Advanced Communications Function for VTAM Data Areas*, LY30-5584
- *Advanced Communications Function for VTAM Programming*, SC23-0115
- *Advanced Communications Function for VTAM Reference Summary*, SC23-0135.

NetView Version 3.1

- *NetView User's Guide*, SC31-8056
- *NetView Installation and Administration Guide*, SC31-8043
- *NetView Installation and Administration and Security Reference*, SC31-8045
- *NetView Customization Guide*, SC31-8052
- *NetView Customization: Writing Command Lists*, SC31-8055
- *NetView Automation Planning*, SC31-8051
- *NetView Automation Implementation*, SC31-8050
- *NetView RODM and GMFHS Programming Guide*, SC31-8049
- *NetView Messages*, SC31-8046

NetView MultiSystem Manager Version 2.2

- *MultiSystem Manager: Open Topology Interface*, SC31-8144
- *MultiSystem Manager: Lovell NetWare Networks Open Topology Interface*, SC31-8129
- *MultiSystem Manager: OS/2 LAN Network Manager Networks*, SC31-8130
- *MultiSystem Manager: Internet Protocol Networks*, SC31-8131

DATABASE 2 (DB2)

- *IBM DATABASE 2 Administration Guide*, SC26-4888
- *IBM DATABASE 2 Application Programming and SQL Guide*, SC26-4889
- *IBM DATABASE 2 Command and Utility Reference*, SC26-4891.

eNetwork Communications Server for OS/2 Warp, Version 5

- *Quick Beginnings*, GC31-8189

Virtual Storage Access Method (VSAM)

- *MVS/ESA Access Method Services Reference for VSAM Catalogs*, GC26-4075
- *MVS/ESA VSAM Administration Guide*, GC26-4151
- *MVS/ESA Catalog User's Guide*, GC26-4041.

Resource Access Control Facility (RACF)

- *Resource Access Control Facility (RACF): General Information*, GC28-0722
- *System Programming Library: Resource Access Control Facility (RACF)*, SC28-1343
- *z/OS Security Server RACF Command Language Reference*, SA22-7687
- *Resource Access Control Facility (RACF) Security Administrators Guide*, SC28-1340.

System Modification Program Extended (SMP/E)

- *System Modification Program Extended: User's Guide*, SC28-1302
- *System Modification Program Extended: (SMP/E) Terminal User's Guide*, SC28-1109

- *System Modification Program Extended: General Information*, GC28-1106
- *System Modification Program Extended: Reference*, SC28-1107.

Sysplex planning

- *System/390 MVS Sysplex Application Migration*, GC28-1211

DFSMS/MVS

- *z/OS DFSMSdfp Storage Administration Reference*, SC26-7402
- *DFSMS/MVS Access Method Services for ICF*, SC26-4906

MVS

- *z/OS MVS Programming: Assembler Services Guide*, SA22-7605
- *z/OS MVS Programming: Assembler Services Reference, Volume 1*, SA22-7606
- *z/OS MVS Programming: Assembler Services Reference, Volume 2*, SA22-7607
- *z/OS MVS Setting Up a Sysplex*, SA22-7625.
- *z/OS MVS Using the Subsystem Interface*, SA22-7642.
- *z/OS MVS Installation Exits*, SA22-7593.
- *z/OS MVS Programming: Authorized Assembler Services Reference Vol 1*, SA22-7609
- *z/OS MVS Programming: Authorized Assembler Services Reference Vol 2*, SA22-7610
- *z/OS MVS Programming: Authorized Assembler Services Reference Vol 3*, SA22-7611
- *z/OS MVS Programming: Authorized Assembler Services Reference Vol 4*, SA22-7612
- *z/OS MVS Planning: Workload Management*, SA22-7602.
- *z/OS MVS Initialization and Tuning Guide*, SA22-7591
- *z/OS MVS Initialization and Tuning Reference*, SA22-7592
- *z/OS MVS Routing and Descriptor Codes*, SA22-7624
- *z/OS Program Directory*, G110-6730
- *z/OS UNIX System Services Planning*, GA22-7800

Determining if a publication is current

IBM regularly updates its publications with new and changed information. When first published, both hardcopy and BookManager softcopy versions of a publication are usually in step. However, due to the time required to print and distribute hardcopy books, the BookManager version is more likely to have had last-minute changes made to it before publication.

Subsequent updates will probably be available in softcopy before they are available in hardcopy. This means that at any time from the availability of a release, softcopy versions should be regarded as the most up-to-date.

For CICS Transaction Server books, these softcopy updates appear regularly on the *Transaction Processing and Data Collection Kit* CD-ROM, SK2T-0730-xx. Each reissue of the collection kit is indicated by an updated order number suffix (the -xx part). For example, collection kit SK2T-0730-06 is more up-to-date than SK2T-0730-05. The collection kit is also clearly dated on the cover.

Updates to the softcopy are clearly marked by revision codes (usually a # character) to the left of the changes.

Accessibility

Accessibility features help a user who has a physical disability, such as restricted mobility or limited vision, to use software products successfully.

You can perform most tasks required to set up, run, and maintain your CICS system in one of these ways:

- using a 3270 emulator logged on to CICS
- using a 3270 emulator logged on to TSO
- using a 3270 emulator as an MVS system console

IBM Personal Communications provides 3270 emulation with accessibility features for people with disabilities. You can use this product to provide the accessibility features you need in your CICS system.

Index

Special characters

&CICS_DIRECTORY symbol
HFS subdirectory 207
&JAVA_HOME
HFS Java subdirectory 207

A

ACB (VTAM), authorizing the region userid to open 70
ACBNAME, parameter of VTAM APPL statement 100
ACBNAME, VTAM APPL statement parameter
CAS 291
CMAS 294
ACCEPT, function of SMP/E 46, 179, 465
accessibility options 354
ACCTFILE, primer sample application accounts data
set 194
ACIXFILE, primer sample application index data
set 194
activating real-time analysis
VTAM definitions
for CAS 293
for CMAS 296
ADDTVOL, parameter of DFHISTAR 35
ADFHAPD1 distribution library 25
ADFHAPD2 distribution library 25
ADFH370 elements 25
ADFHCLIB distribution library 25
ADFHCOB elements 25
ADFHINST distribution library 25
ADFHMAC distribution library 25
ADFHMLIB distribution library 25
ADFHMOD distribution library 25
ADFHMSGS distribution library 25
ADFHMSRC distribution library 25
ADFHPPARM distribution library 25
ADFHPL1 elements 25
ADFHPROC distribution library 25
ADFHSAAMP distribution library 25
AINDEX, parameter of DFHISTAR 34
alerts to NetView
preparing NetView to receive 322
ALINDEX, parameter of DFHISTAR 34
allocating
distribution and target libraries 44
RELFILE data sets 44
SMP/E data sets 45
allocating libraries for IPCS 402
APAR (authorized program analysis report) 465
APAR fixes 179, 180
APF (authorized program facility) 67
APF, authorized program facility 56
APF, MVS initialization parameter
IEASYSxx value 281
APPC parameter, VTAM APPL statement 294
APPL statement
CAS 291, 294

APPL statement (*continued*)
CMAS 294
Application Migration Aid
element in CICS TS 6
application programming interface (API)
installing REXX function package 285
preparing for 284
APPLID
accessing from several MVS images 101
notifying VTAM of the CICS APPLID 244
using for VTAM logon 249
APPLY, function of SMP/E 46, 179, 465
applying service
supplied SMP/E procedure 371
applying service to CICS 179
corequisite fixes 180
servicing the CICS messages data set 182
ASMHCL exec, to create an MVS nucleus module list
for CICS 98
ASMPPTS, parameter of DFHISTAR 35
ASMPMPTS, parameter of DFHISTAR 34
ASMPSCDS, parameter of DFHISTAR 34
ASMPSTS, parameter of DFHISTAR 35
ASREXIT 133
ATCCONxx, VTAM list member 296
ATCSTRxx, VTAM list member 296
attributes for SMP/E data sets 28, 29
AUTH, parameter of VTAM APPL statement 100
AUTH, VTAM APPL statement parameter
CAS 291
CMAS 294
authorized libraries 67
authorized program analysis report (APAR) 465
authorized program facility (APF) 56, 67
authorizing CICS31.CICS.SDFHAUTH 56
authorizing hlq.SDFHAUTH 67
authorizing hlq.SDFJAUTH 210
authorizing SYS1.PARMLIB libraries 283
automated-operation programs
message formatting coexistence considerations 90
automatic installation of terminals 242, 243
AUTOREFRESH 351
AUTORESETTIME 343
auxiliary storage usage 321
auxiliary trace (A) data set, DFHAUXT
creating for a CICS region 192
DD statement in IVP startup procedure 233
auxiliary trace (B) data set, DFHBUXT
creating for a CICS region 192
DD statement in IVP startup procedure 233
AUXTR 343
AZONE, parameter of DFHISTAR 34
AZONECSI, parameter of DFHISTAR 34
AZONELOG, parameter of DFHISTAR 34

B

backing up the data repository 304

- base elements
 - list of 6
- BBACTDEF DD statement
 - with CAS startup JCL 316
 - with CMAS startup JCL 325
- BBIPARM DD statement
 - with CAS startup 316
- BBM9ZA00 program for CAS startup 316
- BBSECURE DD statement
 - with CAS startup 316
- BBVDEF DD statement
 - with CAS startup JCL 316
 - with CMAS startup JCL 325
- BLKFB80 parameter of the DFHISTAR job 24
- BLKISPF parameter of the DFHISTAR job 24
- BLKU parameter of the DFHISTAR job 24
- block sizes for data sets 24
 - block sizes for 24
- BLSCECT
 - updating 401
- browser connection 359

C

- cache sets, VSAM RLS 136
- CAS
 - create data sets 299
 - define VTAM requirements 289
 - activate the major nodes 293
 - create a mode table 289
 - create a VTAM application 291
 - define cross-domain resources 291, 292
 - define information to CICSplex SM 318
 - update the configuration list 292
 - generate post-installation jobs 297
 - JCL requirements
 - BBACTDEF 316
 - BBIPARM 316
 - BBVDEF 316
 - CAS EXEC 316
 - EYUCAS 315
 - STEPLIB 316
 - prepare to start 315
 - prepare user access to CICSplex SM 313
 - start command 316
- CAS (coordinating address space)
 - cross-domain resources 292
- CAS-related data sets
 - parameter repository 299
 - screen repository 299
- CASNAME system parameter 386
- catalogs
 - distribution and target libraries 44
- category 1 transactions
 - authorizing the region userid 57
- category 1 transactions, authorizing the region
userid 71
- CBPDO method of installing
 - compared with ServerPac 5
 - description of 5
- CDRSC
 - CAS-update configuration 292
 - CMAS-update configuration 296
 - create or access member 292
 - in SYS1.VTAMLST library 294, 295
 - defining 295
 - CDRSCT1, parameter of VTAM START command 102
 - CDS (control data set), saved 30
 - CEDA transaction 252
 - installing the CICS sample programs 253
 - CEECCICS, Language Environment interface
module 201
 - CEEMSG, transient data destination, Language
Environment 202
 - CEEOUT, transient data destination, Language
Environment 202
 - CESE, transient data destination, Language
Environment 202
 - CESO, transient data destination, Language
Environment 202
 - checklists for setup
 - CAS 272
 - CMAS 272
 - MVS MAS 272
 - overview 271
 - CHS 344
 - CHS1 344
 - CHS2 344
 - CICS
 - element in CICS TS 6
 - CICS Clients
 - element in CICS TS 6
 - CICS Distributed Data Manager (DDM)
 - element in CICS TS 6
 - CICS Information Center
 - installing and configuring 61
 - CICS libraries
 - authorizing 56, 67
 - SMP/E function ACCEPT (DFHINST6) 46
 - CICS Monitoring Facility (CMF) 337
 - CICS SIT parameters 383
 - CMAS-related 326
 - MVS MAS-related 336
 - CICS Sockets 216
 - CICS storage in a CMAS 329
 - CICS SVCs, installing DFHC SVC in the LPA 108
 - CICS system definition (CSD) files
 - updating 307, 311
 - CICS system definition data set, DFHCSD 242
 - creating for all CICS regions 191
 - DD statement in IVP startup procedure 234
 - requirements for autoinstall 242
 - CICS system initialization parameters 343
 - AUTORESETTIME 343
 - AUXTR 343
 - CPSMCONN 343
 - CWAKEY 343
 - INITPARM
 - EYU9VKEC 344
 - EYU9VWAN 344
 - SYSTR 343

CICS system initialization parameters *(continued)*
 USERTR 343
 WRKAREA 343
 CICS Transaction Gateway
 element in CICS TS 7
 CICS Transaction Server libraries
 creating multiple sets 50
 target libraries 26
 CICS Transaction Server-supplied procedures, copying
 into a 48
 CICS TS
 DASD storage requirements 11
 description of optional features 6
 description of what is shipped 4
 installing 7, 9, 17
 introduction 3
 post installation steps 55
 required software and hardware 9
 CICS Web Interface Feature for MVS/ESA
 element in CICS TS 6
 CICS Web support 342
 CICS-supplied transactions in interactive IVP
 from a terminal 250
 CICSplex SM
 element in CICS TS 6
 CICSplex system parameter 386
 CICSplex SM address space (CMAS)
 add CICS system definitions 300
 CICS SIT parameters 326, 383
 create data repository 299
 define VTAM requirements 293
 activate the major nodes 296
 define APPL statement 294
 define cross-domain resources 294, 295
 define information to CICSplex 330
 update configuration list 296
 journalmodel considerations 308
 preparing for API 284
 restarting 331
 shared CSD 309
 START command for a CMAS 330
 start ESSS 284
 starting
 as a batch job 323
 from the system console 323
 update CICS tables 307
 update CSD using DFHCSDUP 307
 update IEASYSxx 282
 upgrade CSD release 309
 CICSplex SM Starter Set
 creating environment 364
 defining environment 365
 deleting 368
 naming convention 363
 sample libraries 361
 selecting configuration 364
 starting components 365
 using as a model 368
 CMAC, CICS messages facility
 DD statement in IVP startup procedure 233
 defining resources needed 193
 CMAC, CICS messages facility *(continued)*
 defining the messages data set, DFHCMACD 193
 messages data set, DFHCMACD 233
 resources needed to use with the IVP jobs 232
 servicing the messages data set, DFHCMACD 182
 CMACVOL parameter of the DFHISTAR job 27
 CMAS 342
 CMAS (CICSplex SM address space)
 controlling CICS storage 329
 controlling tasks 328
 CMAS (CICSplex SM address space)
 add CICS system definitions 300
 CICS SIT parameters 326, 383
 create data repository 299
 define VTAM requirements 293
 activate the major nodes 296
 define APPL statement 294
 define cross-domain resources 294, 295
 define information to CICSplex 330
 update configuration list 296
 journalmodel considerations 308
 preparing for API 284
 restarting 331
 shared CSD 309
 START command for a CMAS 330
 start ESSS 284
 starting
 as a batch job 323
 from the system console 323
 update CICS tables 307
 update CSD using DFHCSDUP 307
 update IEASYSxx 282
 upgrade CSD release 309
 CMAS journaling 397
 CMAS-related data sets 299
 CMAS-related post installation jobs
 local MAS 297
 CMAS-specific JCL requirements
 BBACTDEF 325
 BBVDEF 325
 CICS EXEC 324
 DFHRPL 325
 EYUCMAS 324
 EYUDREP 325
 EYULOG 325
 EYUPARM 325
 STEPLIB 325
 CMASNAME parameter of EYU9XDUT 301
 CMASYSID system parameter 386
 CMD, MVS initialization parameter
 IEASYSxx value 281
 COBOL under Language Environment 203
 codepage 344
 CHS1 344
 CHS2 344
 ENU1 344
 JPN1 344
 codepage conversion table 345
 coexistence considerations
 automated-operation programs 90
 releases of CICS before this release 90

COIRTASKPRI system parameter 387
COLG 356
color of screens 354
COLORINK 354
COLORINKBANNER 354
COLORINKLINK 354
COLORINKVLINK 354
COLORPAPER 354
COLORPAPERALT 354
COLORPAPERERROR 354
COLORPAPERHEAVY 354
COLORPAPERLIGHT 354
COLORPAPERRULE 354
COLORPAPERWARN 354
COMMNDaa, operator commands member
 for CAS 315
 for CMAS 323
common CICS data sets, creating (DFHCOMDS
job) 191
communications
 CAS-to-CAS
 defining cross-domain resources 292
 CMAS-to-CMAS
 defining cross-domain resources 295
configuration views
 defining CMAS-to-CMAS links 330
console device for the IVP jobs
 defining a TSO user 245
 definition 241
 using transactions 253
CONSOLE macro 141
console message formatting
 activating 89
 default initialization parameters 88
 defining CICS as an MVS subsystem 57, 83
 modules needed 89
console messages 141
console support
 defining a TSO user as a console 245
 TSO CLIST processing 254
consolidated software inventory (CSI) 31, 465
converting the data repository 302
coordinating address space (CAS)
 create data sets 299
 cross-domain resources 292
 define VTAM requirements 289
 activate the major nodes 293
 create a mode table 289
 create a VTAM application 291
 define cross-domain resources 291, 292
 define information to CICSplex SM 318
 update the configuration list 292
 generate post-installation jobs 297
 JCL requirements
 BBACTDEF 316
 BBIPARM 316
 BBVDEF 316
 CAS EXEC 316
 EYUCAS 315
 STEPLIB 316
 prepare to start 315
 coordinating address space (CAS) (continued)
 prepare user access to CICSplex SM 313
 start command 316
COSD transaction 331
coupling facility 143
 definition 152
 recommendations 151
 structures 152
coupling facility cache structures, VSAM RLS 135
coupling facility lock structure, VSAM RLS 135
coupling facility sizing utility, DFHLSCU 160
COUT, transient data extrapartition data set
 DD statement in IVP startup procedure 234
COVA 358
COVC 358, 359
COVE 356, 358
COVG 358
COVI 356
COVP 356, 358
COVU 358
CPSM310.EYUDREP
 converting the data repository 302
 creating the data repository 300
 in CMAS startup JCL 325
 storing CMAS-to-CMAS link definitions 330
CPSM310.EYUIPRM data set
 creating parameter repository 299
 in CAS startup JCL 299
 storing CMAS-to-CMAS link definitions 330
CPSM310.SEYUDEF
 in CAS startup JCL 315
 in CMAS startup JCL 324
CPSM310.SEYUAUTH
 authorizing 283
 in CAS startup JCL 316
 in CMAS startup JCL 325
 in MAS startup JCL 335
CPSM310.SEYUINST 381
CPSM310.SEYUJCL
 JCL for creating Starter Set 361
 JCL for running Starter Set 362
 JCL for Starter Set environment 362
CPSM310.SEYULOAD
 in CMAS startup JCL 325
 in MAS startup JCL 335
 resource definition 307
CPSM310.SEYUPARM 315
CPSM310.SEYUSAMP
 EYUJCLGN 311
 EYUJCLMT 290, 293
 EYUSMPMT 290
CPSM310.SEYUVDEF
 in CAS startup JCL 315
 in CMAS startup JCL 324
CPSM310.TEYUINST
 members
 EYUCAS 297
 EYUCMAS 297
 EYUDEFDS 297
 EYUDFHDS 297
 EYULPMOD 297

CPSM310.TEYUINST (*continued*)
 members (*continued*)
 EYUSMPE 297
 EYUTSODS 313
 tailoring EYUISTAR 297
 CMAS-related parameters 299
 MAS-related parameters 299
 CPSM310.XEYUINST 371
 CPSMCONN 343
 creating CICS system definition
 data repository 299
 creating CICSplex SM data sets 299
 creating mode table 289
 creating VTAM application definition 291
 CRELEASE system parameter 376
 cross system locking, VSAM RLS 135
 cross-domain resources (CDRSC)
 CAS-update configuration 292
 CMAS-update configuration 296
 create or access member 292
 in SYS1.VTAMLST library 294, 295
 defining 295
 cross-system coupling facility (XCF)
 used for interregion communication 211
 CSD 355
 CSD files
 updating 307, 311
 CSI (consolidated software inventory) 31, 465
 CSNE transient data destination 101
 CSSLIB parameter of the DFHISTAR job 35
 customizable view and menu help 346
 customizable view and menu help data set 346
 customizing CICS
 adding ISC support 213
 installing CICS modules in MVS link pack area 107
 using HPO support 58, 97
 CVDASTYLE 349
 CWAKEY 343

D

DASD storage requirements
 for CICS TS 11
 DASD-only logging
 recommendations 167
 data repository
 backing up 304
 converting 302
 creating 299
 defining forward recovery log for 304
 expanding 304
 for each CMAS 299
 identified in CMAS startup JCL 325
 data sets 24
 RELFILE, allocating 44
 data sets (non-SMP/E), assigning a high-level
 index 33
 data sets for CICS 189
 common to all regions, creating (DFHCOMDS
 job) 191

data sets for CICS (*continued*)
 unique to each region, creating (DFHDEFDS
 job) 192
 DATEFORMAT 350
 DATESEPARATOR 350
 DAYLIGHT parameter of EYU9XDUT 301
 DBCTL
 installation verification procedure (IVP) 262
 debugging profiles alternate index data set, DFHDPFMP
 creating for each CICS region 192
 debugging profiles base data set, DFHDPFMB
 creating for each CICS region 192
 debugging profiles path data set, DFHDPFMP
 creating for each CICS region 192
 DECIMALSEPARATOR 350
 Default CICS userid, defining to RACF 77
 default EXCI pipe allocation limit 91
 DEFAULTCICSPLEX 352
 DEFAULTCICSRGN 352
 DEFAULTCMASCTXT 351
 DEFAULTCONNECT 352
 DEFAULTCONTEXT 351
 DEFAULTCSYSGRP 352
 DEFAULTDB2SS 352
 DEFAULTEJCOBEAN 352
 DEFAULTEJDJBEAN 352
 DEFAULTEVENT 352
 DEFAULTLOCFILE 352
 DEFAULTLOCTRAN 352
 DEFAULTMAPCOLL 351
 DEFAULTMENU 351
 DEFAULTNAVIGATE 351
 DEFAULTPROGRAM 352
 DEFAULTTREMFILE 353
 DEFAULTTREMTRAN 353
 DEFAULTSCOPE 351
 DEFAULTTASK 353
 DEFAULTWARNCNT 351
 defining a terminal for online IVP 242
 defining cross-domain resources 292
 Defining the hlq.SDFHLPA library to your MVS 111
 defining VTAM information to CICSplex SM 318
 DEFVOL parameter of the DFHISTAR job 25
 DFH\$AFLA CSD group, FILEA sample programs 253
 DFH\$BTCH, input to the verify batch job 234
 DFH\$FILA CSD group, FILEA sample data set 253
 DFH\$SIP2 member of SYSIN data set 231
 DFH\$SIPn members of SYSIN data set, for IVP
 jobs 231
 DFHASMVS, CICS Transaction Server-supplied
 procedure 48
 DFHAUPLE, CICS Transaction Server-supplied
 procedure 48
 DFHAUXT data set, auxiliary trace
 creating for a CICS region 192
 DD statement in IVP startup procedure 233
 DFHBMSU, CICS Transaction Server-supplied
 procedure 48
 DFHBUXT data set, auxiliary trace
 creating for a CICS region 192
 DD statement in IVP startup procedure 233

DFHCMACD, messages data set 182, 193
 defining associated CICS resources 193

DFHCMACI, job to create and initialize the messages
 data set 193

DFHCNV 345

DFHCOMDS, job to create common CICS data
 sets 191

DFHCSD data set, CICS system definition 242
 creating for all CICS regions 191
 DD statement in IVP startup procedure 234
 requirements for autoinstall 242

DFHCSDUP requirements
 DFHCSD 308, 311
 STEPLIB 308, 311
 SYSIN 308, 311

DFHCSVC, CICS Type 3 SVC 108
 installing in the LPA 108

DFHCSVC, the CICS type 3 SVC
 correct-level check 58, 93
 defining to MVS 93
 installing 57, 93
 using for MRO between different CICS releases 95
 using more than one version 94

DFHCTAIX, sample application alternate index 194

DFHCTCUS, sample application details data set 194

DFHCTHLP, sample application help data set 194

DFHCXRF, transient data extrapartition data set
 DD statement in IVP startup procedure 233
 local request queue data set 234

DFHDEFDS, job to create data sets for each
 region 192

DFHDLI user exits
 XDLIPOST 199
 XDLIPRE 199

DFHDLPSB TYPE=ENTRY macro (remote DL/I) 198

DFHDMPA data set, dump
 creating for a CICS region 192
 DD statement in IVP startup procedure 234

DFHDMPB data set, dump
 creating for a CICS region 192
 DD statement in IVP startup procedure 234

DFHDPFMB debugging profiles alternate index data set
 creating for each CICS region 192

DFHDPFMB debugging profiles base data set
 creating for each CICS region 192

DFHDPFMB debugging profiles path data set
 creating for each CICS region 192

DFHDSPEX, CICS post exit stub 108
 installing in the LPA 108

DFHEBTAL, CICS Transaction Server-supplied
 procedure 48

DFHEITAL, CICS Transaction Server-supplied
 procedure 48

DFHEXTAL, CICS Transaction Server-supplied
 procedure 48

DFHGCD data set, global catalog
 creating for a CICS region 192
 DD statement in IVP startup procedure 233

DFHHPSVC, VTAM authorized path SVC
 defining to MVS 93, 97
 loading into the MVS nucleus 97

DFHHTML 346, 356, 358
 DFHHTML data set for HTML templates
 creating for a CICS region 192

DFHINST1, installation job 44

DFHINST2, installation job 44

DFHINST3, installation job 45

DFHINST4, installation job 46

DFHINST5, installation job 46

DFHINST6, installation job 46

DFHINSTA
 submitting 52

DFHINTRA data set, intapartition transient data
 creating for a CICS region 192
 DD statement in IVP startup procedure 233

DFHIRP, interregion communication program 108
 installing in the LPA 108
 MRO requirement 212

DFHISMKD, installation job 44

DFHISTAR
 editing 51
 submitting 51

DFHISTAR, creating post-installation jobs 186

DFHISTAR, job to define installation-related jobs 20
 BLKFB80 parameter 24
 BLKISPF parameter 24
 BLKU parameter 24
 CMACVOL parameter 27
 CSSLIB parameter 35
 DEFVOL parameter 25
 DINDEX parameter 22
 DISTVOL parameter 25
 DSINFO parameter 33
 DZONE parameter 32
 DZONECSI parameter 31
 DZONELOG parameter 30
 GINDEX parameter 22
 GZONE parameter 32
 GZONECSI parameter 31
 GZONELOG parameter 30
 JAVADIR parameter 37
 JES parameter 21
 JOB parameter 20
 LIB parameter 20
 LINDEX parameter 22
 LOGGER-INFO parameter 38
 OPTVOL parameter 26
 parameter default values 18
 PREFIX parameter 22
 SCEEBND2 dsname 38
 SCEECICS dsname 38
 SCEECPP parameter 36
 SCEELIB dsname 38
 SCEELKED parameter 36
 SCEELKEX parameter 36
 SCEEOBJ parameter 36
 SCEERUN dsname 38
 SCEERUN2 dsname 38
 SCEESAM parameter 36
 SCLBSID parameter 36
 SCOPE parameter 21, 40
 SCSQAU parameter 37

DFHISTAR, job to define installation-related jobs
(*continued*)

- SCSQCI parameter 37
- SCSQL parameter 36
- SCSQLE parameter 37
- SEZACMTX dsname 38
- SEZARPCL dsname 38
- SISLOAD parameter 35
- SMP/E zone and zone log dispositions 32
- SMPLOTS parameter 30
- SMPMTS parameter 29
- SMPPTS parameter 29
- SMPSCDS parameter 30
- SMPSTS parameter 29
- SMPVOL parameter 26
- SMPWORK parameter 29
- SMS parameter 25
- TAPEUNIT parameter 33
- TARGVOL parameter 26
- TEMPLIB parameter 20
- TINDEX parameter 22
- TZONE parameter 32
- TZONECSI parameter 31
- TZONELOG parameter 30
- UTILITIES parameter 21
- WORKUNIT parameter 24

DFHIVPBT, batch IVP 227, 234

- DFH\$BTCH input 234
- expected output 238
- system initialization parameters 231

DFHIVPOL, interactive IVP 227, 241

- CICS-supplied transactions 250
- sample programs 253
- terminating CICS 255
- transactions 253

DFHLCD data set, CICS local catalog

- creating for each CICS region 192
- DD statement in IVP startup procedure 233

DFHLNKVS, CICS Transaction Server-supplied procedure 48

DFHLSCU, log stream sizing utility 160, 171

DFHMAPS, CICS Transaction Server-supplied procedure 48

DFHMAPT, CICS Transaction Server-supplied procedure 48

DFHRPL (dynamic transaction routing exit)

- in CMAS startup JCL 325
- in MAS startup JCL 335

DFHSIP, CICS initialization program 242

DFHSMPE, cataloged procedure 179

DFHSMPE, CICS Transaction Server-supplied procedure 48

DFHSSEN, subsystem interface end-of-memory / end-of-task clean up routine 108

- installing in the LPA 108

DFHSSlly, initialization member 91

DFHSSlly, message-formatting initialization member 87

DFHSTART, CICS startup procedure 232

DFHSTART, CICS Transaction Server-supplied procedure 48

DFHTEMP data set, temporary storage

- creating for each CICS region 192
- DD statement in IVP startup procedure 233

DFHUPDVS, CICS Transaction Server-supplied procedure 48

DFHYBTPL, CICS Transaction Server-supplied procedure 48

DFHYBTVL, CICS Transaction Server-supplied procedure 48

DFHYITDL, CICS Transaction Server-supplied procedure 49

DFHYITEL, CICS Transaction Server-supplied procedure 49

DFHYITPL, CICS Transaction Server-supplied procedure 49

DFHYITVL, CICS Transaction Server-supplied procedure 49

DFHYXTDL, CICS Transaction Server-supplied procedure 49

DFHYXTEL, CICS Transaction Server-supplied procedure 49

DFHYXTPL, CICS Transaction Server-supplied procedure 49

DFHYXTVL, CICS Transaction Server-supplied procedure 49

DFHZATDX, autoinstall user program 243

DFHZITCL, CICS Transaction Server-supplied procedure 49

DFHZITDL, CICS Transaction Server-supplied procedure 49

DFHZITEL, CICS Transaction Server-supplied procedure 49

DFHZITFL, CICS Transaction Server-supplied procedure 49

DFHZITGL, CICS Transaction Server-supplied procedure 49

DFHZITPL, CICS Transaction Server-supplied procedure 49

dfjejbpl 209

dfjjvmpr

- sample properties file 208

dfjjvmpr

- sample properties file 208

DFLTUSER SIT parameter

- for MVS MAS 336

DINDEX parameter of the DFHISTAR job 22

- dispositions, zone and zone log 32
- distribution libraries
 - allocating and cataloging 44
 - installing SYSMODs 465
 - SMP/E function ACCEPT (DFHINST6) 46
- distribution zone 465
- distribution zone (DZONE) 32
 - CSI 31
 - log 30

DISTVOL parameter of the DFHISTAR job 25

DL/I

- adding remote DL/I support 198
- database control (DBCTL) 197
- defining a PSB directory for remote DL/I support 198

DL/I (*continued*)
 DFHDLPSB TYPE=ENTRY (remote DL/I) 198
 function shipping 197
 global user exits 199
 MXSSASZ parameter (remote DL/I) 198
 requirements for remote database access 198
 system initialization parameters (remote DL/I) 198
 DNS 216
 DSINFO parameter of the DFHISTAR job 33
 dump (A) data set, DFHDMPA
 creating for a CICS region 192
 DD statement in IVP startup procedure 234
 dump (B) data set, DFHDMPB
 creating for a CICS region 192
 DD statement in IVP startup procedure 234
 dynamic LU alias 102
 LUAPFX parameter 100
 dynamic parse validation routines, installing 80
 DZONE parameter of the DFHISTAR job 32
 DZONECSI parameter of the DFHISTAR job 31
 DZONELOG parameter of the DFHISTAR job 30

E

EAS parameter, VTAM APPL statement 294
 EAS, parameter of VTAM APPL statement 100
 ECI 215
 elapsed time during installation of CICS Transaction
 Server 42
 elements in CICS TS
 Application Migration Aid 6
 CICS 6
 CICS Clients 6
 CICS Distributed Data Manager (DDM) 6
 CICSplex SM 6
 list of 4
 ONC RPC 6
 Web Interface 6
 ELPA (extended link pack area)
 eligible modules 109
 ENU 344
 ENU1 344
 Environment Services System Services (ESSS)
 adding to MVS linklist 284
 description of 284
 ENVIRONMENT, EYUINST EXEC parameter
 IMBED statements required in BLSCECT 401
 post-installation customization 297
 ESSS (Environment Services System Services)
 adding to MVS linklist 284
 description of 284
 exception trace 343
 EXCI Pipe Allocation 91
 EXCI pipe allocation limit 91
 exclusive element or feature
 description 4
 expanding the data repository 304
 extended recovery facility (XRF)
 sessions, HAVAIL, parameter of VTAM APPL 100
 EYU\$CNV1 345
 EYU9VKEC 344

EYU9VKIT 345
 EYU9VWAN 344
 EYU9XDUT 300
 EYU9XEES module 284
 EYUCAS job 297
 EYUCHS1 345
 EYUCHS2 345
 EYUCMAS job 297
 EYUCMS01
 CICS SIT parameters 326
 EYUCMS1A 351
 EYUCOVE 356, 358
 EYUCOVI 356, 358
 EYUDEFDS job 297
 EYUDEZZZ panel, defining ISPF option 313
 EYUDFHDS job 297
 EYUDREP data set
 converting the data repository 302
 creating the data repository 300
 in CMAS startup JCL 325
 storing CMAS-to-CMAS link definitions 330
 EYUENU1 345
 EYUHISTx 338
 EYUHISTx DD statement 335
 EYUIPRM data set
 CAS startup JCL 315
 creating parameter repository 299
 EYUISTAR
 CMASNAME parameter 300
 DSINFO 300
 EYUJPN1 345
 EYUJWREP 346
 EYULOG 356, 358
 EYULOG DD statement
 CMAS startup JCL 325
 EYULPMOD job 297
 EYUPARM DD statement
 in CMAS startup JCL 325
 in MAS startup JCL 335
 EYUPARM parameters
 description of 385
 summary of 383
 EYUPLX01 351
 EYUSMPE job 297
 EYUWREP 358
 EYUWREP (Web User Interface server
 repository) 346, 356
 EYUWUI 356, 358

F

features in CICS TS
 list of 4
 FILEA data set, sample program data
 creating for each CICS region 192
 DD statement in IVP startup procedure 233
 FILEA sample applications
 transactions used 228
 FMID, keyword of CICS SYSMODs 465
 FORMATMSG, parameter of DFHSSIyy 87
 forward recovery log for data repository 304

function shipping 197
Function SYSMOD 465

G

generating post-installation jobs 297
generic routecodes 88
gethostbyaddr function 216
GIMMPDFT modules, attributes of SMP/E data sets 28
GIMSP messages and control statements 47
GIMZPOOL, member of SYS1.MACLIB 45
GINDEX parameter of the DFHISTAR job 22
global catalog data set, DFHGCD
 creating for a CICS region 192
 DD statement in IVP startup procedure 233
global zone 465
global zone (GZONE) 32
 CSI 31
 log 30
GMMTEXTMSG 350
GRPLIST
 MVS MAS parameter 336
GZONE parameter of the DFHISTAR job 32
GZONECSI parameter of the DFHISTAR job 31
GZONELOG parameter of the DFHISTAR job 30

H

hardware requirements
 installing CICS TS 9
HAVAIL, parameter of VTAM APPL statement 100
help
 customizable view and menu help 346
HFS 10, 205
HFS0DSN parameter of the DFHISTAR job 23
HFS1DSN parameter of the DFHISTAR job 23
HFSADSN parameter of the DFHISTAR job
 HFSADSN parameter 23
HIDEPASSWORD, parameter of DFHSSlyy 87
high level qualifier 79
high-performance option (HPO) 93, 97
 defining the CICS SVCs to MVS 93
 DFHHPSVC, VTAM authorized path SVC 58, 97
 system initialization parameter 97
 VTAM authorized path, DFHHPSVC 97
history recording 338
HISTRECSMSG 338
hlq 79
hostname 344, 359
HTML template data set, DFHHTML
 creating for a CICS region 192
http 344, 359
HTTP 215

I

ICCFCC, CICS Transaction Server-supplied
 procedure 49
ICCFCL, CICS Transaction Server-supplied
 procedure 49

ICCFGL, CICS Transaction Server-supplied
 procedure 49
ICCFCL, CICS Transaction Server-supplied
 procedure 49
IEAAPFxx, MVS authorization member
 authorizing 283
IEASYSxx, MVS initialization member 83
 authorizing libraries 283
 establishing requirements 282
 noting values in 281
 updating
 for a CAS 282
 for a CMAS 282
IEFSSNaa, MVS subsystem initialization member 84
IEW0461 message from the binder 47
IEW2646 message from the binder 47
IEW2651 message from the binder 47
IIOPI 215
implementing MVS workload management 125
IMS, database control (DBCTL) 197
INACTIVETIMEOUT 353
initialize CAS 315
initialize CMAS 324
initialize data repository 300
initialize MVS MAS 334
INITPARM 344
 EYU9VKEC 344
 EYU9VWAN 344
installation
 of CICS sample programs 253
installation jobs
 elapsed time 42
 messages 47
 restarting 42
 running 42
installation libraries for CICSplex SM 374
installation verification procedure (IVP) 227
 applids, defining and activating 228
 auxiliary temporary storage data set,
 DFHTEMP 233
 auxiliary trace data set (A), DFHAUXT 233
 auxiliary trace data set (B), DFHBUXT 233
 batch IVP, DFHIVPBT 234
 CICS region definition data set 234
 CICS startup procedure, DFHSTART 232
 CMAC resources 232
 data sets for 227
 FILEA data set, sample application data 233
 global catalog data set, DFHGCD 233
 interactive IVP, DFHIVPOL 241
 defining a terminal for 242
 local catalog data set, DFHLCD 233
 messages data set, DFHMACD 233
 RACF userid authority 228
 required SVC for 228
 security considerations 229
 SYSIN data set 233
 system definition data set 234
 system initialization parameters 231
 transaction dump (A) data set, DFHDMPA 234
 transaction dump (B) data set, DFHDMPB 234

- installation verification procedure (IVP) *(continued)*
 - transient data extrapartition data set, COUT 234
 - transient data extrapartition data set, DFHCXRF 233
 - transient data extrapartition data set, DFHLRQ 234
 - transient data extrapartition data set, LOGUSR 234
 - transient data extrapartition data set, MSGUSR 234
 - transient data extrapartition data set, PLIMSG 234
 - transient data intrapartition data set, DFHINTRA 233
 - using the CEDA transaction 252
 - using transactions from console device 253
- installation verification procedures (IVPs)
 - installing CICSplex SM on first MVS image 409
 - installing CICSplex SM on second MVS image 425
 - overview 407
- installing CICS TS 7
- installing hlq.SDFJLPA 210
- installing Language Environment support 202
- installing module in link list 284
- Installing modules in the MVS link pack area 111, 112
- installing support for programming languages 201
- installing system
 - software requirements 10
- InstallShield
 - installing CICS Information Center 61
- interface modules
 - CEECICS 201
 - Language Environment 201
- interregion communication (IRC) 211
- intersystem communication (ISC)
 - installation considerations 213
- intrapartition transient data data set, DFHINTRA
 - creating for a CICS region 192
 - DD statement in IVP startup procedure 233
- IPCS tools
 - preparing to use 401
 - updating BLSCECT 401
 - updating library allocations 402
 - types of 401
- IPCSLIB data set for IPCS 402
- ISC (intersystem communication)
 - installation considerations 213
- ISMF control data set application, VSAM RLS 136
- ISMF storage class application 136
- ISPF, update primary menu 313
- ISPMLIB data set for IPCS 402
- ISPPLIB data set for IPCS 402
- ISPPLIB DD statement 313
- IVPs (installation verification procedures)
 - installing CICSplex SM on first MVS image 409
 - installing CICSplex SM on second MVS image 425
 - overview 407

J

- Java
 - components 205
 - HFS files 205
 - JVM 207
 - samples 205

- Java *(continued)*
 - verifying installation 205
- JAVADIR parameter of the DFHISTAR job 37
- JES parameter of the DFHISTAR job 21
- JOB parameter of the DFHISTAR job 20
- journal records, CMAS 397
- journalmodels, CMAS 308
- JPN 344
- JPN1 344
- JRNLDEFCH system parameter 388
- JRNLOPACT system parameter 388
- JRNLRTEV system parameter 388
- JVM
 - JVM profiles 207
 - properties files 208

L

- language 344
- Language Environment 201
 - support for C language 203
 - support for COBOL 203
 - support for PL/I 204
- Language identifiers 344
 - CHS 344
 - ENU 344
 - JPN 344
- language support 341
- LIB parameter of the DFHISTAR job 20
- libraries
 - authorizing 56, 67
 - creating multiple sets 50
 - load libraries
 - support for secondary extents 179
 - RACF-protecting 69
 - SMP/E function ACCEPT (DFHINST6) 46
- libraries, CICSplex SM
 - authorizing 283
 - EYUISTAR related 297
 - skeleton jobs 297
- LINDEX parameter of the DFHISTAR job 22
- link editing CICS Transaction Server modules
 - IEW0461 message 47
 - IEW2646 message 47
 - IEW2651 message 47
 - when running installation jobs 47
- link pack area (LPA)
 - CICS modules required in the LPA 108
 - eligible modules 109
 - installing CICS modules in 107, 112
 - installing required modules
 - DFHC SVC, CICS SVC 108
 - DFHDSPEX, post exit stub 108
 - DFHIRP, interregion communication program 108
 - DFHSSSEN, subsystem interface end-of-memory / end-of-task clean up routine 108
 - space for CICS requirements 111
- link-editing
 - DFHHP SVC into MVS nucleus 97
 - messages during 47

- linkedit temporary store (LTS) 30
- linklist, installing CICS-required modules 80
- linklist, installing module in 284
- listener 215
- LNK, MVS initialization parameter
 - IEASYSxx value 281
- LNKAUTH, MVS initialization parameter
 - IEASYSxx value 281
- LNKLSTxx, MVS linklist member 284
- load libraries 67
 - secondary extents 179
- load module 465
- local catalog (DFHLCD)
 - creating for each CICS region 192
 - DD statement in IVP startup procedure 233
- local MAS 341
- log manager
 - coupling facility considerations 151
 - defining logger environment 143
 - requirements planning 143
 - using DASD-only logging 167
- log stream sizing utility, DFHLSCU 160, 171
- log streams, authorizing the region userid to use 72
- logger environment
 - coupling facility space required for RLS AORs 165
 - RLS implications 165
 - staging data sets 166
- LOGGER-INFO parameter of the DFHISTAR job 38
- LOGMODE tables 100
 - required entries for autoinstall 242
- LOGMODE, parameter of VTAM APPL statement 100
- LOGUSR, transient data extrapartition data set
 - DD statement in IVP startup procedure 234
- LPA (link pack area)
 - CICS modules required in the LPA 108
 - eligible modules 109
 - installing CICS modules in 107, 112
 - installing required modules
 - DFHCSVC, CICS SVC 108
 - DFHDSPEX, post exit stub 108
 - DFHIRP, interregion communication
 - program 108
 - DFHSSN, subsystem interface end-of-memory /
 - end-of-task clean up routine 108
 - space for CICS requirements 111
- LPA, MVS initialization parameter
 - IEASYSxx value 281
- LPA, system initialization parameter 116
- LTS (linkedit temporary store) 30
- LUAPFX, parameter of VTAM APPL statement 100
 - choosing a value 104
- LUTYPE 6 sessions
 - ACQ 100
 - PARSESS 100
 - PERSIST 100

M

- macro temporary store (MTS) 29
- macros
 - DFHDLPSB TYPE=ENTRY (remote DL/I) 198

- MAS 341
- MAS-specific JCL requirements
 - DFHRPL DD 335
 - EYUPARM DD 335
 - STEPLIB DD 335
- MASINITTIME system parameter 389
- MASPLTWAIT system parameter 389
- MAXCAD, MVS initialization parameter
 - IEASYSxx value 281
 - setting 282
- MAXUSER, MVS initialization parameter
 - IEASYSxx value 281
- MAXUSERS 353
- message log (EYULOG)
 - with CMAS JCL 325
- messages
 - GIMSP 47
 - IEW0461, from the binder 47
 - IEW2646, from the binder 47
 - IEW2651, from the binder 47
 - SMP/E 47
 - when running installation jobs 47
- mode table entry
 - CPSM310.SEYUSAMP/EYUSMPMT 290
- MODETAB, VTAM APPL statement parameter 291
 - EYUSMPMT 290
- MODIFY command 254
- modules eligible for the LPA/ELPA 109
- modules, installing in LPA 107
- MRO between different CICS release levels 95
- MSGCASE 350
- MSGCASE system parameter 390
- MSGUSR, transient data extrapartition data set
 - DD statement in IVP startup procedure 234
- MTS (Macro temporary store) 29
- multiple CICS Transaction Server libraries
 - creating 50
- multiregion operation (MRO)
 - between different CICS release levels 95
 - defining CICS as an MVS subsystem 211
 - installation considerations 211
- MVS ASR exit 59
- MVS ASREXIT 133
- MVS definitions
 - CICS protection key 124
 - for CICS performance 125
 - for console messages 141
 - password checking 123
- MVS image
 - XCF/MRO is required for links between CICS regions
 - in different 211
- MVS linklist
 - installing CICS-required modules 80
 - installing IGWABWO 81
 - installing IGWARLS 81
 - other MVS product modules 81
- MVS linklist, installing module in 284
- MVS logger 143
- MVS subsystem, defining CICS as 57, 83
- MVS workload management 125

N

NAME system parameter 391
national language support 341
NetView
 sending generic alerts to 322
network control programs for CAS 289
non-exclusive element or feature
 description 4
NQNMOME, parameter of VTAM START
 command 102
NSINTERADDR 216
NSYSLX, MVS initialization parameter
 IEASYSxx value 281
 setting 282

O

ONC RPC
 element in CICS TS 6
optional source material
 optional source material 52
optional source material, loading 52
OPTVOL parameter of the DFHISTAR job 26

P

Parallel Sysplex considerations
 for CICS TS 60
parameters
 CICS SIT
 for CMAS 326
 for MVS MAS 336
 CICSplex SM system 383
 EYUINST EXEC 375
 in CMAS startup JCL 383
 in MAS startup JCL 383
PARSESS parameter, VTAM APPL statement
 CAS 291
 CMAS 294
PARSESS, parameter of VTAM APPL statement 100
PASS option of VTAM APPL parameter AUTH 294
password checking 123
PDIR (PSB directory) 197
PDSE 10
performance definitions for MVS 125
performance parameters (CICS), matching to service
 policies 126
PERSIST, parameter of VTAM APPL statement 100
PLIMSG, transient data extrapartition data set
 DD statement in IVP startup procedure 234
PLT (program load table) 345
PLTPI 345
PLTSD 345
port 344, 359
post-installation jobs
 CAS-related 297
 EYUCAS 297
 EYUCMAS 297, 324
 EYUDEFDS 297, 300
 EYUDFHDS 297

post-installation jobs (*continued*)
 EYULPMOD 297
 EYUSMPE 297
 MVS MAS-related 297
predefined LU alias 103
PREFIX parameter of the DFHISTAR job 22
preventive service 465
problem state 67
procedures, copying into a procedure library 48
PROG, MVS initialization parameter
 IEASYSxx value 281
program load table (PLT) 345
program temporary fix (PTF) 180
program temporary store (PTS) 465
properties files
 dfjvmp sample 208
 dfjvmps sample 208
protecting CICS load libraries 69
protection key definition 124
PRTAUXT step of IVP jobs 232
PRTBUXT step of IVP jobs 232
PRTDMPA step of IVP jobs 232
PRTDMPB step of IVP jobs 232
PRVMOD, system initialization parameter 116
PTF (program temporary fix) 179, 180, 465
 temporary store (PTS) 465
PTF temporary store (PTS) 29
PTS (PTF temporary store) 29, 465

R

RACF (resource access control facility)
 activating resource classes 75
 authorizing CICS category 1 transactions 57
 authorizing the region userid for category 1
 transactions 71
 authorizing the region userid to open a region's
 VTAM ACB 70
 authorizing the region userid to use MVS log
 streams 72
 defining the default CICS userid 77
 installing the interface routines 80
 IVP userid authority 228
 LOGSTRM general resource class 72
 protecting CICS load libraries 69
RECEIVE, function of SMP/E 179, 465
references, unresolved 47
REGION parameter for CAS startup 316
region userid, authorizing for category 1
 transactions 57, 71
region userid, authorizing to OPEN a region's ACB 70
REJECT function of SMP/E 466
release synchronization of CMAS and CICS 321
RELFILE data sets
 allocating 44
requirements for CICS TS
 hardware 9
 software 10
resource classes, activating 75
resource definitions 355
resource definitions, autoinstall for terminals 242

RESSTATUS system parameter 391
 restarting CMAS 331
 restarting MVS MAS 339
 RESTORE, function of SMP/E 179, 466
 REXX function package, installing 285
 routecodes, generic 88
 ROUTECODES, parameter of DFHSSly 88
 RSVNONR, MVS initialization parameter
 IEASYSxx value 281
 RSVSTRT, MVS initialization parameter
 IEASYSxx value 282
 run times of installation jobs 42
 RUSIZES parameter 289

S

sample applications data sets, creating
 ACCTFILE, primer sample application accounts 194
 ACIXFILE, primer sample application index 194
 DFHCTAIX, sample application alternate index 194
 DFHCTCUS, sample application details 194
 DFHCTHLP, sample application help 194
 sample JCL
 CAS 315
 CMAS 324
 EYUCAS 297
 EYUCMAS 297
 EYUDEFDS 297
 EYUDFHDS 297
 EYUJCLGN 307, 311
 EYULPMOD 297
 EYUSMPE 297
 MAS 335
 sample program data, FILEA
 creating for each CICS region 192
 DD statement in IVP startup procedure 233
 sample programs
 EYU\$CNV1 345
 EYUJWREP 346
 sample programs in interactive IVP 253
 sample programs, installing 253
 saved control data set (SCDS) 30
 SCDS (saved control data set) 30
 SCEEBND2 parameter of the DFHISTAR job 38
 SCEECICS parameter of the DFHISTAR job 38
 SCEECPP parameter of the DFHISTAR job 36
 SCEELIB parameter of the DFHISTAR job 38
 SCEELKED parameter of the DFHISTAR job 36
 SCEELKEX parameter of the DFHISTAR job 36
 SCEEOBJ parameter of the DFHISTAR job 36
 SCEERUN parameter of the DFHISTAR job 38
 SCEERUN2 parameter of the DFHISTAR job 38
 SCEESAMP parameter of the DFHISTAR job 36
 SCLBSID parameter of the DFHISTAR job 36
 SCOPE parameter of the DFHISTAR job 21, 40
 scope, EYUINST EXEC parameter
 post-installation customization 297
 SCSQANLE parameter of the DFHISTAR job 37
 SCSQAUTH parameter of the DFHISTAR job 37
 SCSQCICS parameter of the DFHISTAR job 37
 SCSQLOAD parameter of the DFHISTAR job 36
 SDFHPL1 target library 25
 SDFJAUTH 210
 SDFJLPA 210
 SDSNLOAD parameter
 SDSNLOAD parameter 37
 SDSNLOAD parameter of the DFHISTAR job 37
 SDUMP options 402
 SEC system parameter 391
 secondary extents, load libraries 179
 SECPRFX system parameter 392
 secure sockets layer (SSL) 342, 358
 security 357
 COVA 358
 COVC 358
 COVE 358
 COVG 358
 COVP 358
 COVU 358
 DFHHTML 358
 EYUCOVE 358
 EYUCOVI 358
 EYULOG 358
 EYUWREP 358
 EYUWUI 358
 security policy
 dfjejbpl 209
 security with the CICS IVPs 229
 SELECT, parameter of DFHISTAR 41
 server 341
 ServerPac
 compared with CBIPO 5
 contents 4
 description 4
 software requirements 10
 service, applying
 supplied SMP/E procedure 371
 servicing CICS 179
 corequisite fixes 180
 session outage notification (SON)
 SONSCIP 100
 setting up
 CAS 315
 CMAS 307, 321
 MVS MAS 333
 SEZACMTX parameter of the DFHISTAR job 38
 SEZARPCL parameter of the DFHISTAR job 38
 sharing control data sets, VSAM RLS 137
 SHUtdown action command 331
 shutting down a CMAS 330
 SISpload parameter of the DFHISTAR job 35
 SIT parameters, CICS 383
 CMAS-related 326
 MVS MAS-related 336
 SMF, MVS initialization parameter
 IEASYSxx value 282
 SMP/E data sets, attributes 28, 29
 SMP/E options, specifying 32
 SMP/E zone and zone log dispositions 32
 SMP/E, using to apply service 371
 SMP0001, SMP/E sample USERMOD for SMP/E data
 sets 28

SMPCNTL, DD statement of DFHSMPE 180
 SMPLTS parameter of the DFHISTAR job 30
 SMPMTS parameter of the DFHISTAR job 29
 SMPPTS parameter of the DFHISTAR job 29
 SMPSCDS parameter of the DFHISTAR job 30
 SMPSTS parameter of the DFHISTAR job 29
 SMPVOL parameter of the DFHISTAR job 26
 SMPWORK parameter of the DFHISTAR job 29
 SMS parameter of the DFHISTAR job 25
 software requirements
 installing system 10
 SONSCIP parameter, VTAM APPL statement 294
 SONSCIP, parameter of VTAM APPL statement 100
 source temporary store (STS) 29
 SPOOLCLASS system parameter 393
 SSI definitions for MRO 212
 SSL 215
 SSL (secure sockets layer) 342, 358
 staging data sets 166
 STALL system parameters 393
 START command
 CAS 316
 CMAS 330
 Starter Set
 creating environment 364
 defining environment 365
 deleting 368
 naming convention 363
 sample libraries 361
 selecting configuration 364
 starting components 365
 using as a model 368
 starting
 CAS
 as a batch job 315
 at MVS IPL time 315
 from the system console 315
 sample procedure 315
 CMAS
 as a batch job 323
 from the system console 323
 sample procedure 324
 MVS MAS 335
 stopping
 CAS 318
 MVS MAS 339
 storage key definition 124
 STS (source temporary store) 29
 subsystem definition to MVS 211
 subsystem, MVS, defining CICS as 57, 83
 supervisor state 67
 SUPPRESSCMF system parameter 337, 394
 suppressing CMF records 337, 394
 SVC
 correct-level check for DFHCSVC 58, 93
 defining to MVS 93
 DFHHPSVC, defining 97
 DFHHPSVC, loading into the MVS nucleus 97
 installing the CICS type 3 SVC 57, 93
 using DFHCSVC for MRO between different CICS releases 95
 SVC (*continued*)
 using more than one version of DFHCSVC 94
 SVC Parm statement in an IEASVCcc member 93
 SVCs, installing DFHCSVC in the LPA 108
 SYMREC Authorization Exit 133
 SYMREC macro 59, 133
 synchronization of CMAS and CICS releases 321
 SYS1.CPSM310.SEYULINK
 adding to linklist 284
 authorizing 283
 containing module for MVS linklist 284
 SYS1.CPSM310.SEYULPA
 authorizing 283
 defining to your MVS 287, 288
 SYS1.PARMLIB library
 BLSCECT exit control table 401
 COMMNDaa member with operator commands 323
 IEAAPFaa
 for authorizing CICSplex SM libraries 283
 IEASYSxx member
 establishing requirements 282
 when authorizing libraries 283
 when creating CAS started tasks 282
 when creating CMAS started tasks 282, 307
 LNKLSTxxx member
 when adding MVS linklist 284
 SYS1.PROCLIB
 CAS startup procedure 315
 CMAS startup procedure 323
 SYS1.VTAMLIB
 mode table 290
 SYS1.VTAMLST library 292
 application definitions
 CAS 289
 CMAS 294
 cross-domain resource definition 292, 295
 mode table 289
 SYSID parameter of EYU9XDUT 301
 SYSIN data set, partitioned
 creating for all CICS regions 191
 DD statement in IVP startup procedure 233
 SYSMOD (system modification) 179, 371, 466
 APAR 465
 Function 465
 PTF 465
 USERMOD 466
 SYSNAME, MVS initialization parameter
 IEASYSxx value 282
 sysplex, MVS
 cross-system coupling facility (XCF)
 for MRO links across MVS images 211
 SYSPROC data set for IPCS 402
 SYSTCPD 216
 system abend 722 47
 system initialization parameters 231
 system modification (SYSMOD) 371
 System Modification Program Extended (SMP/E)
 ACCEPT function 46, 179, 465
 APPLY function 46, 179, 465
 DFHSMPE 179
 FMID keyword of CICS SYSMODs 465

System Modification Program Extended (SMP/E)
(continued)
 function SYSMOD 465
 messages 47
 messages during link-editing 47
 RECEIVE function 179, 465
 REJECT function 466
 RESTORE function 179, 466
 UCLIN function 466
 system parameters
 description of 385
 summary of 383
 SYSTR 343

T

tailoring CICS
 installing MRO support 211
 TAPEUNIT parameter of the DFHISTAR job 33
 target libraries
 allocating and cataloging 44
 SMP/E function ACCEPT (DFHINST6) 46
 target zone 466
 target zone (TZONE) 32
 CSI 31
 log 30
 TARGVOL parameter of the DFHISTAR job 26
 TCP/IP
 DNS 216
 ECI 215
 enablement 215
 HTTP 215
 IIOIP 215
 installation requirements 215
 listener 215
 SSL 215
 TCPIPADDRESS 348
 TCPIPHOSTNAME 344, 347, 359
 TCPIPHTTPHOST 348
 TCPIPSPORT 344, 347, 359
 TCPIPSERVICE 342
 TCPIPSSL 349
 TCPIPSSLCERT 349
 TEMPLIB parameter of the DFHISTAR job 20
 temporary storage data set, DFHTEMP
 creating for each CICS region 192
 DD statement in IVP startup procedure 233
 terminals
 defining for the online IVP 242
 THOUSNDSEPARATOR 351
 times taken to run the installation jobs 42
 TIMESEPARATOR 351
 TIMEZONE parameter
 EYUINST EXEC 301, 375
 EYUXDUT 298
 TINDEXT parameter of the DFHISTAR job 22
 TOBATCHREQ
 CICSplex SM system parameter 394
 TOONLINEREQ
 CICSplex SM system parameter 394

TOPOLLINT

CICSplex SM system parameter 395
 transaction dump data sets
 dump (A) data set, DFHDMPA 234
 dump (B) data set, DFHDMPB 234
 transient data destination CSNE 101
 transient data extrapartition data sets
 destination before transient data initialization,
 DFHCXRF 233
 destination before transient data initialization,
 DFHLRQ 234
 destination used by C/370 application
 programs 234
 destination used by CICS services 234
 destination used by PL/I application programs 234
 destination, LOGA, used by CICS sample
 programs 234
 transient data queue definitions 356
 COLG 356
 COVE 356
 COVI 356
 COVP 356
 TSO
 defining a TSO user as a console 245
 type 3 SVC routine
 used for interregion communication 211
 TZONE parameter of the DFHISTAR job 32
 TZONECSI parameter of the DFHISTAR job 31
 TZONELOG parameter of the DFHISTAR job 30

U

UCLIN function of SMP/E 466
 UNIX System Services 205
 unresolved references 47
 UPAGE option of VTAM APPL parameter AUTH 294
 updating CICSplex definition
 BLSCECT 401
 CSD files using DFHCSDUP 307, 311
 CSD release 309
 library allocations for IPCS
 IPCSLIB 402
 ISPMLIB 402
 ISPLIB 402
 SYSPROC 402
 updating configuration list 292, 296
 URL 344, 359
 USERMOD (user modification) 466
 USERTR 343
 USSDIRA, parameter of DFHISTAR 35
 UTILITIES parameter of the DFHISTAR job 21

V

VARY NET command 296
 verification tests, running IVP jobs 227
 verify batch job, DFHIVPBT 234
 DFH\$BTCH input 234
 expected output 238
 verify interactive job, DFHIVPOL 241
 DFHIVPOL 250

- verify interactive job, DFHIVPOL (*continued*)
 - invoking and executing sample programs 253
 - terminating CICS 255
 - using CICS-supplied terminal transactions 250
 - using transactions 253
 - VSPACE option of VTAM APPL parameter AUTH 100
 - VPACING parameter, VTAM APPL statement 294
 - VPACING, parameter of VTAM APPL statement 101
 - VSAM RLS
 - activating the coupling facility structures 139
 - adding new parameters to SYS1.PARMLIB 138
 - altering data set attributes for RLS access 136
 - amending parameters in
 - SYS1.PARMLIB(BPXPRMxx) 84, 210
 - authorizing CICS userids 138
 - CFRM policy 135
 - defining cache sets 136
 - defining coupling facility cache structures 135
 - defining sharing control data sets 137
 - defining SMS storage classes for RLS access 136
 - defining the coupling facility lock structure 135
 - definitions, required 135
 - establishing new procedures 138
 - ISMF control data set application 136
 - ISMF storage class application 136
 - IXCMIAPU utility 135
 - VTAM
 - APPL statement 99
 - ACBNAME parameter 100
 - AUTH parameter 100
 - cross-domain considerations 101
 - EAS parameter 100
 - HAVAIL parameter 100
 - LOGMODE parameter 100
 - LUAPFX parameter 100
 - PARSESS parameter 100
 - PERSIST parameter 100
 - SONSCIP parameter 100
 - VPACING parameter 101
 - authorized path 58, 97
 - CICS APPLID 100
 - cross-domain considerations 101
 - definitions required for CICS 99
 - LOGMODE table entries for autoinstall 242
 - version, release, and modification level
 - indicator 101
 - VTAM ACB, authorizing the region userid to open 70
 - VTAM LU alias 102
 - VTAM requirements
 - activating definitions 293, 296
 - CAS 289
 - CMAS 294
 - defining APPL statement 291, 294
 - defining cross-domain resource 292, 295
 - updating configuration list 292, 296
- W**
- Web User Interface server 341
 - temporary storage models 356
 - Web User Interface server initialization optional
 - parameters 348
 - Web User Interface server initialization
 - parameters 347
 - AUTOREFRESH 351
 - COLORINK 354
 - COLORINKBANNER 354
 - COLORINKLINK 354
 - COLORINKVLINK 354
 - COLORPAPER 354
 - COLORPAPERALT 354
 - COLORPAPERERROR 354
 - COLORPAPERHEAVY 354
 - COLORPAPERLIGHT 354
 - COLORPAPERRULE 354
 - COLORPAPERWARN 354
 - CVDASTYLE 349
 - DATEFORMAT 350
 - DATESEPARATOR 350
 - DECIMALSEPARATOR 350
 - DEFAULTCICSplex 352
 - DEFAULTCICSRGN 352
 - DEFAULTCMASCTXT 351
 - DEFAULTCONNECT 352
 - DEFAULTCONTEXT 351
 - DEFAULTCSYSGRP 352
 - DEFAULTDB2SS 352
 - DEFAULTEJCOBEAN 352
 - DEFAULTEJDJBEAN 352
 - DEFAULTEVENT 352
 - DEFAULTLOCFILE 352
 - DEFAULTLOCTRAN 352
 - DEFAULTMAPCOLL 351
 - DEFAULTMENU 351
 - DEFAULTNAVIGATE 351
 - DEFAULTPROGRAM 352
 - DEFAULTREMFIL 353
 - DEFAULTREMFTRAN 353
 - DEFAULTSCOPE 351
 - DEFAULTTASK 353
 - DEFAULTWARNCNT 351
 - GMMTEXTMSG 350
 - INACTIVETIMEOUT 353
 - MAXUSERS 353
 - MSGCASE 350
 - TCPIPADDRESS 348
 - TCPIPHOSTNAME 344, 347, 359
 - TCPIPHTTPHOST 348
 - TCPIPSPORT 344, 347, 359
 - TCPIPSSL 349
 - TCPIPSSLCERT 349
 - THOUSNDSEPARATOR 351
 - TIMESEPARATOR 351
 - WUITRACE 355
 - Web User Interface server initialization required
 - parameters 347
 - Web User Interface server repository
 - (EYUWREP) 346, 356
 - workload management, MVS 125
 - worksheets for setup
 - CAS 272

worksheets for setup (*continued*)

CMAS 272

MVS MAS 272

overview 271

WORKUNIT parameter of the DFHISTAR job 24

WRKAREA 343

WTO (write-to-operator) macro 141

WUITRACE 355

X

XDLIPOST global user exit 199

XDLIPRE global user exit 199

XRF (extended recovery facility)

sessions, HAVAIL, parameter of VTAM APPL 100

XTRAQUAL parameter

XTRAQUAL parameter 24

XTRAQUAL parameter of the DFHISTAR job 24

XXRSTAT exit, effect on takeover of a VTAM ACB 70

Z

z/OS UNIX System Services 205

zone and zone log dispositions 32

ZONEOFFSET parameter of EYU9XDUT 301

Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply in the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore this statement may not apply to you.

This publication could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact IBM United Kingdom Laboratories, MP151, Hursley Park, Winchester, Hampshire, England, SO21 2JN. Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Programming License Agreement, or any equivalent agreement between us.

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at Copyright and trademark information at www.ibm.com/legal/copytrade.shtml.

Java and all Java-based trademarks and logos are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft and Windows are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, and service names may be trademarks or service marks of others.

Sending your comments to IBM

If you especially like or dislike anything about this book, please use one of the methods listed below to send your comments to IBM.

Feel free to comment on what you regard as specific errors or omissions, and on the accuracy, organization, subject matter, or completeness of this book.

Please limit your comments to the information in this book and the way in which the information is presented.

To ask questions, make comments about the functions of IBM products or systems, or to request additional publications, contact your IBM representative or your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate, without incurring any obligation to you.

You can send your comments to IBM in any of the following ways:

- By mail, to this address:

IBM United Kingdom Limited
User Technologies Department (MP095)
Hursley Park
Winchester
Hampshire
SO21 2JN
United Kingdom

- By fax:
 - From outside the U.K., after your international access code use 44-1962-816151
 - From within the U.K., use 01962-816151
- Electronically, use the appropriate network ID:
 - IBMLink: HURSLEY(IDRCF)
 - Internet: idrcf@hursley.ibm.com

Whichever you use, ensure that you include:

- The publication title and order number
- The topic to which your comment applies
- Your name and address/telephone number/fax number/network ID.



Program Number: 5655-M15

GC34-6426-08



Spine information:



CICS TS for z/OS

Installation Guide

Version 3
Release 1