CICS Transaction Server for z/OS Version 4 Release 1



RACF Security Guide

CICS Transaction Server for z/OS Version 4 Release 1



RACF Security Guide

Note

Before using this information and the product it supports, read the information in "Notices" on page 401.

This edition applies to Version 4 Release 1 of CICS Transaction Server for z/OS (product number 5655-S97) and to all subsequent releases and modifications until otherwise indicated in new editions.

© Copyright IBM Corporation 1989, 2012.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Preface. . What this book is about . Who this book is for . What you need to know to understand this book .	. ix
What this book is about	. ix
Who this book is for	. ix
What you need to know to understand this book .	. ix
Notes on terminology	. ix
Changes in CICS Transaction Server for	\r
z/OS, Version 4 Release 1	
Part 1. Introduction to CICS security	
with RACF	. 1
Chapter 1. Security facilities in CICS .	. 3
What CICS security protects .	3
CICS users	4
The CICS region user ID	
The CICS default user ID	
Terminal user security	7
Non-terminal security	8
Non-terminal security	8
Intercommunication security	9
Generating and using RACF PassTickets	. 10
Chapter 2. RACF facilities	11
Overview of RACF facilities	
RACF administration	
Delegation of RACF administrative responsibility.	. 11
RACE profiles	. 13
RACF profiles RACF user profiles 14
The RACF segment.	. 14
The CICS segment	
The LANGUAGE segment	. 19
RACF group profiles	. 19
RACF group profiles .	. 20
Generic data set profiles	. 21
RACF general resource profiles	. 21
Protecting a resource	. 22
Activating the CICS classes	. 22
Refreshing resource profiles in main storage .	. 22
RACF classes for CICS resources	. 23
RACF classes for CICSPlex SM resources	. 23
RACF resource class names	. 24
RACF classes for protecting system resources	. 24
Resources protected by the FACILITY general	
resource class.	. 26
resource classes for DB2ENTRYs	. 27
Summary of RACF commands	. 27
5	. 30
Defining your own resource classes	. 31
Setting up installation-defined classes	. 31
Controlling access to fields in RACF profiles	. 32

Part 2. Implementing RACF protection in a single CICS region . 33

Chapter	3.	CICS	svstem	resource
onuptor	Ο.	0100	0,000	10000100

security	35
CICS installation requirements for RACF	. 35
CICS-supplied RACF dynamic parse validation	
routines	. 35
Using RACF support in a multi-MVS	
environment	. 35
Setting options on the MVS program properties	
table	. 35
Protecting CICS load libraries	. 36
Specifying the CICS region userid	. 36
Using protected user IDs	. 37
Authorizing CICS procedures to run under RACF	37
Using the ICHRIN03 table for started tasks.	. 37
Using STARTED profiles for started jobs	. 38
Defining user profiles for CICS region userids.	. 39
Coding the USER parameter on the CICS JOB	
statement	. 39
Authorities required for CICS region userids .	. 39
Defining the default CICS userid to RACF	. 41
	. 42
	. 43
Authorizing access with the MVS library	
	. 46
lookaside (LLA) facility	. 46
Authorizing access to the temporary storage pools	47
Authorizing access to temporary storage servers .	. 47
System authorization facility (SAF) responses to	
the TS server	. 48
Authorizing access to named counter pools and	
servers	. 48
Access to named counter pools	. 49
Access to named counter servers	. 49
System authorization facility (SAF) responses to	
the named counter server.	. 50
Authorizing access to SMSVSAM servers	. 50
Authorizing access to the CICS region	. 51
Controlling the opening of a CICS region's VTAM	
ACB	. 52
Controlling userid propagation	. 53
Surrogate job submission in a CICS environment.	. 53
Authorizing the CICS region userid as a surrogate	
user	. 54
JES spool protection in a CICS environment	. 54
Security-related system initialization parameters .	. 55
CICS resource class system initialization	
parameters	. 57
1	. 60
Using IBM-supplied classes with prefixing	. 61
Using installation-defined classes without	
prefixing	. 61
1 0 0 1 0	

Chapter 4. Verifying CICS users 6	
Identifying CICS terminal users	63
The sign-on process	63
Explicit sign-on	
The sign-off process	65
Explicit sign-off	66
Explicit sign-off	66
Goodnight transaction	66
Controlling access to CICS from specific ports of	
entry	66
entry Defining port of entry profiles 	67
Terminal profiles	67
Terminal profiles	67 67
Defining a profile of a group of profiles	68
Profiles in the TERMINAL or GTERMINAL class	68
Universal access authority for undefined	00
	68
terminals	60 60
Conditional access processing	09 60
Console profiles	09 70
Proport tourning acquirity	70
Nerreal executive	70 71
Normal preset security	71
Automatic preset security for consoles	71
Controlling the use of preset-security Other preset security considerations	72
Other preset security considerations	13
	74
Obtaining CICS-related data for a user	
Obtaining CICS-related data for the default user	
Obtaining CICS-related data at signon	
Support for mixed-case passwords	
National language and non-terminal transactions.	79
Chapter 5. Transaction security 8	31
CICS parameters controlling transaction-attach	
security.	81
Transaction-attach processing when SEC=YES	~
and XTRAN=YFS	82
and XTRAN=YES	83
Some recommendations	83
Using conditional access lists for transaction	05
profiles	Q/I
Protecting the CEBT transaction	
Authorization failures and error messages	
Protecting non-terminal transactions	00 05
Triggered transactions	85
PLI programs	85
Chapter 6. Resource security 8	7۶
Introduction to resource security	
Security using the XRES resource security parameter	0/ 0/

Security using the XRES resource security parameter	er	87
Access authorization levels		89
User IDs for access to document templates and		
z/OS UNIX files used by CICS Web support .		90
Resource security checking by CICS and RACF .		91
RESSEC transaction resource security parameter		92
The RESSEC system initialization parameter .		93
Authorization failures		94
Logging RACF audit messages to SMF		94
Security for transient data		95
Defining profiles for transient data queues		95

Access authorization levels	. 96
	. 96
definitions.	. 96
Security for files	. 97
Security for journals and log streams	
Access authorization levels	. 98
Transactions that use WRITE JOURNALNUM	
command	. 99
command	99
Transactions started at terminals	100
Transactions started without terminals	
Access authorization levels	102
Security for application programs	102
Access authorization levels	103
Security for temporary storage	103
Implementing security for temporary storage	100
queues	103
Other temporary storage security considerations	103
A second section levels	104
Access authorization levels	104
Security for z/OS UNIX files	105
Implementing security for z/OS UNIX files	106
Access authorization levels	
Security for program specification blocks	108
Security checking of transactions running under	
CEDF	109
Defining generic profiles for resources	110
Access to all or access to none?	111
	113
Chapter 7. Surrogate user security	
Chapter 7. Surrogate user security Where surrogate user checking applies	113
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user	113 113
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user	113 113 113
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security	113 113 113 114
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security	113 113 113 114
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security	113 113 113 114
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions	 113 113 113 114 114 115 115
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls	 113 113 113 114 114 115 115
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID	 113 113 113 114 114 115 115 116
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters	 113 113 113 114 114 115 115 116
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters	 113 113 113 114 114 115 115 116
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions	 113 113 113 114 115 115 116 117 117
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions	 113 113 113 114 115 115 116 117 117
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking.	 113 113 113 114 115 115 116 117 117
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user	 113 113 113 114 114 115 115 116 117 117 117
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. Examples of RACF definitions for surrogate user checking	 113 113 113 114 114 115 115 116 117 117 117 118
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user	 113 113 113 114 114 115 115 116 117 117 117 118
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. Examples of RACF definitions for surrogate user checking LT security.	113 113 113 114 114 115 115 116 116 117 117 117 117 118 118
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions Examples of RACF definitions for surrogate user checking. Preser definitions for surrogate user Checking Checking Checking Checking Where Surrogate Where Where Complexity Where Where <t< td=""><td>113 113 113 114 114 115 115 115 116 117 117 117 117 118 118 118</td></t<>	113 113 113 114 114 115 115 115 116 117 117 117 117 118 118 118
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. PLT security Chapter 8. CICS command security	113 113 113 114 114 115 115 115 116 117 117 117 117 118 118 118
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. PLT security Chapter 8. CICS command security Introduction to command security CICS resources subject to command security	113 113 113 114 114 115 115 115 116 117 117 117 117 118 118 118 121
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. PLT security Chapter 8. CICS command security Introduction to command security CICS resources subject to command security	113 113 113 114 114 115 115 115 116 117 117 117 117 118 118 118 121
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. Examples of RACF definitions for surrogate user checking PLT security Introduction to command security CICS resources subject to command security PLT security Surrogate set biper to command security	113 113 113 114 114 115 115 115 116 116 117 117 117 117 118 118 118 121
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. Examples of RACF definitions for surrogate user checking PLT security Introduction to command security CICS resources subject to command security PLT security Surrogate set biper to command security	113 113 113 114 114 115 115 115 116 116 117 117 117 117 118 118 118 121
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. Examples of RACF definitions for surrogate user checking PLT security Introduction to command security CICS resources subject to command security Parameters for specifying command security Starteg CICS resources subject to command security CICS resources subject to command security Security checking of transactions running under CEDF	113 113 113 114 114 115 115 116 116 117 117 117 117 118 118 118 118 121 122 128 129
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. Examples of RACF definitions for surrogate user checking PLT security Introduction to command security CICS resources subject to command security Parameters for specifying command security Starteg CICS resources subject to command security CICS resources subject to command security Security checking of transactions running under CEDF	113 113 113 114 114 115 115 116 116 117 117 117 117 118 118 118 118 121 122 128 129
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. Examples of RACF definitions for surrogate user checking PLT security Introduction to command security CICS resources subject to command security Parameters for specifying command security Starteg CICS resources subject to command security CICS resources subject to command security Security checking of transactions running under CEDF	113 113 113 114 114 115 115 116 116 117 117 117 117 118 118 118 118 121 122 128 129
Chapter 7. Surrogate user security Where surrogate user checking applies CICS default user Post-initialization processing Preset terminal security Started transactions BTS processes and activities Transient data trigger-level transactions. Surrogate user checking for EXCI calls The userid on DB2 AUTHID and COMAUTHID parameters The user ID in event bindings The userid on URIMAP resource definitions RACF definitions for surrogate user checking. Examples of RACF definitions for surrogate user checking. PLT security Introduction to command security CICS resources subject to command security Parameters for specifying command security Security checking of transactions running under	113 113 113 114 114 115 115 116 116 117 117 117 117 118 118 118 118 121 122 128 129

Chapter 9. Security checking using the QUEBY SECURITY command

the QUERY SECURITY command	133
How QUERY SECURITY works	133
SEC system initialization parameter	133
SECPRFX system initialization parameter	134
Resource class system initialization parameters	134
Transaction routing	134
	134
RESTYPE values	134
	135
Examples of values returned by QUERY	
	138
	139
~ , , , ,	140
~~~~	140
	141
	141
	141
Example of use of QUERY SECURITY	
RESCLASS	141

## Chapter 10. Security for

CICS-supplied trar	IS	ac	tio	ns	; .			-	143
Categories of CICS-supp	olie	ed	trar	isa	ctic	ns			. 143
Category 1 transactions									. 144
Category 2 transactions									. 147
Category 3 transactions									. 154

## 

## Chapter 11. Overview of

intercommunication security		159
Introduction to intercommunication security		. 159
Planning for intercommunication security .		. 159
Intercommunication bind-time security		. 160
Intercommunication link security		. 160
User security for intercommunication	•	. 161
Transaction, resource, command, and surroga	te	
user security for intercommunication	•	. 161
Summary of intercommunication security leve	els	161

## Chapter 12. Implementing LU6.2

security	163
Bind-time security with LU6.2.	. 163
Defining profiles in the APPCLU general	
resource class	. 164
Specifying bind-time security for LU6.2	. 165
Auditing bind-time security	. 166
Changing RACF profiles that are in	
use—caution	. 167
Link security with LU6.2	. 167
Specifying link security for LU6.2 connections .	. 168
User security with LU6.2	. 168
Non-LOCAL user security verification	
Specifying user security in link definitions.	. 170
Information about remote users	. 172
SNA profiles and attach-time security	. 174

Transaction, resource, and command security with

· · · · · · · · · · · · · · · · · · ·
LU6.2
Transaction security
CICS routing transaction, CRTE
Resource and command security
Transaction routing security with LU6.2 176
Preset-security terminals and transaction routing 177
CICS routing transaction, CRTE
Function shipping security with LU6.2
Distributed program link security with LU6.2 179
Security checking done in AOR with LU6.2 180

## Chapter 13. APPC password

expiration management	3
Introduction to APPC password expiration	
management	3
What APPC PEM does	3
Benefits of APPC PEM	3
What you require to use APPC PEM	1
External security interface	1
Roles of PEM client and CICS PEM server 185	5
An example of signing on with APPC PEM 185	5
Overview of APPC PEM processing	7
PEM client processing	7
CICS PEM server processing	7
Expected flows between PEM client and CICS	
PEM server	3
Setting up the PEM client	)
Format of user data	3
PEM client input and output data	1
Sign-on input data sent by PEM client 195	5
Sign-on output data returned by CICS PEM	
server	5
Application design	3
Examples of PEM client and CICS PEM server	
user data	)

## Chapter 14. Implementing LU6.1

security	205
Link security with LU6.1	. 205
Specifying link security for LU6.1 connections .	. 205
Specifying ATTACHSEC with LU6.1	. 206
Transaction, resource, and command security with	L
LU6.1	. 206
Transaction security	. 206
Resource and command security	. 206
Function shipping security with LU6.1	. 207
Security checking done in AOR with LU6.1	. 208

## **Chapter 15. Implementing IPIC**

L

security	211
IPIC bind-time security	. 211
IPIC link security	. 212
IPIC user security	. 213
Remote user sign-on status with IPIC	. 215
IPIC transaction, resource, and command security	215
CICS routing transaction, CRTE	. 216
Security checking done in AOR with IPIC	. 217

## Chapter 16. Implementing MRO

security.	219
Security implications of choice of MRO access	
	219
method	219
Logon security checking with MRO	219
Connect security	220
Connect security	
(SAF)	222
Link security with MRO.	222
Obtaining the CICS region userid	223
Obtaining the CICS region userid	223
User security with MRO.	223
User security with MRO	224
Information about remote users	225
Transaction, resource, and command security with	
MRO	226
Transaction security	
Resource and command security	226
Resource and command security	227
Preset-security terminals and transaction routing	227
CICS routing transaction, CRTE	
Function shipping security with MRO	228
Distributed program link security with MRO	230
Security checking done in AOR with MRO	232
Security checking done in AOR with MRO With ATTACHSEC(LOCAL) specified	232
With ATTACHSEC(IDENTIFY) specified	232
	202
Chapter 17. Security for data tables	233
Security for CICS shared data tables.	
Security checking for data tables	
SDT server authorization security check	234
CONNECT security checks for AORs	234
Security for coupling facility data tables	234
Authorizing server access to a list structure	237
Authorizing the server	237
	237
Authorizing a CICS region to a coupling facility	
data table	238
The resource security checking	200
Port 4 Security for TCD/ID cliente	220
Part 4. Security for TCP/IP clients	239
Chapter 18. About security for TCP/IP	
clients	
Message protection	
Public key encryption	
	242
Digital certificates	243
Identification and authentication	244
	244
Authentication	248
Configuring CICS to use asserted identity	
	251
authentication	252
SSL encryption<	253

The SSL handsh	nak	æ					. 258
The SSL cache							. 259
The SSL pool							. 259

## Chapter 19. Configuring CICS to use

SSL	261
Authorizing users to administer certificates in the	
key ring	. 262
Requesting a certificate from a certificate authority	263
Building a key ring manually	. 264
Building a key ring with certificates using	
DFH\$RING	. 265
Creating new RACF certificates	. 267
Associating a RACF user ID with a certificate .	. 268
Making a certificate untrusted	. 269
System initialization parameters for SSL	. 269
Defining TCPIPSERVICE resources for SSL	. 270
Customizing encryption negotiations	. 272
Configuring LDAP for CICS use	. 272
Using certificate revocation lists (CRLs)	. 273
Configuring an LDAP server for CRLs	. 274
Running the CCRL transaction	. 275

## Part 5. Security for enterprise

beans 2	7	7	1	1		'	'
---------	---	---	---	---	--	---	---

## Chapter 20. Managing security for

enterprise beans	279
Protecting Java applications in CICS by using the	
Java security policy mechanism	279
Enabling a Java security manager and	
	280
Specifying policy files to apply to all JVMs	282
The CICS-supplied enterprise beans policy file	283
	284
Defining file access permissions for enterprise	
beans	284
0 0	286
Security roles	287
Deployed security roles	288
Enabling and disabling support for security	
	289
5	289
Character substitution in deployed security roles	290
	291
1 0 5	293
	293
Defining security roles to RACF	295

## 

## Chapter 21. Preparing for identity

| | |

Ι

propagation	299
Support and requirements for identity propagation	299
Sample network topologies for using identity	
propagation	. 301

## Chapter 22. Configuring identity

L	propagation
L	Configuring RACF for identity propagation 305
L	Configuring IPIC connections for identity
L	propagation
L	Configuring provider mode Web services for
L	identity propagation

## Chapter 23. Customizing security

processing	313
Overview of the CICS-RACF interface	. 313
The MVS router	. 313
How ESM exit programs access CICS-related	
information	. 314
The RACF user exit parameter list	. 314
The installation data parameter list	. 315
CICS security control points	. 315
Determining the userid of the CICS region .	. 318
Specifying user-defined resources to RACF .	. 318
Adding new resource classes to the class	
descriptor table	. 318
Activating the user-defined resource classes	. 319
Defining resources within the new class .	. 319
Designing applications to use the user-defined	
resources	. 320
Suppressing attach checks for non-terminal	
transactions	. 321
Global user exits in signon and signoff	. 321

## Part 8. Problem determination . . . 323

### 

······································	
Resolving problems when access is denied	
incorrectly	25
Is CICS using RACF for this particular kind of	
resource?	26
Which profile is RACF using?	26
Which userid did CICS supply for the	
authorization check?	26
Which profile is used to protect the resource? 3	27
RACF message ICH408I	29
Resolving problems when access is allowed	
incorrectly	31
CICS initialization failures related to security 3	32
RACF abends	32
SAF or RACF installation exits	32
CICS default user fails to sign on	32
Revoked user attempting to sign on	
User has insufficient authority to access a	
resource	35
CICS region user ID access problem	36
Password expiry management problem	
determination	37
Execution diagnostic facility (EDF) 3	

## Part 9. CICSPlex SM security . . . 339

## Chapter 25. Implementing CICSPlex

SM security
Determining who requires access to CICSPlex SM
resources
General requirements for CICSPlex SM security 344
Creating profiles for the CICSPlex SM data sets 345
Defining the CICSPlex SM started tasks 346
Defining the CICSPlex SM transactions in a CMAS 346
Defining the CICSPlex SM transactions in a
managed CICS region
Defining the CICSPlex SM transactions for a WUI 348
Specifying CICSPlex SM resource names in profiles 349
Using asterisks in resource names
Valid resource name combinations
Activating simulated CICS security
Exempting users and resources from security
checking
Activating security parameters
Refreshing RACF profiles for CICSPlex SM 370
Refreshing general resource profiles in the cache 370
Refreshing user profiles in the cache
CICSPlex SM security checking sequence

## Chapter 26. Invoking a user-supplied

<b>3</b>	
external security manager	375
An overview of the CICSPlex SM ESM interface	
Using the MVS router	
The MVS router exit	. 376
	. 377
Chapter 27. Example tasks: security	379
· · · ·	. 379
appropriate authorizations	. 380
transactions on MVS system A	. 380
Part 10. Appendixes	381
Appendix A. National Language	383
Appendix B. Resource and command check cross reference	385
Appendix C. The sign-on table migration utility	399
Notices	401
Trademarks	
<b>Bibliography</b>	
CICSPlex SM books for CICS Transaction Server	404
for z/OS	. 404 . 404

Other IBM publications	Index
Accessibility.	

## **Preface**

## What this book is about

This manual documents intended Programming Interfaces that allow the customer to write programs to obtain the services of Version 4 Release 1.

This book is about using the IBM[®] Resource Access Control Facility ( $RACF^{\$}$ ) to provide security for CICS[®].

## Who this book is for

This book is intended for security administrators responsible for controlling access to resources used by CICS. These resources are used by CICS terminals, users, or transactions in CICS regions, and by CICS application programs running in those regions. The book will also be of interest for CICS system programmers who may need to communicate their requirements to the security administrator for their installation.

## What you need to know to understand this book

It is assumed that you have a good working knowledge of RACF facilities. It is also assumed that you know something about the types of resource owned and controlled by CICS.

Although this book shows many RACF command examples, it assumes that you have access to the *z/OS Security Server RACF Security Administrator's Guide* and that you know how to issue TSO commands (or use ISPF panels to perform equivalent functions).

## Notes on terminology

When the term "CICS" without any qualification in this book, it refers to the CICS element of CICS Transaction Server for  $z/OS^{\text{®}}$ .

Other terms used are:

- **RACF** refers to the Resource Access Control Facility (RACF) component of Security Server, which is an optional feature of z/OS.
- **MVS**[™] refers to the operating system, which is a base element of z/OS.

## Changes in CICS Transaction Server for z/OS, Version 4 Release 1

For information about changes that have been made in this release, please refer to *What's New* in the information center, or the following publications:

- CICS Transaction Server for z/OS What's New
- CICS Transaction Server for z/OS Upgrading from CICS TS Version 3.2
- CICS Transaction Server for z/OS Upgrading from CICS TS Version 3.1
- CICS Transaction Server for z/OS Upgrading from CICS TS Version 2.3

Any technical changes that are made to the text after release are indicated by a vertical bar (1) to the left of each new or changed line of information.

## Part 1. Introduction to CICS security with RACF

This part is an introduction to CICS security. It explains at a high level how you can use the facilities provided by RACF to make your CICS systems, and the resources in those systems, secure against unauthorized access.

## Chapter 1. Security facilities in CICS

As an online transaction-processing system (often supporting many thousands of users), CICS requires the protection of a security system to ensure that the resources to which it manages access are protected and are secure from unauthorized access. CICS provides a number of facilities that protect your resources against unauthorized access.

To provide the required security for your CICS regions, CICS uses the MVS system authorization facility (SAF) to route authorization requests to an external security manager (ESM), such as RACF, at appropriate points within CICS transaction processing.

For specific security information on Business Transaction Services, see *CICS Business Transaction Services*. For specific security information on the Front End Programming Interface (FEPI), see *CICS Front End Programming Interface User's Guide*.

## What CICS security protects

CICS manages application programs, the application data, and the application output. To prevent disclosure, destruction, or corruption of these assets, you must first safeguard the CICS system components themselves.

There are two distinct areas from which exposures to the CICS system can arise. The first of these is from sources external to CICS. You can use RACF data set protection as the primary means of preventing unauthorized access, from either TSO users or batch jobs, to the assets CICS manages.

The other potential area of exposure arises from CICS users. CICS provides a variety of security and control mechanisms that can limit the activities of CICS users to only those functions that any particular individual user is authorized to use:

#### Transaction security

Ensures that users that attempt to run a transaction are entitled to do so

#### **Resource security**

Ensures that users who use CICS resources are entitled to do so

#### **Command security**

Ensures that users who use CICS system programming commands are entitled to do so

CICS itself does **not** provide facilities to protect its own assets from external access. You must restrict access to the program libraries, to the CICS regions, and to those responsible for incorporating approved application and system changes. Similarly, the data sets and databases used by CICS and by CICS applications must be accessible only by approved batch processing and operations procedures.

CICS does not protect your system from application programs that use undocumented or unsupported interfaces to bypass CICS security. You are responsible for ensuring that such programs are not installed on your system. CICS does not protect your application source libraries. You should ensure that procedures are established and followed that prevent the introduction of unauthorized or untested application programs into your production application base. You must also protect the integrity of your system by exercising control over libraries that are admitted to the system and changes to those libraries.

## **CICS** users

When CICS security is active, requests to attach transactions, and requests by transactions to access resources, are associated with a *user*.

When a user makes a request, CICS calls the external security manager to determine if the user has the authority to make the request. If the user does not have the correct authority, CICS denies the request.

In many cases, a user is a human operator, interacting with CICS through a terminal or a workstation. However, this is not always the case: a user can also be a program executing in a client system. In general, a CICS user is an entity that is identified by a *user identifier* (or *userid*).

All CICS users must be defined to the security manager; when the security manager is RACF, information about each users is stored in a user profile.

Here are some of the ways that the user of a CICS transaction, or a CICS resource, can be identified:

• A human operator signs on (and so provides a userid) at the start of the terminal session. The userid remains associated with the terminal until the terminal operator signs off. Transactions executed from the terminal, and requests made by those transactions, are associated with that userid.

For more information, see "Identifying CICS terminal users" on page 63

• A userid is permanently associated with a terminal. Transactions executed from the terminal, and requests made by those transactions, are associated with the preset userid.

For more information, see "Preset terminal security" on page 70.

- A client program that is communicating with CICS using the Secure Sockets Layer (SSL) supplies a client certificate to identify itself. The security manager maps the certificate to a userid. The transaction that services the client's request, and further requests made by that transaction, are associated with that userid. For more information, see Chapter 18, "About security for TCP/IP clients," on page 241.
- A CICS application program issues a START command with the USERID option. The started transaction, and requests made by that transaction, are associated with the specified userid.

For more information, see "Security for started and XPCT-checked transactions" on page 99.

• A transaction is started when the trigger level of an intrapartition transient data queue is reached. If the USERID attribute is specified in the TDQUEUE definition for the queue, then the started transaction, and requests made by that transaction, are associated with the specified userid.

For more information, see "Protecting non-terminal transactions" on page 85.

• A remote program executing in another system, supplies a userid when it sends an attach request to CICS. The attached transaction, and requests made by that transaction, are associated with the specified userid. For more information, see "User security for intercommunication" on page 161.

- A remote system connects to CICS, and link security is specified for the connection to the remote system. Transactions invoked from the remote system, and requests made by that transaction, are associated with the link userid. For more information, see "Intercommunication link security" on page 160.
- A CICS business transaction services (BTS) process is activated by a RUN command, and the DEFINE PROCESS command specified the USERID option.. The transaction under which the process runs, and requests made by that transaction, are associated with the specified userid.

For more information, see CICS Business Transaction Services.

• A second phase PLT program runs during CICS initialization. Depending upon the value of the PLTPISEC system initialization parameter, requests made by the program are associated with the userid specified in the PLTPIUSR system initialization parameter.

For more information, see "PLT programs" on page 85.

There are two user IDs that CICS uses in addition to those that identify individual end users. They are

#### The region user ID

is used for authorization checking when the CICS system (rather than an individual user of the system) requests access to a resource.

For more information, see "The CICS region user ID."

#### The default user ID

identifies the user whose security attributes are used to protect CICS resources in the absence of other, more specific, user identification.

For more information, see "The CICS default user ID" on page 7.

By itself, a userid does not protect the system from unauthorized access: in many cases, userids are known to other people than the user they identify. To prevent impersonation, another piece of information — known only to the individual user — must be supplied in order to authenticate the user. For example:

- For a terminal user, the password which the user supplies during sign on authenticates the user.
- For a client using SSL, the client certificate authenticates the client.

## The CICS region user ID

The CICS region user ID is used for authorization checking when the CICS system (rather than an individual user of the system) requests access to a resource.

CICS uses the region user ID when checking authorization for these resources:

#### MVS system log streams

For more information, see "Authorizing access to MVS log streams" on page 42.

#### CICS system data sets

For more information, see "Authorizing access to CICS data sets" on page 43.

#### CICS user data sets

For more information, see "Authorizing access to user data sets" on page 46.

#### Temporary storage data sharing servers

For more information, see "Authorizing access to temporary storage servers" on page 47.

### The SMSVSAM server

For more information, see "Authorizing access to SMSVSAM servers" on page 50.

#### Named counter servers

For more information, see "Authorizing access to named counter pools and servers" on page 48.

## The VTAM[®] ACB

For more information, see "Controlling the opening of a CICS region's VTAM ACB" on page 52.

#### JES spool data sets

For more information see "JES spool protection in a CICS environment" on page 54.

#### The CICS interregion program

For more information, see "Logon security checking with MRO" on page 219.

### Coupling facility data tables

For more information, see "Security for coupling facility data tables" on page 236.

#### RACF key rings

For more information, see "Building a key ring manually" on page 264.

CICS may also use the region user ID:

#### When submitting jobs to the JES internal reader

For more information, see "Controlling userid propagation" on page 53.

#### As a surrogate for other user IDs used during CICS execution

For more information, see Chapter 7, "Surrogate user security," on page 113.

#### As a prefix for resource names passed to RACF

For more information, see the description of the **SECPRFX** system initialization parameter in "Security-related system initialization parameters" on page 55.

#### When executing CICS-supplied non-terminal transactions

For more information, see "Category 1 transactions" on page 144.

#### In CICS intersystem communication using LU6.2

For more information, see Chapter 12, "Implementing LU6.2 security," on page 163.

#### In CICS intersystem communication using LU6.1

For more information, see Chapter 14, "Implementing LU6.1 security," on page 205.

## In CICS intersystem communication using MRO

For more information, see Chapter 16, "Implementing MRO security," on page 219.

#### When deriving the distinguished name of an enterprise bean client For more information, see Java Applications in CICS.

The CICS region user ID is assigned to a CICS region at initialization, and is the user ID that is associated with the job or started task. For more information, see "Specifying the CICS region userid" on page 36.

## The CICS default user ID

The CICS default user ID identifies the user whose security attributes are used to protect CICS resources in the absence of other, more specific, user identification.

The default user ID is specified in the **DFLTUSER** system initialization parameter. If you do not specify the parameter, the default user ID is CICSUSER.

- It is assigned to a terminal or a console before a user signs on, and after the user has signed off, except when the terminal or console has preset security specified. For more information, see Chapter 4, "Verifying CICS users," on page 63.
- It is assigned to transient data trigger-level transactions that are not associated with a terminal, and when a user ID is not specified in the definition of the transient data queue. For more information, see "Transient data trigger-level transactions" on page 115.
- It is used as the link user ID for LU6.1 and LU6.2 connections when the SECURITYNAME attribute is not specified in the CONNECTION definition. For more information, see "Link security with LU6.1" on page 205 and "Link security with LU6.2" on page 167.
- It is assigned to transactions attached by LU6.2 and MRO sessions, when the attach request does not contain security parameters, and the CONNECTION definition specifies USEDFLTUSER(YES). For more information, see "SNA profiles and attach-time security" on page 174 and "User security with MRO" on page 223.
- For transactions in an application-owning region (AOR) that are initiated using the CICS routing transaction (CRTE), the default user ID is used if the terminal user does not sign on to the AOR while using CRTE. For more information, see "Transaction routing security with LU6.2" on page 176 and "Transaction routing security with MRO" on page 227.
- It is used when an application-owning region (AOR) issues a request for a remote file that is defined as a shared data table, and the AOR is unable to sign on to the file-owning region (FOR). For more information, see "Security for CICS shared data tables" on page 233.
- In the absence of more explicit identification, it is used to identify TCP/IP clients that connect to CICS. For more information, see "Identification" on page 244.

## Terminal user security

To secure resources from unauthorized access, CICS requires some means of uniquely identifying individual users of the system.

For this purpose, first define the users to RACF by creating an entry in the RACF database, referred to as a *user profile*. To identify themselves to CICS, users sign on by specifying their RACF user identification (user ID) and the associated password, or operator identification card (OIDCARD) in the CICS-supplied sign-on transaction, CESN. Alternatively, they can use an equivalent transaction developed by your own installation by issuing the EXEC CICS SIGNON command provided for this purpose.

When users enter the CESN transaction, CICS verifies user IDs and passwords by a call to RACF. If the terminal user signon is valid, the CICS user domain keeps

track of the signed-on user. Thereafter, CICS uses the information about the user when calling RACF to make authorization checks. If the user fails to complete signon, all subsequent transactions use the CICS default user ID.

See "Terminal profiles" on page 67 for information about the terminal security facilities provided by RACF. See Chapter 4, "Verifying CICS users," on page 63 for information about using terminal user security in CICS.

For some terminals, and for MVS consoles which are used as CICS terminals, it may be appropriate to use *preset terminal security*. Preset terminal security allows you to associate a user ID permanently with a terminal that is defined to CICS. This means that CICS implicitly "signs on" the terminal when it is being installed, instead of the terminal being signed on subsequently. Preset security is often defined for devices without keyboards, such as printers, at which users cannot sign on.

You can also use this form of security on ordinary display terminals as an alternative to terminal user security. This permits anyone with physical access to a terminal with preset security to enter the transactions that are authorized for that terminal, without the need to sign on to CICS. The terminal remains signed on as long as it is installed, and no explicit sign-off can be performed against it. If the user ID associated with a display terminal with preset security authorized to use any sensitive transactions, ensure that the terminal is in a secure location to which access is restricted. For example, terminals physically located within a CICS network control center might be appropriate for preset security.

For more information, see "Preset terminal security" on page 70.

## Non-terminal security

1

You can specify security for transactions that are not associated with terminals.

Transactions that are not associated with terminals include:

- Started non-terminal transactions
- Transient data trigger-level transactions
- Program List Table (PLT) programs that run during CICS initialization

For more information about non-terminal security, see "Protecting non-terminal transactions" on page 85.

## The QUERY SECURITY command

In addition to using CICS security checking for CICS-controlled resources (or as an alternative to it), you can use the QUERY SECURITY command to control security access within the CICS application. This method also allows you to define security profiles to RACF for resources other than CICS resource profiles, and enables a more detailed level of security checking than is available through the standard resource classes.

See "RACF general resource profiles" on page 21 for information about the resource classes that RACF supports for resource security checking within transactions. For more information about resource security checking, see Chapter 6, "Resource security," on page 87.

## Intercommunication security

You can connect a number of CICS regions together by using intercommunication; for example, intersystem communication over SNA (ISC over SNA) which uses an SNA access method, such as ACF/VTAM, to provide the required communication protocols. The basic security principles apply to interconnected systems, but the resource definition is more complex and there are additional security requirements.

#### APPC (LU6.2) session security

One of the ISC over SNA protocols that CICS uses is for advanced program-to-program communication (APPC), which is the CICS implementation of the LU6.2 part of the SNA architecture. CICS treats APPC sessions, connections, and partners as resources, all of which have security requirements. CICS provides the following security mechanisms for the APPC environment:

- Bind-time (or session) security prevents an unauthorized remote system from connecting to CICS.
- Link security defines the complete set of CICS transactions and resources that the remote system is permitted to access across the connection.
- User security checks that a user is authorized both to attach a CICS transaction and to access all the resources and SPI commands that the transaction is programmed to use.

See Chapter 12, "Implementing LU6.2 security," on page 163 for more information.

#### Multiregion operation (MRO)

Another means of using intercommunication is multiregion operation (MRO). This is available for links between CICS regions in a single sysplex, independent of the systems network architecture (SNA) access method. See Chapter 16, "Implementing MRO security," on page 219 for information about MRO security.

#### IP interconnectivity (IPIC) security

The security mechanisms for IPIC connections are similar to those provided for APPC (LU6.2) connections, although they are implemented differently:

- Bind-time security prevents an unauthorized remote system from connecting to CICS. On IPCONNs, bind security is enforced by the exchange of Secure Sockets Layer (SSL) client certificates.
- Link security defines the complete set of CICS transactions and resources that the remote system is permitted to access across the IPCONN.
- User security checks that a user is authorized both to attach a CICS transaction and to access all the resources and SPI commands that the transaction is programmed to use. User security is a subset of link security: that is, a user cannot access a resource, even if it is included in the set defined as accessible by his user ID, if is not also included in the set of resources accessible by the link user ID.

For information about IPIC connections, see the *CICS Intercommunication Guide*.

## Generating and using RACF PassTickets

A PassTicket is a program-generated character string that can be used in place of a password, with the following constraints:

- A specific PassTicket may be used for authentication once.
- The PassTicket must be used within 10 minutes of being generated.
- To ease the problem of system time differences, a specific PassTicket can be used up to 10 minutes earlier or later in a target system, compared to the generating system.

Front end programming interface (FEPI) security can generate a PassTicket for use on a target system. The PassTicket can be used anywhere a password can be used.

**Note:** The PassTicket generation and validation algorithm means that the system that creates the PassTicket and the system that validates it must both use the same level of this function. That is, if the creating system has the function applied, and the validating system does not, the PassTicket is invalid.

For more information about the system time differences, and the use of the PassTicket within the 10 minute interval, see the *z*/OS Security Server RACF Security Administrator's Guide.

Use the PTKTDATA resource class to define profiles that contain the encryption key used for generating and validating PassTickets.

A profile is added for each APPLID that receives sign-ons with PassTickets. The format of the command to add profiles is:

RDEFINE PTKTDATA applid

SSIGNON(KEYMASKED(password-key))
KEYENCRYPTED(password-key))

## **Chapter 2. RACF facilities**

CICS uses a number of RACF facilities in order to protect its resources.

## **Overview of RACF facilities**

RACF provides the following facilities:

- The necessary functions to record information identifying individual users of system resources, and information identifying the resources that require protection. The information you define to RACF about users and resources is stored in user and resource **profiles**.
- The facilities to define which users, or groups of users, are either permitted access, or excluded from access, to the resources for which profiles have been defined. The information recording the users, or groups of users, permitted to access any particular resource is held in an **access list** within the profile that protects a resource.
- A method to process requests, issued by subsystems or jobs running in an MVS system, to authenticate the identity of users defined to RACF, and to check their access authorization to resources.
- The facilities for logging security-related events, such as users signing on and signing off, the issuing of RACF commands, and attempts to access protected resources. Successful attempts to access protected resources may be recorded by the MVS System Management Facility (SMF). If you want to record all attempts to access protected resources, whether successful or not, use RACF auditing, as described in the *z/OS Security Server RACF Auditor's Guide*. The RACF auditor can run the RACF report writer to generate reports based on the SMF records. For information on using RACF to perform **auditing** functions (specifying auditing operands on RACF commands, and using the RACF report writer to generate reports of audited security-related activity), see the *z/OS Security Server RACF Auditor's Guide*.

## **RACF** administration

As the security administrator for one or more CICS regions, and for the users of the CICS applications, it is your job to ensure that your installation's data is properly protected.

Using RACF, you are responsible for protecting all system resources, and, in the context of this manual, CICS resources in particular.

A key feature of RACF is its hierarchical management structure. The RACF security administrator is defined at the top of the hierarchy, with authority to control security for the whole system. If you are not yourself the RACF security administrator, you must ask that person to delegate to you sufficient authority to work with RACF profiles and system-wide settings. You must also work with the RACF auditor, who can produce reports of security-relevant activity based on auditing records generated by RACF.

RACF security administrators have either the system-SPECIAL attribute, the group-SPECIAL attribute, or a combination of other authorities.

- If you have the system-SPECIAL attribute, you can issue any RACF command, and you can change any RACF profile (except for some auditing-related operands).
- If you have the group-SPECIAL attribute, your authority is limited to the scope of the RACF group for which you have the SPECIAL attribute.
- The other authorities include:
  - The CLAUTH (class authority) attribute, which allows you to define RACF profiles in specific RACF classes
  - That authority which goes with being the OWNER of existing RACF profiles, allows you to list profiles, change the access, and delete them
  - Having a group authority such as CONNECT or JOIN in a RACF group

For complete information about the authorities required to issue RACF commands, and for information on delegating authority and on the scope of a RACF group, see the *z*/OS Security Server RACF Auditor's Guide.

For information on the RACF requirements for issuing RACF commands, see the descriptions of the commands in the *z*/OS Security Server RACF Command Language Reference.

You can find out whether you have the system-SPECIAL or group-SPECIAL attribute by issuing the LISTUSER command from a TSO session. If you have the system-SPECIAL attribute, SPECIAL appears after the USER ATTRIBUTES phrase in the first part of the output. If you have the group-SPECIAL attribute, SPECIAL appears after the USER ATTRIBUTES phrase in the offset section that describes your connection to a RACF group. For a complete description, with an example of LISTUSER output, see the *z*/OS Security Server RACF General User's Guide.

## Delegation of RACF administrative responsibility

As CICS security administrator, you perform the following tasks (if you do not have the system-SPECIAL attribute, obtain the necessary authority):

• Define and maintain profiles in CICS-related general resource classes. In general, you grant authority to do this by assigning a user the CLAUTH (class authority) attribute in the specified classes. For example, the RACF security administrator could issue the following command:

ALTUSER your_userid CLAUTH(TCICSTRN)

The above command gives access to all classes of the same POSIT number. The POSIT number is an operand of the ICHERCDE macro of the class descriptor table (CDT). For more information, see "Activating the CICS classes" on page 22.

- Define and maintain profiles in other resource classes. Many of the general resource classes mentioned in this book (such as APPL, APPCLU, FACILITY, OPERCMDS, SURROGAT, TERMINAL, and VTAMAPPL) affect the operation of products other than CICS. If you are not the RACF security administrator, you may need to ask that person to define profiles at your request.
- Add RACF user profiles to the system. In general, you grant this authority by assigning the CLAUTH (class authority) attribute for "USER" in the user's profile. For example, the RACF security administrator could issue the following command:

ALTUSER your_userid CLAUTH(USER)

Whenever you add a user to the system, assign that user a default connect group. This changes the membership of the group (by adding the user as a member of the group). Therefore, if you have JOIN group authority in a group, the group-SPECIAL attribute in a group, or are OWNER of a group, CLAUTH(USER) lets you add users to the system and connect them to groups that are within the scope of the group.

• List RACF system-wide settings and work with all profiles related to CICS. You grant authority to do this by setting up a RACF group, ensuring that certain CICS-related RACF profiles are in the scope of that group, and connecting a user to the group with the group-SPECIAL attribute. For example, the RACF security administrator could issue the following command:

CONNECT your_userid GROUP(applicable-RACF_groupid) SPECIAL

With the SETROPTS GENERICOWNER command in effect and with prefixing active, administrators can be assigned. You do this by creating a generic profile in each class using the prefix as a high-level qualifier. For example:

RDEFINE TCICSTRN cics_region_id.** UACC(NONE) OWNER(cics_region_administrator_userid)

The SETROPTS GENERIC command must be used before defining generic profiles, as described in "Summary of RACF commands" on page 27.

For more information on delegating RACF administration, see the *z*/OS Security Server RACF Security Administrator's Guide .

## **RACF** profiles

In RACF, a *profile* describes the security characteristics of a user, a group of users, or one or more computer resources:

#### **User profiles**

A *user profile* is a description of a RACF-defined user. The information in the profile includes the user ID, the user name, the user's password, the profile owner, user attributes, and other data. The user profile also contains user-related information for subsystems, including CICS.

#### Group profiles

A *group profile* defines a group of users. The information in the profile includes the group name, the profile owner, and the users in the group.

#### Data set profiles

A *data set profile* provides RACF protection for one or more data sets. The information in the profile includes the data set profile name, the profile owner, the universal access authority, the access list, and other data.

Data set profiles can be generic or discrete:

- A *generic profile* protects several resources with similar names and identical security requirements.
- A *discrete profile* protects a single resource.

#### General resource profiles

A *general resource profile* provides RACF protection for computer resources, other than data sets. The information in the profile includes the general resource profile name, the profile owner, the universal access authority, the access list, and other data. General resources with similar characteristics belong to the same *class*.

Like a generic profile, a *resource group profile* protects several resources with identical security requirements. However, the resources do not have to

have similar names. Resource group profiles with similar characteristics belong to the same *resource group class*.

Resource profiles can be generic or discrete:

- A *generic profile* protects several resources with similar names and identical security requirements.
- A *discrete profile* protects a single resource.

## **RACF user profiles**

A user profile is a description of a RACF-defined user. The information in the profile includes the user ID, the user name, the user's password, the profile owner, user attributes, and other data. The user profile also contains user-related information for subsystems, including CICS.

The user profiles consists of one or more segments—a RACF segment, and others that are optional. For CICS users, the important segments are:

- The RACF segment, which holds the basic information for a RACF user profile. See "The RACF segment."
- The CICS segment, which holds data for each CICS user. See "The CICS segment" on page 15.
- The LANGUAGE segment, which specifies the user's national language preference. See "The LANGUAGE segment" on page 19.

## The RACF segment

You identify a RACF user by an alphanumeric userid, which RACF associates with the user profile for that user.

The "user" that you define to RACF need not be a person, such as a CICS terminal user. For example, in the CICS environment, a RACF userid can be associated with the procedure you use to start CICS as a started task; and a userid can be associated with a CICS terminal (for the purpose of preset security). The following list shows some of the basic segment information that RACF holds for a user:

#### Keyword

Description

### USERID

The user's userid

#### NAME

The user's name

## OWNER

The owner of the user's profile—the RACF administrator or other user authorized by the administrator, or a RACF group

#### DFLTGRP

The default group that the user belongs to

## AUTHORITY

The user's authority in the default group

#### PASSWORD

The user's password

You define the RACF segment of a user profile using the ADDUSER command, or the RACF ISPF panels. When planning RACF segments of user profiles for CICS users, identify the groups that you want them to be in. Start by identifying RACF administrative units for the users. For example, you could consider all users who have the same manager, or all users within an order entry function, an administrative unit. RACF handles these units as groups of individual users who have similar requirements for access to CICS system resources.

For an overview of the steps required to add users to the system, see the *z*/OS Security Server RACF Security Administrator's Guide.

## The CICS segment

The CICS segment of the RACF user profile contains data for CICS users.

For information on the order in which CICS searches for the operator information, see "Obtaining CICS-related data for a user" on page 76.

The information you can specify in the CICS segment is as follows:

#### **OPCLASS(**{1 | *number*})

CICS uses the operator classes when routing basic mapping support (BMS) messages initiated within a CICS transaction. The operator classes are numeric values in the range 1–24.

Specify operator classes for users who use CICS transactions that issue EXEC CICS ROUTE commands with the (optional) OPCLASS parameter. For automatic routing to occur, you specify the corresponding value as an operator class in the CICS segment of the user profile.

For more information about message routing, see the CICS Application *Programming Guide*.

#### **OPIDENT({blank** *name*})

The 1- to 3-character operator identification code that you assign to each operator.

CICS stores the code in the operator's terminal entry in the CICS terminal control table (TCTTE) when the operator signs on. This operator ID is displayed in certain CICS messages and can also be used in the EXEC CICS ROUTE command for routing BMS messages. It is also used when using the CEDA LOCK command, as described in the *CICS Resource Definition Guide*.

For more information about message routing, see the CICS Application *Programming Guide*.

#### **OPPRTY({0** *number***}**)

The operator priority value—a decimal number that you want CICS to use when determining the task priority for CICS transactions that the operator invokes at a CICS terminal. The priority value can be in the range 0 through 255, where 255 is the highest priority.

CICS uses the sum of operator priority, terminal priority, and transaction priority to determine the dispatching priority of a transaction.

#### **TIMEOUT({0000**|*hhmm*})

The time that must elapse since the user last used the terminal before CICS "times-out" the terminal.

The time must be a decimal integer in the range 0 through 9959 (the last two digits represent a number of minutes, and must be 00 through 59. Any digits to the left of these represent hours).

To specify one hour and eight minutes you would code a value here of 0108. For example:

ALTUSER userid CICS(TIMEOUT(0108))

The value of 0 (the default) means that the terminal is **not** timed out.

#### XRFSOFF({NOFORCE | FORCE})

The CICS persistent sessions restart and extended recovery facility (XRF) sign-off option. You specify this to indicate whether or not you want CICS to sign off the operator following a persistent sessions restart or an XRF takeover.

#### FORCE

Specify FORCE if you want CICS to sign off the operator automatically in the event of a persistent sessions restart or an XRF takeover.

#### NOFORCE

Specify NOFORCE if you want CICS to leave an operator signed on in the event of a persistent sessions restart or an XRF takeover.

You can specify the XRFSOFF function at the level of groups of similar terminals, and at the CICS system level:

- Use the RSTSIGNOFF attribute of the TYPETERM resource definition to specify the XRFSOFF function for groups of similar terminals.
- Use the **XRFSOFF**system initialization parameter to specify the function at the system level.

In both cases, the default value is NOFORCE. If you specify the FORCE option in the system initialization table or the TYPETERM, it overrides a value of NOFORCE specified in the CICS segment.

Table 1 shows how specifying FORCE or NOFORCE in the system initialization parameters, on the TYPETERM definition, and in the CICS segment together determine whether a terminal remains signed on after a persistent sessions restart or an XRF takeover.

As Table 1 shows, for a terminal to remain signed-on after a persistent sessions restart or an XRF takeover, NOFORCE must be specified in all three locations.

TYPETERM definition	CICS segment	System initialization parameter	Resulting terminal status
FORCE	FORCE	FORCE	Signed-off
FORCE	FORCE	NOFORCE	Signed-off
FORCE	NOFORCE	FORCE	Signed-off
FORCE	NOFORCE	NOFORCE	Signed-off
NOFORCE	FORCE	FORCE	Signed-off
NOFORCE	FORCE	NOFORCE	Signed-off
NOFORCE	NOFORCE	FORCE	Signed-off
NOFORCE	NOFORCE	NOFORCE	Signed-on

Table 1. Effects of FORCE and NOFORCE options

**Note:** If takeover has exceeded the time specified by the **XRFSTME** system initialization parameter, users at terminals that have a nonzero TIMEOUT value do not remain signed-on after takeover. For example, suppose the following has been specified in a system that has XRFSOFF=NOFORCE:

ALTUSER USER1 CICS(XRFSOFF(NOFORCE) TIMEOUT(10)) ALTUSER USER2 CICS(XRFSOFF(NOFORCE) TIMEOUT(1))

If a persistent sessions restart or an XRF takeover occurs to a system in which XRFSTME=5 is specified in the system initialization parameters, and the restart or takeover takes longer than five minutes, USER1 does not remain signed-on, but USER2 does.

### Specifying default values in the CICS segment

The defaults listed are effective only when a CICS segment has been defined for that userid.

You can make the CICS segment default by defining it as follows:

```
ADDUSER userid DFLTGRP(group_name) NAME(user_name)
OWNER(group_id|userid)
PASSWORD(password)
CICS
```

For example, you may want to define a CICS segment in this way if you want to enforce the **system** defaults, rather than the default user attributes, or if you are setting up a test system and have not yet decided on the values you want to use.

If you omit the CICS segment completely, defaults are obtained as described in "Obtaining CICS-related data for a user" on page 76.

If you specify some of the CICS segment options, but omit others, the defaults described above apply to the omitted options.

You can remove the CICS segment as follows: ALTUSER *userid* NOCICS

#### Creating or updating segment data for a CICS user

To create or update CICS segment data for a CICS user, specify the CICS option on the RACF ADDUSER command for a new user, or on the ALTUSER command for an existing user.

For example, the following command adds a new CICS user to the RACF database with associated CICS operator data:

ADDUSER userid DFLTGRP(group_name) NAME(user_name) OWNER(group_id) PASSWORD(password) CICS(OPCLASS(1,2,...,n) OPIDENT(identifier) OPPRTY(priority) TIMEOUT(timeout_value) XRFSOFF(NOFORCE)) LANGUAGE(PRIMARY(primary_language))

The following example of the ALTUSER command adds CICS operator data to an existing user in the RACF database:

ALTUSER userid

```
CICS(OPCLASS(1,2,...,n) OPIDENT(identifier) OPPRTY(priori`ty)
TIMEOUT(timeout_value) XRFSOFF(NOFORCE))
LANGUAGE(PRIMARY(primary_language))
```

Before issuing these commands to define CICS operator data, ensure that the CICS-supplied RACF dynamic parse validation routines are installed in an APF-authorized library in the linklist. See "CICS-supplied RACF dynamic parse validation routines" on page 35 for details of these exits.

If you do not have the system-SPECIAL attribute, ask your RACF security administrator for the authority to list or update the CICS and LANGUAGE segments in the user profiles. Listing or updating these segments is done by creating profiles in the RACF FIELD class. For more information, see "Controlling access to fields in RACF profiles" on page 32.

If you want to change the opclass but you do not want to respecify the list, you can use the ADDOPCLASS and DELOPCLASS operands. For example: ALTUSER *userid* 

CICS(ADDOPCLASS (1,2) DELOPCLASS (6,7))

T

1

Т

T

1

Т

1

T

#### Changing the RACF profile of a remote user:

From z/OS 1.11 onwards, CICS is notified of certain changes in the RACF profile of a signed-on remote user or a signed-on user who is not directly using a physical terminal or console through a type 71 RACF Event Notification (ENF). For example, CICS is notified when you use the REVOKE option on the **ALTUSER** command, with no date specified, to revoke a user ID with immediate effect. However, CICS is not notified when a user ID expires. When a RACF profile change occurs and CICS receives a new attach request for a user ID, CICS performs an implicit sign-on for the user ID and the new RACF profile information is used. Existing tasks for that user continue with the RACF profile that was valid when the task was attached.

For systems earlier than z/OS 1.11, the interval that elapses before a remote user ID is deleted is determined by the value in the **USRDELAY** system initialization parameter. For z/OS 1.11 systems, CICS is notified by RACF that the profile has changed.

If you alter the RACF profile of a signed-on remote user, CICS continues to use the authorization established at the first attach request until one of the following situations occurs:

- The transaction performs a sync point.
- You are using a z/OS 1.11 system or above and the attach request ends.
- You are using a system earlier than z/OS 1.11 and the user ID is unused for the time specified in the **USRDELAY** system initialization parameter.

#### CICS default user

When you are using CICS with external security, CICS assigns the security attributes of the CICS *default user* to all CICS terminal users who do not sign on.

CICS also assigns the operator data from the CICS segment of the default user to signed-on users who do not have their own CICS segment data. To enable CICS to assign default security attributes and operator data, you define a CICS default user id to RACF. You then tell CICS which default user to use by specifying the **DFLTUSER** system initialization parameter. If you do not specify a default user id on the **DFLTUSER** parameter, CICS uses the name "CICSUSER."

Whether you use installation-defined operator data on your **DFLTUSER** parameter, or use the default, it is essential that the userid is defined to RACF and that the region user id has installed surrogate security to use the default user (see Chapter 7, "Surrogate user security," on page 113).

CICS "signs on" the default user during system initialization. If you specify SEC=YES as a system initialization parameter, and CICS cannot "sign on" the default userid, CICS initialization fails.

CICS uses the security attributes of the default userid to perform all the security checks for terminal users who do not explicitly sign on. These security checks include **resource** and **command** security checking, in addition to **transaction-attach** security checking.

**Note:** If the default user's RACF profile specifies a non-zero TIMEOUT, that value does **not** apply to terminals that do not sign on.

## The LANGUAGE segment

The language segment holds information about the national language in which the user receives messages.

You can specify two languages, but CICS assigns each user only one language. It assigns the primary language if it is specified and CICS supports that language. If the primary language is not specified or is not supported, CICS assigns the secondary language if it is specified and CICS supports it.

Specify the user's preferred national languages in the LANGUAGE segment of the RACF user profile, using the LANGUAGE parameter on the ADDUSER or ALTUSER command:

#### LANGUAGE

Use this parameter to specify primary and secondary languages for CICS users. CICS accepts and uses the languages you define in the segment, but ignores the RACF system-wide defaults. This is because CICS has its own system default for national languages, which you specify on the CICS system initialization parameter, NATLANG.

#### PRIMARY(primary_language)

This parameter identifies the user's primary language, overriding the system default. Depending on the national language feature you have installed, you can specify this as one of the 3-character codes in Appendix A, "National Language," on page 383.

#### SECONDARY(secondary_language)

This parameter identifies the user's secondary language, overriding the system default. You can specify this as one of the 3-character codes listed in Appendix A, "National Language," on page 383.

For more information about national language, see "National language and non-terminal transactions" on page 79.

## **RACF** group profiles

In addition to defining individual user profiles in RACF, you can define group profiles. A group profile defines a group of users.

A group profile is not the same thing as a resource group profile, which defines a group of resources and is explained in "RACF general resource profiles" on page 21. A group profile can contain information about the group, such as who owns it, which subgroups it has, a list of connected users, and other information. For details of how to define and use group profiles, see the *z*/OS Security Server RACF Security Administrator's Guide.

Users who are members of groups can share common access authorities to protected resources. For example, you might want to set up groups as follows:

- Users who work in the same department
- Users who work with the same sets of transactions, files, terminals, or other resources that you choose to protect with RACF
- Users who sign on to the same regions (if you have more than one CICS region)

In a CICS environment, group profiles offer a number of advantages:

- Easier control of access to resources
- The ability to assign authorities using the group-SPECIAL attribute or CONNECT group authority
- Fewer refreshes to in-storage profiles.

Aim to make your point of control the presence (or absence) of a user ID in a group, not the access list of the resource profile. When someone leaves a department, removing the user ID from the department user group revokes all privileges. No other administration of profiles is required. Thus, you keep RACF administration to a minimum and avoid an excessive number of resource profiles.

RACF maintains in-storage copies of resource profiles, so changes to those profiles do not take effect on the system until the in-storage profiles are refreshed.

The authority to access a resource is kept in an access list that is part of the resource profile. The authority can be granted to a user or to a group. To add or remove a user from the access list, refresh the profile in main storage. For more information, see "Refreshing resource profiles in main storage" on page 22.

If you connect and remove a user from a group that is already in the access list, that user acquires or loses the authority of the group without needing to refresh the profile. Any user with CONNECT group authority in that group can change the membership of the group, using the CONNECT and REMOVE commands. In this way, you do not have to change the access list of the affected profiles (through the use of the PERMIT command). If you do not change a CICS general resource profile, you do not have to refresh its in-storage copy. However, users might have to sign on again, if their group membership has been changed.

For other benefits obtained from creating groups, see the *z*/OS Security Server RACF Security Administrator's Guide.

The following command sequence creates a new group of users and moves a user from an existing group to the new group:

ADDGROUP group_name2 REMOVE user1 GROUP(group_name1) CONNECT user1 GROUP(group_name2)

For systems earlier than z/OS 1.11, the interval that elapses before a remote user ID is deleted is determined by the value in the **USRDELAY** system initialization parameter. For z/OS 1.11 systems, CICS is notified by RACF that the profile has changed.

## **RACF** data set profiles

|

T

Using RACF facilities, you can protect data sets on direct access storage devices (DASD) and tape by defining profiles for the data sets you want to protect.

The rules for defining data set profiles to RACF are described in the *z*/OS Security Server RACF Security Administrator's Guide, and the *z*/OS Security Server RACF Command Language Reference. For examples, see the *z*/OS Security Server RACF General User's Guide.

You define profiles to protect two RACF categories of data sets:

- 1. Profiles for **user data sets**, where the high-level qualifier is a RACF userid. All RACF-defined users can protect their own data sets.
- 2. Profiles for **group data sets**, where the high-level qualifier is a RACF group name (see "RACF group profiles" on page 19 for information about RACF groups). A RACF-defined user can RACF-protect group data sets provided the user has the necessary authority or attributes. (See the *z*/OS Security Server RACF Security Administrator's Guide for details.)

**Note:** Data set profiles do not apply to CICS terminal users, but only to the CICS region userid.

## Generic data set profiles

By using generic profiles, you can reduce the number of profiles needed to protect data sets, and also reduce the required size of the RACF database. In addition, generic profiles are not volume-specific (that is, data sets protected by a generic profile can reside on any volume).

Usually, you specify generic data set profile names by specifying a generic character; for example percent (%) or asterisk (*) in the profile name. For data set profiles, RACF distinguishes between asterisk (*) and double asterisk (**) if RACF's enhanced generic naming is in effect. See the *z/OS Security Server RACF Command Language Reference* for the rules governing generic profile names in the RACF DATASET class.

For example, if you have a group called CICSTS41.CICS, you can define a generic profile named 'CICSTS41.CICS.**', and any user in the access list of this profile can access, at the authorized level, data sets with the high-level qualifier CICSTS41.CICS. For example:

ADDSD 'CICSTS41.CICS.**' UACC(NONE) NOTIFY(admin_userid)

Use the SETROPTS GENERIC command before defining generic profiles, as described in "Summary of RACF commands" on page 27.

**Note:** Examples in this book show double asterisks (**), which require that enhanced generic naming be in effect. If enhanced generic naming is not in effect, use a single asterisk (*) in place of double asterisks. (You put enhanced generic naming into effect by issuing the RACF SETROPTS EGN command. Note that SETROPTS EGN affects only data set names. Enhanced generic naming is always in effect for general resource profiles, such as TCICSTRN.)

## **RACF** general resource profiles

RACF supplies a number of resource classes that CICS uses for its resources.

A *general resource profile* provides RACF protection for computer resources, other than data sets. The information in the profile includes the general resource profile name, the profile owner, the universal access authority, the access list, and other data. General resources with similar characteristics belong to the same *class*.

Like a generic profile, a *resource group profile* protects several resources with identical security requirements. However, the resources do not have to have similar names. Resource group profiles with similar characteristics belong to the same *resource group class*.

They are described in "RACF classes for CICS resources" on page 23. Other RACF resource classes contain profiles that are used for resources that are used by CICS and other subsystems. They are described in "RACF classes for protecting system resources" on page 24.

## Protecting a resource

These are the steps that you must perform in order to protect a resource:

- 1. Define a profile for the resource in a suitable resource class
- 2. Define an *access list* which specifies:
  - the users that are permitted to access the resource
  - the level of access that each user is allowed

## Activating the CICS classes

To activate the CICS resource class for use in security checking by the CICS region, use the RACF **SETROPTS** command.

As soon as the CICS resource class is defined in the active RACF class descriptor table, administrators can define general resource profiles to the class. For more information, see the descriptions of RDEFINE and PERMIT in "RACF general resource profiles" on page 21. Note that the class must be activated before the CICS system can use the profiles that the administrators define.

The format of the SETROPTS command is SETROPTS CLASSACT(*classname*). For example:

SETROPTS CLASSACT(TCICSTRN)

All sets of RACF general resource classes that have the same POSIT number in their CDT definitions are activated and deactivated together. Therefore, you need only specify one IBM-supplied CICS class to activate all the IBM-supplied CICS-related classes. If you define your own installation-defined classes with the same POSIT number as the IBM-supplied classes, they are activated and deactivated with the IBM-supplied classes. To provide separate controls for sets of installation-defined classes, define them with different POSIT numbers. (For more information on the POSIT number, see the *z*/OS Security Server RACF Macros and Interfaces manual.)

## Refreshing resource profiles in main storage

Refresh the classes defined in RACLIST by using the TSO command: SETROPTS RACLIST(*xxxxxxx*) REFRESH

where *xxxxxxxx* is the RACF class to be refreshed; for example TCICSTRN. A **CENT PERFORM SECURITY REBUILD** command gives a response of NOT REQUIRED.

After adding or updating a profile, either for a member class or a resource grouping class, you must issue the command: SETROPTS RACLIST (TCICSTRN) REFRESH Even if you have added the profile to the GCICSTRN resource grouping class, you must issue this command for the TCICSTRN member class only. When you use this command, the definitions are updated in RACF and CICS uses the changed profiles.

# **RACF classes for CICS resources**

To protect a CICS resource, you must create a general resource profile for the resource in a suitable class or resource grouping class. RACF provides several classes for CICS resources. You can also define your own resource classes.

# Note:

T

1

T

L

1

- 1. The initial character of the class names is significant when you define your own classes. For example, if you define your own classes for CICS programs, the names you choose must start with M and N for the member class and the resource grouping class respectively.
- 2. There are no default resource class names for DB2ENTRY resources. You must define your own resource classes for these resources. See "Resource classes for DB2ENTRYs" on page 27 for more information.
- **3**. Profile names in the RCICSRES class must contain a prefix that specifies the CICS resource type to which they apply: ATOMSERVICE.*name* for ATOMSERVICE definitions, BUNDLE.*name* for bundles, DOCTEMPLATE.*name* for CICS document templates, EVENTBINDING.*name* for event bindings, or XMLTRANSFORM.*name* for XML transforms.

Member class	Resource grouping class	Description	
TCICSTRN	GCICSTRN	CICS transactions, normal attach security	
PCICSPSB	QCICSPSB	CICS PSBs	
ACICSPCT	BCICSPCT	CICS-started transactions and the following EXEC CICS commands: COLLECT STATISTICS TRANSACTION DISCARD TRANSACTION INQUIRE TRANSACTION SET TRANSACTION	
DCICSDCT	ECICSDCT	CICS transient data queues	
FCICSFCT	HCICSFCT	CICS files	
JCICSJCT	KCICSJCT	CICS journals	
MCICSPPT	NCICSPPT	CICS programs	
SCICSTST	UCICSTST	CICS temporary storage queues	
CCICSCMD	VCICSCMD	EXEC CICS SYSTEM commands and EXEC CICS FEPI system commands	
RCICSRES	WCICSRES	Document templates, bundles, event bindings, ATOMSERVICE definitions, and XML transforms	

Table 2. RACF—provided resource classes for CICS resources

# **RACF classes for CICSPlex SM resources**

Protection for CICSPlex SM resources is provided by the following general resource classes:

# **CPSMOBJ**

Controls access to CICSPlex SM resources. The corresponding resource

group class is GCPSMOBJ. For more information, see Chapter 25, "Implementing CICSPlex SM security," on page 341.

### **CPSMXMP**

Controls exemption from simulated CICS security checking in CICSPlex SM. For more information, see "Exempting users and resources from security checking" on page 368

# **RACF** resource class names

By using the resource group profiles, you can reduce the number of profiles you need to maintain in the resource classes.

Further, provided you avoid defining duplicate member names, using this method reduces the storage requirements for the RACF in-storage profiles that CICS builds during initialization.

RACF provides an in-storage checking service to avoid the I/O operations that would otherwise be needed in RACF. (It does this by means of the RACROUTE REQUEST=FASTAUTH macro.) For this purpose, CICS requests RACF to bring its resource profiles into main storage during CICS initialization.

To make administration easier, avoid defining duplicate profiles. If duplicates are encountered as RACF loads the profiles into storage, it merges the profiles according to the ICHRLX02 selection exit. If no selection exit is installed, RACF follows the default merging rules as indicated in the RLX2P data area. For more information about this, see Resolving Conflicts among Multiple Profiles in the *z/OS Security Server RACF Security Administrator's Guide*.

# **RACF** classes for protecting system resources

CICS uses many system resources, and these must be protected against unauthorized access. This protection is provided by profiles in several general resource classes.

#### APPCLU

Verifies the identity of APPC partner logical units (LU type 6.2) during VTAM session establishment. For more information, see "Defining profiles in the APPCLU general resource class" on page 164.

APPL Controls terminal users' access to VTAM applications, including CICS. For more information, see "Authorizing access to the CICS region" on page 51.

### CONSOLE

Controls user access to consoles. For more information, see "Console profiles" on page 69.

### DIGTCERT

Contains digital certificates, and related information. For more information, see "Creating new RACF certificates" on page 267.

### **EJBROLE**

Contains security roles used for enterprise bean security roles. The corresponding resource group class is GEJBROLE. For more information, see *Java Applications in CICS*.

### FACILITY

The FACILITY general resource class is used to protect several different system resources. These are described in "Resources protected by the FACILITY general resource class" on page 26.

FIELD Controls access to fields in RACF profiles. For more information, see "Controlling access to fields in RACF profiles" on page 32.

### IDIDMAP

The IDIDMAP resource profile contains the distributed identity filter. RACF uses the term *distributed identity filter* to describe a mapping association between a RACF user ID and one or more distributed identities. For more information, see "Configuring RACF for identity propagation" on page 305.

### **JESSPOOL**

Protects JES spool data sets. For more information, see "JES spool protection in a CICS environment" on page 54.

#### LOGSTRM

Controls access to the MVS logstreams that CICS uses for its system logs and general logs. For more information, see "Authorizing access to MVS log streams" on page 42.

#### **OPERCMDS**

- Controls which console users are allowed to issue MODIFY commands directed to particular CICS regions. For more information, see "Using an MVS system console as a CICS terminal" on page 74.
- Controls which operator commands CICS can issue; for example, commands in the command list table (CLT), and MODIFY network commands.

## PROGRAM

Controls which users can start CICS. For more information, see "Protecting CICS load libraries" on page 36.

# PROPCNTL

Prevents the CICS region userid being propagated to jobs that are submitted from CICS to the JES internal reader, and that do not specify the USER operand. For more information, see "Controlling userid propagation" on page 53.

### PTKTDATA

Contains the encryption keys used for generating and validating PassTickets. For more information, see "Generating and using RACF PassTickets" on page 10.

### SERVAUTH

Define profiles in the SERVAUTH general resource class to establish a trust relationship between servers when using asserted identity authentication for IIOP clients. For more information, see "Authentication" on page 248.

### STARTED

Contains profiles that provide the userids for MVS started jobs. For more information, see "Using STARTED profiles for started jobs" on page 38.

#### **SUBSYSNM**

Authorizes subsystems (such as instances of CICS) to open a VSAM ACB and use VSAM Record Level Sharing (RLS) functions. For more information, see "Authorizing access to SMSVSAM servers" on page 50.

### SURROGAT

Specifies which userids can act as surrogates for other userids. For more information, see Chapter 7, "Surrogate user security," on page 113.

### TERMINAL

Controls the ability of users to sign on at individual terminals. The

corresponding resource group class is GTERMINL. For more information, see "Preset terminal security" on page 70.

### VTAMAPPL

Controls the ability of users to open a VTAM ACB. For more information, see "Controlling the opening of a CICS region's VTAM ACB" on page 52.

# **Resources protected by the FACILITY general resource class**

The FACILTY general resource class is used to protect several different system resources.

They are:

## Library lookaside (LLA) libraries

The FACILITY class controls a program's ability to use the LLACOPY macro. For more information, see "Authorizing access with the MVS library lookaside (LLA) facility" on page 46.

### The CICS interregion communication program, DFHIRP

The FACILITY class controls a region's ability to log on to the CICS interregion communication program, DFHIRP. For more information, see Chapter 16, "Implementing MRO security," on page 219.

## Shared data tables

The FACILITY class controls a file-owning region's ability to act as a shared data table server. For more information, see "Security for CICS shared data tables" on page 233.

### Coupling facility data tables

The FACILITY class controls the following:

- The ability of a CICS region to connect to a coupling facility data table (CFDT)
- The ability of the CFDT server to act as a server for a CFDT pool
- The ability of the CFDT server region to connect to the coupling facility list structure for its CFDT pool

ability of a coupling facility data table (CFDT) server to act as a server for a CFDT pool. It also controls the server's access to the coupling facility list structure for the pool. For more information, see "Security for coupling facility data tables" on page 236.

# Named counter servers

The FACILITY class controls the following:

- The ability of a CICS region to connect to a named counter server
- The ability of the named counter server to act as server for a named counter pool
- The ability of the named counter server region to connect to the coupling facility list structure for its named counter pool

For more information, see "Authorizing access to named counter pools and servers" on page 48.

# Shared temporary storage

The FACILITY class controls the following:

- The ability of a CICS region to connect to a shared temporary storage (TS) server
- The ability of the shared TS server to act as server for a shared TS pool
- The ability of the shared TS server region to connect to the coupling facility list structure for its shared TS pool

For more information, see "Authorizing access to the temporary storage pools" on page 47.

### Log streams

The FACILITY class controls the ability of a CICS region to connect to the coupling facility list structures used for MVS log streams. For more information, see "Authorizing access to MVS log streams" on page 42.

# AUTHTYPE and COMAUTHTYPE userids in DB2[®] definitions

The FACILITY class controls the following:

- The ability of users to install DB2CONN and DB2ENTRY definitions that specify the AUTHID or COMMAUTHID attributes
- The ability of users to use a CREATE DB2CONN or CREATE DB2ENTRY command that specifies the AUTHID or COMMAUTHID attributes
- The ability of users to change the AUTHID or COMMAUTHID attributes of an installed DB2CONN or DB2ENTRY

For more information, see the CICS DB2 Guide.

# CICSPlex[®] SM resources

The FACILITY class controls access to a many CICSPlex SM resources. For more information, see Chapter 25, "Implementing CICSPlex SM security," on page 341.

# **Resource classes for DB2ENTRYs**

CICS supports resource security checking for CICS-defined DB2ENTRY resources, for which there are no IBM-supplied RACF resource classes.

For DB2ENTRYs, you define security profiles in user-defined class names, and use the XDB2 system initialization parameter to specify the class name to CICS. The syntax for the XDB2 system initialization parameter is XDB2=NO|*name*, which does not support a default class name like the other security system initialization parameters. Use the DFH\$RACF sample job as an example of how to define DB2 resource class names for CICS use.

Do not use one of the CICS default resource classes in which to define DB2ENTRY profiles. CICS uses RACLIST to activate the profiles in the default resource classes according to the *Xname* system initialization security parameters you specify, and XDB2 should specify a user-defined class name defined specifically for DB2ENTRY resources.

# Summary of RACF commands

Much of the RACF activity dealing with protected CICS resources involves creating, changing, and deleting **general resource profiles**.

### Note:

- 1. The commands described here, and the operands used in the examples, are not exhaustive.
- 2. The sequences of commands shown here demonstrate one way to accomplish a given task. There may be other sequences of commands that you can use.

For full details of RACF commands, refer to *z/OS Security Server RACF Command Language Reference* 

### Creating general resource profiles

To create a general resource profile, use the RDEFINE command. Generally, once you have created a profile, you then create an access list for the profile using the PERMIT command.

In this example, the three RDEFINE commands define three profiles named CEMT, CEDA, and CEDB in the TCICSTRN resource class. The three PERMIT commands allow two groups of users to access each transaction:

RDEFINE TCICSTRN CEMT UACC(NONE) NOTIFY(*sys_admin_userid*) RDEFINE TCICSTRN CEDA UACC(NONE) NOTIFY(*sys_admin_userid*) RDEFINE TCICSTRN CEDB UACC(NONE) NOTIFY(*sys_admin_userid*) PERMIT CEMT CLASS(TCICSTRN) ID(*group1, group2*) ACCESS(READ) PERMIT CEDA CLASS(TCICSTRN) ID(*group1, group2*) ACCESS(READ) PERMIT CEDB CLASS(TCICSTRN) ID(*group1, group2*) ACCESS(READ)

### Creating a resource group profile

To define a profile in a resource grouping class, use the RDEFINE command with the ADDMEM operand to add resources as members of the group. Generally, once you have created a profile, you then create an access list for the profile using the PERMIT command.

In this example, the RDEFINE command defines a resource group profile named CICSTRANS in the GCICSTRN resource grouping class. The PERMIT command allows two groups of users to access all transactions in the profile.

RDEFINE GCICSTRN CICSTRANS UACC(NONE)

ADDMEM(CEMT, CEDA, CEDB)

NOTIFY(*sys_admin_userid*) PERMIT CICSTRANS CLASS(GCICSTRN) ID(*group1*, *group2*) ACCESS(READ)

### Creating a general resource profile

Use the RDEFINE command to create a profile in a general resource class: RDEFINE *class profile* UACC(NONE)

where:

*class* is the name of the general resource class *profile* is the name of the new profile

Specify UACC(NONE) to ensure that there is no default access to the profile.

### Permitting access to a general resource

To permit access to a general resource, use the PERMIT command to create an access list for the general resource profile:

PERMIT profile CLASS(class) ID(user) ACCESS(authority)

where:

*profile* is the name of the new profile

*class* is the name of the general resource class

*user* is the user (or group of users) that is being given access authority to the resource

authority is the level of authority that is being granted to the user

### Removing an entry from an access list

To remove the entry for a user or group from an access list, issue the PERMIT command with the DELETE operand instead of the ACCESS operand:

#### PERMIT profile_name CLASS(class_name) ID(user[group) DELETE

### Changing a profile

If you want to change a profile (for example, changing UACC from NONE to READ), use the RALTER command:

RALTER class_name profile_name UACC(READ)

### Deleting a profile

To delete a profile, use the RDELETE command. For example:

RDELETE class_name profile_name

### Copying from a profile

You can copy an access list from one profile to another. To do so, specify the FROM operand on the PERMIT command:

You can copy information from one profile to another. To do so, specify the FROM operand on the RDEFINE or RALTER command:

RDEFINE class_name profile_name FROM(existing-profile name) FCLASS(class name)

**Note:** Do not plan to do this if you are using resource group profiles. RACF does not copy the members (specified with the ADDMEM operand) when copying the profile. Also, there are other ways in which the new profile might not be an exact copy of the existing profile. For example, RACF places the userid of the resource profile owner in the access list with ALTER access authority. For complete information, see the description of the FROM operand on the appropriate commands in the *z/OS Security Server RACF Command Language Reference*.

### Listing profiles in a class

To list the names of profiles in a particular class, use the SEARCH command. The following command lists profiles in the TCICSTRN class: SEARCH CLASS(TCICSTRN)

The following command lists all profiles and their details in the GCICSTRN class:

SEARCH CLASS(GCICSTRN) RLIST GCICSTRN * ALL

For information on resource classes, see "RACF general resource profiles" on page 21.

**Note:** If you are a group-SPECIAL user (not system-SPECIAL), the SEARCH command might not list all the profiles that exist in a class. To get a complete list of profiles in a class, you must have at least the authority to list each profile. For further information, see the description of RACF requirements for the SEARCH command in the *z*/*OS Security Server RACF Command Language Reference*, and "Which profile is used to protect the resource?" on page 327.

### Activating protection for a class

To begin protecting all the resources protected by profiles in a RACF class, activate that class by issuing the SETROPTS command with CLASSACT specified:

SETROPTS CLASSACT(class_name)

### Defining a generic profile

Before you can use RDEFINE to define a generic profile (that is, one that uses an asterisk (*), double asterisk (**), ampersand (&), or percentage (%) character), first issue the command:

SETROPTS GENERIC(class_name)

### Deactivating protection for a class

Deactivating a class turns off protection without disturbing the profiles themselves. If a class is deactivated, RACF issues a "not protected" return code to CICS for **all resources** in that class. CICS treats this response as "access denied". To deactivate a RACF class, issue the SETROPTS command with NOCLASSACT specified:

SETROPTS NOCLASSACT(class_name)

#### **Determining active classes**

To determine which RACF classes are currently active, issue the SETROPTS command with LIST specified:

SETROPTS LIST

### Activating support for mixed case passwords

To turn support for mixed case passwords on, issue the SETROPTS command with PASSWORD specified: SETROPTS PASSWORD(MIXEDCASE)

To turn support for mixed case passwords off, issue the SETROPTS command: SETROPTS PASSWORD(NOMIXEDCASE)

Mixed case passwords are supported in z/OS Security Server (RACF) 1.7 and above.

# Security classification of data and users

RACF gives you the means to classify some or all of the resources on your system. You can use security levels, security categories, or both, to protect any CICS-related resource.

Consider classifying resources if you want to control access to them without having to specify access lists in each resource profile. If you classify a resource, only users whose user profiles are appropriately classified will be able to access that resource. For information on using security levels and security categories, see the *z/OS Security Server RACF Security Administrator's Guide*. Because CICS uses the RACROUTE REQUEST=FASTAUTH function, some services such as security labels and global access checking are not available under CICS. See the *z/OS Security Administrator's Guide* for information on what is available with FASTAUTH.

You can also put users with the same access or logging requirements into groups. A user can belong to one or more groups, one of which is their default. The sign-on process allows the user to override the default RACF user group name. If "list of groups checking" is inactive, signing on with different group names might give a user different authorities.

# Defining your own resource classes

You can define your own resource classes so that you have a unique resource class name for each CICS region.

Defining your own resource class names can have the following benefits:

### Controlling access from other regions

You can prevent users running in one CICS region from accessing the resources of other CICS regions that have different class names specified. (You can also do this by using prefixing; see the description of the SECPRFX parameter in "Security-related system initialization parameters" on page 55.)

### Group administrator for each region

For each CICS region with installation-defined classes, you can authorize a different group administrator to create profiles to be used by that region.

To get this benefit, define the installation-defined classes with a POSIT number other than 5 (the POSIT number of the IBM-supplied CICS classes). Then give the group administrator the CLAUTH (class authority) for at least one of those classes.

Use the SETROPTS GENERIC command before defining generic profiles, as described in "Summary of RACF commands" on page 27.

With prefixing active, you can also assign different administrators without fear of conflict. To do this, create a generic profile in each class, using the prefix as a high-level qualifier. For example:

RDEFINE TCICSTRN cics_region_id.** UACC(NONE) OWNER(cics_region_administrator_userid)

The administrator specified as the OWNER of each such profile can create and maintain more specific profiles. The other administrators cannot do so.

**Note:** If you are running CICS with XRF, think of the active CICS and its alternate as one CICS system as far as RACF is concerned, and define the same resource class names to both the active and alternate CICS region.

# Setting up installation-defined classes

To set up installation-defined classes, work with your RACF system programmer to add new class descriptors to the installation-defined part (module ICHRRCDE) of the RACF class descriptor table (CDT).

For an example of how to add installation-defined classes to the CDT, see Chapter 23, "Customizing security processing," on page 313.

All installation-defined classes defined in the CDT must also be defined in the MVS router table. This is because the MVS router checks any class used in a router request to determine if it exists. If it does not, no request is sent to RACF. To define classes to the MVS router, add them to ICHRFR01, the user-modifiable portion of the MVS router table, as described in the *z/OS Security Server RACROUTE Macro Reference*. Also see "Specifying user-defined resources to RACF" on page 318.

When setting up installation defined classes, we recommend that you copy the IBM-supplied defaults from the CDT, an example of which is in the *z/OS Security Server RACF Macros and Interfaces* manual. You will then need to change the name, group or member name, POSIT number, and ID. See the description of the

ICHERCDE macro in the *z/OS Security Server RACF Macros and Interfaces* manual for details of valid values for these operands. See the same manual for information about creating installation-defined resource classes. For an example of how to add resource classes, see the IBM-supplied sample, DFH\$RACF, which is in CICSTS41.CICS.SDFHSAMP.

For CICS resources, the first character of the resource class name is predefined by CICS, consistent with the default resource class name. You can define the second through eighth characters of the resource class name, but for ease of administration it is recommended that you specify the same characters for both the member and group class. The seven characters specified for the member class are the part of the resource class name you define to CICS in the various *Xname* parameters, except for the following:

- XDB2, which has no CICS-defined prefix letter, so any defined class name of 1to 8-characters can be specified. It is recommended that you use a specific class or classes dedicated to these resources.
- XAPPC and XUSER, which have no "name" option, and are either YES or NO to say whether security is active or not.

You should avoid using the letters "CICS" in the second through fifth characters in any class name you define. RACF requires that at least one of the characters in the classname should be a national or numeric character.

# Controlling access to fields in RACF profiles

Use the FIELD resource class to define profiles that control access to fields in the RACF database.

By creating profiles in the RACF FIELD class, in the following form, you can permit listing or updating of the CICS or LANGUAGE segments in the user profiles, and of appropriate fields in partner-LU profiles.

USER.CICS.OPIDENT USER.CICS.OPCLASSN USER.CICS.OPPRTY USER.CICS.TIMEOUT USER.CICS.XRFSOFF USER.LANGUAGE.USERNL1 USER.LANGUAGE.USERNL2 APPCLU.SESSION.SESSKEY APPCLU.SESSION.KEYINTVL APPCLU.SESSION.SLSFLAGS

Alternatively, you can set up a generic profile USER.CICS.**, to control access to all fields in the CICS segment. Before defining generic profiles use the SETROPTS GENERIC command, as described in "Summary of RACF commands" on page 27.

You need READ access to list these profiles, and UPDATE access to change them. For further guidance, see the section on field level access checking in the *z*/OS *Security Server RACF Security Administrator's Guide*.

# Part 2. Implementing RACF protection in a single CICS region

This part explains how to protect CICS resources in a single CICS region.

# Chapter 3. CICS system resource security

This topic describes how to protect the system resources that CICS requires.

# **CICS installation requirements for RACF**

You can control access to the resources used by your CICS region (or regions) by using RACF facilities. The CICS libraries supplied on the distribution volume include the CICS modules you need to support external security management.

# **CICS-supplied RACF dynamic parse validation routines**

To define CICS terminal operator data, use the CICS-supplied RACF dynamic parse validation routines. Install these routines in SYS1.CICSTS41.CICS.SDFHLINK, which should be made an APF-authorized library in your MVS linklist.

For more information, see the CICS Transaction Server for z/OS Installation Guide.

The routines are as follows:

# DFHSNNFY

CICS segment update notification

### DFHSNPTO

CICS segment TIMEOUT print formatting

# DFHSNVCL

CICS segment OPCLASS keyword validation

### DFHSNVID

CICS segment OPIDENT keyword validation

#### DFHSNVPR

CICS segment OPPRTY keyword validation

### **DFHSNVTO**

CICS segment TIMEOUT keyword validation

# Using RACF support in a multi-MVS environment

If you are operating a multi-MVS environment with shared DASD, which is probably the case if you are running CICS with XRF, you are likely to want the active and alternate CICS systems to have access to the same terminal user characteristics.

You can enable this by having the active and alternate CICS systems share the same RACF database.

# Setting options on the MVS program properties table

If you have an entry for the DFHSIP program in your MVS program properties table (PPT), ensure that the NOPASS option is **not** set for DFHSIP in the PPT statement of the SCHEDxx member of the SYS1.PARMLIB library. Setting the NOPASS option would bypass password and RACF authorization checking on data sets accessed by the CICS region. For more information about specifying CICS MVS PPT options, see the *CICS Transaction Server for z/OS Installation Guide*.

# **Protecting CICS load libraries**

Although, in general, CICS runs in unauthorized state, the CICS initialization program, DFHSIP, must run in authorized state for part of its execution. For this reason, the version of the DFHSIP module supplied on the distribution tape is link-edited with the "authorized" attribute (using the linkage-editor SETCODE AC(1) control statement), and is installed in CICSTS41.CICS.SDFHAUTH. This library must be defined to the operating system as APF-authorized.

To prevent unauthorized or accidental modification of

CICSTS41.CICS.SDFHAUTH, make this library RACF-protected. Without such protection, the integrity and security of your MVS system are at risk. To control the unauthorized startup of a CICS system using DFHSIP, also consider implementing the following:

- If DFHSIP is in a library that has been placed in the MVS link list, protect DFHSIP with a profile in the PROGRAM resource class. Give READ access to this profile only to those users who are allowed to execute CICS.
- If DFHSIP has been placed in the link pack area (LPA), it cannot be protected by the PROGRAM resource class. Instead, control the startup of CICS by controlling the loading of any suffixed DFHSIT load module. Ensure that no DFHSIT load module is included in the LPA, then control the loading of DFHSIT by creating a generic 'DFHSIT*' profile in the PROGRAM resource class. Give READ access to this profile only to those users who are allowed to execute CICS.

Also give RACF protection to SYS1.CICSTS41.CICS.SDFHLINK and to SYS1.CICSTS41.CICS.SDFHLPA; and the other libraries (including CICSTS41.CICS.SDFHLOAD) that make up the STEPLIB and DFHRPL library concatenations.

See "Authorizing access to CICS data sets" on page 43 for more information about protecting CICS data sets and creating suitable data set security profiles.

**Note:** The source statements of your application programs are sensitive; consider having RACF protect the data sets containing them.

# Specifying the CICS region userid

When you start a CICS region (either as a job or as a started task) in an MVS environment that has RACF installed, the job or task is associated with a userid, referred to as the **CICS region userid**.

The authority associated with this userid determines which RACF-protected resources the CICS region can access.

Each CICS region, for either production or test use, should be subject to normal RACF data set protection based on the region userid under which the CICS region executes. You specify the region userid under which CICS executes in one of three ways:

### As a started task:

• In the RACF started procedures table, ICHRIN03, when you start CICS as a started task using the MVS START command. (See "Authorizing CICS procedures to run under RACF" on page 37.) However, do not assign the "trusted" or "privileged" attributes to CICS entries in the started procedures

table. For more information, see the description of associating MVS started procedures with userids in the *z*/*OS Security Server RACF System Programmer's Guide*.

As a started job:

• In a STARTED general resource class profile, on the user parameter of the STDATA segment.

As a job:

• On the USER parameter of the JOB statement when you start CICS as a JOB.

To ensure the authorizations for different CICS regions are properly differentiated, run each with a unique region userid. For example, the userid under which you run the production CICS regions to process payroll and personnel applications should be the only CICS userid authorized to access production payroll and personnel data sets.

If you are using intercommunication, it is particularly important to use unique userids, unless you want to bypass link security checking. For more information, see "Link security with LU6.2" on page 167, "Link security with LU6.1" on page 205, or "Link security with MRO" on page 222, depending on the environment you are using.

# Using protected user IDs

If you run CICS as a started task, consider defining the CICS region user ID and the CICS default userid as protected user IDs.

Protected user IDs cannot be used to enter the system by any means that requires a password, such as logging on to TSO, signing on to CICS, or running a batch job that specifies a password on the JOB card. Users cannot, by inadvertently or deliberately entering an incorrect password, cause a protected user ID to be revoked.

To create a protected user ID, specify the NOPASSWORD and NOIDCARD options attributes on the user profile. For more information about protected user IDs, see *z*/*OS Security Server RACF Security Administrator's Guide*.

# Authorizing CICS procedures to run under RACF

You can invoke your CICS startup procedure to start CICS as a started task or as a started job. RACF provides the ICHRIN03 procedure table for started tasks, and the STARTED general resource class for started jobs. Both options are discussed here:

# Using the ICHRIN03 table for started tasks

If you run CICS as a started task, you should associate the cataloged procedure name with a suitably authorized RACF user through the RACF table, ICHRIN03.

RACF supplies a default ICHRIN03 table, which you can modify. See the *z*/OS *Security Server RACF System Programmer's Guide* for more information about this table, and how you can add the default entry for the cataloged procedure name for starting CICS.

If your ICHRIN03 table contains the default entry, you need not update the table; but define a RACF user with the same name as the cataloged procedure.

If your ICHRIN03 table does not contain the default entry (or you choose not to set the default entry), update the table with an entry that contains the cataloged procedure name and its associated RACF user. This RACF user need not have the same name as the cataloged procedure.

Whether your ICHRIN03 table contains the default entry or a specific entry you have defined, ensure that the RACF user identified through ICHRIN03 has the necessary access authority to the data sets in the cataloged procedure.

For example, if you associate a cataloged procedure called DFHCICS with the RACF userid CICSR, the userid CICSR needs to have access to the CICS resources accessed by the task started by DFHCICS.

# Using STARTED profiles for started jobs

If you start your CICS regions as started jobs, you can use separate userids for each started region, even though they are all started from the same procedure. Alternatively, you can use generic profiles for groups of CICS regions that are to share the same userid—for example, for all regions of the same type, such as terminal-owning regions.

The support for started jobs is provided by the RACF STARTED general resource class, and its associated STDATA segment. You define profiles in this class for each job, or group of jobs, that needs to run under a unique userid.

Ensure that the userids specified in STDATA segments are defined to RACF. Also ensure that the userids are properly authorized to the data set profiles of the CICS regions that run under them.

# Example of a generic profile for multiple AORs

The following example shows how to define a generic profile for jobs that are to be started using a procedure called CICSTASK.

In this example the job names begin with the letters CICSDA for a group of CICS application-owning regions (AORs): RDEFINE STARTED (CICSTASK.CICSDA*) STDATA(USER(CICSDA##))

When you issue the START command to start CICSTASK with a job name of, say, CICSDAA1, MVS passes the procedure name (CICSTASK), and the job name (CICSDAA1) in order to obtain the userid under which this CICS application-owning region is to run. In the example shown above, the CICS region userid is defined as CICSDA##, for all regions started under the generic profile CICSTASK.CICSDA*.

# Example of a unique profile for each region

The following example shows how to define a unique profile for jobs that are to be started using a procedure called CICSTASK, and where each started job is to run under a unique CICS region userid:

RDEFINE STARTED (CICSTASK.CICSDAA2) STDATA( USER(CICSDAA2) )

When you issue the START command to start CICSTASK with the job name CICSDAA2, MVS passes the procedure name (CICSTASK) and the job name (CICSDAA2) to obtain the userid under which this CICS application-owning region is to run. In the example shown above, the CICS region userid is defined as CICSDAA2, the same as the APPLID.

# Defining user profiles for CICS region userids

Before bringing up a CICS region, ensure that the required userids are defined - the CICS region userid and the CICS default userid.

If you are suitably authorized, you can define a RACF user profile for a CICS region by means of the ADDUSER command. For example, to define CICSR as a userid for a CICS region, enter the following RACF command from TSO: ADDUSER CICSR NAME(user-name) DFLTGRP(cics region group)

In this example, DFLTGRP has been specified, so the initial password is the DFLTGRP name. If you do not specify DFLTGRP, the password is set by default to the name of the group to which the person issuing the ADDUSER command belongs. Alternatively, you can specify a password explicitly on the PASSWORD parameter of the ADDUSER command. See "Coding the USER parameter on the CICS JOB statement" for details about changing new userid passwords.

**Do not assign the OPERATIONS attribute to CICS region userids**. Doing so would allow the CICS region to access RACF-protected data sets for which no specific authorization has been performed. CICS region userids do not need the OPERATIONS attribute if the appropriate CONNECT or PERMIT commands have been issued. These commands authorize the CICS region userid for each CICS region to access only the specific data sets required by that region.

# Coding the USER parameter on the CICS JOB statement

If you start CICS from a job, include the parameters USER= and PASSWORD= on the JOB statement.

For example: //CICSA JOB ... ,USER=CICSR,PASSWORD=password

When you define a new user to RACF, the password is automatically flagged as expired. For this reason, the first time you start CICS under a new userid, change the PASSWORD parameter on the JOB statement. For example: PASSWORD=(oldpassword,newpassword)

If you want to avoid specifying the password on the JOB statement, you can allow a surrogate user to submit the CICS job. A surrogate user is a RACF-defined user who is authorized to submit jobs on behalf of another user (the original user), without having to specify the original user's password. Jobs submitted by a surrogate user execute with the identity of the original user. See "Surrogate job submission in a CICS environment" on page 53 for more information. The region userid must also have surrogate authority to use the default user; see Chapter 7, "Surrogate user security," on page 113.

# Authorities required for CICS region userids

The CICS control program runs under the CICS region userid.

Therefore, this userid needs access to all the resources that CICS itself needs to use. There are two types of these resources:

- 1. Resources external to CICS, such as data sets, the spool system, and the VTAM network.
- 2. Resources internal to CICS, such as system transactions and auxiliary userids.

# Authorizing external resources

Like a batch job, each CICS region must be able to access many external resources.

The authority for CICS to access these resources is obtained from the CICS region userid. It doesn't matter which signed-on user requests CICS to perform the actions that access these resources. The external services are aware only that CICS is requesting them, under the region userid's authority.

Give access to these resources:

The MVS system logger

CICS needs authority to use log streams defined in the MVS logger. See "Authorizing access to MVS log streams" on page 42.

• External data sets used by CICS

CICS needs authority to open all the data sets that it uses. See "Authorizing access to CICS data sets" on page 43.

• External data sets used by application programs

CICS needs authority to open all the data sets that your own application programs need. See "Authorizing access to user data sets" on page 46.

Temporary storage servers

CICS needs authority to access temporary storage servers if any TS queues are defined as shared. See "Authorizing access to temporary storage servers" on page 47.

• SMSVSAM servers

CICS needs authority to access the SMSVSAM server if you are using VSAM record-level sharing (RLS). See "Authorizing access to SMSVSAM servers" on page 50.

VTAM applications

Consider carefully for each program whether you will allow it to become a VTAM application. If you do this, CICS needs authority to open its VTAM ACB. See "Controlling the opening of a CICS region's VTAM ACB" on page 52.

• Jobs submitted to the internal reader

If any of your applications submit JCL to the JES internal reader, you should prevent CICS from allowing them to be submitted without the USERID parameter. See "Controlling userid propagation" on page 53.

However, you should not usually require your applications to provide a PASSWORD parameter on submitted jobs. So you **should** allow CICS to be a surrogate user of all the possible userids that may be submitted. See "Surrogate job submission in a CICS environment" on page 53.

• System spool data sets

CICS needs authority to access data sets in the JES spool system. See "JES spool protection in a CICS environment" on page 54.

# Authorizing internal resources

There are several internal functions in which CICS behaves like an application program, but is performing housekeeping functions that are not directly for any end user. The associated transactions execute under control of the CICS region userid, and because they access CICS internal resources, you must give the CICS region userid authority to access them.

These are:

• CICS system transactions

CICS needs authority to attach all the internal housekeeping transactions that it uses. See "Category 1 transactions" on page 144.

Auxiliary user ids

If CICS surrogate user checking is specified with the **XUSER** system initialization parameter (the default), CICS needs authority to use certain additional user ids. These are:

- The default userid
  - See "CICS default user" on page 113.
- The userid used for post-initialization processing (PLTPIUSR)
- See "Post-initialization processing" on page 113.
- The userid used for transient data trigger transactions
  - See "Transient data trigger-level transactions" on page 115.
- Resources used by PLTPI programs

If the **PLTPIUSR** system initialization parameter is omitted, the CICS region userid is used for all PLTPI programs. In this case, give the CICS region userid access to all the CICS resources that these programs use. See "PLT programs" on page 85.

# Defining the default CICS userid to RACF

For each CICS region where you specify SEC=YES, define a RACF user profile whose userid matches the value of the **DFLTUSER** system initialization parameter.

For example, if you specify DFLTUSER=NOTSIGND, define a RACF user profile named NOTSIGND. If you do not specify a value for the **DFLTUSER** parameter, the CICS-supplied default userid is CICSUSER. Define a RACF user profile named CICSUSER.

Define a different default CICS userid for each CICS region if any of the following considerations applies:

- The default CICS userid requires different security attributes (such as membership in RACF groups).
- The default CICS userid requires different operator data (CICS segment of the RACF user profile).
- The default CICS userid requires a different default language (LANGUAGE segment of the RACF user profile).

To define a CICS default user with the system initialization parameter default name (CICSUSER), use the ADDUSER command with the CICS operand, as follows:

ADDUSER CICSUSER DFLTGRP(group_id) NAME(user_name) OWNER(userid or group) PASSWORD(password) CICS(OPCLASS(1,2,...,n) OPIDENT(identifier) OPPRTY(priority) TIMEOUT(timeout_value) XRFSOFF(xrf_sign-off_option))

The security administrator should always define the password for default userids and started tasks, instead of allowing it to default.

Each CICS region should use its own default user, as an aid to debugging. Set up a RACF default user group to keep the definitions similar.

If you have specified the system initialization parameter XUSER=YES (the default), authorize the CICS region userid to be a surrogate user of the default userid. For example:

PERMIT CICSUSER.DFHINSTL CLASS(SURROGAT) ID(cics_region_userid)

During startup, CICS "signs on" the default userid. If the default user sign-on fails (because, for example, the userid is not defined to RACF), CICS issues message DFHXS1104 and terminates CICS initialization.

When CICS successfully signs on a valid RACF userid as the default user, it establishes the terminal user data for the default user from one of the following sources:

- The CICS segment of the default user's RACF user profile
- Built-in CICS system default values

See "Obtaining CICS-related data for a user" on page 76 for details of the sign-on process for obtaining CICS terminal operator data.

CICS assigns the security attributes of the default userid to all CICS terminals before any terminal user begins to sign on. The security attributes and terminal user data of the default user also apply to any terminals at which users do not sign on (using either the CICS-supplied CESN transaction or a user-written equivalent), unless the security has been explicitly preset by specifying a value for the USERID option in the terminal definition.

**Note:** If the default user's RACF profile specifies a non-zero TIMEOUT, that value does **not** apply to terminals that do not sign on.

CICS also assigns the security attributes of the default userid to any "trigger level transactions" that are initiated for transient data queues without a USERID parameter.

Ensure the default userid gives at least the minimum authorities that ought to be granted to any other terminal user. In particular:

- Give the default user access to the region's APPLID. See "Authorizing access to the CICS region" on page 51.
- Give the default user access to the CICS-supplied transactions that are intended to be used by everybody. See the definitions in "Identifying CICS terminal users" on page 63, especially those transactions that are recommended for inclusion in the ALLUSER example group of transactions.

# Authorizing access to MVS log streams

Ensure that you authorize the CICS region userid to write to (and create if necessary) the log streams that are used for its system log and general logs.

You do this by granting the appropriate access authorization to log stream profiles in the LOGSTRM general resource class.

The level of authorization required depends on whether log streams are always explicitly defined to the MVS system logger:

• If CICS is expected to create log streams dynamically, give CICS **ALTER** authority to the relevant log stream profiles, and **UPDATE** authority to the relevant coupling facility structures.

- If all the log streams to which CICS writes are already defined to MVS, give CICS only **UPDATE** authority to the log stream profiles.
- Permit READ access to those users who need to read the CICS log streams.

For example, the generic profile in the following example could be defined to cover all the log streams referenced by the CICS region and identified by its region userid and applid:

RDEFINE LOGSTRM region_userid.** UACC(NONE)

If, however, you have multiple CICS systems sharing the same region userid, but with differing security requirements, include the applid in the generic profile, as follows:

```
RDEFINE LOGSTRM region_userid.applid.* UACC(NONE)
```

The following example allows the CICS region userid under which CICS is running to write journal and log records to log streams in the named coupling facility structure:

PERMIT IXLSTR.structurename CLASS(FACILITY) ACCESS(UPDATE) ID(region_userid)

The following examples give access to three categories of user:

```
PERMIT region_userid.applid.* CLASS(LOGSTRM) ACCESS(ALTER)
ID(region_userid)
PERMIT region_userid.applid.* CLASS(LOGSTRM) ACCESS(READ)
ID(authorized_browsers)
PERMIT region_userid.applid.* CLASS(LOGSTRM) ACCESS(UPDATE)
ID(archive userid)
```

In these examples, region_userid is the CICS region userid under which CICS is running, either as a started task or batch job. The identifier archive_userid is the userid under which an application program runs to purge old data from CICS logs when the data is no longer needed. The identifier authorized_browsers refers to the userids of users allowed to read log streams, but not purge data.

If several CICS regions share the same CICS region userid, you can make profiles more generic by specifying * for the *applid* qualifier.

The number of profiles you define depends on the naming conventions of the logs, and to what extent you can use generic profiling.

# Authorizing access to CICS data sets

When you have defined a region userid for your CICS job (or started task), permit that user id to access the CICS system data sets with the necessary authorization.

When authorizing access to CICS system data sets, choose appropriately from the following levels of access: READ, UPDATE, and CONTROL. Also define data set profiles with UACC(NONE) to ensure that only CICS region user ids can access those data sets. For information about the CICS region user id, see "Specifying the CICS region userid" on page 36.

For CICS load libraries, only permit READ access.

The following four data sets require CONTROL access.

- The temporary storage data set
- The transient data intrapartition data set

- The CAVM control data set (XRF)
- The CAVM message data set (XRF)

Permit UPDATE access for all the remaining CICS data sets.

Therefore, for CICS system data sets you need at least three generic profiles to restrict access to the appropriate level. See Table 3.

Table 3. Summary of generic data set profiles

Required access level	Type of CICS data sets protected	
READ	Load libraries	
UPDATE	Auxiliary trace; transaction dump; system definition; global catalog; local catalog; and restart	
CONTROL	Temporary storage; intrapartition transient data; XRF message; and XRF control	

If you use generic naming of the data set profiles, you can considerably reduce the number of profiles you need for your CICS regions. This policy is illustrated in the examples shown in Figure 1 for a number of sample CICS regions.

You can issue the RACF commands shown in the examples from a TSO session, or execute the commands using the TSO terminal monitor program, IKJEFT01, in a batch job as illustrated in Figure 1. Alternatively, you can use the RACF-supplied ISPF panels. Any of these methods enables you to create the necessary profiles and authorize each CICS region userid to access the data sets as appropriate for the corresponding CICS region.

```
//RACFDEF JOB 'accounting information'
11
               CLASS=A, MSGCLASS=A, MSGLEVEL=(1,1)
//DEFINE EXEC PGM=IKJEFT01
//SYSPRINT DD SYSOUT=A
//SYSTSPRT DD SYSOUT=A
//SYSUDUMP DD SYSOUT=A
//SYSTSIN DD *
ADDSD 'CICSTS41.CICS.SDFHLOAD' NOTIFY(cics sys admin id) UACC(NONE)
PERMIT 'CICSTS41.CICS.SDFHLOAD' ID(cics id1,...,cics group1,..,cics groupn)
                           ACCESS (READ)
ADDSD 'CICSTS41.CICS.SDFHAUTH' NOTIFY(cics sys admin id) UACC(NONE)
PERMIT 'CICSTS41.CICS.SDFHAUTH' ID(cics_id1,...,cics_group1,..,cics_groupn)
                           ACCESS(READ)
ADDSD 'CICSTS41.CICS.applid.**' NOTIFY(cics_sys_admin_id) UACC(NONE)
PERMIT 'CICSTS41.CICS.applid.**' ID(applid userid) ACCESS(UPDATE)
ADDSD 'CICSTS41.CICS.applid.DFHXR*' NOTIFY(cics_sys_admin_id) UACC(NONE)
PERMIT 'CICSTS41.CICS.applid.DFHXR*' ID(applid userid) ACCESS(CONTROL)
ADDSD 'CICSTS41.CICS.applid.DFHINTRA' NOTIFY(cics sys admin id) UACC(NONE)
PERMIT 'CICSTS41.CICS.applid.DFHINTRA' ID(applid_userid) ACCESS(CONTROL)
ADDSD 'CICSTS41.CICS.applid.DFHTEMP' NOTIFY(cics_sys_admin_id) UACC(NONE)
PERMIT 'CICSTS41.CICS.applid.DFHTEMP' ID(applid userid) ACCESS(CONTROL)
ADDSD 'CICSTS41.CICS.DFHCSD'
                                      NOTIFY(cics sys admin id) UACC(NONE)
PERMIT 'CICSTS41.CICS.DFHCSD' ID(cics group1,..,cics groupn) ACCESS(UPDATE)
/*
11
```

Figure 1. Example of a job to authorize access to CICS data sets

**Note:** Data sets that need to be accessed in the same way by all CICS regions (for example, with READ or UPDATE access) should be protected by profiles that do

not include an APPLID. For example, define the partitioned data sets that contain the CICS load modules with profiles that give all CICS region groups (or userids) READ access.

You could also consider protecting all these data sets with one generic profile called 'CICSTS41.CICS.**'. However, you must strictly control who has read access to CICSTS41.CICS.SDFHAUTH, because it contains APF-authorized programs, and the profile protecting this data set **must** be defined with UACC(NONE). In Figure 1 on page 44 all of the partitioned data sets are defined with UACC(NONE) and have an explicit access list.

Although CICS modules exist in libraries SYS1.CICSTS41.CICS.SDFHLPA and SYS1.CICSTS41.CICS.SDFHLINK, no CICS region userid requires access to these libraries.

By establishing a naming convention for the data sets belonging to each region, and one generic profile for each CICS region, with the CICS VTAM APPLID as one of the data set qualifiers, you can ensure that only one CICS region has access to the data sets. In the examples shown in Figure 1 on page 44, all the names have a high-level qualifier of CICSTS41.CICS, but your installation will have its own naming conventions for you to follow.

CICS needs UPDATE access to all the data sets covered by these profiles. The CICS DDNAMEs for the data sets in this category are as follows:

# DFHGCD

Global catalog data set

### DFHLCD

Local catalog data set

DFHAUXT

Auxiliary trace data set, A extent

# DFHBUXT

Auxiliary trace data set, B extent

### **DFHDMPA**

Transaction dump data set, A extent **DFHDMPB** 

Transaction dump data set, B extent

Note: The auxiliary trace data set, the transaction dump data set, and the MVS dump data set may contain sensitive information. Protect them from unauthorized access.

CICS needs CONTROL access for the transient data intrapartition, temporary storage, and CICS availability manager (CAVM) data sets.

The CICS DDNAMEs for the data sets in this category are as follows: **DFHINTRA** Transient data intrapartition data set

# DFHTEMP

Temporary storage data set DFHXRMSG XRF message data set

The CICS system definition data set (CSD) is protected by a discrete profile to which all CICS groups have access. This assumes that all the CICS regions are sharing a common CSD. If your CICS regions do not share a common CSD and each region has its own CSD, or if groups of regions share a CSD, define discrete or generic data set profiles as appropriate.

You must grant the CICS region user ID read access to the VSAM catalog for the DFHCSD file for the CICS system definition data set (CSD).

# Authorizing access with the MVS library lookaside (LLA) facility

If you are using the library lookaside (LLA) facility of MVS, you can control a program's ability to use the LLACOPY macro.

Authorize the CICS region's userid in one of the following ways:

- It must have UPDATE authority to the data set that contains the LLA module.
- It must have UPDATE authority in the FACILITY class to the resource CSVLLA. *datasetname*, where *datasetname* is the name of the library that contains the LLA module. For example:

```
RDEFINE FACILITY CSVLLA.datasetname UACC(NONE) NOTIFY
PERMIT CSVLLA.datasetname CLASS(FACILITY) ID(....) ACCESS(UPDATE)
```

# Authorizing access to user data sets

When you have defined the RACF user ids for your CICS regions and given them access to the CICS system data sets, permit the user IDs to access the CICS **application** data sets with the necessary authority.

You must grant the CICS region user ID read access to each VSAM catalog for files for which CICS has file definitions installed and are to be either opened during CICS startup or at any time after.

The following RACF commands permit the userid specified on the ID parameter to access some CICS user application data sets, with READ authority for the first two data sets, and UPDATE authority for the last two:

PERMIT'CICSTS41.CICS.appl1.dataset1'ID(user or group)ACCESS(READ)PERMIT'CICSTS41.CICS.appl1.dataset2'ID(user or group)ACCESS(READ)PERMIT'CICSTS41.CICS.appl2.dataset3'ID(user or group)ACCESS(UPDATE)PERMIT'CICSTS41.CICS.appl2.dataset4'ID(user or group)ACCESS(UPDATE)

# ACCESS(CONTROL) for VSAM entry-sequenced data sets (ESDS)

CICS file control uses control interval processing when opening a VSAM ESDS (non-RLS mode only). This means that you must specify ACCESS(CONTROL) for all such data sets, otherwise the OPEN command fails with message DFHFC0966.

# ACCESS(ALTER) for VSAM data sets when using BWO

In order to use backup while open (BWO) to back up VSAM data sets that are currently in use and are defined as BACKUPTYPE(DYNAMIC), or BWO(TYPECICS) in the integrated catalog facility (ICF) catalog, give the CICS region userid RACF ALTER authority to the data set or to the ICF catalog in which that data set is defined. If you do not, the OPEN command fails with message DFHFC5803. See the *CICS Recovery and Restart Guide* for guidance on using BWO.

# ACCESS(ALTER) for VSAM data sets when specifying SMS Data Class attribute Dynamic Volume Count

Dynamic Volume Count

You can use SMS Data Class attribute Dynamic Volume Count to extend your VSAM data to multiple volumes. Depending on your SMS release level, ACCESS(ALTER) may be required by the CICS region user ID to update the ICF catalog volume list during EOV extend processing. See the table "Required Security Authorization for VSAM data sets" in,*z*/OS DFSMS: Access Method Services for Catalogs to determine the correct access level for your DFSMS release.

# Authorizing access to the temporary storage pools

You can control access by temporary storage (TS) servers to the TS pools in the coupling facility.

Each TS server can be started as a job or started task. The name of the TS queue pool for a TS server is specified at server startup. For each TS pool there can be only one TS server running on each MVS image in the sysplex.

Two security checks are made against the TS server's userid—that is, the userid under which the job or started task is running. To ensure the server passes these checks, do the following:

• Authorize the TS server region to connect to the coupling facility list structure used for its own TS pool. This requires that the TS server userid has ALTER authority to a coupling facility resource management (CFRM) RACF profile called IXLSTR.*structure_name* in the FACILITY general resource class.

For example, if the userid of the server is DFHXQTS1, and the list structure is called DFHXQLS_TSPRODQS, the following RACF commands define the profile and provide the required access:

RDEFINE FACILITY IXLSTR.DFHXQLS_TSPRODQS UACC(NONE) PERMIT IXLSTR.DFHXQLS_TSPRODQS CLASS(FACILITY) ID(DFHXQTS1) ACCESS(ALTER)

To reduce security administration, use the same TS server userid to start each TS server that supports the same TS pool.

• Give the TS server's userid CONTROL access to the CICS RACF profile called DFHXQ.*poolname* in the FACILITY general resource class. This authorizes the TS server to act as a server for the named TS pool.

For example, if the userid of the server is DFHXQTS1, and the pool name is TSPRODQS, the following RACF commands define the profile and provide the required access:

RDEFINE FACILITY DFHXQ.TSPRODQS UACC(NONE)

PERMIT DFHXQ.TSPRODQS CLASS(FACILITY) ID(DFHXQTS1) ACCESS(CONTROL)

See "System authorization facility (SAF) responses to the TS server" on page 48 for information about the responses to the TS server.

# Authorizing access to temporary storage servers

You can control access by CICS regions to the TS servers.

A security check is made against the CICS region userid to verify that the region is authorized to use the services of a TS server. This check is made each time that a CICS region connects to a TS server. Give each CICS region that connects to a TS server userid UPDATE access to the CICS RACF profile called DFHXQ.*poolname* in the FACILITY general resource class. This authorizes the CICS region to use the services of the TS server for the named TS pool.

For example, if the userid of a CICS region is CICSDAA1, and the pool name is TSPRODQS, the following RACF commands define the profile and provide the required access:

RDEFINE FACILITY DFHXQ.TSPRODQS UACC(NONE) PERMIT DFHXQ.TSPRODQS CLASS(FACILITY) ID(CICSDAA1) ACCESS(UPDATE)

When a CICS region has connected to a TS pool, it can write, read, and delete TS queues without any further security checks being performed by the server. However, the CICS application-owning regions issuing TS API requests can use the existing mechanisms for TS resource security checking

# System authorization facility (SAF) responses to the TS server

If the security profile for a TS pool cannot be retrieved, SAF neither grants nor refuses the access request. In this situation:

Access to the TS pool, either by a CICS region or by the TS server itself, is rejected if:

• A security manager is installed, but is either temporarily inactive or inoperative for the duration of the MVS image. This is a fail-safe action, on the grounds that, if the security manager is active, it might retrieve a profile that does not permit access to the TS pool.

Access to the TS pool, either by a CICS region or by the TS server itself, is accepted if:

- There is no security manager installed, or
- There is an active security manager, but the FACILITY class is inactive, or there is no profile in the FACILITY class. The access request is allowed in this case because there is no evidence that you want to control access to the TS server.

Access is permitted to any TS server without a specific DFHXQ.*poolname* profile, or an applicable generic profile. No messages are issued to indicate this. To avoid any potential security exposures, you can use generic profiles to protect all, or specific groups of, TS servers. For example, specifying: RDEFINE FACILITY (DFHX0.*) UACC(NONE)

ensures that access is allowed only to TS servers with a more specific profile to which a TS server or CICS region is authorized.

# Authorizing access to named counter pools and servers

You can control access by:

- Coupling facility data table (named counter) servers to named counter pools (see "Access to named counter pools" on page 49)
- CICS regions to the named counter servers (see "Access to named counter servers" on page 49).

# Access to named counter pools

You can control access by named counter servers to the named counter pools in the coupling facility.

Each named counter server can be started as a job or started task. The name of the named counter pool for a named counter server is specified at server startup. For each named counter pool there can be only one server running on each MVS image in the sysplex.

Two security checks are made against the named counter server's userid—that is, the userid under which the job or started task is running. To ensure the server passes these checks, do the following:

 Authorize the named counter server region to connect to the coupling facility list structure used for its own named counter pool. This requires that the named counter server userid has ALTER authority to a coupling facility resource management (CFRM) RACF profile called IXLSTR.*structure_name* in the FACILITY general resource class.

For example, if the userid of the server is DFHNCSV1, and the list structure is called DFHNCLS_DFHNC001, the following RACF commands define the profile and provide the required access:

RDEFINE FACILITY IXLSTR.DFHNCLS_DFHNC001 UACC(NONE) PERMIT IXLSTR.DFHNCLS_DFHNC001 CLASS(FACILITY) ID(DFHNCSV1) ACCESS(ALTER)

To reduce security administration, use the same named counter server userid to start each named counter server that supports the same named counter pool.

• Give the named counter server's userid CONTROL access to the CICS RACF profile called DFHNC.*poolname* in the FACILITY general resource class. This authorizes the named counter server to act as a server for the named counter pool.

For example, if the userid of the server is DFHNCSV1, and the pool name is DFHNC001, the following RACF commands define the profile and provide the required access:

RDEFINE FACILITY DFHNC.DFHNC001 UACC(NONE) PERMIT DFHNC.DFHNC001 CLASS(FACILITY) ID(DFHNCSV1) ACCESS(CONTROL)

See "System authorization facility (SAF) responses to the named counter server" on page 50 for information about the responses to the CFDT server.

# Access to named counter servers

You can control access by CICS regions to the named counter servers.

A security check is made against the CICS region userid to verify that the region is authorized to use the services of a named counter server. This check is made each time that a CICS region connects to a named counter server.

Give each CICS region userid that connects to a named counter server UPDATE access to the CICS RACF profile called DFHCF.*poolname* in the FACILITY general resource class. This authorizes the CICS region to use the services of the named counter server for the named named counter pool.

For example, if the userid of a CICS region is CICSDAA1, and the pool name is DFHNC001, the following RACF commands define the profile and provide the required access:

RDEFINE FACILITY DFHNC.DFHNC001 UACC(NONE) PERMIT DFHNC.DFHNC001 CLASS(FACILITY) ID(CICSDAA1) ACCESS(UPDATE) When a CICS region has connected to a named counter pool, it can define, update, delete, get, rewind, and query named counters without any further security checks being performed by the server.

**Note:** Unlike shared temporary storage pools and coupling facility data table pools, named counters can also be accessed by batch application regions. Batch jobs are subject to the same security mechanisms as a CICS region.

# System authorization facility (SAF) responses to the named counter server

If the security profile for a named counter pool cannot be retrieved, SAF neither grants nor refuses the access request. In this situation:

Access to the named counter pool, either by a CICS region or by the named counter server itself, is rejected if:

• A security manager is installed, but is either temporarily inactive or inoperative for the duration of the MVS image. This is a fail-safe action, on the grounds that, if the security manager is active, it might retrieve a profile that does not permit access to the named counter pool.

Access to the named counter pool, either by a CICS region or by the named counter server itself, is accepted if:

- · There is no security manager installed, or
- There is an active security manager, but the FACILITY class is inactive, or there is no profile in the FACILITY class. The access request is allowed in this case because there is no evidence that you want to control access to the named counter server.

Access is permitted to any named counter server without a specific DFHCF.*poolname* profile, or an applicable generic profile. No messages are issued to indicate this. To avoid any potential security exposures, you can use generic profiles to protect all, or specific groups of, named counter servers. For example, specifying:

RDEFINE FACILITY (DFHNC.*) UACC(NONE)

ensures that access is allowed only to named counter servers with a more specific profile to which a named counter server or CICS region is authorized.

# Authorizing access to SMSVSAM servers

SMSVSAM is a data-sharing subsystem running on its own address space to provide the RLS support required by CICS. For CICS regions using VSAM record-level sharing (RLS), access to SMSVSAM servers is controlled by RACF security checks made against the CICS region userid to verify that the region is authorized to register with an SMSVSAM server.

In a test environment you might wish to use the default action and allow any CICS region using VSAM RLS to connect to an SMSVSAM server. If you wish to protect this access, the RACF SUBSYSNM general resource class must be active and you must authorize each CICS region that connects to an SMSVSAM server to have access to that server. This means granting access to the appropriate profile in the RACF SUBSYSNM general resource class.

1

1

T

Т

The general resource class, SUBSYSNM, supports authorizations for subsystems that want to connect to SMSVSAM. The SUBSYSNM profile name is the name by which a given subsystem is known to VSAM. CICS uses its applid as its subsystem name; define a profile for the CICS applid in the SUBSYSNM resource to enable CICS to register the control ACB.
When CICS attempts to register the control ACB during initialization, SMSVSAM calls RACF to check that the CICS region userid is authorized to the CICS profile in the SUBSYSNM class. If the CICS region userid does not have READ authority, the open request fails.
For example, if the applid of a CICS AOR is CICSDAA1, and the CICS region userid (shared by a number of AORs) is CICSDA##, define and authorize the profile as follows:
RDEFINE SUBSYSNM CICSDAA1 UACC(NONE) NOTIFY(userid) PERMIT CICSDAA1 CLASS(SUBSYSNM) ID(CICSDA##) ACCESS(READ)
You can use wildcard characters on the applid to specify more than one CICS region, for example:
PERMIT CICSD%%% CLASS(SUBSYSNM) ID(CICSDGRP) ACCESS(READ)

# Authorizing access to the CICS region

|
|
|

You can restrict access by terminal users to specific CICS regions by defining CICS APPLID profiles in the RACF APPL class.

For this purpose, the APPLID of a CICS region is:

- The VTAM generic resources name if GRNAME is specified as a system initialization parameter
- The XRF generic APPLID if XRF=YES is specified as a system initialization parameter
- The generic APPLID if one is specified on the APPLID system initialization parameter
- The specific APPLID if only one is specified on the system initialization parameter

If you define a profile in the APPL class for a CICS APPLID, or a generic profile that applies to one or more CICS APPLIDs with UACC(NONE), all terminal users trying to sign on to a CICS region must have explicit access to the profile that applies to that region's APPLID, either as an individual profile, or as a member of a group. For example:

RDEFINE APPL cics_region_applid UACC(NONE) NOTIFY(sys_admin_userid)

You need to define only one APPL profile name in the RACF database for all the CICS regions that are members of the same VTAM generic resources name. All sign-on verifications in a CICSplex, where all the terminal-owning regions have the same VTAM generic resources name, are made against the same APPL profile.

For MRO only, the APPLID is propagated from the terminal-owning region (TOR) to the other regions that the user accesses — for example, from the TOR to the application-owning region (AOR), and from the AOR to the file-owning region (FOR). As a consequence:

• You do not need to include users of the AOR and FOR in the APPL profiles for those regions.

• You can force users to sign on through a TOR, by denying access to other APPLIDs

Use the RACF PERMIT command to add authorized users to the access list of CICS APPL profiles. For example:

PERMIT cics_region_applid CLASS(APPL) ID(group1,...,groupn) ACCESS(READ)

permits all users defined in the listed groups to sign on to cics_region_applid.

The APPL class must be active for this protection to be in effect: SETROPTS CLASSACT(APPL)

Also, for performance reasons, consider activating profiles in the APPL class using RACLIST.

SETROPTS RACLIST(APPL)

If the APPL class is already active, refresh the in-storage APPL profiles with the SETROPTS command: SETROPTS RACLIST(APPL) REFRESH

#### Note:

- 1. CICS always passes the APPLID to RACF when requesting RACF to perform user sign-on checks, and there is no mechanism within CICS to prevent this.
- 2. RACF treats undefined CICS APPLIDs as UACC(READ).
- **3**. If the APPL class is active, and a profile exists for a CICS region in the APPL class, ensure that authorized remote CICS regions can sign on to a CICS region protected in this way.

See the *z*/OS Security Server RACF Security Administrator's Guide for more information about controlling access to applications.

# Controlling the opening of a CICS region's VTAM ACB

You can control which users among those who are running non-APF-authorized programs can OPEN the VTAM ACB associated with a CICS address space (CICS region).

This ensures that only authorized CICS regions can present themselves as VTAM applications providing services with this APPLID, thus preventing unauthorized users impersonating real CICS regions. (Note that the CICS region userid needs the OPEN access, not the issuer of the SET VTAM OPEN command.)

For each APPLID, create a VTAMAPPL profile, and give the CICS region userid READ access. For example:

RDEFINE VTAMAPPL applid UACC(NONE) NOTIFY(userid) PERMIT applid CLASS(VTAMAPPL) ID(cics_region_userid) ACCESS(READ)

The correct CICS APPLID to specify in the VTAMAPPL class is the specific APPLID, as specified in the CICS system initialization parameters. If you are using XRF (that is, if CICS is started with XRF=YES in effect), define two VTAMAPPL profiles—one each for both the active and alternate CICS region's **specific** APPLID (the second operand on the CICS APPLID startup option).

**Note:** If your alternate is on another MVS image, ensure that the RACF database is shared, or define the VTAMAPPL profiles in the other system's RACF database.

The VTAMAPPL class must be activated using RACLIST for this protection to be in effect:

SETROPTS CLASSACT(VTAMAPPL) RACLIST(VTAMAPPL)

If the VTAMAPPL class is already active, refresh the in-storage VTAMAPPL profiles with the SETROPTS command: SETROPTS RACLIST(VTAMAPPL) REFRESH

# Controlling userid propagation

Jobs submitted from CICS to the JES internal reader without the USER operand being specified on the JOB statement run under the CICS region user ID. These jobs have the access authorities of the CICS region itself, and so could potentially expose other data sets in the MVS system.

You (or the RACF security administrator) can prevent the CICS region user ID from being propagated to these batch jobs by defining a profile in the PROPCNTL class where the profile name is the CICS regions user ID. For example, if the CICS region userID is CICS1, define a PROPCNTL profile named CICS1: RDEFINE PROPCNTL CICS1

The PROPCNTL class must be activated using RACLIST for this protection to be in effect:

SETROPTS CLASSACT (PROPCNTL) RACLIST (PROPCNTL)

If the PROPCNTL class is already active, refresh the in-storage PROPCNTL profiles with the SETROPTS command:

SETROPTS RACLIST (PROPCNTL) REFRESH

You (or the RACF security administrator) must issue the SETROPTS command to refresh these profiles. Issuing the CICS PERFORM SECURITY REBUILD command does not affect the PROPCNTL class.

# Surrogate job submission in a CICS environment

Batch jobs submitted by CICS can be allowed to run with a USER parameter other than the CICS region's userid, but without specifying the corresponding PASSWORD.

This is called surrogate job submission. These jobs have the access authorities of the USER parameter specified on the JOB statement. If the PASSWORD parameter is specified on the JOB statement, surrogate processing does not occur.

You (or the RACF security administrator) can allow this by defining a profile in the SURROGAT class. For example, if the CICS region's userid is CICS1, and the job is to run for userid JOE, define a SURROGAT profile named JOE.SUBMIT:

RDEFINE SURROGAT JOE.SUBMIT UACC(NONE) NOTIFY(JOE)

Further, you must permit the CICS region's userid to act as the surrogate to the profile just defined:

PERMIT JOE.SUBMIT CLASS(SURROGAT) ID(CICS1) ACCESS(READ)

The SURROGAT class must be activated using RACLIST for this protection to be in effect:

SETROPTS CLASSACT (SURROGAT) RACLIST (SURROGAT)

### Attention:

Any CICS user, whether signed on or not, is able to submit jobs that use the SURROGAT userid, if the CICS userid has authority for SURROGAT. If your installation is using transient data queues to submit jobs, you can control who is allowed to write to the transient data queue that goes to the internal reader. However, if your installation is using EXEC CICS SPOOLOPEN to submit jobs, you cannot control who can submit jobs (without writing an API global user exit program to screen the commands). CICS spool commands do no CICS resource or command checking.

You can use an EXEC CICS ASSIGN USERID command to find the userid of the user who triggered the application code. Application programmers can then provide code that edits a USER operand onto the JOB card destined for the internal reader.

For a complete description of surrogate job submission support, see the *z*/*OS Security Server RACF Security Administrator's Guide*.

# Authorizing the CICS region userid as a surrogate user

When CICS performs surrogate user checking, the CICS region userid must be authorized as a surrogate.

# About this task

Grant authorization for the CICS region userid acting as a surrogate user for the following:

- The CICS default user
- The userid used for post-initialization processing (PLTPIUSR)
- All userids used for transient data trigger level transactions
- All userids specified on the AUTHID or COMAUTHID parameters of a DB2 resource definition.

For more information about surrogate user checking, see Chapter 7, "Surrogate user security," on page 113.

# JES spool protection in a CICS environment

Your installation can protect JES spool data sets with profiles in the JESSPOOL class.

Spool files created by the SPOOLOPEN commands have the userid of the CICS region in their security tokens, not the userid of the person who issued the SPOOLOPEN command. Thus, the userid qualifier in the related JESSPOOL profiles is the CICS region's userid.

When using the SPOOLOPEN INPUT command, CICS checks that the first four characters of the APPLID correspond to the external writer name of the spool file. This checking is independent of any RACF checking that may also be done.

# Security-related system initialization parameters

There are several system initialization parameters that CICS provides for specifying your security requirements at the system level.

For full details of system initialization parameters, see the CICS System Definition *Guide*.

SEC

You use the SEC system initialization parameter to specify the level of resource security management you want for your CICS region. There are two options:

#### YES

This means that the CICS external security interface will be initialized, and control of CICS security is determined by the other security-related system initialization parameters:

CMDSEC	XAPPC	ХРРТ
DFLTUSER	XCMD	XPSB
EJBROLEPRFX	XDB2	XRES
ESMEXITS	XDCT	XRFSOFF
PSBCHK	XEJB	XRFSTME
PLTPISEC	XFCT	XTRAN
RESSEC	XHFS	XTST
SECPRFX	XJCT	XUSER
SNSCOPE	ХРСТ	

**NO** This means that there is no security checking of whether users are allowed to access CICS (and non-CICS) resources from this region, and sign-on cannot take place.

**Note:** Even if you have specified SEC=NO, with MRO bind-time security, the CICS region userid is sent to the secondary system, and bind-time checking is carried out in the secondary system. See "Bind-time security with MRO" on page 219 for more information.

### SECPRFX

This parameter is effective only if you also specify SEC=YES. You use the SECPRFX system initialization parameter to specify whether you want CICS to prefix the resource names that it passes to RACF for authorization. The prefix that CICS uses is the RACF userid under which the CICS region is running.

Prefixing is useful mainly when you have more than one CICS region. It enables you to prevent users on one CICS region from accessing the resources of a different CICS region that has a different prefix. For example, you might have one CICS region with the prefix CICSPROD and another with prefix CICSTEST. Users of the CICSTEST system would be able to use profiles that included the CICSTEST prefix, and users of the CICSPROD system would be able to use profiles that included the CICSPROD prefix. Users of both systems would be able to use resources protected by profiles that included CICS*.

The options on the SECPRFX parameter are:

**NO** CICS does not prefix the resource names in authorization requests that it passes to RACF from this CICS region.

YES

CICS prefixes the resource names with the CICS region userid when passing authorization requests to RACF.

To change these values employ an ICHRTX00 SAF preprocessing exit. For more information, see "Determining the userid of the CICS region" on page 318.

## prefix

CICS prefixes the resource names with the specified prefix when passing authorization requests to RACF.

For example, if a CICS job specifies USER=CICSREG on the JOB statement, and SECPRFX=YES is specified, you can define and allow access to the CICS master terminal transaction (CEMT) in the TCICSTRN resource class as follows:

RDEFINE	TCICSTRN CIO	CSREG.CEMT
	UACC(NONE)	NOTIFY(sys_admin_userid)
PERMIT	CICSREG.CEMT	CLASS(TCICSTRN)
	ID(groupid1,	,groupidn) ACCESS(READ)

You can also use a resource group profile in the GCICSTRN resource class. If you do, specify the prefix on the ADDMEM operand. The following shows CICSREG specified in a profile named CICSTRANS:

RDEFINE GCICSTRN CICSTRANS ADDMEM(CICSREG.CEMT) UACC(NONE) NOTIFY(sys_admin_userid) PERMIT CICSTRANS CLASS(GCICSTRN) ID(groupid1,...,groupidn) ACCESS(READ)

**Note:** If you protect a resource with a resource group profile, avoid protecting the same resource with another profile. If the profiles are different (for example, if they have different access lists), RACF merges the profiles for use during authorization checking. Not only can the merging have a performance impact, but it can be difficult to determine exactly which access authority applies to a particular user. (For more information, see the *z*/*OS Security Server RACF Security Administrator's Guide*.)

#### CMDSEC

Code CMDSEC to specify whether or not you want CICS to honor the CMDSEC option specified on a transaction's resource definition. CMDSEC specified with the option ASIS means that CICS obeys the CMDSEC option. CMDSEC specified with the option ALWAYS means that CICS ignores the CMDSEC option, and always performs the command check. For more information about these options, see the *CICS System Definition Guide*.

#### DFLTUSER

Specify a value for DFLTUSER to identify to CICS the name you have defined to RACF as the default userid. If you omit this parameter, the name defaults to CICSUSER. See "Defining the default CICS userid to RACF" on page 41.

#### **EJBROLEPRFX**

Specifies a prefix that is used to qualify the security role defined in an enterprise bean's deployment descriptor. The prefix is applied to the security role:

- when a role is defined to an external security manager
- when CICS maps a security role to RACF user ID

For more information about how the **EJBROLEPRFX** parameter is used to qualify security roles for enterprise beans, see *Java Applications in CICS*.

### ESMEXITS

Use ESMEXITS to specify whether you want CICS to pass installation data for use by the RACF installation exits. For more information on ESMEXITS, see Chapter 23, "Customizing security processing," on page 313.

### PLTPISEC

Code PLTPISEC to specify whether or not you want CICS to perform command security or resource security checking for PLT programs that run during CICS initialization.

#### PLTPIUSR

Code PLTPIUSR to specify the userid that CICS is to use for security checking for PLT programs that run during CICS initialization.

### PSBCHK

Code PSBCHK to specify that you want CICS to perform PSB authorization checks for remote terminal users who use transaction routing to initiate a transaction in this CICS region (to access an attached IMS[™] system). The default PSBCHK=NO specifies that CICS is to check the remote link but not the remote user. The remote user is checked by specifying PSBCHK=YES.

### RESSEC

Code RESSEC to specify whether or not you want CICS to honor the RESSEC option specified on a transaction's resource definition. RESSEC specified with the option ASIS means that CICS obeys the RESSEC option. RESSEC specified with the option ALWAYS means that CICS ignores the RESSEC option, and always performs the resource check. For more information about these options, see the *CICS System Definition Guide*.

### **SNSCOPE**

SNSCOPE—the sign-on SCOPE—applies to all userids signing on by explicit sign-on request; for example, the EXEC CICS SIGNON command or the CESN transaction. Use it to specify whether or not a userid can have more than one CICS session active at the same time.

The sign-on SCOPE is enforced with the MVS ENQ macro. The SNSCOPE values correspond to the STEP, SYSTEM, and SYSTEMS levels of ENQ scoping. This means that only those CICS systems that specify exactly the same value for SNSCOPE can check the scope of each other.

SNSCOPE affects only users signing on at local terminals, or signing on after using the CRTE transaction to connect to another system. For more information about using SNSCOPE, and the restrictions involved, see the *CICS System Definition Guide*.

# CICS resource class system initialization parameters

You specify at the system level (with the SEC=YES parameter) that you want CICS to use RACF to authorize access to CICS resources. You also specify at the system level which particular CICS resources you want CICS to check by means of the *Xname* system initialization parameters.

The full list of the CICS resource classes is shown in Table 4, each with corresponding *Xname* system initialization parameter.

Table 4. System initialization parameters for the CICS resource classes

System initialization parameter	Resource
XAPPC={ <b>NO</b>   YES}	APPC partner-LU verification

System initialization parameter	Resource			
XCMD={ <b>YES</b>   name   NO}	EXEC CICS system commands EXEC CICS FEPI system commands			
XDB2={ <b>NO</b>   name}	CICS DB2 resources			
XDCT={ <b>YES</b>   name   NO}	Transient data destinations			
$XEJB = \{\underline{YES} \mid NO\}$	Security roles is enabled			
XFCT={ <b>YES</b>   name   NO}	Files			
$XHFS = \{ \underline{YES} \mid NO \}$	z/OS UNIX files managed by z/OS UNIX System Services			
XJCT={ <b>YES</b>   name   NO}	Journals and logs			
XPCT={ <b>YES</b>   name   NO}	Started transactions and EXEC CICS commands: COLLECT STATISTICS TRANSACTION DISCARD TRANSACTION INQUIRE TRANSACTION SET TRANSACTION			
XPPT={ <b>YES</b>   name   NO}	Programs			
XPSB={ <b>YES</b>   name   NO}	DL/I program specification blocks (PSBs)			
XRES={ <b>YES</b>   name   NO}	CICS resources subject to XRES security checks. For a list of resources subject to XRES security checks, see "Security using the XRES resource security parameter" on page 87the "Security using the XRES resource security parameter" topic			
XTRAN={ <b>YES</b>   name   NO}	Attached transactions			
XTST={ <b>YES</b>   name   NO}	Temporary storage entries			
XUSER={ <u>YES</u>   NO}	Surrogate user checking DB2 AUTHTYPE checking			

Table 4. System initialization parameters for the CICS resource classes (continued)

# Note:

- 1. The parameters are effective only with SEC=YES.
- 2. None of the parameters can be entered as a console override.

If you specify YES for any of the *Xname* system initialization parameters where RACF is used to manage resource security, CICS uses the default class name for that parameter. See "RACF classes for CICS resources" on page 23 for a list of these.

As an example, the effect of specifying SEC=YES with three of the resource class parameters specified as *Xname*=YES is illustrated in the following table.

Table 5. Specifying	external	security	with	default	resource classes

System initialization parameter	Effect
SEC=YES	CICS initializes external security interface.
XTRAN=YES	CICS uses the TCICSTRN and GCICSTRN resource class profiles for transaction-attach security checking.
XFCT=YES	CICS uses the FCICSFCT and HCICSFCT resource class profiles for file access security checking.

Table 5. Specifying external	security with default	resource classes	(continued)

System initialization parameter	Effect
XPSB=YES	CICS uses the PCICSPSB and QCICSPSB resource class profiles for PSB access security checking.

As a second example, the effect of specifying SEC=YES with the same three associated resource class parameters specified as *Xname=username* is shown in Table 6.

System initialization parameter	Effect
SEC=YES	CICS uses full RACF security support.
XTRAN=\$usrtrn	CICS uses the T\$usrtrn and G\$usrtrn user-defined resource class profiles for transaction-attach security checking.
XFCT=\$usrfct	CICS uses the F\$usrfct and H\$usrfct user-defined resource class profiles for file access security checking.
XPSB=\$usrpsb	CICS uses the P\$usrpsb and Q\$usrpsb user-defined resource class profiles for PSB access security checking.

Table 6. Specifying external security for user-defined resource classes

When CICS is being initialized, it requests RACF to bring resource profiles into main storage to match all the resource classes that you specify on system initialization parameters. Note that (except for XAPPC, XDB2, and XEJB) *Xname*=YES is the default in the system initialization parameters, and CICS will use the default classnames, for example, GCICSTRN. Supply RACF profiles for all those resources for which you do not specify *Xname*=NO explicitly. If CICS requests RACF to load a general resource class that does not exist or is not correctly defined, CICS issues a message indicating that external security initialization has failed, and terminates CICS initialization.

The system initialization parameter XHFS is an exception to this process. Access controls for z/OS UNIX files are not managed directly by RACF, so they do not require individual RACF profiles, even if XHFS=YES is specified. Access controls for z/OS UNIX files are specified in z/OS UNIX System Services, which makes use of RACF to manage user IDs and groups, but keeps control of the permissions set for the files. If you are using access control lists (ACLs) for z/OS UNIX files, the RACF class FSSEC must be active.

For guidance on the syntax of external security system initialization parameters, see the the *CICS System Definition Guide*.

The way you define the individual transaction definitions in the CSD determines whether you want to use RACF security for the resources and commands used with transactions. See Chapter 4, "Verifying CICS users," on page 63 and Chapter 5, "Transaction security," on page 81 for information about specifying resource and command security for transactions.

#### XAPPC, XEJB, XHFS, and XUSER

The syntax of the XAPPC, XEJB, XHFS, and XUSER system initialization parameters is slightly different from that of the other *Xname* parameters. You can only specify YES or NO.

XAPPC=YES indicates that you want session security for APPC sessions. If XAPPC=YES is specified and the APPCLU class is not activated in RACF, CICS fails to initialize. For more information on what happens in these circumstances, see "CICS initialization failures related to security" on page 332.

XAPPC enables RACF LU6.2 bind-time (also known as APPC) security. For more information, see "Bind-time security with LU6.2" on page 163.

For more information on the APPCLU class, see "Defining profiles in the APPCLU general resource class" on page 164.

XEJB specifies whether support of security roles is enabled. For more information, see *Java Applications in CICS*.

XHFS activates access control for Web client access to z/OS UNIX files in the CICS region. For more information, see "Security for z/OS UNIX files" on page 105.

XUSER activates surrogate user security, and AUTHTYPE checking for DB2. For more information, see Chapter 7, "Surrogate user security," on page 113. If XUSER=YES is specified and the SURROGAT class is not activated in RACF, CICS fails to initialize.

## Using IBM-supplied classes without prefixing

To set up external security for transactions, files, and PSBs, using IBM-supplied resource classes and without prefixing, take the steps described in this topic.

Before you define a profile, activate the relevant classes, using the SETROPTS CLASSACT and SETROPTS GENERIC commands, as described in "Summary of RACF commands" on page 27.

To ensure the least interruption to actual business processes, work in a test region first.

1. Plan and create RACF profiles in the relevant classes:

RDEFINE	TCICSTRN	transaction-name	UACC(NONE)	NOTIFY(userid)
RDEFINE	FCICSFCT	file-name	UACC(NONE)	NOTIFY(userid)
RDEFINE	PCICSPSB	PSB-name	UACC(NONE)	NOTIFY(userid)

2. Permit appropriate users or groups (preferably groups) to have access to the profiles:

 PERMIT
 transaction-name
 CLASS(TCICSTRN)
 ACCESS(READ)

 ID(userid or groupid)
 ERMIT
 file-name
 CLASS(FCICSFCT)
 ACCESS(READ)

 ID(userid or groupid)
 ERMIT
 PSB-name
 CLASS(PCICSPSB)
 ACCESS(READ)

 ID(userid or groupid)
 ID(userid or groupid)
 ACCESS(READ)
 ID(userid or groupid)

**3**. Specify the following CICS system initialization parameters:

SEC=YES SECPRFX=NO	XTRAN=YES XFCT=YES XPSB=YES	XCMD=NO XDB2=NO XDCT=NO XHFS=NO XJCT=NO XPCT=NO XPPT=NO
		XRES=NO
		XTST=N0
		XUSER=NO
		XAPPC=NO

4. Start the CICS region in which you will be using external security.

5. If you add, change, or delete RACF profiles in the related classes, refresh the in-storage profiles. (For more information, see "Refreshing resource profiles in main storage" on page 22.)

# Using IBM-supplied classes with prefixing

To set up external security for transactions, files, and PSBs, using IBM-supplied resource classes with prefixing, take the steps described in this section.

Before you define a profile, you must activate the relevant classes, using the SETROPTS CLASSACT and SETROPTS GENERIC commands, as described in "Summary of RACF commands" on page 27.

To ensure the least interruption to actual business processes, work in a test region first.

**Note:** The following examples assume that the CICS region userid is CICS1, and that SECPRFX=YES.

1. Plan and create RACF profiles in the relevant classes:

RDEFINE	TCICSTRN	CICS1.transaction-name	UACC(NONE)	NOTIFY(userid)
RDEFINE	FCICSFCT	CICS1.file-name	UACC(NONE)	NOTIFY(userid)
RDEFINE	PCICSPSB	CICS1.PSB-name	UACC(NONE)	NOTIFY(userid)

2. Permit appropriate users or groups (preferably groups) to have access to the profiles:

PERMIT		CLASS(TCICSTRN)	ACCESS(READ)
PERMIT	ID(userid or groupid) CICS1.file-name	CLASS(FCICSFCT)	ACCESS(READ)
PERMIT	ID(userid or groupid) CICS1.PSB-name	CLASS(PCICSPSB)	ACCESS(READ)
	ID(userid or groupid)		

3. Specify the following system initialization parameters:

SEC=YES SECPRFX=YES	XTRAN=YES XFCT=YES	XCMD=NO XDB2=NO
SECHARA TES	XPSB=YES	XDCT=NO
		XHFS=N0
		XJCT=NO
		XPCT=NO
		XPPT=NO
		XRES=NO
		XTST=NO
		XUSER=NO
		XAPPC=NO

- 4. Start the CICS region in which you will be using external security.
- 5. If you add, change, or delete RACF profiles in the related classes, refresh the in-storage profiles. (For more information, see "Refreshing resource profiles in main storage" on page 22.)

## Using installation-defined classes without prefixing

To set up external security for transactions, files, and PSBs in installation-defined classes, without prefixing, take the steps described in this topic.

For an example of how to define installation-defined classes (T\$USRTRN and G\$USRTRN) for the XTRAN parameter, see the IBM-supplied sample, DFH\$RACF, in CICSTS41.CICS.SDFHSAMP. See also "Specifying user-defined resources to RACF" on page 318.

Before you define a profile, activate the relevant classes, using the SETROPTS CLASSACT and SETROPTS GENERIC commands, as described in "Summary of RACF commands" on page 27.

# To ensure the least interruption to actual business processes, work in a test region first.

- 1. Set up the following installation-defined classes:
  - T\$USRTRN like TCICSTRN, and G\$USRTRN like GCICSTRN
  - F\$USRFCT like FCICSFCT, and H\$USRFCT like HCICSFCT
  - P\$USRPSB like PCICSPSB, and Q\$USRPSB like QCICSPSB

For specific information on setting up installation-defined classes, see the *z*/OS Security Server RACF System Programmer's Guide.

1. Plan and create RACF profiles in the relevant classes:

RDEFINE	T\$USRTRN	transaction-name	UACC(NONE)	NOTIFY(userid)
RDEFINE	F\$USRFCT	file-name	UACC(NONE)	NOTIFY(userid)
RDEFINE	P\$USRPSB	PSB-name	UACC(NONE)	NOTIFY(userid)

2. Permit appropriate users or groups (preferably groups) to have access to the profiles:

PERMIT	transaction-name		ACCESS(READ)
	ID(userid or grou		
PERMIT	file-name	CLASS(F\$USRFCT)	ACCESS(READ)
	ID(userid or grou	pid)	
PERMIT	PSB-name	CLASS(P\$USRPSB)	ACCESS(READ)
	ID(userid or grou	pid)	

**3**. Specify the following system initialization parameters:

SEC=YES SECPRFX=NO	XTRAN=\$USRTRN XFCT=\$USRFCT XPSB=\$USRPSB	XCMD=N0 XDB2=N0 XDCT=N0 XHFS=N0 XJCT=N0 XPCT=N0 XRES=N0 XTST=N0 XUSER=N0 XAPPC=N0
-----------------------	--------------------------------------------------	--------------------------------------------------------------------------------------------------------------

- 4. Start the CICS region in which you will be using external security.
- 5. If you add, change, or delete RACF profiles in the related classes, refresh the in-storage profiles. (For more information, see "Refreshing resource profiles in main storage" on page 22.)

# Chapter 4. Verifying CICS users

To protect resources from unauthorized access, CICS must be able to identify users of the system when they invoke transactions.

## Identifying CICS terminal users

If you are running CICS with RACF security checking, you control users' access to CICS resources through levels of authorization you define in RACF-managed resource profiles.

You define these authorizations for specific users by adding individual RACF userids (or RACF group IDs) to the resource access lists; or, for unsigned-on users, by adding the default CICS userid to selected resource access lists.

All CICS terminal-user data is defined in the CICS segment of the RACF user profile. See "Obtaining CICS-related data for a user" on page 76 for more information about CICS terminal-user data, and how CICS obtains it.

#### The sign-on process

When users log-on to CICS through VTAM, but do not sign on, they can use only those transactions that the CICS default user is permitted to use.

As these are likely to be strictly limited, users must sign on to obtain authorization to run the transactions that they are permitted to use.

## **Explicit sign-on**

Users can explicitly sign on either by using the CICS-supplied transaction CESN or by using an installation-provided sign on transaction which uses the **SIGNON** command.

- Write a program that uses the
- Create a custom sign-on transaction that calls the program, instead of using CESN.

OIDCARD users can use CESN to sign on if the card reader supports the DFHOPID identifier (AID). If it does not, use your own installation-provided sign-on transaction.

- For programming information about the SIGNON command, see the CICS *Application Programming Reference*.
- For information about CESN, see CICS Supplied Transactions.

When a user signs on to CICS, the sign-on process involves the following phases:

#### Scoping

After the sign-on panel is completed and sent, CICS verifies that the entered userid does not match a userid already signed on within the scope of the **SNSCOPE** definition for the CICS system.

#### Identification

CICS calls RACF with the supplied userid to confirm that a profile has been defined for the user.

#### Verification

CICS passes information to RACF to verify that the user is genuine. For RACF, this is either a password or an OIDCARD or both. If the password entered has expired, CICS prompts the user for a new password. When the new password conforms to the RACF password formatting rules for an installation, the new password and the date-of-change are recorded in the RACF user profile.

The CESN transaction does not warn users when a password is about to expire. To display expiry warnings to users, you must replace CESN with your own transaction that calls a custom sign-on program. This program can use the **VERIFY PASSWORD** API command to return expiry information from RACF.

Immediately following the request to RACF for userid and password verification, CICS clears the internal password field. This minimizes the possibility of the password being revealed in any dump of the CICS address space that may be taken.

You might also voluntarily change your password by entering a new value.

Sign-on for CICS APPLID CICSA100
This is where the good morning message appears
Type your userid and password, then press ENTER:
Userid Groupid
Password
Language
New Password
DFHCE3520 Please type your userid. F3=Exit

Figure 2. The CICS sign-on panel

#### Authorization

RACF performs checks on the application name and the port of entry to verify that the user is allowed to use the CICS system. In the application name check, RACF determines whether the user is authorized to access the application named in the APPLID or GRNAME system initialization parameter. RACF does this by checking the access list of the CICS application profile defined in the RACF APPL resource class. (See "Authorizing access to the CICS region" on page 51 for information about how to define profiles in the APPL resource class.)

With the port of entry check, RACF verifies that the user is authorized to sign on using that port of entry. The use of defined terminals can be restricted to certain times of the day, and to certain days of the week. See "Controlling access to CICS from specific ports of entry" on page 66. These checks restrict the user to signing on only to those CICS regions for which they are authorized, and only from terminals they are authorized to use.

Explicit sign-on, with the CESN transaction, or the SIGNON command, is performed by the user at the port of entry.

Phase	Explicit	Implicit
Scoping	Yes	No
Identification	Yes	Yes
Verification	Yes	No except with ATTACHSEC(IDENTIFY)
Authorization	Yes	Yes

#### User attributes

CICS obtains CICS user attributes from the CICS and LANGUAGE segments of the RACF database.

#### The sign-off process

The sign-off process dissociates a user from a terminal where the user had been previously signed on. The user can explicitly sign off using the CESF transaction or an installation-provided transaction that uses the SIGNOFF API command. If the attributes of the signed-on user include a non-zero value for TIMEOUT, an implicit sign-off occurs if this interval expires after a transaction terminates at this terminal.

When the time-out period expires, if the default GNTRAN=NO is specified, CICS performs an immediate signoff. If GNTRAN specifies a transaction-id to be scheduled and that transaction performs a signoff, the action CICS takes depends on the SIGNOFF option specified in the terminal's TYPETERM resource definition.

An exceptional case is that the goodnight transaction is not used for the user of a CRTE session. A surrogate user whose time expires is signed off, losing the security capabilities the terminal previously had. Message DFHSN1200 is sent to the CSCS log, and indicates what has happened.

For more information about the use of system initialization parameter GNTRAN, see "Goodnight transaction" on page 66. The possible signoff options and the associated actions are as follows:

#### SIGNOFF(YES)

CICS signs off the operator from CICS, but the terminal remains connected.

#### SIGNOFF(LOGOFF)

CICS signs off the operator from CICS and logs off the terminal from VTAM.

In addition, if the terminal is autoinstalled, the delay period specified by the AILDELAY operand in the system initialization parameters commences, and if the delay period expires before the terminal attempts to log on again, CICS deletes the terminal entry (TCTTE) from the TCT. For information about CICS autoinstall, see the *CICS Resource Definition Guide*.

#### SIGNOFF(NO)

CICS leaves the user signed on and the terminal remains logged on, effectively overriding the time-out period.

# **Explicit sign-off**

Explicit sign-off removes the user's scoping. The user must be explicitly signed on before signing off with the CESF transaction or the SIGNOFF command. The user is returned to the default level of security.

**Note:** CESN will not sign the user off until a valid attempt has been made to use the panel, even if the sign-on attempt subsequently fails. It is not recommended that CESN be used for the Goodnight transaction.

# Implicit sign-on and implicit sign-off

Implicit sign-on means that all other userids added to the system by CICS are considered to be implicitly signed on without a password.

A user is implicitly signed off if the transaction suffers a TERMERR condition while attempting to send data to its principal facility. However, the user is not subject to USRDELAY but is signed off immediately. If SNSCOPE is in use, the scope will be released at the time of sign off. If the transaction handles the ABEND, it continues running as a non-terminal task with the authority of the starting user.

## Goodnight transaction

By specifying your own GNTRAN transaction, you can use the CICS API to control the TIMEOUT operation. For example, your transaction could display a screen that prompts for the password.

Specifying the USERID option on the ASSIGN command obtains the userid, and the VERIFY PASSWORD command would validate the input. Based on the response, the user could remain signed on or be signed off.

By default CICS uses the CESF transaction to sign-off a user terminal. The goodnight transaction is not available for a surrogate terminal that is timed out during a CRTE session. Sign-off occurs with a loss of the security capabilities the terminal previously had, leaving a DFHSN1200 message in the log.

## Controlling access to CICS from specific ports of entry

During sign-on processing, CICS issues a request to RACF to verify the user's password, and to check whether the user is allowed to access that terminal.

This check is also performed for the userid specified for preset security terminal definitions. Autoinstalled consoles that are using automatic sign-on are treated as though they have a preset security definition (see "Preset terminal security" on page 70). If the terminal is not defined to RACF, RACF responds to CICS according to the system-wide RACF option specified by the SETROPTS command. The options are as follows:

#### TERMINAL(READ)

With this option in force, terminal users can sign on at any terminal covered by a profile to which they have been permitted access, or at any terminal not defined as protected by RACF.

#### **TERMINAL(NONE)**

With this option in force, terminal users can sign on at only those terminals with specific terminal profiles defined to RACF, and which they are authorized to use.

**Note:** The TERMINAL class does not control access from MVS consoles. These are controlled by the CONSOLE resource class. See "Console profiles" on page 69.

You can override the system-wide terminal options at the RACF group level by means of the group terminal options, TERMUACC or NOTERMUACC.

See "Universal access authority for undefined terminals" on page 68 for more information about the SETROPTS command for terminals, and about the TERMUACC | NOTERMUACC option on groups.

## Defining port of entry profiles

*Port of entry* is the generic term for the device at which the end user signs on. For CICS, the port of entry can be either a terminal or a console. You can use associated port of entry profiles to control whether a user can sign on at a particular device.

## **Terminal profiles**

You can control user access to a terminals using profiles in the TERMINAL and GTERMINAL resource classes.

This section briefly describes some aspects of terminal profiles that are of interest to CICS users. For more detailed information about defining and protecting terminals on MVS systems, particularly on the following topics, see the *z*/OS *Security Server RACF Security Administrator's Guide*.

- Creating a profile in the TERMINAL or GTERMINL class
- Preventing the use of an undefined terminal
- Restricting specific groups of users to specific terminals
- Restricting the days or times when a terminal can be used
- Using a security label to control a terminal.

You can control user access to a terminal by defining it to RACF. (User access is determined at CICS sign-on time.) RACF supports two IBM-supplied resource class names for terminals:

#### TERMINAL

For defining a profile of an **individual** terminal.

#### GTERMINL

For defining a profile of a **group** of terminals.

**Note:** For a GTERMINL profile, RACF always uses an in-storage profile, which must be manually refreshed. Every time you create, change, or delete a GTERMINL profile, you (or the RACF security administrator) must issue a SETROPTS RACLIST(TERMINAL) REFRESH command for the change to take effect.

## Defining a profile of an individual terminal

To define terminals with NETNAMEs NETID1, NETID2, and NETID3 in the TERMINAL resource class, use the command:

RDEFINE TERMINAL (NETID1, NETID2, NETID3) UACC(NONE) NOTIFY(*sys_admin_userid*)

If the terminal IDs start with the same characters, you can create a generic profile to cover a group of terminals with the same initial characters. You must use the SETROPTS GENERIC command before defining generic profiles, as described in "Summary of RACF commands" on page 27. This reduces the amount of effort needed to create the access list. For example:

```
RDEFINE TERMINAL NETID* UACC(NONE)
NOTIFY(sys_admin_userid)
PERMIT netid* CLASS(TERMINAL)
ID(group1, group2,.., groupn) ACCESS(READ)
```

# Defining a profile of a group of profiles

Alternatively, you could define the same terminals in the resource group class, by including them as members of a suitable terminal group. For example:

```
RDEFINE GTERMINL term_groupid
ADDMEM(NETID1, NETID2, NETID3) UACC(NONE)
NOTIFY(sys admin userid)
```

To remove a terminal from a resource group profile, specify the DELMEM operand on the RALTER command. For example:

RALTER GTERMINL term_groupid DELMEM(NETID3)

To allow a group of users in a particular department to have access to these terminals, use the PERMIT command as follows:

PERMIT term_groupid CLASS(GTERMINL) ID(dept_groupid) ACCESS(READ)

# Profiles in the TERMINAL or GTERMINAL class

For CICS, the terminal profiles to define to RACF in the TERMINAL or GTERMINL class are used only for VTAM terminals.

The name of the profile is the value of the NETNAME that is specified in the RDO terminal definition or autoinstall. It is not possible to use TERMINAL profiles with non-VTAM terminals.

## Universal access authority for undefined terminals

RACF supports a universal access facility for undefined terminals, which you can control by means of the SETROPTS TERMINAL command (provided you have the necessary authorization). When SETROPTS TERMINAL(NONE | READ) is in effect, it affects **all** MVS terminal subsystems.

If SETROPTS TERMINAL(READ) is in effect, RACF allows any user to log on at any undefined terminal (that is, a terminal not defined in the TERMINAL or GTERMINL resource classes). If SETROPTS TERMINAL(NONE) is in effect, RACF does not allow anyone to log on at any undefined terminal.

**Note:** Before issuing the SETROPTS TERMINAL(NONE) command, define some TERMINAL or GTERMINL class profiles, with enough authorizations to ensure that at least some of the terminals can be used otherwise no one will be able to access any terminal.

#### Overriding the SETROPTS TERMINAL command

You can override the SETROPTS TERMINAL command at the group level by specifying the TERMUACC or NOTERMUACC option on the ADDGROUP or ALTGROUP command.

The effect of the TERMUACC parameter is to enforce the universal access option. For example, if SETROPTS TERMINAL(READ) is active, the TERMUACC option means that any users in the group can access any undefined terminal. On the other hand, if you specify NOTERMUACC for the group, the SETROPTS TERMINAL command has no effect for that group, and a user in the group needs explicit authorization to use a terminal. To enable a group with the NOTERMUACC option to access terminals, you must add group userid to the access list of the appropriate TERMINAL or GTERMINL profile.

# Conditional access processing

Using RACF, you can permit a user to access resources when that user is signed on a particular terminal or console, but not otherwise. Access that is restricted in this way is known as *conditional access*.

To grant conditional access to a resource, add WHEN(TERMINAL(*netname*))

or

WHEN(CONSOLE(console-name))

to the PERMIT command.

The following example allows members of the PAYROLL group to read the SALARY file wherever they are signed on. They would be able to update it only from the terminal with netname PAY001, by issuing the following commands:

```
RDEFINE FCICSFCT SALARY UACC(NONE)

PERMIT SALARY CLASS(FCICSFCT) ID(PAYROLL) ACCESS(READ)

PERMIT SALARY CLASS(FCICSFCT) ID(PAYROLL)

(WHEN(TERMINAL(PAY001)) ACCESS(UPDATE)
```

To allow members of the operations group OPS to be able to use the CEMT transaction only from the console names MVS1MAST, issue the following command:

RDEFINE TCICSTRN CEMT UACC(NONE) PERMIT CEMT CLASS(TCICSTRN) ID(OPS) WHEN(CONSOLE(MVS1MAST)) AC(READ)

#### Note:

- 1. The CONSOLE class must be active before CONSOLE conditional access lists can be used.
- 2. Conditional access lists may only increase authority and not decrease it.

For other considerations on conditional access lists see, the *z*/OS Security Server RACF Security Administrator's Guide.

## **Console profiles**

Use the CONSOLE resource class to define profiles that control user access to a console.

If the CONSOLE class has been activated, you can control whether a user is allowed to sign on to a console. Console protection is implemented in a method similar to that for protecting terminals, with the exception of the following, which were discussed in "Overriding the SETROPTS TERMINAL command" on page 68:

- 1. The SETROPTS TERMINAL command does not apply to consoles.
- 2. The TERMUACC group attribute does not apply to consoles.

Before activating the CONSOLE class, check the *z/OS MVS Planning: Operations* manual for the effects of console protection on MVS consoles.

The profile used in the console class is the console name or number. For example: RDEFINE CONSOLE CICSCONS UACC(NONE)

The user must have READ access to the console name to sign-on at a console. The following example shows how user CICSOPR would be permitted to sign on to the console named CONCICS1: RDEFINE CONSOLE CONCICS1 UACC(NONE) PERMIT CONCICS1 CLASS(CONSOLE) ID(CICSOPR) ACCESS(READ)

Note that, unlike the case with TERMINAL protection, a sign-on attempt will fail if made at a console that has not been defined in the activated CONSOLE class. The access authority to undefined consoles is NONE.

## Auditing sign-on and sign-off activity

RACF can log all sign-on and sign-off activity to SMF, including any invalid or unsuccessful sign-on attempts. You can use this information in several ways: for example, as an audit trail, to identify possible attempts to breach security, and to help with capacity planning.

You can only properly interpret the logging of unsuccessful sign-on attempts by also recording successful sign-ons. For example, if a user makes one or two unsuccessful attempts followed immediately by a successful sign-on, the unsuccessful sign-ons can be interpreted as being caused by keying errors at the terminal. However, several unsuccessful attempts for a variety of userids occurring within a short space of time, and without any subsequent successful sign-on activity being recorded, may well be cause for a security concern that warrants investigation.

Recording the successful sign-on and sign-off activities establishes an audit trail of the access to particular systems by the terminal user population. This may also be useful for systems capacity planning, and generally constitutes a very modest portion of the information recorded to SMF.

CICS uses its CSCS transient data destination for security messages. Messages of interest to the security administrator for the CICS region are directed to this destination. In some instances, when security-related messages are directed to terminal users, corresponding messages are written to the CSCS transient data destination. In the case of the DFHCE3544 and DFHCE3545 messages that are sent to terminal users, for example, the corresponding messages DFHSN1118 and DFHSN1119 are sent to CSCS. The DFHSNxxxx messages include reason codes that indicate the precise nature of the invalid sign-on attempt.

#### Preset terminal security

For some terminals, and MVS consoles when used as CICS terminals, it is appropriate to use preset terminal security as an alternative to terminal user security.

A terminal becomes a preset security terminal when you specify the USERID attribute on the TERMINAL resource definition.

There are two types of preset security for consoles:

- 1. Normal preset security (the same as preset security for other terminals)
- 2. Automatic preset security

# Normal preset security

CICS preset terminal security allows you to associate a userid permanently with a terminal, or console, that is defined to CICS.

This means that CICS implicitly signs on the device when it is being installed, instead of a subsequent sign-on of that terminal by a user. Typically, you define preset security for devices without keyboards, such as printers, at which users cannot sign on.

You can also use the normal preset security on ordinary display terminals as an alternative to terminal user security. This permits anyone with physical access to a terminal with preset security to enter the transactions that are authorized for that terminal. The terminal remains signed on as long as it is installed, and no explicit sign-off can be performed against it. If the userid associated with a display terminal with preset-security has been authorized to use any sensitive transactions, ensure that the terminal is in a secure location to which access is restricted. Preset-security might be appropriate, for example, for the terminals physically located within a CICS network control center.

You can use preset-security to assign a userid with **lower** authority than the default, for terminals in unrestricted areas.

For example, to define a terminal with preset-security, use RACF and CICS (CEDA) commands as follows:

ADDUSER userid NAME(preset_terminal_user_name) OWNER(owner_userid or group_id) DFLTGRP(group_name)

CEDA DEFINE TERMINAL(cics_termid) NETNAME(vtam_termid) USERID(userid) TYPETERM(cics_typeterm)

For further information on preset-security terminals in the transaction routing environment, refer to "Preset-security terminals and transaction routing" on page 177 (LU6.2 security) and "Preset-security terminals and transaction routing" on page 227 (MRO security).

## Automatic preset security for consoles

Automatic preset security applies only to console definitions. CICS automatic preset security allows you to associate the userid, which MVS has already verified through RACF, with the CICS definition for the console.

Instead of specifying an actual user id on the TERMINAL definition, you specify a special value (*FIRST or *EVERY), to indicate that CICS is to use the user id passed by MVS on the MODIFY command. This means that CICS implicitly signs on the console when it is being installed, and optionally on each input message, instead of a subsequent sign-on of that console by a user. Particularly in the context of autoinstalled consoles, this allows you to gain the advantage of preset security without having to define the user id/console relationship in the CICS terminal definition. Thus, console users do not have to sign-on with passwords in the clear to each CICS region.

You can use this automatic form of preset security on predefined consoles, autoinstalled consoles, and consoles installed with the **CREATE TERMINAL** command.

For example, to define a console with automatic preset-security, which is checked, and altered (if necessary) on every MODIFY, use CICS (CEDA) commands as follows:

```
CEDA DEFINE TERMINAL(cics_termid)
CONSNAME(consolename) USERID(*EVERY)
TYPETERM(cics_typeterm)
```

To define a console with automatic preset-security that is defined on the first valid MODIFY command only, use CICS (CEDA) commands as follows:

```
CEDA DEFINE TERMINAL(cics_termid)
CONSNAME(consolename) USERID(*FIRST)
TYPETERM(cics_typeterm)
```

# Controlling the use of preset-security

When a preset-security terminal is installed, the specified userid is implicitly signed on at the terminal.

Ensure that only a trusted person is allowed to define and install terminals with preset security, because the userid specified on the terminal may have access to CICS resources not available to the installer. Automatic preset security for consoles does not carry the same risks because the console user is associated with their true identity (verified by RACF). For this reason, no checking is carried out when a console device is defined to CICS with either USERID(*EVERY) or USERID(*FIRST).

Surrogate user checking ensures that a user is authorized to act for another user. Surrogate user checking can be enforced when a user installs a terminal that is preset for a different userid, and is specified by the RACF SURROGAT resource class. The CICS *userid*.DFHINSTL resource can be defined in the SURROGAT resource class for authorization to install terminals that are preset for that specific userid.

When a terminal is installed with a preset userid, the surrogate user is the userid performing the installation. See Chapter 7, "Surrogate user security," on page 113 for more information.

The CEDA command checks the authority of the user to install preset terminals. Consider, therefore, whether to restrict the following functions with a view to controlling who can define and install terminals with preset security:

- The CEDA transaction
- The SURROGAT resource class
- The XUSER system initialization parameter
- Batch access to the CSD using the DFHCSDUP utility
- The LOCK command for locking CSD definitions

**Note:** When CICS installs a GRPLIST that contains preset terminal definitions, no checking is done at initialization time. However, you can still ensure that you control who can define and install terminals and sessions with preset security by using the CEDA LOCK command to control the contents of GRPLIST groups.

#### **Restricting use of the CEDA transaction**

If the CEDA transaction is enabled on your production CICS regions, restrict its use to authorized users.

This gives you control over who can define resources, such as terminals, to CICS. See Chapter 10, "Security for CICS-supplied transactions," on page 143 for information about protecting CICS-supplied transactions.

#### Using the SURROGAT resource class

Ensure that you restrict who can install terminals with preset security, so that even when such terminals are defined in the CSD, only authorized users can install them on CICS.

(This authority is additional to the authority needed to run CEDA.) The user must already have authority to run the CEDA transaction.

To define a surrogate profile and authorize a user to install a terminal definition with preset security, use the following commands: RDEFINE userid1.DFHINSTL SURROGAT UACC(NONE) PERMIT userid1.DFHINSTL CLASS(SURROGAT) ID(userid2) ACCESS(READ)

This permits userid2 to install a terminal preset with userid1

#### Defining the XUSER system initialization parameter

To ensure that CICS can perform surrogate user security checks on the use of the CEDA INSTALL command for terminals with preset security, define the **XUSER** system initialization parameter.

See "CICS resource class system initialization parameters" on page 57 for information about defining this parameter.

#### Restricting batch access to the CSD

You can also use the CSD batch utility program, DFHCSDUP, to define resources in the CSD.

So that only authorized users are allowed to update the production CSDs, you should restrict the access list on the CSD data set profile to the CICS region userids and other authorized users only. The INSTALL command is not available in DFHCSDUP.

#### Using the LOCK command

CICS also installs resource definitions in the CSD during an initial or cold start, from the list of groups defined on the **GRPLIST** system initialization parameter.

To control the addition of resource groups to the CICS startup group list, you should use the **CEDA LOCK** command to lock the list. This protects the group list from unauthorized additions. Also, lock all the groups that are specified in this list.

**Note:** The OPIDENT of the signed-on user is used as the key for the **CEDA LOCK** and **CEDA UNLOCK** commands. For more information about the **LOCK** and **UNLOCK** commands, see the *CICS Resource Definition Guide*.

#### Other preset security considerations

If you intend to use preset security, consider these additional topics:

- Autoinstall models
- · Sessions with preset security
- Terminals defined in the TCT

#### Autoinstall models

If you are using autoinstall models with preset security, CICS makes the same surrogate authorization check as for ordinary terminals when the model is installed. It does not check surrogate authorization when the autoinstall model is used to perform autoinstall for a device. Also, CICS does not make a surrogate authorization check when installing models defined with automatic preset security for consoles.

If an autoinstall model with a preset userid becomes invalid (for example, if the userid is revoked), any attempt to install a terminal with the model fails.

#### Sessions

A session becomes governed by preset security if you specify the userid operand on the session definition. The same checking is performed if you install preset security sessions.

#### Terminals defined in the terminal control table

For terminals defined in the terminal control table (TCT) (for example, BSAM terminals), the userid is also defined in the TCT, and, when CICS initializes, it signs on these terminals.

If the sign-on fails (for example, if the userid is revoked), the terminal is put out of service. If the userid later becomes valid (for example, if it is resumed), setting the terminal in service results in a successful sign-on. CICS does not perform a surrogate user check for these terminals.

## Using an MVS system console as a CICS terminal

If you intend to use an MVS system console as a CICS terminal, you might need authorization to use the MVS MODIFY command by using the OPERCMDS resource class.

You can specify automatic preset security on the console's CICS terminal definition, so that the console user obtains the correct level of authority without explicitly performing a CICS signon (which exposes the password).

If preset security is not defined, console users must sign on to get authority different from the default user. In this case, the password can generally be seen on the console and system log. However, if CICS has been defined as an MVS subsystem in a JES2 system, you can use the HIDEPASSWORD=YES option of the DFHSSIxx member in SYS1.PARMLIB, which enables CICS to intercept the command and overwrite the password with asterisks. For details about defining CICS as an MVS subsystem, see the CICS Transaction Server for z/OS Installation Guide.

The format of the CESN command, when entered from a console, is as follows:

```
MODIFY jobname,CESN [USERID=userid][,PS=password]
    [,NEWPS=newpassword][,GROUPID=groupid]
    [,LANGUAGE=language-code]
```

If any of the data entered on the CESN command is invalid, or if the password is missing or expired, CICS prompts the user to enter the missing or invalid data by issuing a system message that requires a response (a WTOR message). Provide a response using the REPLY command. When CICS prompts for a password, it uses a security routing code to ensure that the response is not recorded on the console or in the system hardcopy log. To terminate the sign-on process, a REPLY command with a null operand is required. That is, enter:

REPLY nn,

with nothing after the comma, where nn is the number of the message corresponding to the reply.

You can authorize TSO users to use the TSO CONSOLE command. (For information on this command, see *z/OS TSO/E System Programming Command Reference*.) These users must be defined to CICS as consoles, using the CONSNAME option of the DEFINE TERMINAL command, or be supported by autoinstall for consoles. For more information, see the *CICS Resource Definition Guide*.

When the password parameter is omitted from the CESN command, RACF can produce a security violation message, ICH408I. CESN cannot distinguish a user defined with OIDCARD, NOPASSWORD from a user defined with a PASSWORD who intentionally omits the password. To establish whether to prompt for a PASSWORD or to reject the signon (a user defined with OIDCARD cannot sign on at a console), the signon must be attempted. If the signon fails, message ICH408I is produced, and CICS interprets the return code from RACF to determine whether the PASSWORD or OIDCARD authenticator is required.

These users can sign on using CESN, or you may prefer to use preset security (the normal preset security for CICS terminals, or automatic preset security for consoles). When the TSO user uses the CONSOLE command, that user's userid, by default, becomes a console name. (But it can be changed to be any name using the CONSNAME(*name*) option on the TSO CONSOLE command). This console name can then be used as a CICS terminal if there is a corresponding TERMINAL definition (or one can be autoinstalled) with the CONSNAME option in CICS. If another name has been specified, that name is the one CICS uses to communicate with the console. For example, it is possible for one TSO user to use a name that is the same as another TSO user's ID.

Furthermore, if the CONSOLE command is used to allow TSO operators to sign on to CICS with the CESN transaction, their passwords may be exposed on the TSO screen and in the MVS system log. These potential exposures can be removed by defining the terminal as having preset security. We recommend that you use automated preset security for the following reasons:

- It means that TSO users do not have to sign on, which may expose their ID and password on the log.
- It means that you do not have to define a relationship, in a CICS definition, between a console name and a user, which may change frequently or become invalid.
- It allows you to define one autoinstall model which covers the majority of your console definitions and gives each user the correct level of preset security.

To define automatic preset security, specify USERID(*EVERY) to ensure that the correct user ID is signed on for every command, or USERID(*FIRST) to sign on the console using the userid that first issues a MVS MODIFY command to CICS, and retain this for subsequent commands.

- Choose USERID(*FIRST) if use of a console is restricted to one or more users who have similar security characteristics to CICS using RACF, and you don't use the user ID as an identifier in applications.
- Use USERID(*EVERY) if you need to ensure that each input request is tested to be sure that the console user has the correct security level. You should be aware that checking the user ID imposes an overhead on MODIFY, and changing the preset userid imposes another overhead which is equivalent to the console user signing on using CESN.

# **Obtaining CICS-related data for a user**

CICS obtains CICS-related data from one of the following sources:

- The CICS and LANGUAGE segments of the RACF profile
- Built-in CICS system default values.

This section explains how the data is obtained, for the default user and terminal users signing on.

# Obtaining CICS-related data for the default user

When implicitly signing on the CICS default user during initialization, CICS obtains attributes in the following way:

- CICS calls RACF to request user data for the CICS default user from the CICS segment and the LANGUAGE segment. If the CICS segment or the LANGUAGE segment data is present for the default userid, RACF returns this data to CICS. See "The CICS segment" on page 15 for details of the information that you can define in the CICS segment. See "The LANGUAGE segment" on page 19 for details of the LANGUAGE segment.
- 2. If RACF does not return the CICS segment or LANGUAGE segment data for the default userid, CICS assigns the following built-in system default values:

#### National language

Obtained from the first operand on the NATLANG system initialization parameter. This defaults to US English if not specified.

#### **Operator class**

One (OPCLASS=1)

**Operator identification** Blank (OPIDENT=' ')

**Operator priority** Zero (OPPRTY=0)

#### Timeout

Zero (TIMEOUT=0)

#### XRF signoff

Signoff not forced (XRFSOFF=NOFORCE)

## Obtaining CICS-related data at signon

When handling an explicit sign-on for a CICS terminal user, CICS obtains the terminal user attributes in the following way:

- CICS calls RACF to request data about the CICS terminal user from the CICS segment and the LANGUAGE segment. If the CICS segment or the LANGUAGE segment data is present for the terminal user, RACF returns this data to CICS. See "The CICS segment" on page 15 for details of the information that you can define in the CICS segment. See "The LANGUAGE segment" on page 19 for details of the LANGUAGE segment.
- 2. If RACF does not return the CICS segment or LANGUAGE segment data for the user, CICS uses the user attributes of the CICS default user, defined during system initialization. (See "Obtaining CICS-related data for the default user.")

CICS obtains the national language attribute in the following order:

 The LANGUAGE option on the CICS-supplied CESN transaction, or the LANGUAGECODE or NATLANG option of the SIGNON API command, if supported by CICS. A supported national language is a valid national language that has been specified in the **NATLANG** system initialization parameter and has the corresponding message definitions. See the *CICS System Definition Guide* for more information about defining this parameter.

- 2. The PRIMARY *primary-language* parameter in the LANGUAGE segment of the user's RACF profile, if supported by CICS.
- **3.** The SECONDARY *secondary-language* parameter in the LANGUAGE segment of the user's RACF profile, if supported by CICS.
- 4. The NATLANG parameter in the CSD definition of the user's terminal.
- 5. The language established for the default user as described in "Obtaining CICS-related data for the default user" on page 76.

See Appendix A, "National Language," on page 383 for a list of valid national languages.

**Note:** CICS ignores the RACF default national language defined by the command: SETROPTS LANGUAGE(PRIMARY(...) SECONDARY(...))

#### Defining terminal users and user groups to RACF

You should plan to define your CICS terminal users in groups.

For this purpose, try to place the users of CICS systems in groups for ease of administration. For example, you might consider that all users who have the same manager, or all users within an order entry function, are an administrative unit. You can define such users to RACF as **groups** of individual users who have similar access requirements to CICS system resources. See the *z*/OS Security Server RACF Security Administrator's Guide for more information about:

- · Access control and flexibility of operation for the system administrator
- Use of the group-SPECIAL attribute and its scope of control
- Reducing the need to refresh in-storage profiles

When you define a group, and then define users as members of that group, all the users in the group can access the resources to which the group has been given access.

The group structure selected depends on your own installation's requirements. Use the RACF command ADDGROUP to create a new group:

ADDGROUP groupname OWNER(userid)

Use the ADDUSER command to add new users to the group, defining the group name as the user's default group:

```
ADDUSER userid NAME(username) DFLTGRP(group_id)
CICS(OPCLASS(1,2,..,n) OPIDENT(abc) OPPRTY(255) TIMEOUT(minutes)
XRFSOFF(NOFORCE) LANGUAGE(PRIMARY(language))
```

You can make a terminal user a member of more than one group by using the CONNECT command to add the user to a group other than that user's default group:

CONNECT userid GROUP(groupname)

Use the ALTUSER command to change a user's default group, as follows: ALTUSER userid DFLTGRP(groupname)

Use the ALTUSER command to add CICS data for an existing userid. See "The CICS segment" on page 15 for details of the CICS optional data.

See the *z/OS Security Server RACF Command Language Reference* for the full syntax of these commands.

#### Example of defining terminal users and user groups to RACF

Assume there is a customer service department that:

- Takes orders
- · Answers inquiries about those orders
- Establishes new customers

Consider creating the following customer service group: ADDGROUP custserv OWNER(grpmangr)

In this example, *grpmangr* is the RACF userid of the person in charge of the customer service department system.

The person represented by *grpmangr*, or the RACF security administrator, can then create additional groups within the group CUSTSERV, as follows:

ADDGROUP ORDERS OWNER(SUP1) SUPGROUP(CUSTSERV) ADDGROUP ORDINQ OWNER(SUP2) SUPGROUP(CUSTSERV) ADDGROUP NEWCUST OWNER(SUP3) SUPGROUP(CUSTSERV)

The group owners, the person represented by *grpmangr* or the RACF security administrator can then define users within the groups. For example, the person represented by SUP1 could define users of the group ORDERS, as follows:

ADDUSER AARCHER NAME('ANNE ARCHER') DFLTGRP(ORDERS) ADDUSER JBRACER NAME('JOHN BRACER') DFLTGRP(ORDERS) PASSWORD(XPRDTD) CICS(OPCLASS(1) OPIDENT(JBR) OPPRTY(0) TIMEOUT(15) XRFSOFF(FORCE)) LANGUAGE(PRIMARY(ENU))

#### Note:

- 1. The password of the user Anne Archer defaults to ORDERS, but the password of the user John Bracer is initially set as XPRDTD.
- The user John Bracer is defined with a CICS segment and with a LANGUAGE segment.

#### Support for mixed-case passwords

When the security manager used with CICS supports the use of mixed-case passwords, such as the z/OS Security Server (RACF) for z/OS 1.7, CICS Transaction Server for z/OS, Version 3 Release 1 does not convert passwords to uppercase before passing them to the security manager.

When a password is entered using one of the following mechanisms:

#### API commands

The following commands have a PASSWORD option: CHANGE PASSWORD VERIFY PASSWORD SIGNON

The signon transaction (CESN)

The transaction offers two fields where passwords can be entered: Password New password

CICS can handle the password in one of two ways, depending upon whether the external security manager used with CICS supports mixed-case passwords.

- If the security manager supports mixed-case passwords, then CICS passes the password to the security manager unchanged.
- If not, then CICS converts the password to uppercase before passing it to the security manager.

To turn support for mixed-case passwords on, see "Summary of RACF commands" on page 27.

# National language and non-terminal transactions

When a user specifies a national language during sign-on, the sign-on option overrides the language specified in the user's RACF CICS segment.

The language thus specified is set for the time that the user is signed on at the terminal. Any transaction invoked by the signed-on user runs with the national language specified on the sign-on.

However, if a transaction uses the START command to start another transaction, the national language attribute for the started transaction is derived as follows:

- 1. If the USERID parameter is specified on the START command, the national language is taken from the RACF CICS segment of the specified userid.
- 2. If the user is signed on at a terminal with a preset national language specified on the terminal definition, this preset national language is assigned to the started transaction.
- **3.** If there is no userid on the START command, and no preset national language on the terminal, the started transaction inherits the national language specified in the RACF CICS segment of the signed-on user (not the national language used in the sign-on).

If the national language of the original terminal is required, the terminal's national language can be inquired about before the START command is issued. The information can then be passed as data in the START command for the use of the transaction that has been started.

# Chapter 5. Transaction security

Transacation security (also known as *attach-time security*, and *transaction-attach security*) ensures that users that attempt to run a transaction are entitled to do so.

## CICS parameters controlling transaction-attach security

You control CICS transaction-attach security checking through CICS system initialization parameters.

These are:

**SEC** Specify SEC=YES if you want to use RACF services to control access to any CICS resources—in particular, CICS transactions. (For more information, see "Security-related system initialization parameters" on page 55.)

#### SECPRFX

Specify SECPRFX=YES if your transaction profiles are defined to RACF with a prefix that corresponds to the userid of the CICS region.

Specify SECPRFX=*prefix* if your transaction profiles are defined to RACF with any other prefix. (For more information, see "Security-related system initialization parameters" on page 55.)

#### **XTRAN**

Specify XTRAN=YES or XTRAN=*resource_class_name* if you want CICS to control who can initiate transactions. If you specify YES, CICS uses profiles defined in the RACF default resource classes TCICSTRN and GCICSTRN. (See "RACF classes for CICS resources" on page 23 for details of these resource classes.)

If you specify a resource class name, CICS uses the name you specified, prefixed with T for the resource class, and G for the grouping class.

If you specify XTRAN=NO, CICS does not perform any authorization check on users initiating transactions.

Note that the default is YES. Therefore if you specify SEC=YES and omit the XTRAN parameter, transaction-attach security is in effect, using the default resource class names.

There are no CICS parameters that allow you to control transaction-attach security at the individual transaction level. When you specify SEC=YES and XTRAN=YES (or XTRAN=resource_class_name), CICS issues an authorization request for every transaction. It does this whether the transaction is started from a terminal, by using an EXEC CICS START command, or triggered from the transient data queue, either with or without the termid operand. CICS performs this security check even if no user has signed on. Users who do not sign on can use only those transactions that are authorized to the default user.

Figure 3 on page 82 is an example which shows the main elements of CICS transaction security.




Figure 3. An example of the main elements of CICS transaction security.

In this example:

- The following system initialization parameters are specified:
  - SEC=YES XTRAN=YES

Because XTRAN=YES is specified, the resource class name is TCICSTRN and the grouping class name is GCICSTRN.

- The resource class TCICSTRN contains profiles TRN1, TRN2, and TRN3.
- The grouping class GCICSTRN contains the following group profiles:
- PAYROLL (members SALR, OVRT, INSR, and PENS)
- PERSONNEL (members STAF, MGRS, STDT, and CONT)
- ACCOUNTS (members INVC, LEDG, BUDG, and CASH)

# Transaction-attach processing when SEC=YES and XTRAN=YES

Every time a transaction is initiated at a CICS terminal, CICS issues an authorization request to determine whether the user associated with the terminal is authorized for that transaction. CICS and RACF process the authorization request using the currently active transaction profiles in the RACF class identified by the XTRAN SIT parameter. (For more information, see "Refreshing resource profiles in main storage" on page 22.)

# Defining transaction profiles to RACF

For those CICS regions running with transaction security checking, define transaction profiles for all transactions that need to be protected from unauthorized access.

#### About this task

You can define these profiles either in the default transaction resource classes, or in installation-defined classes that you have added to the RACF class descriptor table. (See "RACF classes for CICS resources" on page 23 for information about the transaction resource classes.)

## Some recommendations

The following recommendations are intended to reduce the amount of work involved:

- Define transactions in the resource group class, GCICSTRN. This minimizes the amount of effort needed to define and maintain transaction profiles and their associated access lists, and also keeps down the size of in-storage profiles. However, note that using resource groups only reduces the amount of storage required if you avoid defining duplicate member names.
- Add users to the access list in groups rather than as individual users, and define access as READ.
- Use generic profiles or member names wherever possible.

For example, the following RDEFINE and PERMIT commands illustrate some payroll transactions, with access given to members of the payroll department:

```
RDEFINE GCICSTRN salarytrans
NOTIFY(pay_manager)
UACC(NONE) ADDMEM(Pay1, Pay2, Pay3,..., Payn)
PERMIT salarytrans CLASS(GCICSTRN)
ID(paydept group userid) ACCESS(READ)
```

In this example, you could instead define the members generically, such as  $\mathsf{P*}$  or  $\mathsf{Pay*}.$ 

However, before you define a generic profile you must issue the command: SETROPTS GENERIC(TCICSTRN)

You cannot specify the GCICSTRN class, because you cannot group classes with the SETROPTS GENERIC command.

If you have transactions that anyone can use, you can avoid maintaining access lists for them by defining RACF transaction profiles for them with UACC(READ). For example:

RDEFINE TCICSTRN tranid UACC(READ)

If you want to avoid defining any of your transactions to RACF, you can specify universal access as follows: RDEFINE TCICSTRN ** UACC(READ) You then need to define to RACF only those transactions that require more restrictive security.

**Note:** If you use a profile like that described above, define new profiles to RACF before installing new CICS resources.

# Using conditional access lists for transaction profiles

You can add another element of security by making the access list conditional upon the user being signed on at a particular terminal or console.

For example, if the earlier payroll examples are defined as generic transactions in the TCICSTRN class, you could define conditional access as follows:

```
RDEFINE TCICSTRN PAY*
NOTIFY(pay_manager) UACC(NONE)
PERMIT pay* CLASS(TCICSTRN) ID(userid) ACCESS(READ)
WHEN(TERMINAL(termid))
WHEN(CONSOLE(*))
```

#### Note:

- 1. The TERMINAL or CONSOLE class must be active for this support to take effect.
- WHEN(TERMINAL(*termid*)) applies only to explicitly signed-on users, and only in the region where the user is explicitly signed on, and in regions connected to it by MRO links only.
- 3. CICS uses only the console and terminal ports of entry.

## Protecting the CEBT transaction

The CEBT transaction (the master terminal transaction used to control the alternate CICS system in an XRF environment) is not subject to transaction security checking.

This means that any user is authorized to use CEBT. CEBT can only be issued from the operating system console, using the MODIFY command. You can use the OPERCMDS resource class to control who is allowed to use the MODIFY command.

For more information, see "Using an MVS system console as a CICS terminal" on page 74.

## Authorization failures and error messages

If a terminal user tries to initiate an unauthorized transaction, CICS issues a security violation message (DFHAC2033) to the terminal.

CICS then sends a corresponding message (DFHAC2003) to the CSMT transient data destination, and a DFHXS1111 message to CSCS. RACF normally issues an ICH408I message to the CICS region's job log and to the security console (the console defined for routing code 9 messages). However, if the transaction has been defined to RACF with LOG(NONE), no ICH408I message is issued. For a description of the ICH408I message, see the *z/OS Security Server RACF Messages and Codes* manual.

For more information on resolving authorization problems, see Chapter 24, "Problem determination in a CICS-RACF security environment," on page 325.

If auditing (such as that requested by the AUDIT operand) is requested for this access, RACF writes an SMF type 80 log record. Your RACF auditor can use the RACF report writer to generate reports based on these records. For more information, see the *z*/*OS Security Server RACF Auditor's Guide*.

# Protecting non-terminal transactions

For all resource security checking, CICS needs a userid in order to check the user's authority to access the resource.

CICS can protect resources against unauthorized use if those resources are used in transactions that are not associated with a terminal. In addition to transactions started by an EXEC CICS START command without a terminal identifier specified, there are two other types:

- Transactions started without a terminal when the trigger level is reached for an intrapartition transient data queue
- Programs executed from the second phase of the program list table (PLT) during CICS startup

# **Triggered transactions**

The CEDA transaction, the CEDA DEFINE TDQUEUE, the EXEC CICS CREATE, and the ATIUSERID option of the EXEC CICS SET command establish security for non-terminal transactions started by a transient data trigger level.

The user issuing the SET, INSTALL, or CREATE command must have surrogate authority for the userid specified on the ATIUSERID option. The user to be associated with the triggered transaction is specified on the USERID attribute of the transient data queue definition.

# PLT programs

If PLT programs are to be executed during CICS startup, CICS performs a surrogate user security check for the region userid. See "Defining user profiles for CICS region userids" on page 39. This check determines whether the CICS job is authorized to be the surrogate of the userid specified on the PLTPIUSR parameter. The PLTPIUSR and PLTPISEC system initialization parameters specify security options for PLT programs that are run from the third stage of CICS startup (which is the second phase of the PLTP initialization).

If the PLTPIUSR parameter is not specified, the PLT programs are run under the CICS region userid when the PLTPISEC=NONE option is defined. No surrogate check is required for this. If your PLT programs issue START commands, the jobstep userid has surrogate authority to start them when no userid is coded. Note that the starter always has surrogate authority to itself. When the started transaction starts up, another check is made to see if the userid has authority to attach the transaction and access this transaction in the TCICSTRN class. Rather than giving the jobstep access to additional resources, you can use the PLTPIUSR and PLTPISEC parameters.

During shutdown, CICS runs PLT programs under the authority of the userid for the transaction that requested the shutdown. The values of the RESSEC and CMDSEC options for that transaction are also applied to the PLT programs. If RESSEC(YES) and CMDSEC(YES) are specified on the definition of the transaction issuing the EXEC CICS PERFORM SHUTDOWN command, security checking is done at the first stage of shutdown.

# Chapter 6. Resource security

Resource security protects CICS resources against unauthorized access. **Related tasks**:

"Security using the XRES resource security parameter"

Use the XRES system initialization parameter to security check the following CICS resources: ATOMSERVICE, BUNDLE, DOCTEMPLATE, EVENTBINDING, JVMSERVER, and XMLTRANSFORM. An example of how to implement resource security for CICS document templates, the DOCTEMPLATE resource, is provided.

# Introduction to resource security

Resource security provides a further level of security to transaction security, by controlling access to the resources used by the CICS transactions. A user who is authorized to invoke a particular CICS transaction might not be authorized to access files, PSBs, or other general resources used within the transaction. Unlike transaction security, which cannot be turned off for individual transactions, you can control resource security checking at the individual transaction level.

Resources defined to CICS to support application programming languages are also subject to security checking if resource or command security checking is specified. df

You control who can access the general resources used by CICS transactions, by:

- Specifying SEC=YES as a system initialization parameter
- Specifying RESSEC=ALWAYS as a system initialization parameter
- Specifying RESSEC(YES) in the TRANSACTION resource definition
- Specifying the types of resource you want to protect by defining CICS system initialization parameters for the RACF general resource classes
- Defining the CICS resources to RACF in resource class profiles, with appropriate access lists.

## Security using the XRES resource security parameter

Use the XRES system initialization parameter to security check the following CICS resources: ATOMSERVICE, BUNDLE, DOCTEMPLATE, EVENTBINDING, JVMSERVER, and XMLTRANSFORM. An example of how to implement resource security for CICS document templates, the DOCTEMPLATE resource, is provided.

#### About this task

CICS profile names consist of 3 parts: *security_prefix.resource_type.resource_name*.

The *security_prefix* is the value specified on the **SECPRFX** SIT parameter; the default value for the **SECPRFX** parameter is N0 which means that the *security_prefix* is omitted. If the value of the **SECPRFX** parameter is YES, the *security_prefix* takes the name of the region userid. Alternatively, you can specify a 1- to- 8 character value for the *security_prefix*.

The *resource_type* specifies the type of CICS resource, such as ATOMSERVICE, BUNDLE, DOCTEMPLATE, EVENTBINDING, JVMSERVER, or XMLTRANSFORM.

The *resource_name* specifies the name of the CICS resource.

For example, a profile name of TEST.JVMSERVER.MyResource has a *security_prefix* of TEST, a *resource_type* of JVMSERVER, and a *resource_name* of MyResource.

CICS profiles are passed to the security manager for checking. Note that security checking is case sensitive.

#### Example

This example task focuses on implementing resource security for CICS document templates.

CICS document templates are controlled in the following cases:

- Document templates delivered as a static response to a Web client's request (specified on the TEMPLATENAME attribute of the URIMAP definition for the request).
- Document templates delivered as part of an application-generated response to a Web client's request (used by an application program that handles the request).
- All EXEC CICS CREATE, INQUIRE, DISCARD and SET DOCTEMPLATE commands.
- All EXEC CICS DOCUMENT INSERT and CREATE commands with the TEMPLATE option.

The EXEC CICS DOCUMENT commands reference document templates using the 48-character name of the template (as specified in the TEMPLATENAME attribute of the DOCTEMPLATE resource definition). However, security checking for these commands uses the name of the DOCTEMPLATE resource definition that corresponds to the TEMPLATENAME attribute. This means that you need to set up only one profile name for each document template, using the name of the DOCTEMPLATE resource definition, and not the TEMPLATENAME attribute.

**Note:** Document templates can be retrieved from a variety of sources including partitioned data sets, CICS programs, CICS files, z/OS UNIX System Services files, temporary storage queues, transient data queues, and exit programs. When resource security checking is carried out for a document template, CICS does not perform any additional security checking on the resource that supplies the document template, even if resource security is specified for that type of resource in the CICS region.

Complete the following steps to implement resource security for CICS document templates:

 Define profiles to RACF in the default RCICSRES resource class or WCICSRES grouping class, or their equivalents if you have user-defined resource class names.

For the profile names, use the name of the DOCTEMPLATE resource definition, prefixed by the resource type DOCTEMPLATE, and any additional prefix specified by the **SECPRFX** system initialization parameter for the CICS region.

For example, use the following commands to define document templates in the RCICSRES class, and authorize users to use them to assemble documents:

RDEFINE RCICSRES (DOCTEMPLATE.doc1, DOCTEMPLATE.doc2, .., DOCTEMPLATE.docn) UACC(NONE) NOTIFY(sys_admin_userid) PERMIT DOCTEMPLATE.doc1 CLASS(RCICSRES) ID(group1, group2) ACCESS(READ)

88 CICS TS for z/OS 4.1: RACF Security Guide

To define document templates as members of a profile in the WCICSRES resource grouping class, with an appropriate access list, use the following commands:

RDEFINE WCICSRES (doc_groupname) UACC(NONE)

ADDMEM(DOCTEMPLATE.doca, DOCTEMPLATE.docb) NOTIFY(sys_admin_userid) PERMIT doc_groupname CLASS(WCICSRES) ID(group_userid) ACCESS(READ)

After you have issued the RDEFINE command for the RCICSRES or WCICSRES class, if the class is not yet active, you need to activate it by issuing a SETROPTS command. For example:

SETROPTS CLASSACT(RCICSRES) RACLIST(RCICSRES)

If the class is active, refresh it using the SETROPTS command: SETROPTS RACLIST(RCICSRES) REFRESH

- 2. Specify **SEC**=YES as a CICS system initialization parameter (and **SECPRFX**=YES if you define profiles with a prefix).
- Specify XRES=YES for the default resource class names of RCICSRES and WCICSRES, or XRES=*name* for user-defined resource class names. XRES=YES is the default.
- 4. Specify RESSEC(YES) in the TRANSACTION resource definition of the transactions that access the CICS document templates.

For CICS Web support, the transaction for all static responses is CWXN, or an alternate transaction that you have specified in place of CWXN using the TRANSACTION attribute on your TCPIPSERVICE definitions. The transaction for application-generated responses is an alias transaction, which can be specified in the URIMAP definition for the request or set by an analyzer program, and defaults to CWBA.

As supplied by CICS, the definition for CWXN specifies RESSEC(YES), but the definition for CWBA specifies RESSEC(NO), and for TRANSACTION resource definitions in general the default is RESSEC(NO).

#### **Related information:**

Chapter 6, "Resource security," on page 87 Resource security protects CICS resources against unauthorized access.

"Resource security checking by CICS and RACF" on page 91

CICS uses RACF to protect the resources that you can access through a CICS application program.

"Defining generic profiles for resources" on page 110

If you control access to CICS transactions by means of transaction-attach security, there is probably only a very small subset of other resource types for which you need a further level of RACF protection.

Appendix B, "Resource and command check cross reference," on page 385 Use this cross reference to check commands against resources.

# Access authorization levels

A minimum of READ access is required for CICS document templates used as static Web pages, document templates used by application programs as part of application-generated responses, and document templates used with all EXEC CICS DOCUMENT INSERT and CREATE commands with the TEMPLATE option.

For information about the access authorization levels for system programming commands which apply to CICS document templates, see Appendix B, "Resource and command check cross reference," on page 385.

# User IDs for access to document templates and z/OS UNIX files used by CICS Web support

When resource security is active for a transaction, the external security manager checks whether the user ID associated with the transaction is authorized to access the required resources. For CICS Web support, the user ID associated with the transaction for a particular Web request can be obtained from different sources. Depending on the level of security that you require, you can arrange your CICS Web support architecture to determine the user IDs that are used for resource security checking against the secured document templates or z/OS UNIX files.

#### Application-generated responses

For CICS Web support, the transaction for application-generated responses is an alias transaction, which can be specified in the URIMAP definition for the request or set by an analyzer program, and defaults to CWBA. CWBA is defined as RESSEC(NO), so if you require resource security for the alias transaction, you must either copy the CWBA definition to your own group and change its RESSEC attribute, or use a different alias transaction.

When a Web client makes a request to CICS Web support, and the response is provided by an application, CICS selects a userid for the alias transaction in the following order of priority:

- 1. A user ID that you set using an analyzer program. This user ID can override a user ID obtained from the Web client or supplied by a URIMAP definition.
- 2. A user ID that you obtained from the Web client using basic authentication, or a user ID associated with a client certificate sent by the Web client. If authentication is required for the connection but the client does not provide an authenticated user ID, the request is rejected.
- 3. A user ID that you specified in the URIMAP definition for the request.
- 4. The CICS default user ID, if no other can be determined.

For application-generated responses, the user ID selected for the Web client applies to the whole alias transaction, and must be authorized to attach the transaction and use the Web application program, as well as to use secured document templates.

Web clients' user IDs do not need specific permissions on z/OS UNIX files for application-generated responses, because applications can only manipulate z/OS UNIX files using EXEC CICS commands when the files are defined as CICS document templates. Security checking is only carried out for the CICS document template, and not again for the z/OS UNIX file.

#### Static responses

The transaction for all static responses specified in URIMAP definitions is the default Web attach task CWXN, or any alias transaction that you have specified in place of CWXN using the TRANSACTION attribute on your TCPIPSERVICE definitions.

When a Web client makes a request to CICS Web support, and the response is a static response specified in a URIMAP definition, the user ID used for the Web client is a user ID that you obtained from the Web client using basic authentication, or a user ID associated with a client certificate sent by the Web client.

1

Т

Resource security checking for document templates is controlled by the XRES system initialization parameter and the RESSEC attribute for the transaction (CWXN or its alias). Access control for z/OS UNIX files is controlled by the XHFS system initialization parameter only.

The user ID for the Web client is used only during the process of resource security checking for the document template or z/OS UNIX file that is to be delivered as the static response. The user ID must be authorized to access the document template or z/OS UNIX file.

# Resource security checking by CICS and RACF

CICS uses RACF to protect the resources that you can access through a CICS application program.

Each resource is described briefly in Table 8, with the associated CICS system initialization parameter that you use to specify the RACF class name. For comprehensive information about application programming commands and system programming commands associated with each system initialization parameter, see Appendix B, "Resource and command check cross reference," on page 385.

Note that no authorization processing is done for BMS commands.

CICS parameter	Resource protected	Further information
ХАРРС	Partner logical units (LU6.2).	Chapter 12, "Implementing LU6.2 security," on page 163.
XCMD	The subset of CICS application programming commands that are subject to command security checking. EXEC CICS FEPI system commands are also controlled by this parameter.	Chapter 8, "CICS command security," on page 121
XDB2	DB2 resource classes for DB2ENTRY are specified to CICS on the XDB2 system initialization parameter.	"Resource classes for DB2ENTRYs" on page 27
XDCT	CICS extrapartition and intrapartition transient data destinations, also known as queues. Define profiles in the destination class to control who is allowed to access CICS transient data queues.	"Security for transient data" on page 95.
XEJB	Enterprise bean methods	Java Applications in CICS
XFCT	CICS file-control-managed VSAM and BDAM files. Define profiles in the file class to control who is allowed to access CICS VSAM and BDAM files.	"Security for files" on page 97.
XHFS	z/OS UNIX files managed by z/OS UNIX System Services. This is a special case, because access controls for z/OS UNIX files are specified in z/OS UNIX System Services, so z/OS UNIX files do not require individual RACF profiles. No application programming commands or system programming commands are associated with this resource.	"Implementing security for z/OS UNIX files" on page 106.
ХЈСТ	CICS system log and general logs. Define profiles in the journal class to control who is allowed to access CICS journals on CICS log streams.	"Security for journals and log streams" on page 98.

Table 8. General resource checking by CICS

CICS parameter	Resource protected	Further information			
XPCT	CICS started transactions and EXEC CICS commands: COLLECT STATISTICS TRANSACTION, DISCARD TRANSACTION, INQUIRE TRANSACTION, INQUIRE REQID, SET TRANSACTION, and CANCEL. Define profiles in the started-transactions class to control who is allowed access to started CICS transactions.	"Security for started and XPCT-checked transactions" on page 99.			
XPPT	CICS application programs. Define profiles in the program class to control who is allowed to access CICS application programs.	"Security for application programs" on page 102.			
XPSB	DL/I program specification blocks (PSBs). Define profiles in the program specification block class to control who is allowed to access the DL/I PSBs used in CICS application programs.	"Security for program specification blocks" on page 108.			
XRES	CICS resource definitions that use the XRES parameter are: ATOMSERVICE, BUNDLE, DOCTEMPLATE, EVENTBINDING, JVMSERVER, and XMLTRANSFORM.	"Security using the XRES resource security parameter" on page 87.			
	For example, define profiles in the DOCTEMPLATE resource class to control who is allow				
XTRAN	CICS transactions.	Chapter 5, "Transaction security," on page 81.			
XTST	CICS temporary storage destinations. Define profiles in the temporary storage class to control who is allowed to access CICS temporary storage queues.	"Security for temporary storage" on page 103.			
XUSER	Surrogate user security.	Chapter 7, "Surrogate user security," on page 113.			

Table 8. General resource checking by CICS (continued)

#### **Related tasks**:

"Security using the XRES resource security parameter" on page 87 Use the XRES system initialization parameter to security check the following CICS resources: ATOMSERVICE, BUNDLE, DOCTEMPLATE, EVENTBINDING, JVMSERVER, and XMLTRANSFORM. An example of how to implement resource security for CICS document templates, the DOCTEMPLATE resource, is provided.

# **RESSEC** transaction resource security parameter

Specifying RESSEC(YES) in the definition of a transaction, together with the appropriate resource classes defined in the system initialization parameters, introduces another layer of security checking in addition to the transaction-attach security described in "Transaction-attach processing when SEC=YES and XTRAN=YES" on page 82.

For most simple (or single-function) transactions, this extra layer of security is not necessary. For example, if the transaction is designed to enable the terminal user to update a personnel file and nothing else, it should be sufficient to authorize access to the transaction without controlling access to the file also. However, if you have a complex transaction that offers users a choice of functions, or you are unsure about all the options available within a transaction, you may want to add the extra layer of security to restrict access to the data as well as to the transaction. Before

implementing resource security checking, take into account the extra overhead that resource security checking involves, and only implement it if you believe the extra cost is worthwhile.

If you specify RESSEC(YES) on a transaction definition, CICS calls RACF for each CICS command (or in the case of z/OS UNIX files, each operation) that applies to one of the following resources, for which you have requested security, using an *Xname* resource class parameter:

- extrapartition and intrapartition transient data destinations (XDCT parameter)
- file-control-managed VSAM and BDAM files (XFCT parameter)
- system logs and general log (XJCT parameter)
- started transactions and EXEC CICS commands: COLLECT STATISTICS TRANSACTION, DISCARD TRANSACTION, INQUIRE TRANSACTION, INQUIRE REQID, SET TRANSACTION, and CANCEL (XPCT parameter)
- application programs (XPPT parameter)
- resources subject to XRES security checks: ATOMSERVICE, BUNDLE, DOCTEMPLATE, EVENTBINDING, JVMSERVER, and XMLTRANSFORM (XRES parameter)
- temporary storage destinations (XTST parameter)

Consider this example:

```
The system initialization parameters include:
SEC=YES
XDCT=NO
XFCT=YES
XTRAN=YES
XTST=YES
Transaction TRN1 contains the following EXEC CICS commands:
• 4 file control READ commands
• 1 file control WRITE command

    2 transient data WRITEQ commands

    1 temporary storage WRITEQ command

When TRN1 executes, the seven calls are made to RACF:

    1 at transaction attach, because XTRAN=YES is specified

    5 for file control access, because XFCT=YES is specified

    1 for temporary storage access, because XTST=YES is specified

RACF is not called for transient data access, because XDCT=NO is specified.
```

# The RESSEC system initialization parameter

You can force the effect of RESSEC=YES for all CICS transactions by specifying the RESSEC=ALWAYS system initialization parameter.

In general, this is not recommended, for the following reasons:

- For most simple transactions, just controlling access to the transaction is enough to control everything that the transaction can do.
- Invoking a resource check for every CICS resource consumes extra overhead that reduces the performance of all your transactions.
- Some CICS-supplied transactions may access resources of which you are unaware. It is your responsibility to ensure that users of these transactions are given enough authority to allow the transactions to continue to work.

# Authorization failures

If a terminal user is not authorized to access the resource specified on a CICS command, CICS returns the NOTAUTH condition to the application program.

CICS indicates this authorization failure by setting the EIBRESP field of the EXEC interface block (DFHEIBLK) to a value of 70 (and X'46' in byte 0 of the EIBRCODE field). Design your CICS applications to handle security violations by passing control to an appropriate routine. They can do this in either of the following ways:

• Test the EIBRESP condition by adding the RESP option to each command that may receive a NOTAUTH condition. For example (in COBOL):

```
EXEC CICS FILE('FILEA')
INTO(REC) RIDFLD(KEY)
RESP(COMMAND-RESPONSE)
END-EXEC.
```

```
EVALUATE COMMAND-RESPONSE
WHEN DFHRESP(NORMAL)
CONTINUE
WHEN DFHRESP(NOTAUTH)
PERFORM SECURITY-ERROR
END-EVALUATE.
```

• Code an EXEC CICS HANDLE CONDITION NOTAUTH(*label*) command, where *label* is the name of the security violation routine.

If an application does not cater for security violations, CICS abends the transaction with an AEY7 abend code.

## Logging RACF audit messages to SMF

Except when processing certain security commands (see Chapter 9, "Security checking using the QUERY SECURITY command," on page 133), CICS issues security authorization requests with the logging option. This means that RACF writes SMF type 80 log records to SMF. Which events are logged depends on the auditing in effect. For example, events requested by the AUDIT or GLOBALAUDIT operand in the resource profile, or by the SETROPTS AUDIT or SETROPTS LOGOPTIONS command, can be logged.

In addition to the SMF TYPE 80 log record, RACF issues an ICH408I message to consoles designated to receive messages for route code 9.

For more information on auditing, including how to use the RACF report writer to review SMF type 80 log records, see the *z/OS Security Server RACF Auditor's Guide*.

#### Use of the WARNING option

The RACF WARNING option, if used on RACF profiles, is honored by CICS. The WARNING option allows users access to resources that otherwise would be denied. RACF logs to SMF those accesses that would have failed had WARNING not been in effect.

The selective use of WARNING can be particularly useful during the initial implementation of resource security for an application, as a means of checking for errors or omissions in the RACF security definitions. When WARNING results in an SMF type 80 record being recorded, you should verify whether the user should be added to the access list for the resource, and modify the RACF profiles

accordingly. You should strictly limit the time during which resources are accessed with the warning option in force, and keep logging to a minimum during the warning period.

**Note:** Specify the NOTIFY option, if you want to be notified at once when access is denied to a user.

## Security for transient data

To implement security for transient data destinations (queues), do the following:

- 1. Specify RESSEC(YES) in the CSD resource definition of the appropriate transactions.
- 2. Define profiles to RACF in the DCICSDCT or ECICSDCT resource classes (or their equivalent if you have user-defined resource class names), with access lists as appropriate. Transient data queue names are a maximum of 4 characters in length, such as CSMT, L86O, L86P, and so on.

For example, use the following commands to define queues in the DCICSDCT class, and to authorize users to both read from and write to these queues:

RDEFINE DCICSDCT (qid1, qid2, ..., qidn) UACC(NONE) NOTIFY(sys_admin_userid) PERMIT qid1 CLASS(DCICSDCT) ID(group1, group2) ACCESS(UPDATE) PERMIT qid2 CLASS(DCICSDCT) ID(group1, group2) ACCESS(UPDATE)

To define transient data queues as members of a profile in the CICS transient data resource group class, with an appropriate access list, use the following commands:

RDEFINE ECICSDCT (queue_groupname) UACC(NONE) ADDMEM(qida, qidb, ..., qidz) NOTIFY(sys_admin_userid) PERMIT queue_groupname CLASS(ECICSDCT) ID(group_userid) ACCESS(UPDATE)

- **3**. Specify SEC=YES as a CICS system initialization parameter (and SECPRFX if you define profiles with a prefix).
- 4. Specify XDCT=YES for the default resource class names of DCICSDCT and ECICSDCT (or XDCT=class_name for user-defined resource class names).

# Defining profiles for transient data queues

When you are defining profile names to RACF to control access to transient data queues, define profiles only for:

- intrapartition transient data queues
- extrapartition transient data queues.

Do not define profiles for indirect transient data queues; CICS directs all requests for an indirect queues to another queue, which can be extrapartition, intrapartition, or remote. The redirection can also be to another indirect queue.

If you are running CICS with security checking for transient data queues, CICS issues a call to RACF for each command that specifies a queue name. However, the resource name that CICS passes to RACF is the queue name of the final queue, which is not necessarily the name of the queue specified on the command.

For example, if an EXEC CICS command specifies queue QID2, which is defined as indirect to QID1, CICS calls RACF for an authorization check on QID1, not QID2. This is illustrated as follows:

TDQ definition: DEFINE TDQUEUE(QID1)

TYPE(EXTRA) TYPEFILE(OUTPUT) RECORDSIZE(132)

RE BL DD	OCKSIZE(136) CORDFORMAT(VARIABLE) OCKFORMAT(UNBLOCKED) NAME(CICSMSGS) OUP(DFHDCTG)
TY IN	QUEUE(QID2) PE(INDIRECT) DIRECTNAME(QID1) OUP(DFHDCTG)
CICS transaction: EXEC	CICS WRITEQ TD QUEUE(QID2) FROM(data_area) LENGTH(length)
	the terminal user of the CICS transaction UPDATE authorization for QID1?

## Access authorization levels

You can read an item from a transient data queue only once, because whenever you read from a transient data queue, CICS deletes the entry (by performing a "destructive read").

Therefore, if you specify security with SEC=YES as a system initialization parameter, CICS requires a minimum authorization level of UPDATE for all TD commands (DELETEQ, WRITEQ, and READQ).

For information about the access authorization levels for system programming commands which apply to transient data queues, see Appendix B, "Resource and command check cross reference," on page 385.

# CICS-required transient data queue resource definitions

CICS itself uses a number of transient data queues. These queues are defined in group DFHDCTG, which is part of DFHLIST. If you want to protect access to these definitions from user application programs, define them to RACF with UACC(NONE) and without an access list.

In the supplied resource definitions, most of the transient data queues are indirect, pointing to the transient data queues CSSL or CCSO. If you use the definitions as supplied, define to RACF only the queue names CSSL and CCSO, as follows:

RDEFINE ECICSDCT CICSQUEUES UACC(NONE) ADDMEM(CSSL, CCSO) NOTIFY(sys_admin_userid)

# **Considerations for triggered transactions**

For intrapartition TD queues with a trigger level greater than zero, CICS derives the userid associated with the triggered transaction from the following sources:

- The USERID parameter specified on the intrapartition transient data resource definition (DESTFAC=FILE).
- The userid associated with the terminal (for queues that have been defined with a destination facility of terminal) (DESTFAC=TERMINAL). This can be the CICS default userid if no user is signed on at the terminal.
- The link userid on the connection definition (for queues that have been defined with a destination facility of system) (DESTFAC=SYSTEM).

### Security for files

CICS application programs process files, which, to CICS, are logical views of physical VSAM or BDAM data sets.

You identify a file to CICS by an 8-character file name, and you can define many files to CICS that refer to the same physical data set, which is separately identified by a 44-character data set name (DSNAME). For example, you can define file resource definitions called FILEA, FILEB, and FILEC, all of which refer to one physical VSAM data set, but with each file definition specifying different attributes.

CICS transactions access the data in physical data sets using the CICS file control name. Therefore, you control access to CICS-managed files by defining profiles in the RACF general resource classes for CICS files, not in the RACF data set class. You define the profiles using the CICS 8-character file name to identify the resource. (RACF data set authorization based on the 44-character data set name is used only during OPEN processing, to determine whether the CICS region userid is authorized to access the data set for which the OPEN has been requested. This does not depend on the userid running the transaction that caused the OPEN to be performed.)

To implement security for files managed by CICS file control:

- 1. Specify RESSEC(YES) in the CSD resource definition of the transactions that access the files.
- 2. Define profiles to RACF in the FCICSFCT or HCICSFCT resource classes (or their equivalent if you have user-defined resource class names), using the CICS file names to identify the profiles. For example, use the following commands to define files in the FCICSFCT class, and authorize users to read from or write to the files:

RDEFINE FCICSFCT (file1, file2, ..., filen) UACC(NONE) NOTIFY(sys_admin_userid) PERMIT file1 CLASS(FCICSFCT) ID(group1, group2) ACCESS(UPDATE) PERMIT file2 CLASS(FCICSFCT) ID(group1, group2) ACCESS(READ)

To define files as members of a profile in the CICS file resource group class, with an appropriate access list, use the following commands:

RDEFINE HCICSFCT (file_groupname) UACC(NONE) ADDMEM(filea, fileb, .., filez) NOTIFY(sys_admin_userid) PERMIT file groupname CLASS(HCICSFCT) ID(group userid) ACCESS(UPDATE)

- **3**. Specify SEC=YES as a CICS system initialization parameter (and SECPRFX if you define profiles with a prefix).
- 4. Specify XFCT=YES for the default resource class names of FCICSFCT and HCICSFCT (or XFCT=class_name for user-defined resource class names).

Note that RDO transactions do not use file commands to access the CSD, and are not, therefore, subject to these mechanisms.

# Access authorization levels

If you specify security with SEC=YES as a system initialization parameter, CICS requires a level of authorization appropriate to the file access intended: a minimum of READ for read intent, and a minimum of UPDATE for update or delete intent.

For information about the access authorization levels for system programming commands which apply to files, see Appendix B, "Resource and command check cross reference," on page 385.

# Security for journals and log streams

The CICS log manager provides facilities to write to and read from:

- The CICS system log
- The CICS general logs, which comprise user journals, forward recovery logs, and autojournals

The system log is used only for recovery purposes—for example, during dynamic transaction backout, or during emergency restart. Do not use it for any other purpose. Do not, therefore, write to it from a user application using the **WRITE JOURNALNAME** command.

CICS uses journal identifier **DFHLOG** for its primary system log. Do not permit user transactions to write to this. You can prevent them doing so by using the following command to define the system log in the JCICSJCT class, without any access list:

RDEFINE JCICSJCT DFHLOG UACC(NONE) NOTIFY(sys_admin_userid)

In addition to the automatic journaling and forward recovery logging that CICS performs for user transactions (depending on the options in the file resource definitions), user applications can also write user journal records using the WRITE JOURNALNAME command.

Users needing to write journal records must have authority to write to the JOURNALNAME (as defined in JCICSJCT). CICS calls RACF to perform a security check only for attempts to access a user journal by a CICS API command, and not for the journaling it performs in response to journaling options in the file resource definition. The CICS API does not provide a READ command for reading journals from a CICS transaction. For this reason, with proper exercise of control over the installation of applications on your CICS systems, you might consider it unnecessary to add RACF protection for journals that cannot be read from within CICS.

If you decide to implement security for CICS journals:

- 1. Specify RESSEC(YES) in the CSD resource definition of the transactions that write to journals.
- Define profiles to RACF in the JCICSJCT or KCICSJCT resource classes (or their equivalent if you have user-defined resource class names) using the CICS journal name to identify the profiles.

To define journals as members of a profile in the journal resource group class, with an appropriate access list, use the following commands:

RDEFINE	KCICSJCT	userjnls UACC(NONE)
		ADDMEM(JRNL001, JRNL002,)
		NOTIFY(sys admin userid)
PERMIT	userjnls	CLASS(KCICSJCT) ID(group userid) ACCESS(UPDATE)

- **3**. Specify SEC=YES as a CICS system initialization parameter (and SECPRFX if you define profiles with a prefix).
- 4. Specify XJCT=YES for the default resource class names of JCICSJCT and KCICSJCT (or XJCT=class_name for user-defined resource class names).

# Access authorization levels

If you specify security with SEC=YES as a system initialization parameter, CICS requires a minimum authorization of UPDATE for journal access.

For information about the access authorization levels for system programming commands which apply to journals, see Appendix B, "Resource and command check cross reference," on page 385.

# Transactions that use WRITE JOURNALNUM command

The WRITE JOURNALNUM command is supported in CICS Transaction Server for z/OS, Version 4 Release 1 for compatability with earlier releases: the WRITE JOURNALNAME command is preferred for new applications. If resource security applies to a transaction executing WRITE JOURNALNUM, the journal number is prefixed with 'DFHJ' before the security check is applied. Thus, writing to journal number 2 requires UPDATE access to the resource DFHJ02.

## Security for started and XPCT-checked transactions

A CICS transaction initiated by a terminal user can start other transactions by means of an EXEC CICS START command. Transactions started in this way are known as **started transactions**, and you can use CICS RACF security to control who can start other transactions using the START command.

Started transactions are defined in the ACICSPCT and BCICSPCT resource class profiles. These profiles also control access to transactions specified in certain other EXEC CICS commands, if the transaction issuing the command is defined with RESSEC(YES). The commands affected are:

- COLLECT STATISTICS TRANSACTION
- DISCARD TRANSACTION
- INQUIRE TRANSACTION
- SET TRANSACTION
- INQUIRE REQID
- CANCEL

When a transaction issues an EXEC CICS START TRANSID(*tranid*) command, CICS calls RACF to check that the user of the transaction issuing the command is authorized for the started transaction.

To implement security for started transactions and for transactions checked against the XPCT class:

- 1. Specify RESSEC(YES) in the CSD resource definition of the transactions that issue START commands.
- 2. Define profiles to RACF in the ACICSPCT or BCICSPCT resource classes (or their equivalent if you have user-defined resource class names) using the name of the started transaction to identify the profiles.

For example, use the following commands to define a transaction in the ACICSPCT class, and to authorize one user only:

RDEFINE ACICSPCT (tran1, tran2, ..., trann) UACC(NONE) NOTIFY(sys_admin_userid) PERMIT tran1 CLASS(ACICSPCT) ID(userid) ACCESS(READ) PERMIT tran2 CLASS(ACICSPCT) ID(userid) ACCESS(READ)

To define started transactions as members of a profile in the started transaction resource group class, with an appropriate access list, use the following commands:

RDEFINE BCICSPCT started_trans UACC(NONE) ADDMEM(trana, tranb, ..., tranx) NOTIFY(sys_admin_userid) PERMIT started_trans CLASS(BCICSPCT) ID(group_userid) ACCESS(READ)

- **3**. Specify SEC=YES as a CICS system initialization parameter (and SECPRFX if you define profiles with a prefix).
- 4. Specify XPCT=YES for the default resource class names of ACICSPCT and BCICSPCT (or XPCT=class_name for user-defined resource class names).

#### Transactions started at terminals

The START command enables a CICS application program to start another transaction associated with a terminal other than the one from which the start command is issued. For example, the following command issued in CICS transaction tranid1, invoked at termid1, starts another transaction called tranid2 at termid2:

```
EXEC CICS START
TRANSID(tranid2)
AT HOURS('18') MINUTES('50')
TERMID(termid2)
```

When a TERMID is specified for the started transaction, CICS performs a transaction-attach security check, using the classes TCICSTRN and GCICSTRN, on the userid associated with the terminal (termid2 in this example). You must therefore ensure that the userid associated with the terminal (termid2) is authorized to invoke the transaction. This userid is that of the signed-on user, or the CICS default userid if no user is signed on. If termid2 is **not** authorized, message DFHAC2033 is issued to the user of termid2. The user of the terminal that issued the START command gets a "normal" response. If the started transaction is defined with RESSEC(YES), also ensure that the userid associated with the terminal (termid2 in this example) is suitably authorized to access protected resources.

#### Starting tasks at terminals defined with preset security

Typically, started transactions associated with a terminal are printing tasks, where the specified terminal is a printer.

In this case, to associate a specific userid with the terminal, you define the terminal with preset security. See "Preset terminal security" on page 70 for more information.

## Transactions started without terminals

The START command enables a CICS application program to start another transaction that is not associated with any terminal. When no TERMID is specified for the started transaction, the userid associated with the new transaction depends on whether you also specify the USERID option.

#### Userid of a non-terminal started transaction

The USERID option of the START command (or the terminal user if no TERMID or USERID is included in the START command) determines the userid for a non-terminal started transaction. Without the USERID option, the non-terminal started transaction has the same userid as the transaction that executed the START command. If the USERID option is specified on the START command, the specified userid is used instead.

When an START command is executed without the TERMID option, CICS performs a surrogate user check to ensure that the transaction is authorized for the userid to be used by the non-terminal started transaction. For information about the link authorization of surrogate users, see "Intercommunication link security" on page 160. For information about EDF authorization of surrogate users, see "Conditional access processing" on page 69.

#### Access to resources by a non-terminal started transaction

If the USERID option is not specified on the **START** command, the non-terminal started transaction does not always inherit all of the security of the transaction that executed the command. Also, it does not inherit resource access determined by link security, or resource access determined by a userid for EDF when used in dual-screen mode. This means:

- If a transaction-routed transaction executes a START command, or if a START command is function shipped, the non-terminal started transaction is not subject to link security.
- If EDF is used in dual-screen mode for a transaction that issues a START command, the non-terminal started transaction is not subject to resource access determined by the userid of the EDF terminal.

If you want the started transaction to have exactly the same security capabilities as the starting transaction, omit the USERID option. Without the USERID option, resource access by the non-terminal started transaction is determined by the sign-on parameters of the terminal transaction. These include the RACF group and the port of entry at which the terminal user signed on; that is, the terminal or console used to sign on, as shown in the following example:

A terminal user signs on using the CESN transaction at a terminal with netname NETNAMEX. For RACF, therefore, the port of entry is NETNAMEX. At the CESN screen the terminal user enters userid USERID1, and groupid GROUPID2. The terminal user then runs a terminal transaction which executes an EXEC CICS START command without the TERMID option or the USERID option specified. The non-terminal started transaction has resource access determined by userid USERID1, groupid GROUPID2, and port of entry NETNAMEX.

If a non-terminal transaction is denied access to a resource by RACF, the error message produced can include the terminal sign-on parameters, userid, and groupid. It can also include a port of entry. The userid, groupid, and port of entry can be those inherited from the terminal transaction that started the non-terminal transaction.

If the USERID option is specified on a START command, the non-terminal started transaction has access to resources determined by the userid specified on the USERID option.

We recommend that you do not specify the current userid of a terminal transaction on the USERID option. The non-terminal started transaction may not have the same resource access as the terminal transaction. The following examples show how the non-terminal started transaction can have different resource access:

#### Example 1

RACF conditional access lists can be used by specifying WHEN(TERMINAL( ... )) or WHEN(CONSOLE( ... )) on the RACF PERMIT command to allow a terminal transaction access to certain resources because the specified port of entry is in use. See "Conditional access processing" on page 69.

If a START TRANSID USERID command is executed by a terminal transaction specifying the same userid that the terminal user entered when signing on with CESN, the started transaction has access to resources determined by the specified userid, but not to the resources determined by the port of entry.

The started transaction is not subject to the conditional access list effective for the terminal transaction that executed the EXEC CICS START USERID command.

#### **Example 2**

Using RACF you can grant (or deny) group access to a RACF protected resource.

A terminal user can enter a groupid and a userid when signing on with CESN. When the terminal user runs a terminal transaction, the groupid can determine resource access.

If a START TRANSID USERID command is executed by a terminal transaction specifying the same userid as that entered by the terminal user when signing on with CESN, the started transaction has access to resources determined by the specified userid. Resource access is not determined by the groupid that the terminal user entered when signing on with CESN. Resource access for the non-terminal started transaction can be determined by the default groupid for the specified userid.

The started non-terminal transaction is not subject to the group access effective for the terminal transaction that executed the START USERID command.

## Access authorization levels

CICS requires a minimum authorization of READ for started transactions.

For information about the access authorization levels for system programming commands which apply to transactions, see Appendix B, "Resource and command check cross reference," on page 385.

# Security for application programs

You control access to the initial program specified in the transaction resource definition by authorizing the user to initiate the transaction (transaction-attach security).

However, CICS application programs can invoke other programs by means of the LINK, LOAD, and XCTL commands. Also, the load status of programs can be altered by the CICS RELEASE, ENABLE, and DISABLE commands. Note, however, that there is no separate security check on the RELEASE of programs loaded for task lifetime. This is done on the corresponding LOAD.

You control access to programs invoked using these commands by defining profiles in the CICS application program classes, and which you define to CICS on the XPPT system initialization parameter.

To control which users can invoke or change the load status of other programs:

- 1. Specify RESSEC(YES) in the CSD resource definition of the transactions that use the above commands.
- 2. Define profiles to RACF in the MCICSPPT or NCICSPPT resource classes (or their equivalent if you have user-defined resource class names) using the name of the program invoked on the LINK, LOAD, or XCTL command to identify the profiles.

For example, use the following commands to define a program in the MCICSPPT class, and to authorize one user only:

RDEFINE MCICSPPT (prog1, prog2, ..., progn) UACC(NONE) NOTIFY(sys_admin_userid) PERMIT prog1 CLASS(MCICSPPT) ID(userid) ACCESS(READ) PERMIT prog2 CLASS(MCICSPPT) ID(userid) ACCESS(READ) To define programs as members of a profile in the application program resource group class, with an appropriate access list, use the following commands: RDEFINE NCICSPPT cics_programs UACC(NONE) ADDMEM(proga, progb, ..., progx) NOTIFY(sys admin userid)

PERMIT cics_programs CLASS(NCICSPPT) ID(group_userid) ACCESS(READ)

- **3**. Specify SEC=YES as a CICS system initialization parameter (and SECPRFX if you define profiles with a prefix).
- 4. Specify XPPT=YES as a CICS system initialization parameter for the default resource class names of MCICSPPT and NCICSPPT (or XPPT=class_name for user-defined resource class names).

#### Exception for distributed program link (DPL) commands

If CICS finds that a program referenced on a **LINK** command is a remote program, it does not perform the security check in the region in which the link command is issued. The security check is performed only in the CICS region in which the linked-to program finally executes.

For example, if CICSA function ships a DPL command to CICSB, where the program then executes, CICSB issues the security check. If the DPL request is function shipped again to CICSC for execution, it is CICSC that issues the security check.

## Access authorization levels

CICS requires a minimum authorization of READ for programs.

For information about the access authorization levels for system programming commands which apply to programs, see Appendix B, "Resource and command check cross reference," on page 385.

## Security for temporary storage

Unlike the other resources for which you specify RESSEC(YES), temporary storage queues, for which you require RACF protection, also require the security attribute in a suitable TSMODEL resource definition.

You specify TSMODEL definitions in the CSD. See the *CICS Resource Definition Guide* for information about TSMODEL resource definitions.

# Implementing security for temporary storage queues

To implement security for temporary storage queues:

- 1. Specify RESSEC(YES) in the CSD resource definition of the appropriate transactions.
- 2. Specify the security attribute on suitable TSMODEL resource definitions in the CSD. CICS does not perform any security checks on temporary storage queues that specify SECURITY=NO on the matching TSMODEL definition.
- **3**. Define profiles to RACF in the SCICSTST or UCICSTST resource classes (or their equivalent if you have user-defined resource class names), with access

lists as appropriate. For example, use the following commands to define queues in the SCICSTST class, and to authorize users to both read from and write to these queues:

RDEFINE SCICSTST (tsqueue1, tsqueue2, ..., tsqueuen) UACC(NONE) NOTIFY(sys_admin_userid) PERMIT tsqueue1 CLASS(SCICSTST) ID(group1, group2) ACCESS(UPDATE) PERMIT tsqueue2 CLASS(SCICSTST) ID(group1, group2) ACCESS(UPDATE)

To define temporary storage queues as members of a profile in the CICS temporary storage resource group class, with an appropriate access list, use the following commands:

RDEFINE UCICSTST tsqueue_group UACC(NONE) ADDMEM(tsqueuea, tsqueueb, ..., tsqueuex) NOTIFY(sys_admin_userid) PERMIT tsqueue group CLASS(UCICSTST) ID(group userid) ACCESS(UPDATE)

For more information about defining temporary storage profiles, see "Other temporary storage security considerations."

- 4. Specify SEC=YES as a CICS system initialization parameter (and SECPRFX if you define profiles with a prefix).
- 5. Specify XTST=YES as a CICS system initialization parameter for the default resource class names of SCICSTST and UCICSTST (or XTST=class_name for user-defined resource class names).

**Note:** CICS continues to support the DFHTST TYPE=SECURITY macro for defining temporary storage security. However, you are recommended to migrate your temporary storage tables (TSTs) to the CSD as TSMODEL definitions.

# Other temporary storage security considerations

You can define the queue names on the PREFIX attribute of the TSMODEL resource definition as follows:

- By specifying a fully identified name that exactly matches the queue name specified on a READQ TS or WRITEQ TS command. This can be from 1 to 16 alphanumeric characters.
- By specifying a generic name, or prefix, that corresponds to the leading alphanumeric characters of a set of queue names.

It follows that a prefix can only be from 1 to 15 characters, because if you specify the full 16 characters for a queue name, it must be the name of a specific temporary storage queue.

When a CICS application issues a temporary storage command (for example, DELETEQ TS, READQ TS, or WRITEQ TS) and temporary storage security is in effect, CICS searches the TST for a DATAID that corresponds to the leading characters of the queue name.

Note that if you include a temporary storage queue with hexadecimal characters in a temporary storage queue name, unpredictable results may occur. Also, if a temporary storage queue name contains an imbedded blank, RACF truncates the resource name to that blank.

# Access authorization levels

If you specify security with SEC=YES as a system initialization parameter, CICS requires a level of authorization appropriate to the temporary storage queue access intended, for example, a minimum of READ for READQ TS, and a minimum of UPDATE for DELETEQ TS and WRITEQ TS.

For information about the access authorization levels for system programming commands which apply to temporary storage queues, see Appendix B, "Resource and command check cross reference," on page 385.

# Security for z/OS UNIX files

Files stored in the z/OS UNIX System Services file system can be used to supply Web pages through CICS Web support, as static responses provided by URIMAP definitions. When access control for these files is specified, you can control access to them on the basis of the user IDs for individual Web clients. Access control for z/OS UNIX files is enabled by default.

Access control for z/OS UNIX files is activated by the XHFS system initialization parameter. The default for this parameter is YES, meaning that resource security for z/OS UNIX files is active. If you do **not** want resource security for these files, set this system initialization parameter to NO.

Access control for z/OS UNIX files is based on a user ID that is obtained from the Web client using basic authentication, or a user ID associated with a client certificate sent by the Web client. The user ID is used only during the process of security checking.

Access control for z/OS UNIX files differs from standard resource security for the other resource types controlled by *Xname* system initialization parameters, in some important ways:

- Access controls for z/OS UNIX files are not managed directly by RACF. They are specified in z/OS UNIX System Services, which makes use of RACF to manage user IDs and groups of user IDs, but keeps control of the permissions set for the files and directories. Because of this, you do not need to define RACF profiles for individual files, and you cannot use the QUERY SECURITY command to check access to them. You check and specify permissions for z/OS UNIX files and directories in the z/OS UNIX System Services shell environment, using z/OS UNIX commands. RACF is used to manage user profiles, groups and access control lists (ACLs). If you are using ACLs, you need to activate the FSSEC class for these to be checked.
- Security checking for z/OS UNIX files is not affected by the RESSEC attribute in the TRANSACTION resource definition of the transactions that access the files. If XHFS=YES is specified as a system initialization parameter for the CICS region, all z/OS UNIX files used by CICS Web support as static responses (and their directories) are subject to security checking, regardless of the RESSEC attribute for the transaction that is accessing them. (However, the SEC system initialization parameter does affect whether or not security checking is carried out, as for all resources.)
- z/OS UNIX files are not referenced directly by any CICS application
  programming commands or system programming commands. They can only be
  referenced by EXEC CICS commands when they are defined as CICS document
  templates. In this situation, resource security for CICS document templates
  (specified by the XRES system initialization parameter) controls access to them
  for users. CICS does not perform any additional permissions check on the z/OS
  UNIX files using the Web client's user ID. This is the case even if access control
  is specified for z/OS UNIX files in the CICS region, or if resource security is not
  active for document templates. Where z/OS UNIX files are defined as CICS
  document templates, you therefore need to set up Web clients' user ID access
  controls in RACF for the CICS document templates, rather than in z/OS UNIX
  System Services for the z/OS UNIX files. (However, the CICS region user ID

always needs to have **read** permissions on z/OS UNIX files, even if they are defined as document templates.) Note in particular that this situation applies to all application-generated responses from CICS Web support, and to any URIMAP definitions for static responses where the TEMPLATENAME attribute is used, rather than the HFSFILE attribute.

# Implementing security for z/OS UNIX files

To implement access control for z/OS UNIX files used by CICS Web support, when they are specified as static responses in URIMAP definitions using the HFSFILE attribute, follow the steps listed in this topic.

## Before you begin

Note that the CICS region user ID must always have a minimum of **read** access to all z/OS UNIX files that it uses for CICS Web support, and to the directories containing them. The user ID of the Web client is only used when accessing z/OS UNIX files as a static response, but the CICS region user ID applies to all other attempts to access the file. If the CICS region user ID does not have permission to access the file, even an authorized Web client will be unable to view it. This is the case even when the file is defined as a CICS document template.

# About this task

#### Procedure

- 1. Select an appropriate method to give permissions to Web clients to access the z/OS UNIX files and directories. You might choose to use the group permissions for the files and directories, or access control lists (ACLs). Even if it is possible for you to use group permissions, the use of ACLs is the recommended solution for giving permissions to Web clients' user IDs. With ACLs, you can allow access to multiple user groups, and the access can be set for single files or once for all the files in a directory. Directory permissions can be arranged in the same way. You can also use ACL commands to modify permissions for the files and directories. Although you work with ACLs in the z/OS UNIX System Services shell environment, they are created and checked by RACF, so if you are using a different security product, check its documentation to see if ACLs are supported. When you have chosen your preferred method, follow the relevant steps in the remainder of this procedure.
- 2. Identify the authenticated user IDs used by Web clients. These must be the basis of your access control. (You cannot supply an override using an analyzer program, as you can with application-generated responses.) Authenticated user IDs will already have a user profile defined in your security manager.
- 3. For each Web client user ID, choose and assign a suitable z/OS UNIX user identifier (UID). The UIDs are numbers that can be in the range 0 to 16 777 216. (0 is a superuser ID with system privileges, which should not be assigned to CICS users.) To assign UIDs, specify the UID value in the OMVS segment of the user profile for each user ID. "RACF user profiles" on page 14 tells you how to update a RACF user profile using the ALTUSER command. For example, if the Web client's user ID is WEBUSR1, and the UID you want to assign is 2006, use the command:

ALTUSER WEBUSR1 OMVS(UID(2006))

All users must have a z/OS UNIX user identifier (UID) in their user profile in order to use z/OS UNIX function, even if you are not assigning permissions

on the basis of the UID. *z/OS UNIX System Services Planning*, GA22-7800, explains how to manage the UIDs and GIDs for your z/OS UNIX system.

- 4. Choose, or create, RACF groups that can be used by groups of Web clients with the same permissions. For best performance, even if you are using ACLs, you should assign permissions to groups rather than individual users.
- 5. For each RACF group, choose a suitable z/OS UNIX group identifier (GID), and assign the GID to the RACF group. To assign a GID, specify the GID value in the OMVS segment of the RACF group profile. For example, if the RACF group is CICSWEB1, and the GID you want to assign is 9, use the command:

ALTGROUP CICSWEB1 OMVS(GID(9))

- 6. Make sure that each of your Web client user IDs connects to a RACF group to which you assigned a z/OS UNIX group identifier (GID). If your Web clients need to connect to more than one RACF group, RACF list of groups must be active in your system.
- 7. Before you modify the permissions for the z/OS UNIX files and directories, ensure that your user ID is either a superuser on z/OS UNIX, or the owner of each z/OS UNIX file and directory you want to work with. Also, if you are working with groups, the owner of the files and directories must be connected to the RACF groups that you are using.
- 8. Optional: If you have chosen to use ACLs, set up ACLs that apply to all of the z/OS UNIX files and directories used by CICS Web support for static responses, using the setfacl command in the z/OS UNIX System Services shell environment. *z/OS UNIX System Services Planning*, GA22–7800, has information about using ACLs, and examples of how to use the setfacl command.
  - a. For files, you can set up access ACLs, which apply to an individual file, or file default ACLs, which apply to all the files within a directory and within its subdirectories.
  - b. For directories, you can set up access ACLs, which apply to an individual directory, or directory default ACLs, which apply to the subdirectories within a directory.
  - **c.** To minimize the impact to performance, assign group permissions for the files to the RACF groups to which your Web clients' user IDs connect, rather than using individual user IDs. (There is also a limit on the number of items that can be specified in an ACL.)
  - d. If you need to change the permissions granted to the groups (the base permission bits which specify **read**, **write** and **execute** access), you can specify this using the setfacl command as well. Web clients need to have **read** access to the z/OS UNIX files and directories.
  - e. If you are using ACLs, ensure that the FSSEC class is activated. Use the RACF command SETROPTS CLASSACT(FSSEC) to do this. You can define ACLs before activating the FSSEC class, but you must activate the FSSEC class before ACLs can be used in access decisions.
- 9. Optional: If you have chosen to use group permissions without using ACLs, assign the group permissions for each z/OS UNIX file and directory to a group to which your Web clients connect, and give the group read permissions. Use the UNIX command chmod to do this. *z/OS UNIX System Services Command Reference*, SA22-7802, and *z/OS UNIX System Services User's Guide*, SA22-7801, have information about using this command. (Note that as group permissions can only be assigned to one group if you are using this method, some of your Web clients' user IDs might need to connect to more than one group to acquire all the correct permissions.)

- **10.** Specify SEC=YES as a CICS system initialization parameter. (SECPRFX is not relevant for z/OS UNIX files, as they do not have RACF profiles).
- 11. Specify XHFS=YES as a CICS system initialization parameter. This step activates access control for all z/OS UNIX files in the CICS region.

#### Results

When you have completed the setup procedure, from this point onwards:

- All Web clients who use a connection with basic authentication or client certificate authentication and attempt to access any HFS files, must have a user profile in the security manager which contains a valid z/OS UNIX UID, and connects to a RACF group with a valid z/OS UNIX GID.
- To be able to view a Web page derived from a z/OS UNIX file, Web clients who use a connection with basic authentication or client certificate authentication must have **read** permissions to the file and to the directories containing it, either individually or through the RACF groups to which they are connected.

If these conditions are not in place, Web clients will receive a 403 (Forbidden) status code, and CICS issues message DFHXS1116.

#### Access authorization levels

The user IDs of Web clients, and also the CICS region user ID, must have a minimum of **read** access for z/OS UNIX files, and the directory containing them, which are used with CICS Web support as static responses provided by URIMAP definitions (specified by the HFSFILE attribute).

If z/OS UNIX files are defined as CICS document templates, and the document templates are used either in URIMAP definitions as static responses (specified by the TEMPLATENAME attribute), or by applications, CICS does **not** perform any additional permissions check on the files using the Web client's user ID. However, the CICS region user ID still needs to have read permissions on the files, even when they are defined as document templates.

z/OS UNIX files are not manipulated directly by any CICS application programming commands or system programming commands. They can only be manipulated by EXEC CICS commands when they are defined as CICS document templates. In this situation, resource security for CICS document templates controls access to them for users.

# Security for program specification blocks

DL/I program specification blocks (PSBs) are IMS control blocks that describe databases and logical message destinations used by an application program. PSBs consist of one or more program communication blocks (PCBs), which describe an application program's interface to an IMS database.

To implement security for PSBs scheduled in CICS applications:

 Define profiles to RACF in the PCICSPSB or QCICSPSB resource classes (or their equivalent if you have user-defined resource class names), with access lists as appropriate. The resource profile names you define to RACF must correspond to the names of PSBs specified in CICS PSB schedule commands. For example, use the following commands to define PSBs in the PCICSPSB class, and to authorize users to access these queues: RDEFINE PCICSPSB (psbname1, psbname2, ..., psbnamen) UACC(NONE) NOTIFY(sys_admin_userid) PERMIT psbname1 CLASS(PCICSPSB) ID(group1, group2) ACCESS(READ) PERMIT psbname2 CLASS(PCICSPSB) ID(group1, group2) ACCESS(READ) To define PSBs as members of a profile in the CICS PSB resource group class, with an appropriate access list, use the following commands: RDEFINE QCICSPSB psbname_group UACC(NONE) ADDMEM(psbnamea, psbnameb, ..., psbnamex) NOTIFY(sys_admin_userid) PERMIT psbname_group CLASS(QCICSPSB) ID(group_userid) ACCESS(UPDATE)

- 2. Specify SEC=YES as a CICS system initialization parameter (and SECPRFX if you define profiles with a prefix).
- **3**. Specify XPSB=YES as a CICS system initialization parameter for the default resource class names of PCICSPSB and QCICSPSB (or XPSB=class_name for user-defined resource class names).
- 4. Specify PSBCHK=YES if you want full security for PSBs that are accessed in transaction-routed transactions. This applies to both types of DL/I interface (remote and DBCTL). If you specify PSBCHK=NO, the authority of the remote user is **not used** in transaction-routed transactions.

Note: CICS requires a minimum authorization of READ for PSBs.

If you are using DBCTL, see *CICS IMS Database Control Guide* for information on defining security in a CICS-DBCTL environment.

#### Security checking of transactions running under CEDF

When a transaction is run under the CEDF transaction, CICS takes into account the security settings for both the target transaction and CEDF.

Table 9 shows the security checking performed for the transaction XSUB for different settings of RESSEC.

CEDF	XSUB	Security checking
RESSEC(YES)	RESSEC(YES)	Any access to CICS resources causes a security check.
RESSEC(YES)	RESSEC(NO)	Any access to CICS resources causes a security check. (Logical OR results in RESSEC on.)
RESSEC(NO)	RESSEC(YES)	Any access to CICS resources causes a security check. (Logical OR results in RESSEC on.)
RESSEC(NO)	RESSEC(NO)	Access to CICS resources does not cause a security check. (Logical OR results in RESSEC off.)

Table 9. Security checking of transactions running under CEDF

To achieve the expected security processing for a transaction when it runs under CEDF, ensure that RESSEC for the CEDF transaction definition is set to NO. The

IBM-supplied definition of CEDF in the DFHEDF group specifies RESSEC(YES). Definitions in the IBM-supplied groups cannot be modified, so to change the definition, copy it to another group.

When the CEBR and CECI are invoked from within EDF they are transaction-attach checked. The CMDSEC and RESSEC definitions are forced when CEBR or CECI are invoked in this environment, regardless of what is coded in their transaction definitions. The CMDSEC(YES) and RESSEC(YES) values for CEDF or CEDX override the CMDSEC and RESSEC values of the user transaction.

When CEDF is used to test a transaction, the authorities of the user executing the CEDF transaction are taken into account, as well as those of the user executing the transaction being tested. For each resource accessed by the tested transaction, both users must have access authority, otherwise a NOTAUTH condition is raised. This applies to all resource checks:

- Transaction attach
- CICS resource
- CICS command
- Non-CICS resources accessed through the QUERY SECURITY command
- Surrogate user

#### Defining generic profiles for resources

If you control access to CICS transactions by means of transaction-attach security, there is probably only a very small subset of other resource types for which you need a further level of RACF protection.

For example, there may be just a few programs in the CICS application program resource class that are particularly sensitive, and a much larger number that constitute no significant risk. In this case, you could protect the few by defining specific RACF profiles for only those programs that are sensitive. You ensure that everyone can access the remaining, nonsensitive, programs by defining a completely generic resource profile, as follows: RDEFINE MCICSPPT * UACC(READ) ...

This profile applies to any authorization request for programs not covered by one of the specific profiles. RACF processing logic is such that the most specific profile for any given resource name is always used.

Note that to determine whether a profile is generic, you need only check if 'G' appears after the name of the profile when it is listed with RLIST or SEARCH. For example:

SEARCH CLASS(TCICSTRN)

may give the following output:

C* CED% (G) ** (G)

The above output shows that both CED% and ** are generic profiles. The C* profile is not generic because it is not followed by (G). This could have occurred if the C* profile was created before generic profiles had been enabled with a SETROPTS command. The C* profile can be deleted and redefined as a proper generic profile as follows:

SETROPTS NOGENERIC(TCICSTRN) SETROPTS NOGENCMD(TCICSTRN) RDEL TCICSTRN C* SETROPTS GENERIC(TCICSTRN) RDEFINE TCICSTRN C* UACC(NONE)

#### **Related tasks:**

"Security using the XRES resource security parameter" on page 87 Use the XRES system initialization parameter to security check the following CICS resources: ATOMSERVICE, BUNDLE, DOCTEMPLATE, EVENTBINDING, JVMSERVER, and XMLTRANSFORM. An example of how to implement resource security for CICS document templates, the DOCTEMPLATE resource, is provided.

#### Access to all or access to none?

If RACF can find neither a specific nor generic profile, it returns a "no profile found" condition.

CICS treats this return code exactly the same as the "user not authorized" return code, and returns the NOTAUTH condition to the CICS application program. If RACF cannot find the APPL class, it returns a "READ access intent" condition.

You can either use the completely generic profile to permit access to any resources not otherwise covered by more specific profiles, or, to prevent any access, use the UACC(READ | UPDATE) or UACC(NONE) options. For example, RDEFINE DCICSDCT * UACC(NONE)

prevents access to any transient data queue not covered by any of the other profiles defined to RACF, and results in RACF writing an SMF record.

On the other hand, you can define files as "public" by the following command: RDEFINE FCICSFCT * UACC(READ)

If you are using generic profiles, ensure that generic profile checking has been activated for the CICS RACF resource classes (both the IBM-supplied classes and any installation-defined classes added to the RACF class descriptor table) by issuing a SETROPTS GENERIC(*classname*) command for any one of the CICS classes having the same POSIT value. This ensures generic checking for all other CICS classes with the same POSIT value. If you change a generic profile, you must issue a SETROPTS GENERIC(*classname*) REFRESH command. For more information about POSIT values and defining generic classes, see the *z*/OS Security Server RACF System Programmer's Guide.

# Chapter 7. Surrogate user security

A surrogate user is a RACF-defined user who is authorized to act on behalf of another user (the original user). CICS uses surrogate user security in a number of different situations.

## Where surrogate user checking applies

A surrogate user is one who has the authority to start work on behalf of another user. A surrogate user is authorized to act for that user without knowing that other user's password. To enable surrogate user checking, XUSER=YES must be specified as a system initialization parameter.

CICS performs surrogate user security checking in a number of situations, using the surrogate user facility of an external security manager (ESM) such as RACF. If surrogate user checking is in force, it applies to:

- The CICS default user
- PLT post-initialization processing
- Preset terminal security
- Started transactions
- The userid associated with a CICS business transaction services (BTS) process or activity that is started by a RUN command
- The userid associated with a transient data destination
- The userid supplied as a parameter on an EXCI call
- The userid supplied on the AUTHID and COMAUTHID attributes of the DB2CONN and DB2ENTRY resource definitions
- The user ID in event bindings
- The userid supplied on the USERID attribute of URIMAP resource definitions
- A CPSM MAS agent started with the COLM transaction
- A CPSM local MAS agent started with the CORM transaction

#### CICS default user

CICS performs a surrogate user security check against its own userid (the CICS region userid) to ensure that it is properly authorized as a surrogate of the default userid specified on the DFLTUSER system initialization parameter.

## Post-initialization processing

If you specify a program list table on the **PLTPI** system initialization parameter, CICS checks that the region user ID is authorized as a surrogate user of the user ID specified in the **PLTPIUSR** system initialization parameter.

The **PLTPIUSR** system initialization parameter specifies the user ID that CICS is to use for PLT programs that run during CICS initialization. The CPLT transaction and all PLT programs run under the authority of the specified user ID. The user ID must be authorized to run the CPLT transaction and all the resources referenced by the programs.

The scope of PLT security checking is defined by the **PLTPISEC** system initialization parameter. This parameter specifies whether command security checks and resource security checks are to apply to PLTPI programs.

If you do not specify the **PLTPIUSR** parameter, CICS runs PLTPI programs under the authority of the CICS region user ID, in which case CICS does not perform a surrogate user check. However, the CICS region user ID must then be authorized to all the resources referenced by the PLT programs. Furthermore, the CICS region user ID is associated with any transactions started by PLT programs, and therefore must be authorized to run such transactions.

# Preset terminal security

When you install a terminal that is defined with a preset security userid, CICS checks that the userid performing the install is authorized as a surrogate user of the preset userid.

This is discussed in "Preset terminal security" on page 70.

# **Started transactions**

CICS performs surrogate user checks when you use a START command to start a transaction that is not associated with a terminal.

In the following, the userid under which the transaction issuing the START command runs is called the *starting-userid*, and the userid under which the started transaction runs is called the *started-userid*:

- If the TERMID option is specified on the START command, surrogate user checking does not apply. The *started-userid* is inherited from the terminal at which the transaction runs.
- If the USERID option is specified on the START command, the *started-userid* is set to that specified userid.
- If neither TERMID nor USERID is specified on the START command, the *started-userid* is set to be the same as the *starting-userid*.

CICS requires that all the userids associated with the transaction issuing the START are surrogates of the *started-userid*. CICS also assumes that any userid is always a surrogate of itself. So userids that are the same as *started-userid* are regarded as surrogates already, and the external security manager is not called for them.

A transaction can be associated with userids that are different from *starting-userid* when it is using CICS intercommunication, and when it is using EDF in the two-terminal mode.

#### Intercommunication and started transactions

If a START command (without TERMID) is function shipped or is executed from a transaction-routed transaction, the command can be subject to link security. If link security is in effect, CICS also performs a surrogate user check to verify that the userid for link security is authorized as a surrogate user to the userid for the started transaction. The surrogate check is done at this stage even if the USERID is omitted (if the *started-userid* is different from the link userid). For more information see "Intercommunication link security" on page 160.

#### EDF in dual-screen mode and started transactions

If an EXEC CICS START command (without TERMID) is executed under control of EDF in dual-screen mode, CICS also performs a surrogate user check, to verify that the userid for the EDF terminal is authorized as a surrogate user of the userid for the started transaction.

This check is done even if USERID is omitted, if the *started-userid* is different from the EDF userid.

Surrogate user checking can be subject to link security. If EDF is in use in dual-screen mode, the security of the user executing EDF is also checked. If a NOTAUTH condition occurs with an EXEC CICS START command, this can be because of link security or because of EDF user security.

## BTS processes and activities

When a CICS business transaction services (BTS) process or activity is activated by a **RUN** command, it may run under a different userid from that of the transaction that issues the RUN. For more information about BTS, see *CICS Business Transaction Services*.

The application programmer can specify under whose authority a process or activity is to run, when it is activated by a RUN command, by coding the USERID option of the **DEFINE PROCESS** or **DEFINE ACTIVITY** command. If the USERID option is omitted, the value defaults to the userid of the transaction that issues the DEFINE command.

If the USERID option is specified, CICS performs (at define time) a surrogate security check to verify that the userid of the transaction that issued the DEFINE command is authorized to use the userid specified by USERID.

#### Transient data trigger-level transactions

When a transient data queue is defined by RDO with a non-terminal trigger-level transaction and a USERID parameter, the user installing the definition is checked.

Likewise, when such a transient data queue is created with the CREATE TDQUEUE command, the user executing the command is checked.

The userid for a transient data trigger-level transaction that is not associated with a terminal can be specified on the TDQUEUE resource definition or on the SET TDQUEUE command.

#### Intrapartition transient data resources

CICS uses the user ID specified on transient data queue definition for security checking in any trigger-level transactions that are not associated with a terminal.

Code the USERID operand with the userid that you want CICS to use for security checking for the trigger-level transaction specified on the TRANSID operand. USERID is valid only when the destination facility is a file.

The trigger-level transaction runs under the authority of the specified userid, which must be authorized to all the resources used by the transaction.

If you omit the userid from a qualifying trigger-level entry, CICS uses the default userid specified on the **DFLTUSER** system initialization parameter. Ensure that the userid of any CICS region in which the transient data queue definition is installed is defined as a surrogate of all the user IDs specified in the transient data destination definition. This is because, during a cold start, CICS performs a surrogate user security check for the CICS region userid against all the user IDs specified in transient data queue definitions that are being installed. If the surrogate security check fails, the transient data queue definition is not installed.

#### EXEC CICS SET TDQUEUE ATIUSERID

The system programming command, SET TDQUEUE with the ATIUSERID option, specifies the userid for a transient data trigger-level transaction that is not associated with a terminal. The destination facility must be a file.

CICS performs a surrogate user security check against the userid of the transaction that issues the SET TDQUEUE command, to verify that the transaction userid is authorized as a surrogate user of the userid specified on the ATIUSERID parameter.

#### Surrogate user checking for EXCI calls

A surrogate user check is performed to verify that the batch region's userid is authorized to issue DPL calls for another user (that is, is authorized as a surrogate of the userid specified on the DPL_request call).

If you want your external CICS interface (EXCI) client jobs to be subject to surrogate user checking, specify SURROGCHK=YES in the EXCI options table, DFHXCOPT. If you specify SURROGCHK=YES, authorize the batch region's userid as a surrogate of the userid specified on all DPL_request calls. This means the batch region's userid must have READ access to a profile named *userid*.DFHEXCI in the SURROGAT general resource class (where *userid* is the userid specified on the DPL call). For example, the following commands define a surrogate profile for a DPL userid, and grant READ access to the EXCI batch region:

RDEFINE SURROGAT dpl_userid.DFHEXCI UACC(NONE) OWNER(DPL_userid) PERMIT userid.DFHEXCI CLASS(SURROGAT) ID(batch_region_userid) ACCESS(READ)

If surrogate user checking is enabled (SURROGCHK=YES), but no userid is specified on the DPL call, no surrogate user check is performed, because the userid on the DPL call defaults to the batch region's userid.

If you do not want surrogate user security checking, specify SURROGCHK=NO in the DFHXCOPT options table.

Surrogate user checking is useful when the batch region's userid is the same as the CICS server region userid, in which case the link security check is bypassed. In this case, a surrogate user check is recommended, because the USERID specified on the DPL call is not an authenticated userid (no password is passed).

If the batch region's userid and the CICS region userid are different, link security checking is enforced. With link security, an unauthenticated userid passed on a DPL call cannot acquire more authority than that allowed by the link security check. It can acquire only the same, or less, authority than allowed by the link security check.

## The userid on DB2 AUTHID and COMAUTHID parameters

When you install a DB2CONN resource definition that specifies the AUTHID, SIGNID, or COMAUTHID attribute, or when you install a DB2ENTRY resource definition that specifies AUTHID, or when you modify one of these attributes, CICS checks that the user ID performing the operation is authorized as a surrogate user of AUTHID, COMAUTHID, or SIGNID. This checking also applies to the CICS region user ID during group list install on a CICS cold or initial start.

For more information about these attributes, see the CICS Resource Definition Guide.

The **XUSER** system initialization parameter is also used to control access to the AUTHTYPE and COMAUTHTYPE attributes, but the security control for these parameters is managed through the facility general resource class. See Security in a CICS DB2 environmentthe *CICS DB2 Guide* for more information.

# The user ID in event bindings

When you install a BUNDLE resource that includes an event binding for which you specified a user ID in the **Adapter** tab of the CICS event binding editor, CICS checks that the User ID performing the install operation is authorized as a surrogate user of the user ID specified in the CICS event binding editor. This check also applies to the CICS region user ID during group list install on a CICS cold or initial start.

For more information, see Specifying adapter and dispatcher information.

#### **Related information:**

"RACF definitions for surrogate user checking"

To enable CICS surrogate user checking, you define the appropriate SURROGAT class profiles for CICS in the RACF database and you authorize CICS surrogate users to the appropriate SURROGAT profiles.

# The userid on URIMAP resource definitions

When you install a URIMAP resource definition that specifies the USERID attribute, or when you modify this attribute, CICS checks that the userid performing the operation is authorized as a surrogate user of the user ID specified for the USERID attribute. This also applies to the CICS region userid during group list install on a CICS cold or initial start.

URIMAP resource definitions are used for CICS Web support. For more information about this resource definition, see the CICS *Resource Definition Guide*.

# **RACF** definitions for surrogate user checking

To enable CICS surrogate user checking, you define the appropriate SURROGAT class profiles for CICS in the RACF database and you authorize CICS surrogate users to the appropriate SURROGAT profiles.

You can define two forms of surrogate class profile names for CICS surrogate user checking. The names of these SURROGAT class profiles must conform to the following naming conventions:

#### userid.DFHSTART

- *userid* represents one of the following:
- The user ID under which a started transaction is to run
- The user ID associated with a CICS business transaction services (BTS) process or activity that is started by a RUN command

#### userid.DFHINSTL

userid represents one of the following:

- The PLT user ID specified on the PLTPIUSR system initialization parameter
- · The user ID associated with a trigger-level transaction
- The CICS default user ID specified on the DFLTUSER system initialization parameter
- The user ID specified for preset terminal security

- The user ID specified on the AUTHID or COMAUTHID parameter of a DB2 resource definition
- The event binding user ID

Note that if the user ID associated with a task issuing either a CREATE IPCONN or CREATE CONNECTION command is not an authorized surrogate of the user specified in the SECURITYNAME option, a NOTAUTH error is returned.

You can also define a form of surrogate class profile for external CICS interface (EXCI) security checking:

#### userid.DFHEXCI

I

*userid* represents the user specified on the DPL call in the client batch region.

To authorize a surrogate to this EXCI profile, grant the user ID of the EXCI batch region READ access.

Note that surrogate security checks in an EXCI batch region are independent of security definitions in the target CICS region. If SURROGCHK is specified in the EXCI options table (DFHXCOPT), surrogate security checks are performed in the EXCI client program address space regardless of the CICS security settings.

To authorize a surrogate user to one of these profiles, you must grant READ access.

You do not need to define a user as its own surrogate. CICS bypasses the surrogate check in this case.

The *z/OS Security Server RACF Security Administrator's Guide* gives more information about defining surrogate resource classes. Refer to it if you need to use RACF facilities such as generic resource classes or RACFVARS profiles to help make many RACF definitions.

## Examples of RACF definitions for surrogate user checking

You define surrogate users to RACF by:

- Defining a *userid.resource_name* profile in the SURROGAT general resource class for each user requiring a surrogate user to act on their behalf. For this purpose you use the RACF RDEFINE SURROGAT command.
- Authorizing each userid that is to act as a surrogate for a user defined in a SURROGAT class profile. For this purpose you use the RACF PERMIT command.

## **PLT** security

For PLT security checking, the CICS region userid must be authorized as a surrogate of the PLT userid defined on the PLTPIUSR system initialization parameter.

This means granting the CICS region userid access to a SURROGAT resource class profile owned by the PLT userid, as shown in the following example, where the CICS region userid is CICSHT01, and the PLT security userid is PLTUSER: RDEFINE SURROGAT PLTUSER.DFHINSTL UACC(NONE) OWNER(PLTUSER) PERMIT PLTUSER.DFHINSTL CLASS(SURROGAT) ID(CICSHT01) ACCESS(READ) In addition to enabling PLT security by defining SURROGAT profiles, ensure that when PLT security is active (through the use of the PLTPISEC system initialization parameter) you also add the PLT userid to the access lists of all the resources accessed by PLT programs. For example, if you specify PLTPISEC=RESSEC, ensure that the PLT userid is authorized to all the CICS resources for which security is active.

#### **Started transactions**

For started transactions, CICS can require as many as three levels of surrogate user.

(See "Started transactions" on page 114 for details of the different surrogate users that can be required for a START command.)

For started transaction security at the first level, the userid of the transaction that issues the START command must be authorized as a surrogate for the userid specified on the START command.

For example, a transaction running under USERID2 issues: EXEC CICS START TRANSID('TBAK') USERID('USERID1')

USERID2 must be defined to RACF as a surrogate of USERID1 (with READ authority). This is illustrated in the following RACF commands: RDEFINE SURROGAT USERID1.DFHSTART UACC(NONE) OWNER(USERID1) PERMIT USERID1.DFHSTART CLASS(SURROGAT) ID(USERID2) ACCESS(READ)

For more information about surrogate security, see "Querying a user's surrogate authority" on page 140.

# **Chapter 8. CICS command security**

CICS command security controls the use of system programming commands; that is, commands that require the special CICS translator option, SP.

# Introduction to command security

CICS command security applies to system programming commands; that is, commands that require the special CICS translator option, SP. Security checking is performed for these commands, when they are issued from a CICS application program, and for the equivalent commands that you can issue with the CEMT master terminal transaction.

Table 10 shows the commands that are subject to command security checking:

Table 10. Access required for system programming commands

Command name	Access required
	READ
COLLECT	
CSD DISCONNECT	
CSD ENDBRGROUP	
CSD ENDBRLIST	
CSD ENDBRRSRCE	
CSD GETNEXTGROUP	
CSD GETNEXTLIST	
CSD GETNEXTRSRCE	
CSD INQUIREGROUP	
CSD INQUIRELIST	
CSD INQUIRERSRCE	
CSD STARTBRGROUP	
CSD STARTBRLIST	
CSD STARTBRRSRCE	
EXTRACT STATISTICS	
INQUIRE	
	UPDATE
DISABLE	
CSD ADD	
CSD ALTER	
CSD APPEND	
CSD COPY	
CSD DEFINE	
CSD DELETE	
CSD LOCK	
CSD REMOVE	
CSD RENAME	
CSD UNLOCK	
CSD USERDEFINE	
ENABLE	
EXTRACT (but not EXTRACT STATISTICS)	
PERFORM	
RESYNC	
SET	

|
|
|

Table 10. Access required for system programming commands (continued)

Command name	Access required
	ALTER
CREATE	
CSD INSTALL	
DISCARD	
Note: Because the PERFORM CORBASERVER SCAN might result in the dynamic creation	

and installation of DJAR resources, the PERFORM CORBASERVER SCAN command requires ALTER access to the DJAR command security resource as well as UPDATE authority to the CORBASERVER resource.

Command security operates in addition to any transaction or resource security that you define for a transaction. For example, if a user is permitted to use a transaction called FILA, which issues an EXEC CICS INQUIRE FILE command that the user is *not* permitted to use, CICS issues a "not authorized" (NOTAUTH) condition in response to the command, and the command fails.

Front End Programming Interface security uses the same mechanism for authorization as the system programming commands, using the FEPIRESOURCE resource name.

**Note:** To determine who is allowed to use the SP option on the CICS translator, you can use RACF to control who is allowed to load the DFHEITBS table at translation time. For a description of RACF program control, see the *z/OS Security Server RACF Security Administrator's Guide*. DFHEITBS is the language definition table that defines the system programming commands. It is loaded only on demand.

#### CICS resources subject to command security checking

For transaction and resource security checking, you identify the resources to RACF using the identifiers that you have assigned to them; for example, file names, queue names, and transaction names. However, in the case of command security, the resource identifiers are all predefined by CICS, and you use these predefined names when defining resource profiles to RACF.

The full list of resource identifiers that are subject to command security checking with the associated commands, is shown in Table 11. Most of these commands are common to both the CEMT and EXEC CICS interfaces; the ones that are unique to one or the other are prefaced with CEMT or EXEC CICS, as appropriate.

Resource name 1	Related CICS commands
ASSOCIATION	INQUIRE ASSOCIATION
ATOMSERVICE	CREATE ATOMSERVICE DISCARD ATOMSERVICE INQUIRE ATOMSERVICE SET ATOMSERVICE
AUTINSTMODEL	DISCARD AUTINSTMODEL INQUIRE AUTINSTMODEL
AUTOINSTALL	INQUIRE AUTOINSTALL SET AUTOINSTALL
BEAN	INQUIRE BEAN

Table 11. CICS resources subject to command security checking

T

1

Resource name 1	Related CICS commands
BRFACILITY	INQUIRE BRFACILITY SET BRFACILITY
BUNDLE	CREATE BUNDLE DISCARD BUNDLE INQUIRE BUNDLE SET BUNDLE
BUNDLEPART	EXEC CICS INQUIRE BUNDLEPART
CAPTURESPEC	INQUIRE CAPTURESPEC
CFDTPOOL	INQUIRE CFDTPOOL
CLASSCACHE	INQUIRE CLASSCACHE PERFORM CLASSCACHE SET CLASSCACHE
CONNECTION	CREATE CONNECTION DISCARD CONNECTION INQUIRE CONNECTION SET CONNECTION
CORBASERVER	CREATE CORBASERVER DISCARD CORBASERVER INQUIRE CORBASERVER PERFORM CORBASERVER SET CORBASERVER
CSD	EXEC CICS CSD ADD EXEC CICS CSD ALTER EXEC CICS CSD APPEND EXEC CICS CSD COPY EXEC CICS CSD DEFINE EXEC CICS CSD DELETE EXEC CICS CSD DISCONNECT EXEC CICS CSD ENDBRGROUP EXEC CICS CSD ENDBRLIST EXEC CICS CSD ENDBRLST EXEC CICS CSD GETNEXTGROUP EXEC CICS CSD GETNEXTGROUP EXEC CICS CSD GETNEXTRSRCE EXEC CICS CSD INQUIREGROUP EXEC CICS CSD INQUIRELIST EXEC CICS CSD INQUIRELIST EXEC CICS CSD INQUIRELIST EXEC CICS CSD INQUIRESRCE EXEC CICS CSD INSTALL EXEC CICS CSD REMOVE EXEC CICS CSD REMAME EXEC CICS CSD STARTBRGROUP EXEC CICS CSD STARTBRGROUP EXEC CICS CSD STARTBRLIST EXEC CICS CSD UNLOCK EXEC CICS CSD UNLOCK EXEC CICS CSD USERDEFINE
DB2CONN	CREATE DB2CONN DISCARD DB2CONN INQUIRE DB2CONN SET DB2CONN

Table 11. CICS resources subject to command security checking (continued)

Ι T L Ι L I I I Ι L L Ι Ι T Ι I I

Resource name 1	Related CICS commands
DB2ENTRY	CREATE DB2ENTRY DISCARD DB2ENTRY INQUIRE DB2ENTRY SET DB2ENTRY
DB2TRAN	CREATE DB2TRAN DISCARD DB2TRAN INQUIRE DB2TRAN SET DB2TRAN
DELETSHIPPED	INQUIRE DELETSHIPPED PERFORM DELETSHIPPED SET DELETSHIPPED
DISPATCHER	INQUIRE DISPATCHER SET DISPATCHER
DJAR	CREATE DJAR DISCARD DJAR INQUIRE DJAR PERFORM DJAR Note: ALTER access to the associated DJAR resource is required for the PERFORM CORBASERVER SCAN command.
DOCTEMPLATE	CREATE DOCTEMPLATE DISCARD DOCTEMPLATE INQUIRE DOCTEMPLATE SET DOCTEMPLATE
DSNAME	INQUIRE DSNAME SET DSNAME
DUMP	CEMT PERFORM SNAP PERFORM DUMP
DUMPDS	INQUIRE DUMPDS SET DUMPDS
ENQMODEL	CREATE ENQMODEL INQUIRE ENQMODEL SET ENQMODEL
EVENTBINDING	DISCARD EVENTBINDING INQUIRE EVENTBINDING SET EVENTBINDING
EVENTPROCESS	INQUIRE EVENTPROCESS SET EVENTPROCESS
EXCI	INQUIRE EXCI
EXITPROGRAM	EXEC CICS ENABLE PROGRAM EXEC CICS DISABLE PROGRAM EXEC CICS EXTRACT EXIT EXEC CICS RESYNC ENTRYNAME INQUIRE EXITPROGRAM
FEPIRESOURCE	Certain EXEC CICS FEPI commands 3
FILE	CREATE FILE DISCARD FILE INQUIRE FILE SET FILE
HOST	INQUIRE HOST SET HOST

Table 11. CICS resources subject to command security checking (continued)

Resource name 1	Related CICS commands
IPCONN	CREATE IPCONN DISCARD IPCONN INQUIRE IPCONN SET IPCONN
IRC	INQUIRE IRC SET IRC
JOURNALMODEL	CEMT INQUIRE JMODEL EXEC CICS INQUIRE JOURNALMODEL EXEC CICS CREATE JOURNALMODEL EXEC CICS DISCARD JOURNALMODEL
JOURNALNAME	INQUIRE JOURNALNAME SET JOURNALNAME
JVM	INQUIRE JVM
JVMPOOL	INQUIRE JVMPOOL SET JVMPOOL
JVMPROFILE	INQUIRE JVMPROFILE
JVMSERVER	CREATE JVMSERVER DISCARD JVMSERVER INQUIRE JVMSERVER SET JVMSERVER
LIBRARY	CREATE LIBRARY DISCARD LIBRARY INQUIRE LIBRARY SET LIBRARY
LINE	CEMT INQUIRE LINE CEMT SET LINE
LSRPOOL	CREATE LSRPOOL
MAPSET	CREATE MAPSET
MODENAME	INQUIRE MODENAME SET MODENAME
MONITOR	INQUIRE MONITOR SET MONITOR
MQCONN	CREATE MQCONN DISCARD MQCONN INQUIRE MQCONN SET MQCONN
MQINI	INQUIRE MQINI
MVSTCB	COLLECT STATISTICS INQUIRE MVSTCB
PARTITIONSET	CREATE PARTITIONSET
PARTNER	CREATE PARTNER DISCARD PARTNER INQUIRE PARTNER
PIPELINE	CREATE PIPELINE DISCARD PIPELINE INQUIRE PIPELINE PERFORM PIPELINE SET PIPELINE

| | |

| | | |

Table 11. CICS resources subject to command security checking (continued)

Resource name 1	Related CICS commands
PROCESSTYPE	CEMT INQUIRE PROCESSTYPE CEMT SET PROCESSTYPE EXEC CICS CREATE PROCESSTYPE EXEC CICS DISCARD PROCESSTYPE
PROFILE	CREATE PROFILE DISCARD PROFILE INQUIRE PROFILE
PROGRAM	CREATE PROGRAM DISCARD PROGRAM INQUIRE PROGRAM SET PROGRAM
REQID	EXEC CICS INQUIRE REQID
RESETTIME	PERFORM RESETTIME 4
REQUESTMODEL	INQUIRE REQUESTMODEL
RRMS	INQUIRE RRMS
SECURITY	PERFORM SECURITY REBUILD
SESSIONS	CREATE SESSIONS
SHUTDOWN	PERFORM SHUTDOWN 2
STATISTICS	INQUIRE STATISTICS SET STATISTICS EXEC CICS COLLECT STATISTICS EXEC CICS EXTRACT STATISTICS EXEC CICS PERFORM STATISTICS RECORD
STORAGE	INQUIRE STORAGE
STREAMNAME	INQUIRE STREAMNAME
SUBPOOL	INQUIRE SUBPOOL
SYSDUMPCODE	INQUIRE SYSDUMPCODE 4 Set sysdumpcode 4
SYSTEM	INQUIRE SYSTEM SET SYSTEM
TASK	INQUIRE TASK INQUIRE TASK LIST SET TASK LIST
TCLASS	CREATE TRANCLASS DISCARD TRANCLASS INQUIRE TRANCLASS SET TRANCLASS INQUIRE TCLASS SET TCLASS
TCPIP	INQUIRE TCPIP SET TCPIP
TCPIPSERVICE	CREATE TCPIPSERVICE DISCARD TCPIPSERVICE INQUIRE TCPIPSERVICE SET TCPIPSERVICE

Table 11. CICS resources subject to command security checking (continued)

Table 11. CICS resources subject to command security checking (continued)

Resource name 1	Related CICS commands
TDQUEUE	CREATE TDQUEUE DISCARD TDQUEUE INQUIRE TDQUEUE SET TDQUEUE
TERMINAL	INQUIRE NETNAME SET NETNAME CREATE TERMINAL DISCARD TERMINAL INQUIRE TERMINAL SET TERMINAL
TRACEDEST	EXEC CICS INQUIRE TRACEDEST EXEC CICS SET TRACEDEST
TRACEFLAG	EXEC CICS INQUIRE TRACEFLAG EXEC CICS SET TRACEFLAG
TRACETYPE	EXEC CICS INQUIRE TRACETYPE EXEC CICS SET TRACETYPE
TRANDUMPCODE	INQUIRE TRANDUMPCODE 4 SET TRANDUMPCODE 4
TRANSACTION	CREATE TRANSACTION DISCARD TRANSACTION INQUIRE TRANSACTION SET TRANSACTION
TSMODEL	CREATE TSMODEL DISCARD TSMODEL INQUIRE TSMODEL
TSPOOL	INQUIRE TSPOOL
TSQUEUE	EXEC CICS INQUIRE TSQUEUE
TSQNAME	INQUIRE TSQNAME SET TSQNAME
TYPETERM	CREATE TYPETERM
UOW	INQUIRE UOW SET UOW
UOWDSNFAIL	INQUIRE UOWDSNFAIL
UOWENQ	INQUIRE UOWENQ
UOWLINK	EXEC CICS SET UOWLINK INQUIRE UOWLINK
URIMAP	CREATE URIMAP DISCARD URIMAP INQUIRE URIMAP SET URIMAP
VTAM	INQUIRE VTAM SET VTAM
WEB	INQUIRE WEB SET WEB
WEBSERVICE	CREATE WEBSERVICE DISCARD WEBSERVICE INQUIRE WEBSERVICE SET WEBSERVICE

Table 11. CICS resources subject to command security checking (continued)

Resource name 1	Related CICS commands
WORKREQUEST	INQUIRE WORKREQUEST SET WORKREQUEST
XMLTRANSFORM	INQUIRE XMLTRANSFORM SET XMLTRANSFORM

#### Note:

- 1. If you are using prefixing, the CICS region userid must be prefixed to the command resource name.
- **2**. Be cautious when authorizing access to these and any other CICS commands that include a SHUTDOWN option.
- **3.** For more information about FEPI security, see the *CICS Front End Programming Interface User's Guide*.
- 4. See "CEMT considerations" on page 130.

If you are running CICS with command security, define resource profiles to RACF, with access lists as appropriate, using the resource names in Table 11 on page 122 as the profile names. Alternatively, you can create resource group profiles in the VCICSCMD class.

In the following example, the **RDEFINE** command defines a profile named CMDSAMP. The commands protected by this profile are specified on the ADDMEM operand. The PERMIT command allows a group of users to issue the commands for INQUIRE:

RDEFINE VCICSCMD CMDSAMP UACC(NONE) NOTIFY(*sys_admin_userid*) ADDMEM(AUTINSTMODEL, AUTOINSTALL, CONNECTION, DSNAME, TRANSACTION, TRANDUMPCODE, VTAM) PERMIT CMDSAMP CLASS(VCICSCMD) ID(*operator_group*) ACCESS(READ)

The second example defines a profile called CMDSAMP1 with the same commands in the ADDMEM operand, as in the previous example. The **PERMIT** command allows a group of users to issue PERFORM, SET, and DISCARD against these commands:

RDEFINE VCICSCMD CMDSAMP1 UACC(NONE) NOTIFY(*sys_admin_userid*) ADDMEM(AUTINSTMODEL, AUTOINSTALL, CONNECTION, DSNAME, TRANSACTION, TRANDUMPCODE, VTAM) PERMIT CMDSAMP1 CLASS(VCICSCMD) ID(*op_group_2*) ACCESS(UPDATE)

If you are running CICS with SEC=YES, users require the access levels shown in Table 11 on page 122.

#### Parameters for specifying command security

In addition to the **SEC** and **SECPRFX** system initialization parameters, CICS provides the **XCMD** system initialization parameter and the CMDSEC attribute on the TRANSACTION resource definition option to enable you to specify that you want command security.

These parameters are summarized as follows:

XCMD system initialization parameter

Use the XCMD system initialization parameter to specify whether you want command security active in the CICS region, and, optionally, to specify the RACF resource class name in which you have defined the command security profiles.

If you are using the IBM-supplied RACF resource class names for CICS command profiles (CCICSCMD and VCICSCMD), specify XCMD=YES. CICS then requests RACF to build the in-storage profiles from these default resource classes.

If you are using installation-defined resource class names for CICS command profiles, specify XCMD=*user_class*, and CICS requests RACF to build the in-storage profiles from your own installation-defined resource classes.

If you do not want command security in a CICS region, specify XCMD=NO.

#### The CMDSEC system initialization parameter

You can force the effect of CMDSEC=YES for all CICS transactions by specifying the CMDSEC=ALWAYS system initialization parameter. The CMDSEC option is recommended for installations that need total control of the system programming commands.

#### The CMDSEC transaction definition attribute

You specify which transactions you want command security to apply to by using the CMDSEC attribute on the TRANSACTION resource definition, as follows:

#### CMDSEC(NO)

You do not want command security checking the transaction.

#### CMDSEC(YES)

You want command security checking on the system programming commands in Table 10 on page 121.

For each of these commands issued in a user application or by the CICS-supplied transactions CEMT and CECI, CICS calls RACF to check that the terminal operator who initiated the transaction has authority to use the command for the specified resource.

To view all of the attributes of this resource, see the *CICS Resource Definition Guide* 

# Security checking of transactions running under CEDF

When a transaction is run under the CEDF transaction, CICS takes into account the security settings for both the target transaction and CEDF.

When a transaction runs under the CEDF transaction, CICS uses the CMDSEC attribute in the definition of the target transaction *and* the CEDF transaction:

CEDF	target transaction	Security checking
CMDSEC(YES)		Any access to CICS commands causes a security check.

Table 12. Security checking for transactions running under CEDF

Table 12. Security of	checking for	transactions	running	under CEDF	(continued)
-----------------------	--------------	--------------	---------	------------	-------------

CEDF	target transaction	Security checking
CMDSEC(YES)	CMDSEC(NO)	Any access to CICS commands causes a security check.
CMDSEC(NO)	CMDSEC(YES)	Any access to CICS commands causes a security check.
CMDSEC(NO)	CMDSEC(NO)	Access to CICS commands does not cause a security check.

To achieve the expected security processing for a transaction when it runs under CEDF, ensure that CMDSEC for the CEDF transaction definition is set to NO. The IBM-supplied definition of CEDF in the DFHEDF group specifies CMDSEC(YES). Definitions in the IBM-supplied groups cannot be modified, so to change the definitions, copy them to another group.

When CEBR or CECI is invoked from within EDF it is transaction-attach checked. In the same environment the CMDSEC and RESSEC definitions are forced regardless of what is coded in their transaction definitions. The CMDSEC(YES) and RESSEC(YES) values for CEDF or CEDX override the CMDSEC and RESSEC values of the user transaction.

When CEDF is used to test a transaction, the authorities of the user executing the CEDF transaction are taken into account, as well as those of the user executing the transaction being tested. For each resource accessed by the tested transaction, both users must have access authority, otherwise authority, otherwise a NOTAUTH condition is raised. This applies to all resource checks:

- Transaction-attach
- CICS resource
- CICS command
- Non-CICS resources accessed through the QUERY SECURITY command
- Surrogate user

**Note:** When an EXEC CICS SIGNON, EXEC CICS VERIFY PASSWORD, or EXEC CICS CHANGE PASSWORD command is issued by a transaction running under CEDF, the password (and new password, where applicable) is blanked out.

#### **CEMT** considerations

In general, the resources that the CICS-supplied CEMT master terminal transaction operates on are the same as the equivalent system programming commands.

The equivalent system programming commands are shown in Table 10 on page 121. If, in addition to normal transaction-attach security, you are using command security, you must ensure that authorized users of CEMT are also authorized for the CICS commands, as appropriate. If a user is authorized to initiate the CEMT transaction, but is not authorized for the resources on which the system programming commands in Table 10 on page 121 depend, CICS returns a NOTAUTH condition. To allow your system programmers to use the CEMT command in a command security environment, give them UPDATE access to the group profile that protects commands on which you want them to issue the PERFORM, SET, and DISCARD commands. UPDATE authority should be given to

users specifying XPPT=YES and XCMD=YES when they issue a CEMT SET PROG(xxx) command. and you should provide READ access to the group profile that protects the commands on which you want them to issue only INQUIRE and COLLECT commands.

PERMIT profile_name CLASS(VCICSCMD) ID(user or group) ACCESS(READ)
PERMIT profile_name CLASS(VCICSCMD) ID(user or group) ACCESS(UPDATE)

# **Resource names for CEMT**

In general, the resource names of the CEMT commands correspond to the resource names of the equivalent CICS API command.

However, there are some exceptions, and in all these cases it is the API resource name that you use to define the security profile to RACF.

- The CEMT system dump option is spelled differently from the EXEC CICS equivalent. CEMT INQUIRE | SET SYDUMPCODE corresponds to EXEC CICS INQUIRE | SET SYSDUMPCODE.
- The CEMT transaction dump option is spelled differently from the EXEC CICS equivalent. CEMT INQUIRE | SET TRDUMPCODE corresponds to EXEC CICS INQUIRE | SET TRANDUMPCODE.
- The CEMT PERFORM RESET option corresponds to the EXEC CICS PERFORM RESETTIME command.
- The AUXTRACE, INTTRACE, and GTFTRACE options of the CEMT INQUIRE and SET commands all correspond to the TRACEDEST option of the API.

To use the CEMT INQUIRE | SET NETNAME command, you need access to the resource TERMINAL, not NETNAME.

# Authorization failures in application programs

CICS returns a RESP2 value of 100 for command security failures, a value of 101 for resource security failures, and a value of 102 for surrogate security failures.

If you are running with CICS command security, CICS returns the NOTAUTH condition, RESP value 70, to your application, which is the same condition as for a resource security failure. CICS also issues message DFHXS1111 to the CICS security transient data destination CSCS. To test for this value in your application, it is recommended that you code DFHRESP(NOTAUTH) rather than explicitly coding a value.

To distinguish between a command security failure, a resource security failure, and a surrogate security failure, check the RESP2 value:

- For a command security failure, CICS returns a value of 100 in RESP2.
- For a resource security failure, a value of 101 is returned in RESP2.
- For a surrogate security failure, a value of 102 is returned in RESP2

For background information on using RESP and RESP2, see CICS Application *Programming Guide;* for programming information, see the CICS Application *Programming Reference* and CICS System Programming Reference.

# Chapter 9. Security checking using the QUERY SECURITY command

Use the QUERY SECURITY command in an application program to determine the level of access that the transaction user has to a particular resource. The QUERY SECURITY command does not grant or deny access to a resource. Instead, the application program uses the values returned by the command to determine what action to take.

# How QUERY SECURITY works

How QUERY SECURITY works depends on:

- Whether SEC=YES or SEC=NO is specified in the system initialization parameters
- The value specified for the SECPRFX system initialization parameter
- Which resource classes are active
- Whether the transaction issuing the request is subject to transaction routing, and if so:
  - Which ATTACHSEC parameter was specified on the connection definition
  - For RESTYPE('PSB') only, whether the PSBCHK system initialization parameter is specified as YES or NO

**Note:** QUERY SECURITY is **not** affected by the RESSEC and CMDSEC keywords on the transaction definition.

There are two distinct forms of the QUERY SECURITY command, depending on the options chosen.

- QUERY SECURITY RESTYPE
- QUERY SECURITY RESCLASS

# SEC system initialization parameter

Table 13 assumes that the relevant resource class is active; for example, that XFCT=YES is specified when issuing QUERY SECURITY RESTYPE('FILE').

SEC	RACF Access	Query Security Read	Query Security Update	Query Security Control	Query Security Alter
YES	NONE READ UPDATE CONTROL ALTER	notreadable readable readable readable readable	notupdatable notupdatable updatable updatable updatable	notctrlable notctrlable notctrlable ctrlable ctrlable	notalterable notalterable notalterable notalterable alterable
NO	n/a	readable	updatable	ctrlable	alterable

Table 13. The effect of the SEC parameter on QUERY SECURITY commands

# SECPRFX system initialization parameter

The SECPRFX system initialization parameter determines whether CICS applies a prefix to the RESID option on the QUERY SECURITY command. For example, if you issue the following command:

QUERY SECURITY RESTYPE('FILE') RESID('PAYFILE')

- When SECPRFX=YES, CICS applies the CICS region userid as a prefix, and calls RACF to check the user's access to *cics_region_userid*.PAYFILE.
- When SECPRFX=*prefix*, CICS applies the prefix supplied, and calls RACF to check the user's access to *prefix*.PAYFILE.
- If SECPRFX=NO is specified, CICS does not apply a prefix, and calls RACF to check the user's access to PAYFILE.

## **Resource class system initialization parameters**

Table 13 on page 133 shows how the QUERY SECURITY RESTYPE command works if the system initialization parameter for the relevant resource class (for example, XFCT) system initialization parameter is active. If, however, the relevant *Xname* parameter is **not** active (for example, if XFCT=NO has been specified), the resource is READABLE, UPDATABLE, CTRLABLE and ALTERABLE.

### Transaction routing

When the QUERY SECURITY command is issued from a transaction that has been routed to a remote system, CICS checks the link user's access to the specified resource, and the terminal user's access to the resource, if appropriate.

For more information, see "Link security with LU6.2" on page 167, or "Link security with MRO" on page 222, depending upon the environment you are using.

In order to perform a check against the terminal user as well as the link user when transaction routing a QUERY SECURITY RESTYPE('PSB') RESID(*psb_name*), the following conditions must both be satisfied:

- ATTACHSEC on the connection definition must not be LOCAL (that is, it can be IDENTIFY, PERSISTENT, MIXIDPE, or VERIFY).
- PSBCHK=YES must be specified as a system initialization parameter in the remote system.

# The **RESTYPE** option

Use the QUERY SECURITY command with the RESTYPE option to query access levels to CICS resources (including DB2 resource definitions) contained in the classes activated at initialization by RACLIST.

The response to the QUERY SECURITY command indicates the result of a resource check on this resource. If the resource is not defined to RACF, CICS does not grant access and the response is NOTREADABLE. Ensure the length of the resource name passed to RACF with a RESTYPE request is the actual maximum length for that resource type.

# **RESTYPE** values

RESTYPE is a resource type that corresponds to one of the X*name* system initialization parameters.

RESTYPE can take any of the values shown in Table 14 on page 135.

RESTYPE value	Xname parameter
ATOMSERVICE	XRES
BUNDLE	XRES
BUNDLEPART	XRES
CAPTURESPEC	XRES
CSD	XRES
DB2ENTRY	XDB2
DOCTEMPLATE	XRES
EVENTBINDING	XRES
EVENTPROCESS	XRES
FILE	XFCT
JOURNALNAME	ХЈСТ
JOURNALNUM 2	ХЈСТ
JVMSERVER	XRES
MQCONN	XRES
MQINI	XRES
PROGRAM	XPPT
PSB	XPSB
SPCOMMAND 1	XCMD
TDQUEUE	XDCT
TRANSACTION	ХРСТ
TRANSATTACH	XTRAN
TSQUEUE	XTST
TSQNAME	XTST
XMLTRANSFORM	XRES

Table 14. QUERY SECURITY RESTYPE values

- 1. SPCOMMAND is a resource type which allows you to specify a RESID for a command.
- 2. Supported for compatibility with earlier releases.

The system initialization parameter XHFS, which controls resource security for z/OS UNIX files, does not have a corresponding RESTYPE value on the QUERY SECURITY command. This is because access controls for z/OS UNIX files follow the system of permissions used by z/OS UNIX System Services, so they operate in a different way.

## **RESID** values

|

| | |

١

In all cases (except for the SPCOMMAND resource type), the resource identifiers (RESID values) are defined by your installation.

When defining RESID values, be aware of the effects of using blanks (X'40') in resource identifiers. For example, in: QUERY SECURITY RESTYPE('PSB') RESID('A B')

the blank delimits the RESID and causes RACF to use a resource name of A.

For SPCOMMAND, the identifiers are predetermined by CICS. The list of possible RESID values for SPCOMMAND is as follows:

- ASSOCIATION
- ATOMSERVICE
- AUTINSTMODEL
- AUTOINSTALL
- BRFACILITY
- BUNDLE

I

I

I

L

- CFDTPOOL
- CONNECTION
- CORBASERVER
- CSD
- DB2CONN
- DB2ENTRY
- DB2TRAN
- DISPATCHER
- DJAR
- DOCTEMPLATE
- DSNAME
- DUMP
- DUMPDS
- ENQUEUE
- EXCI
- EXITPROGRAM
- FEPIRESOURCE
- FILE
- HOST
- IPCONN
- IRC
- JOURNALMODEL
- JOURNALNAME
- JVMPOOL
- LIBRARY
- MODENAME
- MONITOR
- MQCONN
- MQINI
- MVSTCB
- PARTNER
- PIPELINE
- PROCESS
- PROFILE
- PROGRAM
- REQID
- REQUEST

- RESETTIME
- RRMS
- SECURITY
- SHUTDOWN
- STATISTICS
- STORAGE
- SUBPOOL
- SYSDUMPCODE
- SYSTEM
- TASK
- TCLASS
- TCPIP
- TCPIPSERVICE
- TDQUEUE
- TERMINAL
- TRACEDEST
- TRACEFLAG
- TRACETYPE
- TRANDUMPCODE
- TRANSACTION
- TSQUEUE
- TSMODEL
- TSPOOL
- TYPETERM
- UOW
- UOWDSNFAIL
- UOWENQ
- UOWLINK
- URIMAP
- VOLUME
- VTAM
- WEB
- WEBSERVICE
- WORKREQUEST

QUERY SECURITY RESTYPE enables an application program to request from RACF the level of access a terminal user has to the specified resource for the environment in which the transaction is running.

Before calling RACF, CICS checks that the resource is installed. If the resource does not exist, CICS does not call RACF and returns the NOTFND condition. However, note that this check is **not** made for PSBs.

When the RESTYPE is TRANSATTACH and the transaction specified on the RESID parameter is unknown in the local region, a NOTFND condition is returned. However, if dynamic transaction routing is being used, there is no need for the

transaction to be installed in the terminal-owning region. The transaction specified on the DTRTRAN system initialization parameter is attached if an unknown transaction identifier is entered.

Application programmers should be aware that the NOTFND condition does not necessarily indicate that a terminal user will be unable to enter a transaction identifier, because the transaction may be routed dynamically.

# Examples of values returned by QUERY SECURITY RESTYPE

This section gives a number of examples of the values returned by QUERY SECURITY RESTYPE, depending on what has been specified in the system initialization parameters:

#### SEC=NO

When SEC=NO is specified, issuing: QUERY SECURITY RESTYPE('FILE') RESID('PAYFILE') ALTER(*alter cvda*)

returns:

alter_cvda = DFHVALUE(ALTERABLE)

because SEC=NO means that no security checking is done for the entire CICS region.

#### SEC=YES and XFCT=NO

When SEC=YES and XFCT=NO are specified, issuing: QUERY SECURITY RESTYPE('FILE') RESID('PAYFILE') ALTER(*alter_cvda*)

returns: alter_cvda = DFHVALUE(ALTERABLE)

because XFCT=NO means that no security checking is done for files.

#### SEC=YES, XDCT=YES, and SECPRFX=NO

When SEC=YES, XDCT=YES, and SECPRFX=NO are specified, issuing: QUERY SECURITY RESTYPE('TDQUEUE') RESID('TDQ1') READ(*read cvda*)

returns: read cvda = DFHVALUE(READABLE)

if the user has READ (or higher) access to 'TDQ1' in the DCICSDCT class or the ECICSDCT group class.

#### SEC=YES, XTRAN=YES, and SECPRFX=YES

When SEC=YES, XTRAN=YES, and SECPRFX=YES are specified, issuing: QUERY SECURITY RESTYPE('TRANSATTACH') RESID('TRN1') READ(*read cvda*)

returns: read_cvda = DFHVALUE(NOTREADABLE)

if the user **does not** have READ (or higher) access to cics_region_userid.TRN1 in the TCICSTRN class or GCICSTRN group class.

#### SEC=YES, XTRAN=YES, and SECPRFX=YES

When SEC=YES, XTRAN=YES, and SECPRFX=YES are specified, issuing: QUERY SECURITY RESTYPE('TRANSATTACH') RESID('TRN1') READ(*read_cvda*)

returns: read_cvda = DFHVALUE(NOTREADABLE)

if the user **does not** have READ (or higher) access to cics_region_userid.TRN1 in the TCICSTRN class or GCICSTRN group class.

#### SEC=YES, XCMD=\$USRCMD, and SECPRFX=prefix

When SEC=YES, XCMD=\$USRCMD, and SECPRFX=*prefix* are specified, issuing: QUERY SECURITY RESTYPE('TRANSATTACH') RESID('TRN1') READ(*read_cvda*)

returns: read cvda = DFHVALUE(NOTREADABLE)

if the user **does not** have READ (or higher) access to prefix.TRN1 in the TCICSTRN class or GCICSTRN group class.

### The RESCLASS option

Use the QUERY SECURITY command with the RESCLASS option when you want to query access levels for non-CICS resources.

RESCLASS is the name of a valid RACF general resource class, such as TERMINAL, FACILITY, or a similar installation-defined resource class. See "RACF classes for protecting system resources" on page 24. The class name identified by RESCLASS is treated literally, with no translation.

**Note:** The RACF classes DATASET, GROUP, and USER do not appear in the class descriptor table (CDT), which means that you cannot query against these classes.

Prefixing, as specified in the SECPRFX system initialization parameter, does not apply to QUERY SECURITY RESCLASS. That is, CICS does **not** prefix the RESID with the CICS-region userid, nor with a user-specified prefix, before calling RACF.

If SEC=NO is specified in the system initialization parameters, QUERY SECURITY RESCLASS always returns READABLE, UPDATABLE, CTRLABLE and ALTERABLE.

For QUERY SECURITY RESCLASS, both the RESID **and** the RESIDLENGTH option must be specified. The maximum length of a resource (RESID) within a RACF class is specified in the class descriptor table (CDT). When defining RESID values, you should be aware of the effects of including blanks (X'40') in RESIDs. For example, in:

QUERY SECURITY RESCLASS ('MYCLASS') RESID ('MY PROFILE') RESIDLENGTH (10)

the presence of a blank causes an INVREQ condition. This is because RACF does not allow blanks to be embedded in a profile name.

**Note:** To determine access to CICS resources you should normally use RESTYPE, when the resource class is determined by the *Xname* system initialization parameter. However, if, for special reasons, you want to inquire about specific

CICS resource classes, you should note that the class name must be the member class, and **not** the group class; that is, CCICSCMD, and not VCICSCMD. The profiles in the grouping class are checked automatically if the member class has been activated by RACLIST. For example, if SEC=YES, and XCMD=YES are specified, both CCICSCMD and VCICSCMD are activated by RACLIST in the CICS region, which means that QUERY SECURITY RESCLASS('CCICSCMD') checks profiles in both CCICSCMD and VCICSCMD.

CICS can RACLIST groups only if the relevant *Xname* classes are active (for example, XCMD=YES or XCMD=\$USRCMD).

You can also use the RESCLASS option for querying access to DB2ENTRY resources defined in a user-defined resource class, which you specify to CICS on the XDB2 system initialization parameter. The rules about activating classes by means of the RACLIST command also apply to DB2ENTRY resource classes named on the XDB2 system initialization parameter. See "Resource classes for DB2ENTRYs" on page 27 for more information about user-defined DB2ENTRY resource classes.

Issuing QUERY SECURITY RESCLASS('TERMINAL') checks profiles in both TERMINAL and GTERMINL (the terminal grouping class) only if the TERMINAL class has been activated by RACLIST at the system level by the command: SETROPTS RACLIST(TERMINAL)

For **non-CICS** resource classes, you can issue the SETROPTS RACLIST(classname) command to perform a global RACLIST. See "Specifying user-defined resources to RACF" on page 318 for details.

# Querying a user's surrogate authority

To query a user's surrogate authority, you can use the QUERY SECURITY command with the RESCLASS('SURROGAT') option.

You also need to specify the RESID and RESIDLENGTH options. The RESID value you should provide is described in "RESID values" on page 135. However, this command is **not** controlled by the XUSER system initialization parameter, so you might obtain an unexpected response of NOTREADABLE if XUSER=NO has been specified. For example, to check whether the current user is allowed to start a transaction with a new userid of NEWUSER, when XUSER=YES is specified, issue the command:

```
QUERY SECURITY RESCLASS('SURROGAT') RESID('NEWUSER.DFHSTART')
RESIDLENGTH(16) READ(read cvda)
```

# Logging for QUERY SECURITY

You can control logging on the QUERY SECURITY command by specifying one of the following options:

- LOG
- NOLOG
- LOGMESSAGE(cvda), where cvda value is 54 for LOG, or 55 for NOLOG

The default is LOG.

If logging is in effect, and the terminal user does not have the requested access to the specified resource, message DFHXS1111 is issued to the CICS security transient data destination CSCS. Where relevant, RACF message ICH408I is also issued. SMF records may also be recorded, depending on the auditing and logging options that have been specified for that resource. For more information, see the *z*/OS Security Server RACF Auditor's Guide.

For programming information about CVDAs, refer to CICS System Programming Reference.

# Using the QUERY SECURITY command

You can use the two forms of the QUERY SECURITY command in a number of different ways to customize resource security checking within an application. This section gives a number of examples of doing so.

# Changing the level of security checking

You can use QUERY SECURITY to perform a different level of security checking from that which CICS would perform for application programs that specify RESSEC(YES) or CMDSEC(YES).

For example, suppose a transaction has RESSEC(YES) and contains a number of EXEC CICS READ FILE commands and a number of EXEC CICS WRITE FILE commands. For each command, CICS performs a security check to ensure that the terminal user has access to the relevant file, even though the same file may be being accessed each time. An alternative to this is to switch off security checking at the transaction level by specifying RESSEC(NO) on the transaction definition and then, when the application starts, execute a command such as:

EXEC CICS QUERY SECURITY RESTYPE('FILE') RESID(file_name) UPDATE(cvda)

This command allows the transaction to continue without any further calls to RACF.

**Note:** Switching resource security checking off, using RESSEC(NO), means that **all** resource checks—not just of files as in the above example—are bypassed.

# Checking which transactions to offer a user

You can use the QUERY SECURITY command to check whether a user is authorized to use a particular transaction **before** displaying the transaction code as part of an introductory menu.

When you use the command for this purpose, you will probably want to avoid logging the checks for users who are not allowed to use certain transactions. To do this, use the NOLOG option.

# Example of use of QUERY SECURITY RESCLASS

Normal CICS resource security checking for files operates at the file level only. You can use QUERY SECURITY to enable your application to control access to data at the **record** or **field** level.

To do this, define resource names (which represent records or fields within particular files) with the appropriate access authorizations for the records or fields you want to control. You could define these resources in an installation-defined RACF general resource class and then use the QUERY SECURITY RESCLASS command to check a terminal user's access to a specific field within a file before displaying or updating the field. (The application logic would determine which field.) For example:

QUERY SECURITY RESCLASS('\$FILEREC') RESID('PAYFILE.SALARY') RESIDLENGTH(14) READ(*read_cvda*) NOLOG

where '\$FILEREC' is an installation-defined RACF general resource class. For more information, see "Designing applications to use the user-defined resources" on page 320.

# Chapter 10. Security for CICS-supplied transactions

This topic discusses security for CICS-supplied transactions, and contains a number of recommendations to ensure that your CICS regions are adequately protected. Where applicable, it describes the recommended security specifications that you will need for the CICS-supplied transactions defined in the group list DFHLIST, and stored in the CICS system definition data set (CSD). These recommendations cover all CICS-supplied transactions—those that are intended for use from a user terminal or console, and those that are for CICS internal use only.

# Categories of CICS-supplied transactions

The RACF profile definitions for your CICS-supplied transactions are described in three categories. Each transaction is identified within a category that describes its use within CICS. Each category specifies the recommended security specifications you need, in terms of both the CICS transaction definitions and the corresponding RACF profiles.

The three categories are as follows:

#### **Category 1 transactions**

Transactions that are for CICS internal use only and must not run from a user terminal.

#### **Category 2 transactions**

Transactions that must be restricted to specific signed-on users; for example, you might want to limit access to transactions that define and install CICS resources.

#### **Category 3 transactions**

Transactions that are available to all terminal users, whether signed-on or not.

The three categories contain all the required CICS transactions, which are generated in their designated groups when you initialize your CICS system definition data set (CSD). The CSD does not include the CICS sample transactions (those that are in groups starting with DFH\$). Sample applications should not require RACF protection, because you are unlikely to install them on a CICS production system.

See Chapter 25, "Implementing CICSPlex SM security," on page 341 for details of CICSPlex SM-related transactions.

By default, all CICS transactions are subject to RACF protection (with the exception of category 3 transactions—see "JES spool protection in a CICS environment" on page 54), unless you run your CICS regions with transaction security switched off. You can do this either by:

- Specifying the system initialization parameter SEC=NO, which switches off all security checking, or
- Specifying the system initialization parameter XTRAN=NO, which switches off transaction-attach security checking only.

There is no parameter on the transaction resource definition that allows you to run with transaction security on some transactions but not others. If you are running

with transaction security (SEC=YES and XTRAN=YES), CICS issues a security check for each transaction attach, other than a transaction within category 3, to establish whether the user is permitted to run that transaction.

The following CICS–supplied transactions CDBN and CSXM are not subject to security checking, and are exempt from security categorization. Any security definitions for these transactions are redundant. **CDBN** 

DBCTL interface connection transaction

- **CEKL** Master terminal transaction for emergency use. This transaction can be used only at an operating system console that has the authority to issue MODIFY commands for the CICS region.
- **CSXM** The transaction used by CICS services to get and free a transaction environment

## Category 1 transactions

Category 1 transactions are never associated with a terminal. They are for CICS internal use only, and must not be started from a user terminal. CICS checks that the region user ID has the authority to attach these transactions.

However, if the region user ID is not authorized to access all of the category 1 transactions, CICS issues message DFHXS1113 and fails to initialize. For category 1 transactions, specify the following:

#### To CICS

RESSEC(NO) and CMDSEC(NO) on the transaction resource definition.

#### To RACF

UACC(NONE) and AUDIT(FAILURES) in the corresponding transaction profiles. AUDIT(FAILURES) is the default value. The access list should contain only user IDs (or groups containing userids) that can be specified as CICS region user IDs.

For example:

```
RDEFINE GCICSTRN CICSCAT1 UACC(NONE)

ADDMEM(CSKP CSPQ CDBD . . . . . . CXRE CSNE)

NOTIFY(security_admin_userid)

OWNER(userid or groupid)

PERMIT CICSCAT1 CLASS(GCICSTRN) ID(cat1grp1,...,cat1grpz) ACCESS(READ)
```

By defining these transactions to RACF with UACC(NONE), and an access list, you prevent any terminal user initiating these transactions (accidentally or otherwise). It is important, because starting these transactions at a terminal has unpredictable results. The sample CLIST DFH\$CAT1 helps you define the category 1 profiles to RACF. The sample CLIST is in library CICSTS41.CICS.SDFHSAMP.

The table lists the category 1 transactions supported in CICS Transaction Server for z/OS, Version 4 Release 1:

- The transactions that have operator interfaces are marked by an asterisk (*). The other transactions have no operator interface.
- Transactions CGRP, CSSY, CSTP, and CSXM are transaction names that are used by some CICS tasks.
- Transaction CPLT might run under a different user ID if the **PLTPIUSR** system initialization parameter is specified. For more information, see "Post-initialization processing" on page 113.

In addition to the transactions described in the following table, transactions CSGX, CSLG, and CSSX are included in DFH\$CAT1 for compatibility reasons.

Table 15. Category 1 transactions

Transactio	onProgram	CSD group	Security category	Description
CATA	DFHZATA	DFHSPI	1	Defines autoinstall automatic terminal
CATD	DFHZATD	DFHSPI	1	Deletes autoinstall terminal
CDBD	DFHDBDI	DFHDBCTL	1	DBCTL disable function
CDBF	DFHD2CM3	DFHDB2	1	CICS DB2 attachment facility shutdown force transaction
CDBO	DFHDBCT	DFHDBCTL	1	DBCTL control function
CDBQ	DFHD2CM2	DFHDB2	1	CICS DB2 attachment facility shutdown quiesce transaction
CDTS	DFHZATS	DFHSPI	1	Provides remote single delete transaction
CEPD	DFHEPDS	-	1	Event processing dispatcher
CEPM	DFHEPSY	-	1	Event processing queue manager
CESC*	DFHCESC	DFHSIGN	1	Processes timeout and signoff for idle terminals
CEX2	DFHD2EX2	DFHDB2	1	CICS DB2 protected thread purge mechanism and other CICS DB2 services.
CFCL	DFHFCDL	-	1	CFDT Load
CFOR	DFHFCQT	-	1	RLS offsite recovery
CFQR	DFHFCQT	-	1	RLS quiesce receive
CFQS	DFHFCQT	-	1	RLS quiesce send
CFTL	DFHDTLX	-	1	Shared DT load
CFTS	DFHZATS	DFHSPI	1	Provides remote mass flag transaction
CGRP	DFHZCGRP	-	1	Provides VTAM persistent sessions (See note)
CIOD	DFHIIOPA	DFHIIOP	1	Default IIOP interface, started by CIOR
CIOF	DFHIIOPA	DFHIIOP	1	CICS Generic factory, started by CIOR
CIOR	DFHIIOP	DFHIIOP	1	CICS IIOP interface, started by SO_Domain
CIRR	DFHIIRRS	DFHIIOP	1	Default CICS IIOP request receiver
CIS4	DFHISCIS4	DFHISCIP	1	IPIC External Security Interface (ESI) transaction
CISB	DFHISCOP	DFHISCIP	1	IPIC release IPCONN on the server side of a connection (BIS processing)
CISC	DFHISCOP	DFHISCIP	1	IPIC acquire IPCONN on the client side of a connection

| | | |

Chapter 10. Security for CICS-supplied transactions 145

TransactionProgram		CSD group	Security category	Description
CISD	DFHISCOP	DFHISCIP	1	IPIC release IPCONN on the client side of a connection
CISE	DFHISCIP	DFHISCIP	1	IPIC error and message program
CISM	DFHISRSP	DFHISCIP	1	IPIC remote scheduler
CISQ	DFHISLQP	DFHISCIP	1	IPIC local queue processing
CISR	DFHISRRP	DFHISCIP	1	IPIC request/response receiver
CISS	DFHISCOP	DFHISCIP	1	IPIC acquire IPCONN on the server side of a connection
CIST	DFHISCOP	DFHISCIP	1	IPIC terminate IPCONN
CISU	DFHISREU	DFHISCIP	1	IPIC recovery transaction
CISX	DFHISREX	DFHISCIP	1	IPCONN recovery and resynchronization transaction for XA clients
CITS	DFHZATS	DFHSPI	1	Provides remote autoinstall transaction
CJGC	DFHSJGC	DFHJAVA	1	CICS JVM garbage collection transaction
CJPI	DFHSJPI	DFHJAVA	1	Starts JVMs following a PERFORM JVMPOOL command
CJSR	DFHCJSR	DFHSTAND	1	CICS JVM server resolution transaction
CJTR	DFHOTR	DFHOTS	1	CORBA Object Transaction Services (OTS) resynchronization transaction
CMTS	DFHZATS	DFHSPI	1	Remote mass delete transaction
COVR	DFHZCOVR	-	1	Provides open VTAM retry transaction
CPIR	DFHPIITL	DFHSTAND	1	Pipeline resolution transaction
CPIS	DFHPIR	DFHPIPE	1	WS-AT transaction that is attached when resynchronization is required
CPLT	DFHSIPLT	-	1	Initializes PLT processing
CRLR	DFHRLR	DFHRL	1	Bundle resource resolution transaction
CRMD	DFHZATMD	DFHSPI	1	Provides remote mass delete transaction
CRMF	DFHZATMF	DFHSPI	1	Provides remote mass flag transaction
CRSQ	DFHCRQ	DFHISC	1	Remote schedule purging (ISC)
CRSY	DFHRMSY	DFHRMI	1	Resource manager resynchronization
CRTP	DFHZRTP	DFHPSSGN	1	Persistent sessions restart timer transaction

1

| |

TransactionProgram		CSD group	Security category	Description
CSFR	DFHFCRD	-	1	RLS cleanup
CSFU	DFHFCU	DFHOPCLS	1	File open utility
CSHA	-	-	1	Scheduler services (Autoinstalled by CICS)
CSHQ	DFHSHSY	-	1	Scheduler services domain long running task
CSKP	DFHAKP	DFHCOMP5	1	Writes system log activity keypoint
CSNC	DFHCRNP	DFHISC	1	Interregion control program (MRO)
CSNE	DFHZNAC	DFHVTAM	1	Provides VTAM node error recovery
CSOL	DFHSOL	-	1	TCP/IP listener (Autoinstalled by CICS)
CSPQ	DFHTPQ	DFHBMS	1	Terminal page cleanup (BMS)
CSQC	DFHLGQC	DFHLGQC	1	CICS quiesce after system log failure
CSSY	DFHAPATT	-	1	Provides entry point attach
CSTE	DFHTACP	DFHSTAND	1	Processes terminal abnormal conditions
CSTP	DFHZCSTP	-	1	Provides terminal control transaction
CSZI	DFHSZRMP	DFHFEPI	1	Front End Programming Interface (FEPI), only active if FEPI installed.
CTSD	DFHTSDQ	-	1	Temporary storage delete recoverable queue
CWBG	DFHWBGB	DFHWEB	1	CICS Web support cleanup transaction
CWXN	DFHWBXN	DFHWEB	1	CICS Web support attach transaction
CWXU	DFHWBXN	DFHWEB	1	CICS Web support USER protocol attach transaction
CXCU	DFHCXCU	DFHSTAND	1	Performs XRF tracing catchup
CXRE	DFHZXRE	DFHSTAND	1	Reconnects terminals following XRF takeover

Table 15. Category 1 transactions (continued)

# **Category 2 transactions**

L

I

|

I

Category 2 transactions are initiated by CICS users or are associated with CICS users; for example, a category 2 transaction can be started by an **EXEC CICS START** command that is initiated by a user running another transaction. Restrict authorizations to initiate these transactions to user IDs belonging to specific RACF groups.

For the CICS resource definitions, the IBM-supplied transactions are defined with the recommended RESSEC and CMDSEC options. In particular, CECI, CEDF, CEMT, CEST, and CIRP are all supplied with RESSEC(YES) and CMDSEC(YES). The mirror transactions are defined with RESSEC(YES). If you need to change any of these definitions, you can do so by copying them to another group. You are **not** recommended to change the supplied definitions of any other transactions.

For most category 2 transactions, you are recommended to specify the following to RACF:

- UACC(NONE) and AUDIT(FAILURES) in the transaction profile. AUDIT(FAILURES) is the default, and does not have to be specified.
- Access list as appropriate.

It is unlikely that all of your users require access to all the transactions in this category, so consider defining them in several subcategories. You can choose to group CICS transactions in the way that best suits your installations needs. The example that follows shows one way that you might group the category 2 transactions.

The sample CLIST DFH\$CAT2, in library CICSTS41.CICS.SDFHSAMP, can help you define the category 2 profiles to RACF. If you want to use this example, review and edit the CLIST for your installation before running it. If you want to use a different setup, you can adapt the CLIST, or provide your own. The sample groups the transactions into the following categories:

- SYSADM, containing CCRL, CDBC, CEDA, CEMN, CEMT, CESD, CETR, CIND, and CREA.
- DEVELOPER, containing CADP, CEBR, CECI, CECS, CEDB, CEDF, and CEDX.
- INQUIRE, containing CDBI, CEDC, CKBM, CKDL, CKDP, CKQC, CKRT, CLDM, and CREC.
- OPERATOR, containing CBAM, CEOT, CEST, CIDP, CKAM, CKBM, CKBP, CKCN, CKDL, CKDP, CKQC, CKRS, CKRT, CKSD, CMSG, CKSQ, CRTE, CKTI, CSFE, CWTO, and DSNC.
- DBCTL, containing CDBC, CDBI, CDBM, and CDBT.
- INTERCOM, containing CDFS, CEHP, CEHS, CPMI, CSHR, CSMI, CSM1, CSM2, CSM3, CSM5, CTIN, and CVMI.

If you are using function shipping, the mirror transactions must be available to remote users in a function shipping environment. When a database or file resides on another CICS region, CICS function ships the request to access the data. The request runs under one of the CICS-supplied mirror transactions. In this case, the following conditions apply:

- The terminal user running the application must be authorized to use the mirror transaction. (See Chapter 5, "Transaction security," on page 81.)
- The terminal user must also be authorized to use the data that the mirror transaction accesses. (See Chapter 6, "Resource security," on page 87.) The mirror transactions are supplied with RESSEC(YES) defined; so, even if the user's transaction specifies RESSEC(NO), the mirror transaction fails if the user is not authorized to access the data.

If you do not use resource security checking, change the mirror transaction definitions to specify RESSEC(NO). Because the mirror transactions are an IBM-protected resource, first copy these definitions into your own groups and then change them.

- IIOPUSER, containing CIRP.
- WEBUSER, containing CWBA and CW2A.

1

The CICS default user requires access to the CWBA transaction initially, even if an analyzer program is then used to assign another user ID to the task. Ensure that the CICS default user that is specified in the **DFLTUSER** system initialization parameter has access to this transaction. If you use the supplied CLIST DFH\$CAT2 to create a WEBUSER RACF profile, the default user must have access to this profile.

- RPCUSER, containing CRPA, CRPC, and CRPM.
- CMCIUSER, containing CWWU.

1

I

I

- PIPEUSER, containing CPIH, CPIL, CPIQ, and CPIA.
- EVENTUSER, containing CEPH, CEPQ, and CEPT.

CEPH, CEPQ and CEPT are the default EP adapter transaction IDs used when security checking is required. They are defined with RESSEC(YES) and CMDSEC(YES) options. When these options are not the ones you want, you must specify your own transaction IDs in the adapter tab **Advanced Options** section of the CICS event binding editor. For more information, see Specifying adapter and dispatcher information.

• ALLUSER, containing CMAC, CRTX, and CSGM.

Define the CICS messages and codes transaction CMAC, and the "good morning" transaction CSGM (or the transaction that is defined in the **GMTRAN** system initialization parameter) as UACC(READ) in a group of their own, because all users need access to them. If your installation uses CSGM, users who are not authorized to use CSGM receive message DFHAC2002 when they attempt to use CICS. Also include your "good night" transaction in this group, if you defined one with the **GNTRAN** system initialization parameter.

Figure 4 on page 150 shows how to use RDEFINE and PERMIT commands to define the example groups for category 2 transactions.

RDEFINE GCICSTRN INOUIRE UACC(NONE) ADDMEM(CDBI, CEDC, CKBM, CKDL, CKDP, CKQC, CKRT, CLDM, and CREC) NOTIFY(security admin userid) OWNER(userid or groupid) PERMIT SYSADM CLASS(GCICSTRN) ID(sysgrp1,..,sysgrpz) ACCESS(READ) RDEFINE GCICSTRN DEVELOPER UACC(NONE) ADDMEM(CADP, CEBR, CECI, CECS, CEDB, CEDF, CEDX) NOTIFY(security admin userid) OWNER(userid or groupid) DEVELOPER CLASS(GCICSTRN) ID(devgrp1,..,devgrpz) ACCESS(READ) PERMIT RDEFINE GCICSTRN INQUIRE UACC(NONE) ADDMEM(CDBI,CEDC,CKBM,CKDL,CKDP,CKQC,CKRT,CREC) NOTIFY(security admin userid) OWNER(userid or groupid) PERMIT INQUIRE CLASS(GCICSTRN) ID(inqgrp1,..,inqgrpz) ACCESS(READ) RDEFINE GCICSTRN OPERATOR UACC(NONE) ADDMEM(CBAM,CEOT,CEST,CIDP,CKAM,CKBM,CKBP,CKCN,CKDL,CKDP,CKQC,CKRS,+ CKRT,CKSD,CMSG,CKSQ,CRTE,CKTI,CSFE,CWTO,DSNC) NOTIFY(security_admin_userid) OWNER(userid or groupid) OPERATOR CLASS(GCICSTRN) ID(opsgrp1,..,opsgrpz) ACCESS(READ) PERMIT RDEFINE GCICSTRN DBCTL UACC(NONE) ADDMEM(CDBC,CDBI,CDBM,CDBT) NOTIFY(security admin userid) OWNER(userid or groupid) PERMIT DBCTL CLASS(GCICSTRN) ID(dbctgrp1,..,dbctgrpz) ACCESS(READ) RDEFINE GCICSTRN INTERCOM UACC(NONE) ADDMEM(CEHP,CEHS,CPMI,CSHR,CSMI,CSM1,CSM2,CSM3,CSM5,CVMI,CDFS,CTIN) NOTIFY(security admin userid) OWNER(userid or groupid) INTERCOM CLASS(GCICSTRN) ID(intrgrp1,..,intrgrpz) ACCESS(READ) PERMIT RDEFINE GCICSTRN ALLUSER UACC(READ) ADDMEM(CMAC, CRTX, CSGM) NOTIFY(security admin userid) OWNER(userid or groupid) PERMIT ALLUSER CLASS (GCICSTRN) ID(allrgrp1,..,allrgrpz) ACCESS(READ) RDEFINE GCICSTRN WEBUSER UACC(NON) ADDMEM(CWBA,CW2A) NOTIFY(security admin userid) OWNER (userid or groupid) PERMIT WEBUSER CLASS (GCICSTRN) ID(webrgrp1,..,webgrpz) ACCESS(READ) RDEFINE GCICSTRN RESTUSER UACC(NON) ADDMEM(CWWU) NOTIFY(security_admin_userid) OWNER(userid or groupid) PERMIT WEBUSER CLASS (GCICSTRN) ID(rstrgrp1,..,rstgrpz) ACCESS(READ) RDEFINE GCICSTRN RPCUSER UACC(NON) ADDMEM(CRPA, CRPC, CRPM) NOTIFY(security_admin_userid) OWNER(userid or groupid) PERMIT RPCUSER CLASS (GCICSTRN) ID(rpcrgrp1,..,rpcrgrpz) ACCESS(READ) RDEFINE GCICSTRN IIOPUSER UACC(NONE) ADDMEM(CIRP) NOTIFY(security_admin_userid) OWNER(userid or groupid) PERMIT IIOPUSER CLASS (GCICSTRN) ID(iiopgrp1,..,iiopgrpz) ACCESS(READ) RDEFINE GCICSTRN PIPEUSER UACC(NONE) ADDMEM(CPIH, CPIL, CPIQ, CPIA) NOTIFY(security_admin_userid) OWNER(userid or groupid) PERMIT PIPEUSER CLASS(GCICSTRN) ID(pipeline access list) RDEFINE GCICSTRN CMCIUSER UACC(NONE) ADDMEM(CWWU) NOTIFY(security_admin_userid) OWNER(userid or groupid) PERMIT CMCIUSER CLASS(GCICSTRN) ID(cmciuser access list) RDEFINE GCICSTRN EVENTUSER UACC(NONE) ADDMEM(CEPH, CEPQ, CEPT) CICS TS for z/OS 4.1: RACF Security Guide of groupid) PERMIT EVENTUSER CLASS(GCICSTRN) ID(eventuser access list)

1

150

#### Note:

- 1. With RESSEC(YES) and CMDSEC(YES) defined for these transactions, ensure that the user groups authorized to use the transactions are also authorized to access the CICS resources and commands that the transactions use.
- 2. If you protect a resource with a resource group profile, you must avoid protecting the same resource with another profile. If the profiles are different (for example, if they have different access lists), RACF merges the profiles for use during authorization checking. The merging can have a performance impact and it can be difficult to determine exactly which access authority applies to a particular user. See the *z*/OS Security Server RACF Security Administrator's Guide for further information.

Table 16. Category 2 transactions.

Transacti	onProgram	CSD group	Security category	Description
CADP*	DFHDPLU	DFHDP	2	Application debugging profile manager
CBAM*	DFHECBAM	DFHOPER	2	BTS objects browser
CCRL*	DFHSOCRL	DFHOPER	2	CICS certificate revocation list transaction
CDBC*	DFHDBME	DFHDBCTL	2	DBCTL interface menu transaction
CDBI*	DFHDBIQ	DFHDBCTL	2	DBCTL interface inquiry transaction
CDBM*	DFHDBMP	DFHDBCTL	2	DBCTL operator transaction
CDBT	DFHDBDSC	DFHDBCTL	2	DBCTL interface disconnection transaction
CDFS	DFHDFST	DFHISC	2	Dynamic starts with interval
CDST	DFHMIRS		2	CICS Dynamic routing of non-term starts
CEBR*	DFHEDFBR	DFHEDF	2	Browse temporary storage
CECI*	DFHECIP	DFHINTER	2	Command level interpreter
CECS*	DFHECSP	DFHINTER	2	Command level interpreter
CEDA*	DFHEDAP	DFHSPI	2	Resource definition online - full (RDO)
CEDB*	DFHEDAP	DFHSPI	2	Resource definition online - restricted (RDO)
CEDC*	DFHEDAP	DFHSPI	2	Views resource definition online (RDO)
CEDF*	DFHEDFP	DFHEDF	2	Execution diagnostic facility
CEDX*	DFHEDFP	DFHEDF	2	Execution diagnostic facility for non-terminal tasks
CEHP	DFHCHS	DFHISC	2	CICS OS/2 request handler
CEHS	DFHCHS	DFHISC	2	CICS/VM request handler
CEMN	DFHCEMNA	DFHOPER	2	CICS monitoring facility transaction

The transactions that have operator interfaces are marked by an asterisk (*). The remainder therefore have no operator interface.

#### Table 16. Category 2 transactions (continued).

The transactions that have operator interfaces are marked by an asterisk (*). The remainder therefore have no operator interface.

Transacti	onProgram	CSD group	Security category	Description
CEMT*	DFHEMTP	DFHOPER	2	Master terminal
CEOT*	DFHEOTP	DFHOPER	2	Terminal status
CEPH	DFHECEAH	DFHEP	2	HTTP EP adapter for event processing
CEPQ	DFHECEAM	-	2	WMQ adapter for event processing
CEPT	DFHECEAT	-	2	TSQ adapter for event processing
CESD	DFHCESD	DFHSDAP	2	Shutdown assist
CEST*	DFHESTP	DFHOPER	2	Supervisory terminal
CETR*	DFHCETRA	DFHOPER	2	Inquire and set trace options
CIDP*	DFHDPIN	DFHDP	2	Inactivate debugging profiles utility
CIND*	DFHINDT	DFHINDT	2	CICS indoubt testing tool
CIRP	DFHIIRP	DFHIIOP	2	Default CICS IIOP request processor transaction
CKAM	DFHMQMON	DFHMQ	2	CICS-MQ Adapter alert monitor
СКВМ	DFHMQBAS	DFHMQ	2	CICS-MQ Adapter base panel transaction
СКВР	CSQCBP00	DFHMQ	2	CICS-MQ Bridge DPL bridge task
CKCN	DFHMQQCN	DFHMQ	2	CICS-MQ Adapter start connection transaction
CKDL	DFHMQDSL	DFHMQ	2	CICS-MQ Adapter, display status transaction
CKDP	DFHMQDIS	DFHMQ	2	CICS-MQ Adapter, display transaction
CKRS	DFHMQRS	DFHMQ	2	CICS-MQ Adapter modify transaction
CKRT	DFHMQRET	DFHMQ	2	CICS-MQ Adapter screen return transaction
CKSD	DFHMQDSC	DFHMQ	2	CICS-MQ Adapter stop connection transaction
CKSQ	DFHMQSSQ	DFHMQ	2	CICS-MQ Adapter start/stop CKTI transaction
CKQC	DFHMQCTL	DFHMQ	2	CICS-MQ Adapter control transaction
CKTI	DFHMQTSK	DFHMQ	2	CICS-MQ Adapter - task initiator transaction
CLDM*	DFHLDMAP	DFHOPER	2	CICS load module map
CMAC	DFHCMAC		2	Messages utility

I

T

#### Table 16. Category 2 transactions (continued).

The transactions that have operator interfaces are marked by an asterisk (*). The remainder therefore have no operator interface.

TransactionProgram		CSD group	Security category	Description	
CMSG*	DFHMSP	DFHMSWIT	2	Message switching	
CPIA*	DFHPITE	DFHPIPE	2	Invokes CPIS from the terminal	
CPIH	DFHPIDSH	DFHPIPE	2	CICS pipeline HTTP inbound router	
CPIL	DFHPILSQ	DFHPIPE	2	SOAP WMQ inbound listener	
CPIQ	DFHPIDSQ	DFHPIPE	2	SOAP WMQ inbound router	
CPMI	DFHMIRS	DFHISC	2	CICS LU 6.2 synchronization level 1 mirror	
CREA*	DFHADDRM	DFHADST	2	Create REQUESTMODELs for enterprise beans	
CREC*	DFHADDRM	DFHADST	2	Create REQUESTMODELs for enterprise beans (read only)	
CRPA	DFHRPAS	DFHRPC	2	ONC/RPC Alias transaction	
CRPC	DFHRPC00	DFHRPC	2	ONC/RPC Update transaction	
CRPM	DFHRPHS	DFHRPC	2	ONC/RPC Server controller	
CRTE*	DFHRTE	DFHISC	2	Transaction routing	
CRTX	-	DFHISC	2	Dynamic transaction routing transaction definition	
CSFE*	DFHFEP	DFHFE	2	Terminal test, trace, storage	
CSGM	DFHGMM	DFHVTAM	2	"Good-morning" signon	
CSHR	DFHMIRS	DFHISC	2	Scheduler services remote routing	
CSM1	DFHMIRS	DFHISC	2	SYSMSG model	
CSM2	DFHMIRS	DFHISC	2	Scheduler model	
CSM3	DFHMIRS	DFHISC	2	Queue model	
CSM5	DFHMIRS	DFHISC	2	DL/I model	
CSMI	DFHMIRS	DFHISC	2	Mirror transaction	
CTIN	DFHZCT1	DFHCLNT	2	CICS Client	
CVMI	DFHMIRS	DFHISC	2	CICS LU6.2 synchronization level 1 mirror	
CWBA	DFHWBA	DFHWEB	2	CICS Web support alias transaction	
CWTO*	DFHCWTO	DFHCONS	2	Write to console operator	
CWWU	DFHWBA	DFHCURDI	2	Web support alias transaction for the CICS management client interface	
CW2A	DFHW2A	DFHWEB2	2	Atom feed alias transaction	
DSNC	DFHD2CM1	DFH\$DB2	2	DB2 attachment facility transaction	

| | |

L

# **Category 3 transactions**

Category 3 transactions are either initiated by the terminal user or associated with a terminal.

All CICS terminal users, whether they are signed on or not, require access to transactions in this category. For this reason, category 3 transactions are exempt from any security check, and CICS permits any terminal user to initiate these transactions.

For category 3 transactions you are recommended to specify RESSEC(NO) and CMDSEC(NO) on the CICS transaction resource definition. These transactions should be defined to RACF; although this definition does not affect task attach-time processing, it is required to support the QUERY SECURITY command.

Table 17. Category 3 transactions.

The transactions that have operator interfaces are marked by an asterisk (*). The remainder therefore have no operator interface.

Transacti	onProgram	CSD group	Security category	Description
CATR	DFHZATR	DFHSPI	3	Deletes autoinstall restart terminal
CCIN	DFHZCN1	DFHCLNT	3	CICS Client
CEGN	DFHCEGN	DFHSIGN	3	Schedules good night transaction
CEJR	DFHEJITL	DFHSTAND	3	Corbaserver resolution
CESF*	DFHSFP	DFHSIGN	3	Signs off terminal user
CESN*	DFHSNP	DFHSIGN	3	Signs on terminal user
CIEP	DFHIEP	DFHIPECI	3	ECI for TCP/IP listener
CLQ2	DFHLUP	DFHISCT	3	Outbound resynchronization for APPC and MRO
CLR1	DFHZLS1	DFHISCT	3	Inbound CNOS for APPC and MRO
CLR2	DFHLUP	DFHISCT	3	Inbound resynchronization for MRO
CLS1	DFHZLS1	DFHISC	3	Provides ISC LU services model
CLS2	DFHLUP	DFHISC	3	Provides ISC LU services model
CLS3	DFHCLS3	DFHISC	3	ISC LU services model
CLS4	DFHCLS4	DFHISC	3	Manages password expiry
СМРХ	DFHMXP	DFHISC	3	Ships ISC local queuing
СРСТ	DFHZPCT	DFHPSSGN	3	Catalog signed on terminals for persistent session signon retention
CPSS	DFHZSGN	DFHPSSGN	3	Persistent sessions signon
CQPI	DFHCLS5	DFHISC	3	Connection quiesce. Architected transaction (inbound).

#### Table 17. Category 3 transactions (continued).

The transactions that have operator interfaces are marked by an asterisk (*). The remainder	
therefore have no operator interface.	

Transacti	onProgram	CSD group	Security category	Description
CQPO	DFHCLS5	DFHISC	3	Connection quiesce. Architected transaction (outbound).
CQRY	DFHQRY	DFHSTAND	3	Provides ATI query support
CRSR	DFHCRS	DFHISC	3	Provides ISC remote scheduler
CSAC	DFHACP	DFHSTAND	3	Provides program abnormal condition
CSCY	DFHCPY	DFHVTAMP	3	Provides 3270 screen print
CSPG*	DFHTPR	DFHBMS	3	Provides BMS terminal paging
CSPK	DFHPRK	DFHVTAMP	3	Provides 3270 screen print support
CSPP	DFHP3270	DFHHARDC	3	Provides 3270 print support
CSPS	DFHTPS	DFHBMS	3	Schedules BMS terminal paging
CSRK	DFHRKB	DFHVTAMP	3	Provides 3270 screen print - release keyboard
CSRS	DFHZRSP	DFHRSEND	3	Synchronizes 3614 message
CSSF	DFHRTC	DFHISC	3	Cancels CRTE transaction routing session
CXRT	DFHCRT	DFHISC	3	Provides Transaction routing relay

# Part 3. Intercommunication security

These topics tell you how to plan and implement security in an intersystem communication (ISC) environment using LU6.2 or LU6.1, in a multiregion operation (MRO) environment, and in an IP interconnectivity (IPIC) environment.

# Chapter 11. Overview of intercommunication security

This topic gives an overview of how security works when CICS systems are interconnected or connected to other compatible systems.

## Introduction to intercommunication security

In a single CICS system, you use security to make sure that terminal users can access only those parts of the system they need to work with.

For interconnected systems, the same basic principles apply, but now you also include definitions for connections, sessions, and partners. You also need to allow for the fact that users of one CICS system can initiate transactions and access resources in another CICS system.

This topic assumes that you are already familiar with setting up security for a single CICS system.

In particular, you should understand the following concepts:

- User signon. (See "The sign-on process" on page 63.)
- How the relationship between user security and transaction security determines which transactions a particular user is allowed to invoke. (See Chapter 4, "Verifying CICS users," on page 63 and Chapter 5, "Transaction security," on page 81.)
- How resource security determines which other resources a user is allowed to access. (See Chapter 6, "Resource security," on page 87.)

An interconnected group of CICS systems differs from a single CICS system in that you may have to define a user profile or group profile more than once. (See "RACF user profiles" on page 14 and "RACF group profiles" on page 19 for information on defining these profiles.) That is, you may have to define these profiles in each CICS system that is using a separate RACF database, and in which a user is likely to want to attach a transaction or access a resource. When planning these profiles, you must consider all cases in which a user could initiate function shipping, transaction routing, asynchronous processing, distributed program link, distributed transaction processing, or external call interface (EXCI). (For descriptions of these methods of intercommunication, see the *CICS Intercommunication Guide* and the *CICS Distributed Transaction Programming Guide*.)

# Planning for intercommunication security

Intercommunication security in a CICS system is concerned with incoming requests for access to CICS resources, rather than with requests that are sent to other systems.

The security issue with incoming requests occurs when a particular user at a particular remote system is trying to access resources of your CICS system. Is this access authorized, or should it be rejected?

The following sections describe the points in the processing of an incoming request at which you can apply security checks.

# Intercommunication bind-time security

The first requirement is for a session to be established between the two systems. This does not, of course, happen on every request; a session, once established, is usually long-lived. Also, the connection request that establishes the session can, depending on the circumstances, be issued either by the remote system or by your CICS system. However, the establishment of a session presents the first potential security exposure for your system.

Your security concern is to prevent unauthorized remote systems from being connected to your CICS system; that is, to ensure that the remote system is really the system that it claims to be. This level of security is called **bind-time security**. (For ISC over SNA connections, it is also known as **systems network architecture (SNA) session security**.) It can be applied when a request to establish a session is received from, or sent to, a remote system.

Note: We use the term **bind** to refer to all of the following:

- The **SNA BIND** command that is used to establish SNA sessions between systems
- The **CICS connection request** that is used to establish an IPIC connection between systems
- The CICS connection request that is used to establish MRO sessions for CICS interregion communication

You can specify bind-time security for APPC (LU6.2), IPIC , and multiregion operation (MRO) links, but **not** for LU6.1 links. For information on defining bind-time security in your system, see "Bind-time security with LU6.2" on page 163, "IPIC bind-time security" on page 211, or "Bind-time security with MRO" on page 219, depending on the environment you are using.

# Intercommunication link security

Each link between systems is given an authority defined by a userid.

It is important to note that users cannot access any transactions or resources over a link that is itself unauthorized to access them. This means that each user's authorization is a subset of the link's authority as a whole.

To limit the remote system's access to your transactions and resources, you use **link security**. Link security is concerned with the single user profile that you assign to the remote system as a whole. Like user security in a single-system environment, link security governs:

- **Transaction security**. This controls the link's authority to attach specific transactions.
- **Resource security**. This controls the link's authority to access specific resources. This applies for transactions, executing on any of the sessions from the remote system, that have RESSEC(YES) specified in their transaction definition.
- **Command security**. This controls the link's authority for the commands that the attached transaction issues. This applies for transactions, executing on any of the sessions from the remote system, that have CMDSEC(YES) specified in their transaction definition.
- **Surrogate user security**. This controls the link's authority to START transactions with a new userid, and to install resources with an associated userid.

For more information, see "Transaction, resource, command, and surrogate user security for intercommunication."

## User security for intercommunication

In addition to the security profile that you set up for the link, you can further restrict each remote user's access to the transactions, commands, and resources in your system.

For ISC over SNA and MRO links, specify the ATTACHSEC parameter on the CONNECTION definition. For IPIC links, specify the USERAUTH parameter on the IPCONN resource definition.

User security, like link security, distinguishes between transaction, resource, command, and surrogate security. User security can never increase a user's authority above that of the link. For more information, see "Transaction, resource, command, and surrogate user security for intercommunication."

For information on defining user security in your system, see "User security with LU6.2" on page 168, "IPIC user security" on page 213, or "User security with MRO" on page 223, depending on the environment you are using.

You cannot specify user security for LU6.1 links. For LU6.1, the user security is taken to be the same as the link security.

# Transaction, resource, command, and surrogate user security for intercommunication

The last step in defining security for your system is to make sure that the access parameters match the profiles you have defined for your transactions, resources, commands, and surrogate users for the link and the individual remote users.

For information on defining these levels of security in a single-system environment, see Chapter 5, "Transaction security," on page 81, Chapter 6, "Resource security," on page 87, and Chapter 8, "CICS command security," on page 121.

Resources and commands are unsecured unless you explicitly request security protection in your transaction definitions.

For information on defining transaction and resource security in your system, see one of the following, depending on the environment you are using:

- "Transaction, resource, and command security with LU6.2" on page 175
- "Transaction, resource, and command security with LU6.1" on page 206
- "IPIC transaction, resource, and command security" on page 215
- "Transaction, resource, and command security with MRO" on page 226

# Summary of intercommunication security levels

Table 18 on page 162 shows bind-time, transaction, resource, and command security, and how CICS enforces these levels of security under the LU6.1, LU6.2, IPIC, and MRO protocols. It also shows how the two levels of authorization (user and link) are involved at the three security levels.

For guidance on choosing between these environments, see the CICS *Intercommunication Guide*.

#### Table 18 shows a summary of intercommunication security.

Table 18. Summary of intersystem and interregion security

Security level	Security checks	LU type 6.1	LU type 6.2	IPIC	MRO
Bind-time security (when BIND is received)	Should the BIND request be accepted?	No check	Session key from RACF	SSL Client Certificate from partner	DFHAPPL profiles in RACF FACILITY class
Bind-time security (when BIND is sent)	Is the remote system the correct one?	No check	Session key from RACF	SSL Client Certificate to partner	DFHAPPL profiles in RACF FACILITY class
Link security	Does the link have authority to attach the transaction?	Link authority is established just after the session is bound, by signon of the user ID specified in the SECURITYNAME attribute of the CONNECTION definition or the USERID attribute of the SESSIONS definition.		Link authority is established just after the connection is established, by signon of a user ID determined according to the IPCONN LINKAUTH attribute.	Link authority is established just after the session is bound, by signon of the user ID specified in the USERID attribute of the SESSIONS definition.
Transaction security	Does the remote user have authority to access this system?	No check	The authority of th time	e remote user is est	ablished at signon
Transaction security	Does the remote user have authority to attach the transaction?	Link authority	The authority of the remote user is established at this attach request (or possibly at an earlier attach request from the same user) by sign-on		
Resource, command, and surrogate security	Does the session have the authority to access other resources that the transaction uses?	Link authority is established just after the session is bound, by signon of the user ID specified in the SECURITYNAME attribute of the CONNECTION definition or the USERID attribute of the SESSIONS definition.		Link authority is established just after the connection is established, by signon of a user ID determined according to the IPCONN LINKAUTH attribute.	Link authority is established just after the session is bound, by signon of the user ID specified in the USERID attribute of the SESSIONS definition.
Resource, command, and surrogate security	Does the remote user have authority to access other resources that the transaction uses?	Link authority		e remote user is est possibly at an earlier r) by sign-on	

**Note:** Remember to define profiles for your resources and users to RACF, as described for single systems in Chapter 2, "RACF facilities," on page 11.

# Chapter 12. Implementing LU6.2 security

This topic tells you how to implement security for LU6.2.

# Bind-time security with LU6.2

A security check can be applied when a request to establish an APPC session is received from, or sent to, a remote system; that is, when the session is bound. This is called bind-time security (or, in SNA terms, session security), and is part of the CICS implementation of the LU6.2 architecture.

Its purpose is to prevent an unauthorized system from binding a session to one of your CICS systems.

Bind-time security is optional in the LU6.2 architecture; you should not specify bind-time security if the remote system does not support it. SNA defines how session security is to be applied, and CICS TS conforms to this architecture. If you want to connect to another system, make sure the other system is also compatible with this architecture.

When you define an LU6.2 connection to a remote system, you assume that all inbound bind requests originate in that remote system, and that all outbound bind requests are routed to the same system. However, where there is a possibility that a transmission line might be switched or broken into, guard against unauthorized session binds by specifying session security at both ends of the connection.

For a bind request to succeed, both ends must hold the same session key, which is defined to RACF. When a session is bound, the action CICS takes depends on:

- How you specified the SEC and XAPPC system initialization parameters
- How you specified the BINDSECURITY attribute of the CONNECTION definition
- Whether you have defined an APPCLU security profile for the link.

If you have specified SEC=YES and XAPPC=YES in your SIT, and BINDSECURITY(YES) in your CSD connection definition, and BINDSECURITY(YES) is also specified for the partner system, a bind security validation will be attempted.

If you have BINDSECURITY(NO), then the SIT specification is immaterial.

Table 19 summarizes what happens.

SEC value	XAPPC value	BINDSECURITY value	RACF APPCLU profile	Resulting CICS action
YES	YES	YES	Defined (See note 1)	CICS extracts the APPCLU profile from RACF at bind-time to verify the remote system.

Table 19. APPC bind-time security—relationship to resource definition

SEC value	XAPPC value	BINDSECURITY value	RACF APPCLU profile	Resulting CICS action
YES	YES	YES	Not defined	CICS is unable to extract the APPCLU profile from RACF and therefore rejects the bind.
YES	YES	NO	Any value	CICS is unable to validate the bind, and rejects it.
YES	NO	Any value	Any value	CICS is unable to validate the bind, and rejects it.
NO	Any value	Any value	Any value	CICS is unable to validate the bind, and rejects it.

#### Note:

- 1. If the RACF APPCLU profile is defined, but the session segment is locked or expired, and no value is specified for SESSKEY, the bind request is always rejected.
- 2. The table shows the response when the partner has specified BINDSECURITY(YES).

# Defining profiles in the APPCLU general resource class

If you use bind-time security with LU6.2, you must define profiles in the APPCLU general resource class: the APPCLU resource class is used to verify the identity of APPC partner logical units (LU type 6.2) during VTAM session establishment.

To do this, take the following steps:

- 1. Ask your VTAM system programmer for the following information for each session partner:
  - The network ID and the LU identifiers.
- **2**. For each pair of session partners, create two profiles in the APPCLU general resource class.

On one system, enter the following RDEFINE command:

```
RDEFINE APPCLU netid1.luid1.luid2 UACC(NONE)
        SESSION(SESSKEY(password))
```

On the other system, enter the following RDEFINE command:

where:

netid1

#### netid2

are the network IDs (NETID) of the partners. These IDs are specified on the VTAM start option NETID, which is in the ATCSTRxx member of SYS1.VTAMLST.

#### luid1

#### luid2

are the LU names of the partners. In each case, the first LU name specified is the local LU name and the second is the remote LU name.

#### session-key

is the 16-hexadecimal-digit or 8-character password that matches the session key of the remote system. Enclose hexadecimal digits in quotes; for example, SESSKEY(X'0123456789ABCDEF').

You should specify the same session key in both systems: if the session keys do not match, the session cannot be established.

Although RACF does not require that you specify a session key, CICS will reject the bind if no session key is specified.

3. Define the attributes of the sessions between the partners of each LU pair. To do this, define a SESSION segment for each APPCLU profile using the SESSION option of the RDEFINE and RALTER commands. You can specify the following information in each SESSION segment:

#### CONVSEC

Specifies the levels of security checking performed for each conversation between the partners of the LU pair. CICS does not use this information; instead it uses the information specified in the ATTACHSEC operand of the CONNECTION resource. For more information see the *CICS Resource Definition Guide*.

#### INTERVAL

Specifies the maximum number of days the session key is valid before it must be changed.

You should be aware of the impact this may have on the users at the remote end of the link. If either password expires, the link cannot be established. Depending upon the auditing of the profile records, ICH415I messages may or may not be written out. See "Specifying bind-time security for LU6.2." (CICS issues message DFHZC4942 to the CSNE destination when the password has expired.) Ensure that you are aware when a password interval is about to expire so that links do not fail for this reason. CICS does not display messages when the password is about to expire, but it does write records to the SMF log.

#### LOCK

Marks the profile as locked. If the profile is locked, the session does not bind, and CICS issues message DFHZC4941.

#### NOLOCK

Marks the profile as unlocked.

For more information about controlling on controlling VTAM LU6.2 binds, see the *z/OS Security Server RACF Security Administrator's Guide*.

# Specifying bind-time security for LU6.2

You define bind-time security in the CONNECTION resource definition, although you must also choose the appropriate system initialization parameters.

Figure 5 on page 166 shows how to define APPC external session security, for which you need to specify the BINDSECURITY option.

```
CEDA DEFINE CONNECTION(name)
GROUP(groupname)
ACCESSMETHOD(VTAM)
SECURITYNAME(name)
PROTOCOL(APPC)
NETNAME(name)
BINDSECURITY(YES)
```

Figure 5. Bind-time security

**Note:** For APPC terminals defined as a TERMINAL-TYPETERM pair, the BINDSECURITY operand is on the TERMINAL definition.

# Auditing bind-time security

If security is active (SEC=YES is specified in the system initialization parameters), CICS performs bind security auditing.

The following conditions are considered bind failures, and cause RACF to write an SMF record, and to issue a message:

- · Session key does not match partner's.
- Session segment is locked.
- Session segment has expired.
- Session key is null.
- Session segment does not exist.
- · Session segment retrieval was unsuccessful.
- Session bind was unsuccessful.

The following conditions are considered bind successes, and cause RACF to write an SMF record, but **not** to issue a message:

- Session was successfully bound.
- Session key will expire in less than six days.

An SMF record is written if either of the following is true:

- The profile's audit option is set (AUDIT(ALL(READ))).
- SETROPTS LOGOPTIONS(ALWAYS(APPCLU)) is set.

Two things happen when an SMF audit record is written:

- Message ICH700051 is sent to the userid specified in the profile's notify option. It is suggested that you specify the TSO userid of a RACF administrator who is responsible for the APPCLU class.
- The security console (any MVS console with a routing code of 9) receives message ICH415I, which contains text similar to message ICH70005I.

These audit records can be extracted from SMF and listed using the following sample RACF Report Writer control statements:

```
//RACFRW EXEC PGM=IKJEFT01
//SORTWKxx DD your sort files
//SYSPRINT DD SYSOUT=*
//SYSTPRT DD SYSOUT=*
//RSMFIN DD DSN=your smf dumped data, DISP=SHR
//SYSTIN DD *
RACFRW TITLE('Bind Security Reports') GENSUM
SELECT PROCESS
```

EVENT APPCLU

LIST SORT(DATE,TIME) END

//

The RACF Report Writer is described in the *z*/OS Security Server RACF Auditor's Guide.

### Changing RACF profiles that are in use—caution

Take care when changing RACF profiles for APPC connections that are in use.

CICS recognizes the change in the profile after a SETROPTS RACLIST(APPCLU) REFRESH command is issued. Bind-time security processing occurs when each session in a connection is acquired. Not all the sessions in a connection are acquired and the APPC profile becomes invalid, then an attempt to establish any of the unacquired sessions causes a bind security failure. This can cause transactions that attempt to allocate one of these unused sessions to be suspended indefinitely.

#### **Reasons for invalid profiles**

An APPC profile can become invalid for a number of reasons; for example:

- The session key expires
- The session key changes and a SETROPS REFRESH takes place in one system without the corresponding change and refresh occurring in the other system
- The profile is locked while REFRESH takes place.

Sessions that are already acquired still continue to function normally if bind security fails in another session. If you are using expiring session keys, then the connection can still be used after the expiry date, if any of the sessions on the connection were acquired before the date of expiration, and have remained acquired. Hence, you see the effect of an expiring session key only when the connection (or session) is acquired.

No warning messages are produced stating that the session key is about to expire. However, an SMF record can be written when a key is used that will expire shortly. Therefore, you can use the RACF Report Writer regularly to find out which keys need maintenance. Otherwise, if expiring session keys are used, you must remember when the keys are due to expire. You must also take appropriate action to minimize any disruption that may occur because the connection is unavailable because of an expired session key. For example, you should plan for the changing of the session keys, for security rebuilds (for both CICS systems) and for the possibility of having to reacquire the connection.

You can avoid the problem of APPC profiles becoming invalid while the connection is in use by specifying AUTOCONNECT(YES) or AUTOCONNECT(ALL) on the SESSIONS definition. This causes all sessions to be established (acquired) when the connection is acquired.

### Link security with LU6.2

Link security further restricts the resources a user can access, depending on the remote system from which they are accessed.

The practical effect of link security is to prevent a remote user from attaching a transaction or accessing a resource for which the link userid has no authority.

When link security is in use, each session is given an authority defined by a *link userid*. For LU6.2, all sessions in a connection can have the same link userid, or different groups of sessions within the connection can have different link userids. You can also specify that some groups of sessions should use link security, and that others should not.

You can never transaction route or function ship to CICS without having at least one security check, but the security checks are minimized if the link userid matches the local region userid:

- If the userids match, only one security check is made. This will either be against the default user (for ATTACHSEC=LOCAL) or against the userid that is in the received FMH-5 attach request (ATTACHSEC=non-LOCAL).
- If the userids do not match, then for ATTACHSEC=LOCAL, resource checks are done only against the link userid. For ATTACHSEC=non-LOCAL there are always two resource checks. One is against the link userid, and the second is against the userid received from the remote user in the attach request.

If a failure occurs in establishing link security, the link is given the security of the local region's default user. This would happen, for example, if the preset session userid had been revoked.

# Specifying link security for LU6.2 connections

### About this task

You specify link security on the CONNECTION or SESSIONS resource definitions. If you require more information about either of these resources, see the *CICS Resource Definition Guide*.

### Procedure

- To specify that all sessions of a connection should have the same link userid, specify the SECURITYNAME attribute of the CONNECTION resource definition. If you do not specify a value for this attribute, CICS uses the default user ID.
- To specify different link user ids for individual groups of sessions within a connection, specify the USERID attribute of the SESSION resource definition. For each group of sessions, the value specified overrides the SECURITYNAME attribute of the CONNECTION definition.

# User security with LU6.2

User security causes a second check to be made against a user signed onto a terminal, in addition to the link security described in "Link security with LU6.2" on page 167. After reading the following descriptions, consider whether you want the extra level of security checking that user security provides.

You can specify the following levels of user security using the ATTACHSEC parameter of the CONNECTION definition:

• *LOCAL*, which you specify if you do **not** want to make a further check on users by requiring a user identifier or password to be sent. Choose LOCAL if you do not want user security because you consider that the authority of the link is sufficient for your system. See "Specifying user security in link definitions" on page 170 for information on doing so.

- *Non-LOCAL*, which you specify if you *do* want to make a further check on users by requiring a user identifier, or a user identifier and a password, to be sent. Non-LOCAL includes the following types of checking:
  - IDENTIFY
    - A user identifier must be sent, but no password is requested
  - VERIFY

A password must also always be sent

PERSISTENT VERIFICATION

Password is sent on the first attach request for a user

– MIXIDPE

Either identify or persistent verification

**Note:** "Non-LOCAL user security verification" further describes these types of user checking checking. See "Specifying user security in link definitions" on page 170 for information on specifying them.

### Non-LOCAL user security verification

In a CICS-to-CICS system connection, where you have a terminal-owning region (TOR), an application-owning region (AOR), and a data-owning region (DOR), the terminal operator signs on to the TOR, attaches a transaction in the AOR, and accesses resources in the DOR. If all three systems implement non-local user security, then the same operator is registered as a user in each of them. The usual procedure is for the operator to sign on to the TOR with a password. CICS assumes that the password is valid for the entire systems complex, and that it does not need to be passed on to the AOR and the DOR for further verification. All that is needed is for the AOR and the DOR to IDENTIFY the user, who is then signed on without a password. Therefore, the password is not sent with the attach request to the AOR. This is considered to be more secure, because the password is not passed on a network.

Specify IDENTIFY when you know that CICS can trust the remote system to verify its users (by some sort of sign-on mechanism) before letting them use the link. Use IDENTIFY if you want user security for CICS-to-CICS communication (CICS does not support password flows on CICS-to-CICS connection).

Note: This excludes CICS Transaction Server for OS/2.

If the front end does not have a security manager it may not be possible to VERIFY the user by means of a user identifier and password before the attach request reaches the AOR. The AOR must then receive both user identifier and password from the front end so that it can verify the user itself by a sign-on with password.

Specify VERIFY if you have reasons for wanting your own system to verify the remote system's users even if they have already been checked by the remote system itself, or if the remote system does not have a security manager and therefore cannot verify its own users. VERIFY must be used if the request comes from CICS for OS/2, which does not support PERSISTENT.

If programmable workstations make repeated requests to attach transactions in the AOR, performance suffers because of many verifications. The LU6.2 architecture, which defines these security procedures, allows persistent verification to reduce the software overhead. Using this protocol, the first attach request contains a user

identifier and a password, but once the user has signed on, only the user identifier is needed for all the attach requests that follow.

Specify PERSISTENT to reduce the verification overhead if remote users repeatedly send attach requests. However, the remote system must be able to cooperate in the management of persistent verification by keeping a list of users who are currently signed on.

Some remote APPC systems have mixed sign-on requirements that vary from conversation to conversation (for example, CPI communications conversations). In this case, CICS must accept incoming identify or persistent requests.

To decide which of these types of user verification to use, you need to know how far the remote system is capable of managing its own security and, if it cannot, to what extent it must depend on the CICS system you are defining.

- Do you need to know the user identifier? If not, use LOCAL.
- Can the remote system verify its own users? If so, use IDENTIFY. If not, can it send a user identifier and a password with the attach request? If so, use VERIFY.
- Does the remote system support persistent verification by keeping track of its user identifiers and passwords? If so, specify PERSISTENT, unless you are using CICS-to-CICS communications, in which case specify MIXIDPE.

You specify these levels of checking for each connection using the ATTACHSEC operand of the CONNECTION definition, as described in "Specifying user security in link definitions."

### Specifying user security in link definitions

The level of user security you require for a remote system is specified in the ATTACHSEC operand in the CONNECTION definition, as shown in Figure 6.

This topic describes how CICS interprets the parameters of the ATTACHSEC operand of the CONNECTION definition. However, special rules apply for CICS transaction routing, as described in "Transaction routing security with LU6.2" on page 176. Figure 6 shows an example of defining ATTACHSEC using CEDA.

```
CEDA DEFINE CONNECTION(name)
GROUP(groupname)
ATTACHSEC(LOCAL|IDENTIFY|VERIFY|PERSISTENT|MIXIDPE)
```

Figure 6. Defining sign-on level for user security

**Note:** For APPC terminals defined as a TERMINAL-TYPETERM pair, the ATTACHSEC operand is on the TERMINAL definition.

The ATTACHSEC operand specifies the sign-on requirements for incoming transaction attach requests. It has no effect on attach requests that are issued by your system to a remote system; these are dealt with in the remote system.

When an APPC session is bound, each side tells the other the level of attach security user verification that will be performed on its incoming requests. There is no negotiation on this.

### Meanings of ATTACHSEC operand

The following are the possible operands of ATTACHSEC:

#### LOCAL

specifies that a user identifier is not to be supplied by the remote system. If one is received, the attach fails. CICS makes the user security profile equivalent to the link security profile. You do not need to specify RACF profiles for the remote users. LOCAL is the default value.

#### IDENTIFY

specifies that a user identifier is expected on every attach request. All remote users of a system must be identified to RACF.

If an attach request with both a user identifier and a password is received on a link with ATTACHSEC(IDENTIFY), CICS does not reject the attach request. CICS handles the attach request as if the connection was defined with ATTACHSEC(VERIFY).

If a null (X'00') user identifier or an unknown user identifier is received, CICS rejects the attach request.

#### VERIFY

specifies that, in addition to a user identifier, a user password is required for verification against the local RACF database. All remote users of a system must be identified to RACF.

The rules that apply to the checking of the user identifier for ATTACHSEC(IDENTIFY) also apply for ATTACHSEC(VERIFY). If a valid user identifier is received but the password verification fails, CICS rejects the attach request. If the communicating system is CICS for AIX, ATTACHSEC=IDENTIFY should be used.

**Note:** Products other than CICS can connect to a CICS Transaction Server for z/OS AOR via an LU6.2 link. They then use the SNA LU6.2 FMH-5 ATTACH mechanism to start a transaction on the CICS AOR. Where this mechanism is being used from an insecure system, the ATTACHSEC=VERIFY option should be used on the connection definition to protect the transaction on the AOR. (See "SNA profiles and attach-time security" on page 174.

#### PERSISTENT

specifies that a user identifier and a user password are required with the first attach request for a new user, but all following attach requests for the same user need supply only a user identifier. (All remote users of a system must be identified to RACF.) The first attach signs on the user, even if the attach request is later unsuccessful because the user is not authorized to attach the transaction.

Note: PERSISTENT cannot be used for CICS-to-CICS communication.

#### MIXIDPE

specifies that the sign-on level for the remote user is determined by parameters sent with the attach request. The possibilities are: PERSISTENT or IDENTIFY.

#### Remote user sign-on status with LU6.2

With the ATTACHSEC parameters, IDENTIFY, MIXIDPE, PERSISTENT, and VERIFY, the remote user remains signed on after the conversation associated with the first attach request is complete.

CICS then accepts attach requests from the same user without a new sign-on until one of the following events occurs:

- The period specified in the system initialization parameter, **USRDELAY**, elapses after completion of the last transaction associated with the attach request for this user.
- From z/OS 1.11 onwards, CICS is notified of certain changes in the RACF profile of a signed-on remote user or a signed-on user who is not directly using a physical terminal or console through a type 71 RACF Event Notification (ENF). For example, CICS is notified when you use the REVOKE option on the **ALTUSER** command, with no date specified, to revoke a user ID with immediate effect. However, CICS is not notified when a user ID expires. When a RACF profile change occurs and CICS receives a new attach request for a user ID, CICS performs an implicit sign-on for the user ID and the new RACF profile information is used. Existing tasks for that user continue with the RACF profile that was valid when the task was attached.
- The CICS region shuts down.

T

L

T

T

1

1

|

1

If you alter the RACF profile of a signed-on remote user, CICS continues to use the authorization established at the first attach request until one of the following situations occurs:

- The transaction performs a sync point.
- You are using a z/OS 1.11 system or above and the attach request ends.
- You are using a system earlier than z/OS 1.11 and the user ID is unused for the time specified in the **USRDELAY** system initialization parameter.

#### **Password checking**

If you are using ATTACHSEC(PERSISTENT) (or ATTACHSEC(MIXIDPE) being treated as ATTACHSEC(PERSISTENT)), CICS maintains a table for each remote system called the **persistent verification (PV) signed-on-from list**.

This is a list of users whose passwords have been checked and who do not require a further password check as long as the entry remains in the list. Entries remain in the list until:

• The period specified in the system initialization parameter PVDELAY elapses after the user's sign-on entry was last used.

PVDELAY defines how long entries can remain in the PV signed-on-from list for the remote system, which means that their passwords do not need to be revalidated for each attach request. For information on specifying a value for PVDELAY, see the *CICS System Definition Guide*. See the *CICS Performance Guide* for information on tuning.

• The connection with this system is terminated because: CICS is restarted, the connection is lost, or CICS receives an invalid attach request from the user.

When persistent verification is in operation for a remote user, and that user is removed from the PV signed-on-from list, CICS informs the remote system by issuing a sign-off request for the user to remove the entry from the PV signed-on-to list in the remote system.

If you specify ATTACHSEC(VERIFY), the remote user's password is checked for *every attach request*. This is to ensure that the user has authority to access this system, to verify that this password is correct, and to establish security authorities for the user.

### Information about remote users

Information about the user can be transmitted with the attach request from the remote system.

This means that you can protect your resources not only on the basis of which remote system is making the request, but also on the basis of which user at the remote system is making the request.

This topic describes some of the concepts associated with remote-user security, and how CICS sends and receives user information.

You have to define your users to RACF. If a remote user is not defined to RACF, any attach requests from that remote user are rejected.

CICS remote-user security for LU6.2 links implements the LU6.2 architecture. The LU6.2 architecture allows user identifiers, user passwords, and user profiles to be transmitted with requests to attach a transaction.

User profiles can be transmitted instead of, or in addition to, user identifiers. The profile name, if supplied, is treated as the groupid.

If the user has been added to the front-end system with a group ID explicitly specified; for example in EXEC CICS SIGNON or by filling in the GROUPID parameter on the CESN panel, this will be propagated by CICS in outbound attach FMHs for LU6.2 links where ATTACHSEC(IDENTIFY) has been specified in the CONNECTION definition. If the group ID has been allowed to default at the time the user was originally added to the front-end system, the profile field will not be included in the outbound FMH5. If the group ID is passed to the back-end system, the group ID will be used as part of ADD_USER processing on the back-end. That is, the user ID must be defined as a member of the group passed in the ESM on the back-end for the ADD_USER to be successful.

It is advisable to use the PLTPIUSR system initialization parameter if there is a possibility that a task started by PLTPI processing will access remote resources. This avoids problems in the remote region where the user ID is not in the same group as the user in the local region. This is because the PLTPI user in the local region is not added with an explicit groupid, and as a result the groupid is not propagated to the remote region.

CICS sends userids on ATTACHSEC(IDENTIFY) conversations. Table 20 shows how CICS decides which userid to send.

Characteristics of the local task	User identifier sent by CICS to the remote system
Task with associated terminal—user identifier	Terminal user identifier
Task with associated terminal—no user signed on and no USERID specified in the terminal definition	Default user identifier for the local system
Task with no associated terminal or USERID started by interval control START command (if using function shipping or distributed transaction processing (DTP))	User identifier for the task that issued the START command
Task started with USERID option	User identifier specified on the START command
CICS internal system task	CICS region userid

Table 20. Attach-time user identifiers—LU6.2

Table 20. Attach-time user identifiers—LU6.2 (continued)

Characteristics of the local task	User identifier sent by CICS to the remote system
Task with no associated terminal started by transient data trigger	User identifier specified on the transient data destination definition that defines the queue
Task with associated terminal started by transient data trigger	Terminal user identifier
Task started from PLTPI	PLTPIUSR

Signing on the remote user has two purposes:

- To ensure that the remote user is allowed to access the CICS system
- If the sign-on is successful, to establish the authority for the remote user

CICS signs off the remote user under the circumstances described in "Remote user sign-on status with LU6.2" on page 171.

### SNA profiles and attach-time security

Implementation of the LU6.2 attach-time security in CICSTS41.CICS conforms strictly to the architecture.

In particular, note the following:

- The introduction of SNA profile support and the conformance to SNA attach-time security processing might cause upgrade problems.
- Profile support means that badly coded profiles sent in an attach FMH-5 cause certain attach requests to be rejected.
- The checks to prevent problems in the access security subfields of an FMH-5 are:
   Check for unrecognized subfield
  - Check for invalid length subfield
  - Check for multiple subfields of the same type
- The full 10-character userid and password are accepted. Any trailing blanks ((X'40') are removed before being passed to the security manager, which either rejects the attach request, or converts the userid and password into 8- character form before proceeding.
- If an attach request does not contain security parameters in the FMH-5, it is rejected, unless USEDFLTUSER(YES) has been specified on the CONNECTION resource definition. In that case, the security capabilities of the default user apply.
- Valid SNA profiles received are treated as the ESM groupid with which the userid in the FMH-5 will be associated after the userid in the FMH-5 is signed on.
- When a SNA profile is received and the connection had ATTACHSEC=PERSISTENT, it is validated to conform to the architecture. It is not used to further qualify users in the signed-on-from list. This also applies to persistent signed-on flows received on a connection that has ATTACHSEC=MIXIDPE specified.

### Transaction, resource, and command security with LU6.2

As in a single-system environment, users must be authorized to:

- Attach a transaction (transaction security)
- Access all the resources that the transaction is programmed to use. These levels are called **resource security**, **surrogate user security**, and **command security**

# **Transaction security**

As in a single-system environment, the security requirements of a transaction are specified when the transaction is defined, as described in Chapter 5, "Transaction security," on page 81.

In an LU6.2 environment, two basic security requirements must be met before a transaction can be initiated:

- The link must have sufficient authority to initiate the transaction.
- If anything other than ATTACHSEC(LOCAL) has been specified, user security is in force. The user who is making the request must therefore have sufficient authority to access the system and to initiate the transaction.

**Note:** Transaction security also applies to the mirror transactions. See "Function shipping security with LU6.2" on page 178.

# **CICS** routing transaction, CRTE

L

L

Т

You can use the CICS routing transaction, CRTE, with IPIC, LU6.2, or MRO links to run transactions that are on a connected remote system, instead of defining these transactions as remote in the local system.

CRTE is particularly useful for infrequently used transactions, or for transactions such as CEMT that are on all systems.

Ensure that the terminal through which CRTE is started is defined on the remote system or is defined as shippable in the local system. The terminal operator needs RACF authority if the remote system is protected.

Security checking in the AOR for transactions that run under CRTE does not depend on what is specified on ATTACHSEC (for MRO and LU6.2 links) or USERAUTH (for IPIC links), nor does it depend on the user ID signed on in the TOR. Instead, security checking depends on whether the user signs on when using CRTE:

- If the user does *not* sign on, the surrogate terminal created is associated with the AOR default user. When a transaction is run, the security checks are carried out against this default user. A check is also made against the link user ID to see whether the routing application itself has authority to access the resource.
- If the user *does* sign on, using the CESN transaction while running CRTE, the surrogate points to the user ID of the signed-on user. For transactions attempting to access resources, security checking is made against the user ID of the signed-on user in the surrogate and the link user ID.

#### **Related concepts:**

Using the routing transaction, CRTE The routing transaction, CRTE, is a CICS-supplied transaction used by a terminal operator to call transactions that are owned by a connected CICS system.

### Resource and command security

Resource and command security in an intercommunication environment are handled in much the same way as in a single-system environment.

Resource and command security checking are performed only if the installed TRANSACTION definition specifies that they are required; for example, on the CEDA DEFINE TRANSACTION command, as shown in Figure 7.

```
CEDA DEFINE TRANSACTION
.
RESSEC(YES)
CMDSEC(YES)
.
```

Figure 7. Specifying resource and command security for transactions

If a TRANSACTION definition specifies resource security checking, using RESSEC(YES), both the link and the user must also have sufficient authority for the resources that the attached transaction accesses.

If a TRANSACTION definition specifies command security checking, using CMDSEC(YES), both the link and the user must also have sufficient authority for the system programming commands shown in Table 10 on page 121 that the attached transaction issues.

For further guidance on specifying resource and command security, see Chapter 6, "Resource security," on page 87 and Chapter 8, "CICS command security," on page 121.

#### NOTAUTH exceptional condition

If a transaction tries to access a resource, but fails the resource security checks, the NOTAUTH condition occurs.

When the transaction is the CICS mirror transaction, the NOTAUTH condition is returned to the requesting transaction, where it can be handled in the usual way.

## Transaction routing security with LU6.2

In transaction routing, the authority of a user to access a transaction can be tested in both the TOR and the AOR.

In the TOR, a test is made to ensure that the user has authority to access the transaction defined as remote, just as if it were a local transaction. This test determines whether the user is allowed to run the relay program.

The terminal through which the transaction is invoked must be defined on the remote system (or defined as "shippable" in the local system), and the terminal operator needs RACF authority if the remote system is protected. The way in which the terminal on the remote system is defined affects the way in which user security is applied:

- If the definition of the remote terminal does not specify the USERID parameter:
  - For links defined with ATTACHSEC(IDENTIFY), the transaction security and resource security of the user are established when the remote user is signed on. The userid under which the user is signed on, whether explicitly or implicitly (in the DFLTUSER system initialization parameter), has this security capability assigned in the remote system.
  - For links defined with ATTACHSEC(LOCAL), transaction security, command security, and resource security are limited by the authority of the link.

In both cases, tests against the link security are made as described in "Link security with LU6.2" on page 167.

**Note:** During transaction routing, the 3-character operator identifier from the TOR is transferred to the surrogate terminal entry in the AOR. If the surrogate terminal was shipped in, this identifier is not used for security purposes, but it may be referred to in messages.

When transaction routing PSB requests, the following conditions must both be satisfied:

- ATTACHSEC on the connection definition must not be LOCAL (that is, it can be IDENTIFY, PERSISTENT, MIXIDPE, or VERIFY).
- PSBCHK=YES must be specified as a system initialization parameter in the remote system.

### Preset-security terminals and transaction routing

A terminal has preset-security if a value is specified on the USERID parameter of the TERMINAL definition. When considering the security aspects of transaction routing from a preset-security terminal, you must remember that preset-security is an attribute of the terminal rather than of the user who initiated the transaction routing request.

During transaction routing, a surrogate terminal is created in the AOR to represent the terminal at which the transaction routing request was issued. Whether the surrogate terminal has preset security or not depends upon a number of factors:

- If a remote terminal definition exists in the AOR for the terminal at the TOR, and specifies the USERID parameter, the surrogate terminal is preset with this userid. If the USERID parameter is not specified in the remote terminal definition, the surrogate terminal does not have preset security.
- If a remote terminal definition does not exist in the AOR, the preset security characteristics of the surrogate terminal are determined from the terminal definition shipped from the TOR. If the shipped terminal definition has preset security, the surrogate also has preset security, unless the connection to the AOR is defined with ATTACHSEC=LOCAL, in which case any preset security information shipped to the AOR is ignored.

# **CICS routing transaction, CRTE**

You can use the CICS routing transaction, CRTE, with IPIC, LU6.2, or MRO links to run transactions that are on a connected remote system, instead of defining these transactions as remote in the local system.

CRTE is particularly useful for infrequently used transactions, or for transactions such as CEMT that are on all systems.

Ensure that the terminal through which CRTE is started is defined on the remote system or is defined as shippable in the local system. The terminal operator needs RACF authority if the remote system is protected.

Security checking in the AOR for transactions that run under CRTE does not depend on what is specified on ATTACHSEC (for MRO and LU6.2 links) or USERAUTH (for IPIC links), nor does it depend on the user ID signed on in the TOR. Instead, security checking depends on whether the user signs on when using CRTE:

- If the user does *not* sign on, the surrogate terminal created is associated with the AOR default user. When a transaction is run, the security checks are carried out against this default user. A check is also made against the link user ID to see whether the routing application itself has authority to access the resource.
- If the user *does* sign on, using the CESN transaction while running CRTE, the surrogate points to the user ID of the signed-on user. For transactions attempting to access resources, security checking is made against the user ID of the signed-on user in the surrogate and the link user ID.

#### Related concepts:

L

Т

Using the routing transaction, CRTE The routing transaction, CRTE, is a CICS-supplied transaction used by a terminal operator to call transactions that are owned by a connected CICS system.

# Function shipping security with LU6.2


When CICS receives a function-shipped request, the transaction that is invoked is the **mirror transaction**.

The CICS-supplied definitions of the mirror transactions all specify resource, but not command, security checking. This means that you are prevented from accessing the remote resources if either the link or your userid profile on the other system does not have the necessary authority.

If the CICS-supplied definitions of the mirror transactions are not what your security strategy needs, you can change them by copying the definitions in group DFHISC into your own group, changing them and then reinstalling them. For more information, see "Category 2 transactions" on page 147.

If you include a remote resource in your resource definitions, you can arrange for security checking to be done locally, just as if the resource were a local one. Also, the system that owns the resource can be made to apply an independent check, if it is able to receive the user identifier. You can therefore choose to apply security restrictions on both sides, on either side, or not at all.

**Note:** Be aware that if you specify the SYSID option on a function-shipped request, security checking is done in the remote system but is **bypassed in the local system**. Figure 8 on page 179 summarizes what happens.



*Figure 8. Security checking done with and without SYSID.* This example illustrates what security checking is done when a transaction in an application-owning region issues a file control request against a remote file.

- In the application-owning region (AOR), file RFILE is defined as remote, with a name of LFILE in the file-owning region (FOR). Resource security checking is active for the transaction that issues the file control request.
- In the FOR, resource security checking is active for the mirror transaction.

There are two cases. In the first case:

- 1. The transaction in the AOR issues EXEC CICS READ FILE('RFILE'). Resource security checking is performed for file RFILE.
- 2. The request is transmitted to the FOR, where resource security checking is performed for file LFILE.

In the second case:

The transaction in the AOR issues EXEC CICS READ FILE('RFILE') *specifying the SYSID* option. Resource security checking *is not performed* for file RFILE.

The request is transmitted to the FOR, where resource security checking is performed for file LFILE.

### Distributed program link security with LU6.2

The CICS distributed program link (DPL) facility enables a CICS program (the client program) to call another CICS program (the server program) in a remote CICS region. DPL is used when the SYSID option on the LINK API command, or the REMOTESYSTEM option of the PROGRAM resource definition, specifies a remote CICS region.

When the SYSID option on the LINK command specifies a remote CICS system, the client region does not perform any resource security checking, but leaves the resource check to be performed in the server region.

The server program in the remote region is executed by a mirror transaction, in a similar way to other function-shipped CICS requests. However, the transaction name associated with the mirror depends on how the LINK command is invoked in the client region. You must be aware of the transaction name because normal attach security applies to the mirror transaction:

- If the TRANSID option is specified on the DPL command, the specified transaction name is used for the mirror.
- If the TRANSID option is omitted from the DPL command, but the TRANSID option is used in the program resource definition in the client region, the name for the mirror is taken from the program's TRANSID specification.

Otherwise, a default name for the mirror transaction is used, and this depends on the origin and LU6.2 sync level of the conversation:

- If the client program is executing in a CICS OS/2 system, the transaction name for the mirror is **CPMI**.
- If synclevel 1 is being used, the default transaction name for the mirror is **CVMI**. This transaction name is used:
  - If the SYNCONRETURN option is specified on the DPL command in the client region
  - If the LU6.2 CONNECTION definition specifies SINGLESESS(YES)
  - If the connection is by means of an LU6.2 terminal; that is, a terminal whose resource definition uses a TYPETERM with a specification of DEVICE(APPC)
- If sync level 2 is being used, the default transaction name is **CSMI**. This transaction name is used when none of the other previous conditions is met.

Authorize your users to access the transaction name that the mirror runs under. The userids to be authorized depend on whether LOCAL or non-LOCAL attach security is being used, and are described in "Security checking done in AOR with LU6.2." If the mirror transaction is defined with RESSEC(YES) in the server region, these userids must also be authorized to access the server program that is being linked to by the mirror. If the server program accesses any CICS resources, the same userids must be authorized to access them. If the server program invokes any system programming commands, and the mirror transaction is defined with CMDSEC(YES) in the server region, the same userids must be authorized to access the commands.

If the mirror transaction cannot be attached because of security reasons, the NOTAUTH condition is not raised, but the TERMERR condition is returned to the issuing application in the client region. If the mirror transaction is successfully attached, but it is not authorized to link to the distributed program in the server region, the NOTAUTH condition is raised. The NOTAUTH condition is also raised if the server program fails to access any CICS resources for security reasons.

The server program is restricted to a DPL-subset of the CICS API commands when running in a server region. The commands that are not supported include some that return security-related information. For programming information about which commands are restricted, see the *CICS Application Programming Reference*. For further information about DPL, refer to the *CICS Intercommunication Guide*.

# Security checking done in AOR with LU6.2

Security checking is different depending on how SECURITYNAME is specified in the AOR and TOR.

The link userid referred to in Table 21 and Table 22 on page 182 is the one specified in the SECURITYNAME on the CONNECTION resource definition, or the USERID on the SESSION resource definition.

If a USERID is specified on the SESSIONS definition, and a link check is done, the userid used is the one on the SESSIONS definition.

If no userid is specified in SECURITYNAME, then the default userid of the AOR is used instead. However, if the SECURITYNAME userid is the same as the region userid for the AOR, then the link is deemed to have the same security as the AOR, and **link security is omitted altogether**. The effect of omitted link security depends on whether LOCAL or non-LOCAL attach security is specified for the link:

- For LOCAL attach security, the security specified in the USERID on the SESSIONS definition is used. If this too is omitted, then the default userid for the AOR is used.
- For non-LOCAL attach security, the security specified in the USERID on the sessions definition is **not** used. Only the userid received from the TOR is used to determine security.

**Note:** Neither the region userid for the TOR, nor the SECURITYNAME in the TOR'S CONNECTION definition for the AOR, is relevant to security checking in the AOR.

Table 21 shows how checking is done when ATTACHSEC(LOCAL) is specified.

Region userid for AOR	SECURITYNAME in connection definition	USERID in SESSION definition	Checking in AOR
USERIDA	Not specified	Not specified	Check against AOR DFLTUSER
USERIDA	Not specified	USERIDA	Check against AOR DFLUTSER
USERIDA	Not specified	USERIDB	Check against USERIDB
USERIDA	USERIDA	Not specified	Check against AOR DFLTUSER
USERIDA	USERIDB	Not specified	Check against USERIDB
USERIDA	USERIDA	USERIDA	Check against AOR DFLTUSER
USERIDA	USERIDA	USERIDB	Check against USERIDB
USERIDA	USERIDB	USERIDA	Check against DFLTUSER
USERIDA	USERIDB	USERIDB	Check against USERIDB
USERIDA	USERIDB	USERIDC	Check against USERIDC

Table 21. LU6.2 and ATTACHSEC(LOCAL)

Table 22 on page 182 shows how checking is done when the ATTACHSEC parameter IDENTIFY (or PERSISTENT, or MIXIDPE) has been specified.

Region userid for AOR	SECURITYNAME in connection definition	USERID in SESSION definition	Checking in AOR
USERIDA	Not specified	Not specified	Transmitted userid and AOR DFLTUSER
USERIDA	Not specified	USERIDA	Transmitted userid only
USERIDA	Not specified	USERIDB	Transmitted userid and USERIDB
USERIDA	USERIDA	Not specified	Transmitted userid only
USERIDA	USERIDA	USERIDA	Transmitted userid only
USERIDA	USERIDA	USERIDB	Transmitted userid and USERIDB
USERIDA	USERIDB	Not specified	Transmitted userid and USERIDB
USERIDA	USERIDB	USERIDC	Transmitted userid and USERIDC

Table 22. LU6.2 and ATTACHSEC(IDENTIFY), ATTACHSEC(PERSISTENT), and ATTACHSEC(MIXIDPE)

# Chapter 13. APPC password expiration management

This topic contains information on advanced program-to-program communications (APPC) password expiration management (PEM).

### Introduction to APPC password expiration management

This section introduces, and describes the benefits of, APPC password expiration management.

You might find it useful to copy and modify an example program. For your guidance sample programs are shipped in library CICSTS41.CICS.SDFHSAMP. Their names are:

- 1. DFH\$\$.SNPW PEM sample program for Windows NT
- 2. DFH\$\$.SNP2 PEM sample program for OS/2

For examples of PEM requester and CICS PEM server user data produced by a program, see:

- "Sign-on with correct userid and password" on page 199
- "Sign-on with new password" on page 200
- "Response to correct sign-on data" on page 200
- "Response to incorrect data format" on page 202.

**Note:** In this topic the word 'sign-on' is used in the sense defined in the APPC architecture, which is different from the meaning used elsewhere in this book.

### What APPC PEM does

APPC PEM with CICS provides receive support for an APPC architected sign-on transaction that verifies user ID, password pairs, and processes requests for a password change by:

- · Identifying a user and authenticating that user's identification
- Notifying specific users during the authentication process that their passwords have expired
- Letting users change their passwords when (or before) the passwords expire
- Telling users how long their current passwords will remain valid
- Providing information about unauthorized attempts to access the system using a particular user identifier

### Benefits of APPC PEM

APPC PEM has the following benefits:

• It enables users to update passwords on APPC links.

This can be particularly useful in the case of expired passwords. On APPC links that do **not** support APPC PEM, when users' passwords expire on remote systems, they are unable to update them from their own systems. The only alternative on a non-APPC PEM system is to log on directly to the remote system using a non-APPC link, such as an LU2 3270-emulation session, to update the password.

• It provides APPC users with additional information regarding their sign-on status; for example, the date and time at which they last signed on.

• It informs users whether their userid is revoked, or the password has expired, when they provide the correct password or PassTicket.

# What you require to use APPC PEM

To use APPC PEM, you need:

#### A PEM client

The PEM client can be any APPC logical unit (LU) or node that is capable of initiating a conversation with the architected sign-on transaction. However, the benefits of using APPC PEM are increased when using an LU or node that does not have its own ESM; for example, a programmable workstation. APPC PEM enables users of such LUs or nodes to manage their password values within the ESM used by CICS. The PEM client is linked to a *PEM server*.

#### A PEM server

The PEM server can be any APPC LU that supports APPC PEM. This information describes the PEM server provided by CICS Transaction Server for z/OS, Version 4 Release 1. It is referred to in the rest of this book as the CICS PEM server.

#### An external security manager

An external security manager, such as RACF, or an equivalent ESM, must be available to the PEM server.

The PEM client (requester) and the PEM server are linked by an APPC session. This configuration is shown in Figure 9.




Figure 9. APPC PEM configuration

### External security interface

Password expiration management has been enhanced to include the External Security Interface (ESI).

The ESI is not part of CICS Transaction server for z/OS, but it allows a non-CICS application to invoke services provided by advanced APPC PEM. ESI provides additional functions which make it easier for a non-CICS application to change and verify a password.

The 2 functions provided by ESI are:

- **CICS_VerifyPassWord** which allows a client application to verify that a password matches the password recorded by RACF, or an equivalent external security manager, for a specified user ID.
- **CICS_ChangePassWord** which allows a client application to change the password recorded by RACF for a specified user ID.

These functions allow a non-CICS application program to act as a PEM requestor without the application programmer having to manage an APPC conversation which implies knowledge of the formats for PEM requests and replies, and of the interface to the local SNA server.

For more information about the ESI password management functions, see the *Client/Server Application Programming* manual.

### Roles of PEM client and CICS PEM server

CICS Transaction Server for z/OS, Version 4 Release 1 does not send passwords on APPC conversations. This means that it can **attach**, but not **initiate** the sign-on transaction, and must always act as the PEM server. Therefore, in your configuration always include an LU that is capable of initiating the sign-on transaction to act as the PEM client.

The PEM client collects sign-on information and sends it to the CICS PEM server via a sign-on transaction program. The sign-on transaction program is a SNA service transaction program, as described in *SNA LU 6.2 Peer Protocols* manual.

Note that PEM signon is not to be confused with a CICS signon. In CICS, PEM signon allows the APPC LU to verify and manage user IDs and passwords. Following verification or updating, the user ID or password is intended to be included in the ASIS part of the FMH5 attach header. When this FMH5 is sent into CICS through the APPC link, provided ATTACHSEC is non-local, the user ID will be signed on to CICS. Therefore, a PEM signon does not result in the ESM last—connect, last-access information being updated.

The CICS PEM server then processes the sign-on request, updates the user's password (if necessary), and returns a reply to the PEM client containing responses and other data, such as a password expiry and information about unauthorized attempts to sign on. The PEM client then processes the data, as appropriate.

**Note:** When you successfully verify your password with CICS Transaction Server for z/OS, Version 2 Release 1, you are not signed on in the target CICS system.

If your CICS connection specifies persistent verification, a successful password verification will cause you to be added to the LUIT table. If no other attaches are received, you will receive a CLS3 transaction flow after the PVDELAY interval.

### An example of signing on with APPC PEM

This example shows the sequence of events when a user signs on to a PEM client with an expired password.

The sequence is illustrated in Figure 10 on page 186.

- 1. The user attempts to sign on to the PEM client, and supplies a password.
- 2. The PEM client sends the user ID and password to the CICS PEM server.
- **3**. The CICS PEM server passes the user ID and password to the external security manager.
- 4. The external security manager checks the password.
- 5. Because the password has expired, the sign on attempt fails. The external security manager informs the CICS PEM server, which, in turn, informs the PEM client.
- **6**. The PEM client informs the user that the password has expired, and requests a new one.
- 7. The user enters a new password.
- **8**. The PEM client sends the user ID, the old password, and the new password to the CICS PEM server.

- **9**. The CICS PEM server passes the user ID, the old password, and the new password to the external security manager.
- **10**. The external security manager checks the old and new password.Because a new passowrd is provided, the sign on attempt is succesful. The external security manager informs the CICS PEM server, which, in turn, informs the PEM client.
- 11. The PEM client informs the user that the sign on request has been successful.




Figure 10. Example of signing on with APPC PEM

### **Overview of APPC PEM processing**

CICS provides the PEM server, the receive side of APPC PEM as a CICS transaction that is started when an ATTACH for the sign-on transaction program is received from the PEM client.

CICS retrieves the sign-on data associated with the request, calls the ESM to perform a sign-on, and retrieves sign-on details for the userid. If the sign-on data includes a new password value, CICS includes this value when it calls the ESM to request a sign-on.

If PV is being used, and sign-on completes correctly, the user is added to the PV "signed-on-*from* list" in CICS, and the PV "signed-on-*to* list" in the PEM client. The "signed-on-"lists keep track of verified user IDs.

The CICS PEM server builds a reply and returns it to the PEM client, after which the CICS PEM server transaction terminates normally.

# **PEM client processing**

The PEM client sign-on transaction program:

- 1. Obtains sign-on information, for example by:
  - Displaying a message to the user requesting sign-on information; that is, userid, password, and, if required, new password; or
  - Accessing sign on information from a user who has already been authenticated locally.
- 2. Sends the sign-on information to the CICS PEM server via an APPC conversation.
- 3. Receives replies from the CICS PEM server on the same APPC conversation.
- 4. If PV is being used (either ATTACHSEC=PERSISTENT or ATTACHSEC=MIXIDPE is specified on the CONNECTION definition), and sign-on is successful, adds the user's name to the PV signed-on-to list.
- 5. Processes the reply information from the CICS PEM server; for example, by:
  - Displaying the information to the user
  - Processing the data and saving it in a file to which only the user has access.

### **CICS PEM server processing**

The CICS PEM server performs the following processing:

- 1. Accepts the userid and password, with optional new password, from the sign-on PEM client.
- 2. Tries to validate the user with its ESM.

If the userid and password are valid and the password has not expired, the CICS PEM server extracts the following information from its ESM:

- Date and time of the last successful sign-on
- Data and time the password will expire (calculated by data extracted from the ESM by the CICS PEM server itself)
- Number of unsuccessful sign-on attempts since the last successful sign-on.
- **3**. Returns a response to the PEM client, indicating whether the sign-on was succeeded or failed, and the reason for any failure:

Status	= (X'00') OK
Date-Time	= Current date and time
Last-Date-Time	= Date and time of previous successful sign-on

Expiry-Date-Time = Date and time password will expire Revoke-Count = Number of unsuccessful sign-on attempts made with this userid since the previous successful sign-on

For detailed information about the response, see "PEM client input and output data" on page 194.

**Note:** The ESM increments the revoke count whenever it processes an invalid sign-on attempt. The sign-on request may originate from a non-CICS system (for example, a TSO user).

If sign-on is unsuccessful, CICS returns to the PEM client a sign-on completion status value and, if appropriate, a formatting error value. See "PEM client input and output data" on page 194 for more information.

4. If PV is being used (either ATTACHSEC=PERSISTENT or ATTACHSEC=MIXIDPE is specified on the CONNECTION definition), and sign-on is successful, adds the user's name to the PV signed-on-from list.

### Expected flows between PEM client and CICS PEM server

Figure 11 on page 189 through Figure 14 on page 192 show expected flows for successful and unsuccessful sign-on attempts with and without PV.

**Note:** CICS support for the PEM client sign-on transaction assumes that the request for sign-on (or sign-on and change password) is for a single user. Batching of sign-on requests for different userids within a single sign-on transaction is not supported. If multiple sign on requests are passed in the input data, the CICS PEM server processes only the first one.

#### Successful sign-on—non-PV connection

Figure 11 on page 189 shows the expected flows between the PEM client and CICS PEM server during a successful sign-on when PV is not being used.

PEM client LU	Network	CICS PEM server LU
•	-LU-LU session setup	
Gather data		
Send sign-on transaction		
program request		
data, requesting reply		
(BB,	CD,FMH-5(SIGN-ON), d I	ata)  (Ignore FMH security fields)
		Receive request
		Process data: - issue sign-on or sign-on and change password - issue sign-off
Receive reply	 (CEB,reply data)_	Send reply, with deallocation
Process reply	(CED, CPTy data)-	

*Figure 11. Expected flows for a successful sign-on with a non-PV connection.* This is the expected sequence of events:

- 1. The session between the PEM client logical unit and the CICS PEM server logical unit is established.
- 2. The PEM client gathers data, and sends data for the sign-on program request to the server, requesting a reply. The request flow contains BB, CD, FMH5, and data.
- **3**. The CICS PEM server ignores the security fields in the FMH5. It processes the data to issue the sign on (or sign on with changed password).
- 4. The server sends the reply and deallocates the session. The reply flow contains CEB and data.
- 5. The client receives and processes the reply.

**Note:** All security fields in the FMH-5 (userid, password and UP, AV, PV1 and PV2 bits) are ignored by the CICS PEM server when it attaches the sign-on transaction.

#### Unsuccessful sign-on—non-PV connection

Figure 12 on page 190 shows the expected flows for an unsuccessful sign-on between a PEM client and CICS PEM server when PV is not being used.

PEM client LU	Network	CICS PEM server LU
•	- LU-LU session setup	
Gather data		
Send signon transaction program request data, requesting reply		
(BB,	CD,FMH-5(SIGN-ON), d '	ata)  (Ignore FMH security fields)
		(ignore that security fretus)
		Receive request
		Process data: - issue sign-on or sign-on and change password (fails)
Receive reply	(CEB,reply data)	Send error reply data, with deallocation
Process reply		

*Figure 12. Unsuccessful sign-on—non-PV connection.* This is the expected sequence of events:

- 1. The session between the PEM client logical unit and the CICS PEM server logical unit is established.
- 2. The PEM client gathers data, and sends data for the sign-on program request to the server, requesting a reply. The request flow contains BB, CD, FMH5, and data.
- **3**. The CICS PEM server ignores the security fields in the FMH5. It processes the data to issue the sign on (or sign on with changed password). The request fails.
- 4. The server sends the error reply and deallocates the session. The reply flow contains CEB and data.
- 5. The client receives and processes the reply.

**Note:** The CICS PEM server schedules sign-off against the PEM client if a sign-on request for a userid fails.

### Successful sign-on—PV connection

Figure 13 on page 191 shows the expected flows between the PEM client and CICS PEM server during a successful sign-on on a PV connection.

PEM client LU	Network	CICS PEM server LU
4	-LU-LU session setup	
Gather data	·	
Send sign-on transaction program request data, requesting reply		
(BB	,CD,FMH-5(SIGN-ON),d	ata) (Ignore FMH security fields)
		(ignore FMH security fields)
		Receive request
		Process data: - issue sign-on or sign-on and change password - add user to PV signed-on-from list
Receive reply	(CEB,reply data)	Send reply, with deallocation
Process reply		
Add userid to PV signed-onto-list		

*Figure 13. Successful sign-on—PV connection.* This is the expected sequence of events:

- 1. The session between the PEM client logical unit and the CICS PEM server logical unit is established.
- 2. The PEM client gathers data, and sends data for the sign-on program request to the server, requesting a reply. The request flow contains BB, CD, FMH5, and data.
- **3**. The CICS PEM server ignores the security fields in the FMH5. It processes the data to issue the sign on (or sign on with changed password).
- 4. The server adds the user to the PV signed-on-from list.
- 5. The server sends the reply and deallocates the session. The reply flow contains CEB and data.
- 6. The client receives and processes the reply.
- 7. The client adds the userid to the signed-onto list.

#### Note:

- 1. All security fields in the FMH-5 (userid, password and UP, AV, PV1 and PV2 bits) are ignored by the CICS PEM server when it attaches the sign-on transaction.
- The CICS PEM server adds the userid to its PV signed-on-from list only if the sign-on and change password request is successful and either ATTACHSEC=MIXIDPE or ATTACHSEC=PERSISTENT is specified in the CONNECTION definition.
- **3**. The PEM client must add the userid to its PV signed on-to list only if a successful sign-on reply is received from the CICS PEM server. The userid has been added to the PV signed on from list in the CICS PEM server, so all subsequent attach requests from this userid can flow as signed on.

#### Unsuccessful sign-on—PV connection

Figure 14 on page 192 shows the expected flows between a PEM client and CICS PEM server during an unsuccessful sign-on on a PV connection.

PEM client LU	Network	CICS PEM server LU
4	-LU-LU session setup	
Gather data		
Send sign-on transaction program request data, requesting reply (BB	,CD,FMH-5(SIGN-ON),d	ata)
	, ob , i i iii i o ( o i u ii o ii ) , u	(Ignore FMH security fields)
		Receive request
		Process data: - issue sign-on or sign-on and change password (fails)
		Do not add user to PV signed on from list Purge user, if present, and schedule sign-off
Receive reply	—(CEB,reply data)—	Send error reply data, with deallocation
Process reply		
Do not add user to PV signed on to list		

Figure 14. Unsuccessful sign-on-PV connection. This is the expected sequence of events:

- 1. The session between the PEM client logical unit and the CICS PEM server logical unit is established.
- 2. The PEM client gathers data, and sends data for the sign-on program request to the server, requesting a reply. The request flow contains BB, CD, FMH5, and data.
- **3.** The CICS PEM server ignores the security fields in the FMH5. It processes the data to issue the sign on (or sign on with changed password). The request fails.
- 4. The server does not add the user to the signed-on-from list. If the user is already on the list, the user is purged from it, and a signoff is scheduled.
- **5**. The server sends the error reply and deallocates the session. The reply flow contains CEB and data.
- 6. The client receives and processes the reply.
- 7. The user is not added to the signed-onto list.

**Note:** CICS schedules sign-off against the PEM client if a sign-on request for a userid fails, and that user is in the PV signed on from list. In this case, CICS sends the sign-off transaction program output data to the PEM client, where it is processed and the userid removed from the PV signed on to list.

### Setting up the PEM client

When setting up your PEM client, note the following:

• Use the basic (also known as **unmapped**) conversation type. In addition to sending the data you want the partner to receive, you must add control bytes (in Assembler language or C) to convert the data into an SNA-defined format called a **generalized data stream** (GDS).

- The SNA service transaction program name for the sign-on transaction program is **X'06F3F0F1'**, which is also the transaction id (XTRANID) that must be used for the CICS transaction CLS4. You specify XTRANID in the CICS TRANSACTION definition.
- Run the CICS PEM server sign-on transaction as a **sync level 0** transaction. If it is initiated with a sync level other than 0, it sends an ISSUE ABEND and frees the conversation.
- Translate the userid and password into EBCDIC; if they are not in this form, the ESM cannot recognize them and issues an error. See one of the the example programs which is described in "Introduction to APPC password expiration management" on page 183, for an example of converting userids and passwords to EBCDIC.

If the ESM is RACF, the userid and password must also be in uppercase characters.

- On the ATTACH request for the sign-on transaction program specify SECURITY(NONE). CICS ignores any ATTACH security fields passed in the ATTACH function management header, FMH-5, for this transaction.
- CICS does not support the receipt of the PROFILE option in the sign-on transaction program. If data identifier (ID) X'00' is provided, CICS returns status value X'06' (incorrect data format) with formatting error X'0002' (precluded structure present). For information about status values and formatting error values, see "PEM client input and output data" on page 194.
- The new password ID, X'06', is permitted and required only with the X'FF01' request data ID. If the new password is provided with a data ID other than X'FF01', CICS returns status value X'06' (incorrect data format) with formatting error X'0002' (precluded structure present). For information about status values and formatting error values, see "PEM client input and output data" on page 194.
- CICS only supports userids and passwords up to 8 characters long. If the userid or password length (after stripping blanks and nulls) exceeds 8, CICS returns status value X'06' (incorrect data format) with formatting error X'000F' (data value out of range). For information about status values and formatting error values, see "PEM client input and output data" on page 194.
- Program initialization parameter (PIP) data is optional on the ALLOCATE for the sign-on transaction, and is ignored if sent.
- If the sign-on transaction receives a GDS ISSUE SIGNAL command, it is ignored.
- If the CICS PEM server receives a GDS ISSUE ERROR command, it replies with ERROR and frees the conversation.
- If the CICS PEM server receives a GDS FREE command, it frees the conversation. (It does not provide diagnostic information about the type of conversation error.)
- The CICS PEM server transaction does not support the receipt of data exceeding the maximum buffer size. If the concatenation bit in the initial LL is set, the command is ignored; concatenated data is also ignored.

# Format of user data

As part of the general rules for APPC basic conversations, the user data must be in LL-ID-data format (where LL and ID are each two bytes long), and must follow the attach FMH-5 header.

The CICS DFHCLS4 program requires the user input data stream to fit into the format shown in Figure 15; if it does not, CICS rejects the data.




Figure 15. Format of user data.

#### Note:

- 1. This is an attach FMH-5 header with its data. Data is passed between the PEM client and the CICS PEM server via GDS variables. (For information on GDS, see the *SNA LU 6.2 Peer Protocols* manual.)
- 2. The GDS record contains GDS data in the format LL-ID-data where:
  - LL, which is two bytes long, is the length of the GDS record, including the LL and ID lengths.
  - ID, which is two bytes long, indicates what the data record represents; for example, X'1221' (sign-on data).
- The GDS data record is itself an LL-ID-data record; in this example, a transaction program record (or TP record) where:
  - LL, which is two bytes long, is the length of the TP record including the LL and ID lengths.
  - ID which is two bytes long, indicates the function the TP is to perform; for example, X'FF00' (sign-on) or X'FF01' (signon and change password).
- The TP data record is divided up into L-ID-data records (where L and ID are each one byte long). These are known as subfield (or SF records) where:
  - L is the length of the SF record, including the L and ID lengths.
  - ID indicates the subfield being passed; for example, X'01' (userid), X'02' (password), and X'06' (new password).

### PEM client input and output data

To perform the functions described in "CICS PEM server processing" on page 187, the CICS PEM server takes input data from, and sends output data to, the PEM client sign-on transaction program:

- The PEM client sends data to the CICS PEM server, as described in Table 23 on page 195.
- The CICS PEM server sends data to the PEM client, as described in Table 24 on page 195 through Table 27 on page 198.

Ensure the data conforms to the standards described in "Setting up the PEM client" on page 192, and that its format is as described in "Format of user data" on page 193. See "Sign-on with correct userid and password" on page 199 and "Sign-on with new password" on page 200 for examples of sign-on output data in GDS flows.

Basic conversation information and data are contained in the attach FMH, as described in "Format of user data" on page 193. The sign on request attaches a transaction X'06F3F0F1', which is the SNA service transaction program name for the sign-on transaction program.

# Sign-on input data sent by PEM client

Table 23 shows the input data that the CICS PEM server needs from the PEM client sign-on transaction program. See "Sign-on with correct userid and password" on page 199 and "Sign-on with new password" on page 200 for examples of sign-on input data in GDS flows.

Length (bytes)	Value	Meaning	
2	X'nnnn'	Length of entire GDS data, including this 2-byte length value.	
2	X'1221'	Data ID for sign-on data.	
2	X'nnnn'	Length of this second (nested) data structure (length, data ID, and data), including this 2-byte length value.	
2	X'FF00' or X'FF01'	Data ID for sign-on or sign-on and change password request data, respectively. (New password subfield is not permitted for X'FF00'.)	
1	X'nn'	Length of subfield for userid, including this 1-byte length value.	
1	X'01'	Data ID of subfield for userid.	
X'nn'-2	C'xxxxxxx'	Userid.	
1	X'mm'	Length of subfield for password, including this 1-byte length value.	
1	X'02'	Data ID of subfield for password.	
X'mm'-2	C'xxxxxxx'	Password.	
1	X'pp'	Length of subfield for new password, including this 1-byte length value.	
1	X'06'	Data ID of subfield for new password.	
X'pp'-2	C'xxxxxxx'	New password.	

Table 23. Sign-on request and data sent to CICS PEM server

# Sign-on output data returned by CICS PEM server

Table 24 lists the sign-on output data that the CICS PEM server returns to the PEM client. See "Response to correct sign-on data" on page 200 and "Response to incorrect data format" on page 202 for examples of sign-on output data in GDS flows.

Length (bytes)	Value	Required or optional	Meaning
2	X'nnnn'	Required	Length of entire GDS data, including this 2-byte length value.
2	X'1221'	Required	Data ID of subfield for sign-on data.

Table 24. Sign-on output data returned to PEM client

Length (bytes)	Value	Required or optional	Meaning
2	X'nnnn'	Required	Length of this second (nested) data structure (length, data ID, and data), including this 2-byte length value.
2	X'FF02'	Required	Data ID for sign-on reply data.
1	X'03'	Required	Length of subfield for sign-on completion status, including this 1-byte length value.
1	X'00'	Required	Data ID of subfield for sign-on completion status.
1	X'00' through X'06'	Required	Sign-on completion status—see Table 26 on page 198.
1	X'04'	Optional	Length of subfield for sign-on request formatting error, including this 1-byte length value.
1	X'01'	Optional	Data ID of subfield for sign-on request formatting error.
2	X'0000' through X'0003', X'0005' through X'0007', X'000F'	Optional	Sign-on request formatting error—see Table 27 on page 198.
1	X'0A'	Optional	Length of subfield for date and time of current successful sign-on, including this 1-byte length value.
1	X'02'	Optional	Data ID of subfield for date and time of current successful sign-on.
8	See Table 25 on page 197 for format	Optional	Date and time of current successful sign-on. The date and time returned are extracted by the ESM from the user profile.
1	X'0A'	Optional	Length of subfield for date and time of last successful sign-on, including this 1-byte length value.
1	X'03'	Optional	Data ID of subfield for date and time of last successful sign-on.
8	See Table 25 on page 197 for format	Optional	Date and time of last successful sign-on. The date and time returned are extracted by the ESM from the user profile.

Table 24. Sign-on output data returned to PEM client (continued)

Length (bytes)	Value	Required or optional	Meaning
1	X'0A'	Optional	Length of subfield for date and time password will expire, including this 1-byte length value.
1	X'04'	Optional	Data ID of subfield for date and time password will expire.
8	See Table 25 for format.	Optional	Date and time password will expire. (The date and time returned are calculated from data obtained from the ESM.)
1	X'04'	Optional	Length of subfield for revoke count, including this 1-byte length value.
1	X'05'	Optional	Data ID of subfield for revoke count.
2	X'nnnn'	Optional	Revoke count.

Table 24. Sign-on output data returned to PEM client (continued)

#### Format of date and time subfields

Table 25 lists the format of the date and time subfields that the CICS PEM server can return to the PEM client, as referred to in Table 24 on page 195. See "Response to correct sign-on data" on page 200 for an example of date and time subfields in a GDS flow.

Position	Meaning
00	Two-byte year value; for example, 1994=X'07CB'.
02	One-byte month value; January=X'01', December=X'0C'.
03	One-byte day value; first day=X'01', thirty-first day=X'1F'.
04	One-byte hour value; midnight=X'00', 23rd hour=X'17'.
05	One-byte minute value; on the hour=X'00', 59th minute=X'3B'.
06	One-byte second value; on the minute=X'00', 59th second=X'3B'.
07	One-byte 100ths of a second value; on the second=X'00', maximum=X'63'.

Table 25. Format of date and time subfields using 24-hour clock

**Note:** The maximum time value for a given day is 23 hours, 59 minutes, and 59.99 seconds (decimal). Midnight is 0 hours, 0 minutes, and 0 seconds on the following day.

#### Sign-on completion status values returned to PEM client

Table 26 on page 198 describes the sign-on completion status values (referred to in Table 24 on page 195) that the CICS PEM server can return to the PEM client in the status completion subfield in the sign-on reply data. See "Response to correct sign-on data" on page 200 for an example of sign-on completion status values in a GDS flow.

Table 26. Sign-on completion status values returned to PEM client

Status value	Meaning
X'00'	<ul> <li>All of the following conditions apply:</li> <li>Userid valid</li> <li>Password valid</li> <li>Password not expired or new valid password specified</li> <li>When this status value is returned, the new password is set if specified, and PV processing (if used) is complete.</li> </ul>
X'01'	Userid not known to the receiver.
X'02'	Userid valid, password incorrect.
X'03'	Userid valid, password correct but expired. New password must be set.
X'04'	Userid valid, password correct, new password not acceptable to receiving security system.
X'05'	Security function failure. Function not performed.
X'06'	Incorrect data format. Specific error is contained in the sign-on request formatting error subfield described in Table 27.

**Note:** The CICS PEM server never returns either of the following sign-on status values to the PEM client:

- X'07'—general security error
- X'08'—password change completed, but sign-on failed.

### Sign-on request formatting errors returned to PEM client

Table 27 lists the sign-on request formatting error values (referred to in Table 24 on page 195) that the CICS PEM server can return to the PEM client. Each is a 2-byte binary value. See "Response to incorrect data format" on page 202 for an example of sign-on request formatting errors in a GDS flow.

Table 27. Sign-on request formatti	ng error values returned to PEM client
------------------------------------	----------------------------------------

Error value	Description
X'0000'	Undefined error not described below.
X'0001'	Required structure absent.
X'0002'	Precluded structure present.
X'0003'	Several occurrences of a nonrepeatable structure.
X'0005'	Unrecognized structure present where precluded.
X'0006'	Length outside specified range. This value assumes that the length arithmetic balances and that the sender intended to send the structure at that length.
X'0007'	Length exception. Length arithmetic is out of balance.
X'000F'	Data value out of range.

# **Application design**

Design your applications to run the sign-on transaction before any other transaction.

This keeps that any password check and any password changing separate from the application's own functions. In multitasking systems, it is possible for more than one sign-on transaction to start on parallel sessions. It is important that the code

dealing with application-level ALLOCATE requests, serializes the sign-on process to completion, thus ensuring both flow as signed-on.

To record the date and time of a previous successful sign-on, the CICS PEM server sign-on program extracts password data from the ESM **before** it performs sign-on. If your system uses shared userids, and two users attempt to sign on at the same time, or if a user is multitasking, the time values returned to the PEM client for the current sign-on may not be the same as the timestamp recorded on the ESM database. Remember this if you are writing an application that is to run on multiple systems, and depends on the sign-on time returned to the PEM client. (This situation should not apply on a single system, provided the sign-on process is serialized as suggested.)

If PV is being used, and the interval specified in PVDELAY is exceeded, and the userid is removed from the PV sign on from list, applications must allow for the sign-on process to be serialized again.

### Examples of PEM client and CICS PEM server user data

Data is passed between the PEM client and the CICS PEM server via GDS variables.

To help you check the data being sent by your PEM client, the examples that follow show:

- "Sign-on with correct userid and password"
- "Sign-on with new password" on page 200
- "Response to correct sign-on data" on page 200
- "Response to incorrect data format" on page 202.

These examples are produced by the sample PEM client program shown in the library *CICSTS41.CICS.SDFHSAMP*, described in "Introduction to APPC password expiration management" on page 183. That program uses a **partner_LU_alias** of hostcics, an **LU_alias** of ps2lua, and a **mode_name** of lu62ss. When writing your own PEM client program, use the values defined in your communications manager configuration.

#### Sign-on with correct userid and password

Figure 16 shows a sample flow for a successful sign-on.

PEM hostcics ps2lua lu62ss sec2r01 drtnnom

Figure 16. Sign-on with correct userid and password, no new password

A valid userid (sec2r01) and password (drtnnom) are correctly entered. No new password is entered.

The PEM client sends the following hexadecimal user data to the CICS PEM server:

001A12210016FF000901E2C5C3F2D9F0F10902C4D9E3D5D5D6D4

This contains the following values, as described in Table 23 on page 195:

- **001A** Length of the entire GDS data, including this 2-byte length value
- **1221** Data ID for sign on data
- **0016** Length of this second (nested) data structure (length, data ID, and data), including this 2-byte length value

- FF00 Data ID for sign-on request data
- **09** Length of subfield for userid, including this 1-byte length value
- 01 Data ID of subfield for userid

#### E2C5C3F2D9F0F1

Userid (SEC2R01) in EBCDIC

- **09** Length of subfield for password, including this 1-byte length value
- **02** Data ID of subfield for password

#### C4D9E3D5D5D6D4

Password (DRTNNOM) in EBCDIC

#### Sign-on with new password

The following is an example of a successful sign-on using a new password. PEM hostcics ps2lua lu62ss sec2r01 drtnnom hursley

A userid, password, and new password are correctly entered.

The PEM client sends the following hexadecimal user data to the CICS PEM server:

0231221001FFF010901E2C5C3F2D9F0F10902C4D9E3D5D5D6D40906C8E4D9E2D3C5E8

This contains the following values, as described in Table 23 on page 195:

- 0023 Length of entire GDS variable, including this 2-byte length value
- **1221** Data ID for sign
- **001F** Length of this second (nested) data structure (length, data ID, and data), including this 2-byte length value
- FF01 Data ID for sign-on and change password request data
- **09** Length of subfield for userid, including this 1-byte length value
- **01** ID of subfield for userid

#### E2C5C3F2D9F0F1

Userid (SEC2R01) in EBCDIC

- **09** Length of subfield for password, including this 1-byte length value
- **02** ID of subfield for password

#### C4D9E3D5D5D6D4

Password (DRTNNOM) in EBCDIC

- **09** Length of subfield for new password, including this 1-byte length value
- **06** ID of subfield for new password

#### C8E4D9E2D3C5E8

New password (HURSLEY) in EBCDIC

#### Response to correct sign-on data

Figure 17 on page 201 shows an example of the response to the correct sign-on data being entered.

```
PEM_OK
GDS_LLID
00 2d 12 21
Sign-on Reply LLID
00 29 ff 02
Sign-on Completion Status Subfield
03 00 00
Date & Time of Current Successful Sign-on Subfield
0a 02 07 ca 01 14 0d 24 31 62
Date & Time of Last Successful Sign-on Subfield
0a 03 07 ca 01 11 16 1b 23 3e
Date & Time Password Will Expire Subfield
0a 04 07 ca 02 03 00 00 00 00
Revoke Count Subfield
04 05 00 00
```

Figure 17. Response to correct sign-on data

The first three lines of hexadecimal user data returned to the PEM client show the following *required* values, as described in Table 24 on page 195.

- **002d** Total length of the GDS variable, including this 2-byte length value
- **1221** Data ID for sign-on data
- **0029** Length of this second (nested) data structure (length, data ID, and data), including this 2-byte length value
- FF02 Data ID for sign-on reply data
- **03** Length of subfield for sign-on completion status, including this 1-byte length value
- **00** Data ID for sign-on completion status
- **60** Sign-on completion status. 00 indicates that the userid and password were valid, and the password had not expired. (See Table 26 on page 198 for a list of sign-on completion status values.)

In Figure 17, the last four lines of hexadecimal user data returned to the PEM client show the following optional values, as described in Table 24 on page 195. (Note that the formatting error subfields shown in Table 24 on page 195 are not included, indicating that there are no errors.)

- **0A** Length of subfield for date and time of current successful sign-on including this 1-byte length value
- **02** Data ID for date and time of current successful sign-on

Date and time of current successful sign-on, as described in Table 25 on page 197:

- **07CA** Year (1994)
- **01** Month (January)
- 14 Day (20)
- **OD** Hour (13)
- **24** Minutes (36)
- **31** Seconds (49)
- 62 Hundredths of a second (98)
- **0A** Length of subfield for date and time of previous successful sign-on,

**03** Data ID for date and time of previous successful sign-on

Date and time of previous successful sign-on, as described in Table 25 on page 197:

- **07CA** Year (1994)
- **01** Month (January)
- **11** Day (17)
- **16** Hour (22)
- **1B** Minutes (27)
- **23** Seconds (35)
- **3E** Hundredths of a second (62)
- **0a** Length of subfield for date and time password will expire (including this 1-byte length value)
- **04** Length of subfield for data ID for date and time password will expire

Date and time password will expire, as described in Table 25 on page 197:

- **07ca** Year (1994)
- **02** Month (February)
- **03** Day (14)
- **00** Hour (00)
- **00** Minutes (00)
- **00** Seconds 00)
- **00** Hundredths of a second (00)
- 04 Length of subfield for revoke count, including this 1-byte length value
- **05** Data ID of subfield for revoke count
- **0000** Revoke count. (0000 means that there have been no unsuccessful sign-on attempts since the last successful sign-on with this userid.)

#### Response to incorrect data format

Figure 18 shows an example response to incorrect data being entered.

```
PEM_OK
GDS_LLID
00 0F 12 21
Sign-on Reply LLID
00 0B FF 02
Sign-on Completion Status Subfield
03 00 06
Sign-on Request Formatting Error Subfield
04 01 00 0F
```

Figure 18. Response to incorrect data format

The first three lines of hexadecimal user data returned to the PEM client show the following required values, as described in Table 24 on page 195:

- **000F** Length of entire GDS data, including this 2-byte length value
- **1221** Data ID for sign-on data

- **000B** Length of this second (nested) data structure (length, data ID, and data), including this 2-byte length value
- FF02 Data ID for sign-on reply data
- **03** Length of subfield for sign-on completion status, including this 1-byte length value
- **00** Data ID of subfield for sign-on completion status
- **06** Sign-on completion status 06 indicating incorrect data format (see Table 26 on page 198 for a list of signon completion status values.)

The last line of hexadecimal user data returned to the PEM client shows the following **optional** values, which are returned only if there is an error. (The optional values are described in Table 24 on page 195.)

- **04** Length of subfield for sign-on request formatting error, including this 1-byte length value
- 01 Data ID of subfield for sign-on request formatting error
- **000F** Sign-on request formatting error, indicating "data value out of range" (see Table 27 on page 198 for a description of other possible formatting errors).

# Chapter 14. Implementing LU6.1 security

This topic tells you how to implement link security for LU6.1.

For LU6.1 links, CICS cannot check the identity of the requesting system, and the bind request is never rejected on security grounds. You are advised to use the intersystem security offered by LU6.2 links whenever possible. Note that no bind-time or user security can be applied to LU6.1 links.

### Link security with LU6.1

Link security restricts the resources that a user can access, depending on the remote system from which they are accessed.

The practical effect of link security is to prevent a remote user from attaching a transaction or accessing a resource for which the link userid has no authority.

Each link between systems is given an access authority defined by a link userid. A link userid for LU6.1 is a userid defined on your sessions definition for this connection. If not defined there, the link userid is taken to be the SECURITYNAME userid specified on the connection definition. If there is no SECURITYNAME, the link userid is the local region's default userid.

You cannot function ship to CICS without having a security check. However, the security check is minimized if the link userid matches the local region's userid:

- If the userids match, the resource check is made against the local region's default user.
- If the userids do not match, the resource check is carried out against the link userid.

If a failure occurs in establishing link security, the link is given the security of the local region's default user. This would happen if, for example, the preset session userid had been revoked.

# Specifying link security for LU6.1 connections

#### About this task

You specify link security on the CONNECTION or SESSIONS resource definitions. If you require more information about either of these resources, see the *CICS Resource Definition Guide*.

### Procedure

- To specify that all sessions of a connection should have the same link userid, specify the SECURITYNAME attribute of the CONNECTION resource definition. If you do not specify a value for this attribute, CICS uses the default user ID.
- To specify different link userids for individual groups of sessions within a connection, specify the USERID attribute of the SESSIONS resource definition. For each group of sessions, the value specified overrides the SECURITYNAME attribute of the CONNECTION definition.

### Specifying ATTACHSEC with LU6.1

With LU6.1 links, information about the remote user is not available for security purposes. In this case, the authority of the user is taken to be that of the link itself, and you must rely on link security alone to protect your resources.

With LU6.1, you can specify only ATTACHSEC(LOCAL) in the CONNECTION resource definition. Figure 19 shows an example of doing this using CEDA.

```
CEDA DEFINE CONNECTION(name)
GROUP(groupname)
```

ATTACHSEC(LOCAL)

Figure 19. Defining sign-on level for user security with LU6.1

LOCAL is the default value. It specifies that a user identifier is not required from the remote system, and, if one is received, it is ignored. Here, CICS makes the user security profile equivalent to the link security profile. You do not need to specify RACF profiles for the remote users.

### Transaction, resource, and command security with LU6.1

As in a single-system environment, links must be authorized to:

- Attach a transaction
- Access all the resources that the transaction is programmed to use.

This results in security levels called **transaction security**, **resource security**, and **command security**.

### Transaction security

As in a single-system environment, the security requirements of a transaction are specified when the transaction is defined, as described in Chapter 5, "Transaction security," on page 81.

In an LU6.1 environment, a transaction can be initiated only if the link has sufficient authority.

### Resource and command security

Resource and command security in an intercommunication environment are handled in much the same way as in a single-system environment.

CICS performs resource and command security checking only if the installed TRANSACTION definition specifies that they are required; for example, on the CEDA DEFINE TRANSACTION command, as shown in Figure 20 on page 207.

```
CEDA DEFINE TRANSACTION
.
RESSEC(YES)
CMDSEC(YES)
.
```

Figure 20. Specifying resource and command security for transactions

If a transaction definition specifies resource security checking, using RESSEC(YES), the link must have sufficient authority for the resources that the attached transaction accesses.

If a transaction definition specifies command security checking, using CMDSEC(YES), the link must have sufficient authority for the commands (COLLECT, DISCARD, INQUIRE, PERFORM, and SET) that the attached transaction issues.

For further guidance on specifying resource and command security, see Chapter 6, "Resource security," on page 87 and Chapter 8, "CICS command security," on page 121.

#### NOTAUTH exceptional condition

If a transaction tries to access a resource, but fails the resource security checks, the NOTAUTH condition is raised.

When the transaction is the CICS mirror transaction, the NOTAUTH condition is returned to the requesting transaction, where it can be handled in the usual way.

# Function shipping security with LU6.1

When CICS receives a function-shipped request, the transaction that is invoked is the **mirror transaction**.


The CICS-supplied definitions of the mirror transactions all specify resource security checking, but not command security checking. This means that you are prevented from accessing the remote resources if the link does not have the necessary authority.

Note that **transaction routing** across LU6.1 links is not supported.

If the CICS-supplied definitions of the mirror transactions are not what your security strategy needs, you can change them by copying the definitions in group DFHISC into your own group, changing them, and then reinstalling them. For more information, see "Category 2 transactions" on page 147.

If you include a remote resource in your resource definitions, you can arrange for security checking to be done locally, just as if the resource were a local one. Also, the system that owns the resource can be made to apply an independent check, if it is able to receive the user identifier. You can therefore choose to apply security restrictions on both sides, on either side, or not at all.

**Note:** Be aware that if you specify the SYSID option on a function-shipped request, security checking is done in the remote system but is **bypassed in the local system**. Figure 21 on page 208 summarizes what happens.



*Figure 21. Security checking done with and without SYSID.* This example illustrates what security checking is done when a transaction in an application-owning region issues a file control request against a remote file.

- In the application-owning region (AOR), file RFILE is defined as remote, with a name of LFILE in the file-owning region (FOR). Resource security checking is active for the transaction that issues the file control request.
- In the FOR, resource security checking is active for the mirror transaction.

There are two cases. In the first case:

- 1. The transaction in the AOR issues EXEC CICS READ FILE('RFILE'). Resource security checking is performed for file RFILE.
- 2. The request is transmitted to the FOR, where resource security checking is performed for file LFILE.

In the second case:

The transaction in the AOR issues EXEC CICS READ FILE('RFILE') *specifying the SYSID option*. Resource security checking *is not performed* for file RFILE.

The request is transmitted to the FOR, where resource security checking is performed for file LFILE.

For programming information on specifying the SYSID option, see the the CICS *Application Programming Reference*.

### Security checking done in AOR with LU6.1

This section summarizes how security checking is done in the AOR according to how SECURITYNAME is specified in the AOR and TOR, in an LU6.1 environment.

The link userid referred to in Table 28 on page 209 is the one specified in the SECURITYNAME on the CONNECTION definition, or the USERID on the SESSIONS definition.

If a USERID is specified on the SESSIONS definition, and a link check is done, the userid used is the one on the SESSIONS definition.

Table 28 shows how checking is done when ATTACHSEC(LOCAL) is specified.

Neither the region userid for the TOR, nor the SECURITYNAME in the TOR's CONNECTION definition for the AOR, is relevant to security checking in the AOR.

Region userid for AOR	SECURITYNAME in CONNECTION definition	USERID in SESSION definition	Checking in AOR
USERIDA	Not specified	Not specified	Check against AOR DFLTUSER
USERIDA	Not specified	USERIDA	Check against AOR DFLTUSER
USERIDA	Not specified	USERIDB	Check against USERIDB
USERIDA	USERIDA	Not specified	Check against AOR DFLTUSER
USERIDA	USERIDB	Not specified	Check against USERIDB
USERIDA	USERIDA	USERIDA	Check against AOR DFLTUSER
USERIDA	USERIDA	USERIDB	Check against USERIDB
USERIDA	USERIDB	USERIDA	Check against AOR DFLTUSER
USERIDA	USERIDB	USERIDB	Check against USERIDB
USERIDA	USERIDB	USERIDC	Check against USERIDC

Table 28. Security checking done in AOR

# Chapter 15. Implementing IPIC security

These topics tell you how to implement security for IPIC connections. **Related information**: Defining IP interconnectivity links

### **IPIC bind-time security**

A security check can be applied when a request to establish a connection is received from, or sent to, a remote system. This is called *bind-time security*. Its purpose is to prevent an unauthorized system from connecting to CICS.

When CICS uses IPIC to communicate with another CICS region, each CICS system must have an IPCONN resource and a TCPIPSERVICE resource defined.

Each CICS system uses the IPCONN to transmit data to the partner system TCPIPSERVICE, which acts as a receiver. The CICS region that starts the communication is the client, the remote system is the server.

For IPIC, bind security is supported by the exchange of Secure Sockets Layer (SSL) client certificates. To allow two CICS regions to connect successfully, and to prevent an unauthorized system from connecting:

- The SEC system initialization parameter must be "YES" on both regions.
- The IPCONN definitions on both the local and remote regions must specify:
  - SSL(YES).
  - CIPHERS(*cipher_suite_code_list*). This is a string of up to 56 hexadecimal digits that is interpreted as a list of up to 28 2-digit cipher suite codes. When you use CEDA to define the resource, CICS automatically initializes the attribute with a default list of acceptable codes, depending on the level of encryption that is specified by the ENCRYPTION system initialization parameter.
  - Optionally, CERTIFICATE(*X.509_certificate_label*). The named certificate is used as the client certificate, during the SSL handshake when the IPCONN is acquired. If CERTIFICATE is not specified, the default certificate defined in the key ring for the CICS region user ID is used.

The IPCONN defines the *outbound* side of the connection: these settings tell CICS to initiate an SSL handshake. During the SSL handshake, CICS will ask the partner region for the certificate specified on the TCPIPSERVICE. If the remote region TCPIPSERVICE specifies SSL(CLIENTAUTH), the remote system requests the certificate of the originating system as part of the handshake.

- The TCPIPSERVICE definitions on both the local and remote regions specify:
  - PROTOCOL(IPIC).
  - SSL(CLIENTAUTH) or SSL(YES).
  - CIPHERS(*cipher_suite_code_list*).
  - Optionally, CERTIFICATE(*X.509_certificate_label*). The named certificate is used as the server certificate. If CERTIFICATE is not specified, the default certificate defined in the key ring for the CICS region user ID is used.

The TCPIPSERVICE definitions define the *inbound* side of the connection: these settings tell CICS that it must receive a valid SSL client certificate before allowing

the client to acquire the IPCONN. These settings also specify that CICS will send the TCPIPSERVICE CERTIFICATE, or the default, when not specified, as a server certificate to the client.

If the TCPIPSERVICE is specified with SSL(YES), the server does not ask for, nor receive, a client certificate during the handshake.

If the TCPIPSERVICEs in both CICS regions are specified with SSL(YES), both CICS regions are authenticated.

If the TCPIPSERVICEs in both CICS regions are specified with SSL(CLIENTAUTH), both CICS regions are authenticated twice.

For most circumstances, an adequate level of security is achieved by specifying TCPIPSERVICE with SSL(YES) in both regions, or SSL(NO) in one region and SSL(CLIENTAUTH) in the other.

**Note:** If LINKAUTH is specified CERTUSER, the IPCONN must refer to a TCPIPSERVICE that is defined with SSL(CLIENTAUTH).

When the TCPIPSERVICE is specified SSL(NO) on both regions, bind-time security is not possible

If the remote client is trusted by the CICS server, bind time security is not required, however, any user ID and password passed for transaction attach must be valid in the server region's external security manager.

### **IPIC** link security

Link security restricts the resources a user can access, depending on the remote system from which they are accessed. The practical effect of link security is to prevent a remote user from attaching a transaction or accessing a resource for which the link user ID has no authority.

When link security is in use, all requests are given an authority defined by the *link user ID*. For IPCONNs, all requests for a connection have the same link user ID.

#### Specifying IPIC link security

To specify the link user ID of an IPCONN, use the LINKAUTH option to specify how the user ID for link security is established in a CICS system with security initialized (SEC=YES). You can specify the following:

#### CERTUSER

TCP/IP communication with the partner system must be configured for SSL and a certificate must be received from the partner system during SSL handshake.

The IPCONN resource must refer to a TCPIPSERVICE resource that is defined with SSL(CLIENTAUTH).

The received certificate must be defined to the external security manager so that it is associated with a user ID, which is used to establish link security.

#### SECUSER

Specifies that the user ID specified in the SECURITYNAME attribute is used to establish link security.

If you do not specify a value for SECURITYNAME, CICS uses the default user ID.

In a CICS system with security initialized (SEC=YES), the link user ID is used to establish the authority of the remote system. The link user ID must be a valid RACF user ID on this region. Access to protected resources on this region is based on the RACF user profile and its group membership.

At least one security check is always performed when a transaction is attached by a remote user, but the security checks are minimized if the specified link user ID matches the local region user ID:

If the user IDs match, only one security check is made. This is either against the default user (for USERAUTH=LOCAL or DEFAULTUSER) or against the user ID that is in the received inbound attach request (USERAUTH=IDENTIFY or VERIFY).

If the user IDs do not match, then for USERAUTH=LOCAL, resource checks are done only against the link user ID. For USERAUTH=IDENTIFY or VERIFY there are always two resource checks. The first against the link user ID, and the second is against the user ID received from the remote user in the attach request. For USERAUTH=DEFAULTUSER there are always two resource checks. The first against the link userid, and the second is against the default user.

See also "IPIC user security."

If a failure occurs in establishing link security, the link is given the security of the local region's default user. This can happen, for example, when the link user ID has been revoked.

### IPIC user security

User security causes a second check of the received security context that flows from the requestor and under which the transaction operates. The received security context usually contains the user ID of the user running the client.

The security context might identify one of the following types of user:

- A user signed onto a terminal in a TOR
- A user ID of the transaction issuing the DPL request
- A client user of an ECI request

For IPIC connections, the USERAUTH attribute on the IPCONN resource definition specifies the sign-on requirements for incoming requests. It has no effect on requests that are issued by your system to a remote system; these are dealt with by the remote system. The equivalent attribute for MRO and SNA connections is the ATTACHSEC attribute. For more information about the ATTACHSEC attribute and specifying user security with other intercommunications methods, see "Specifying user security in link definitions" on page 170.

For IPIC connections, you can specify the following types of user authentication:

#### LOCAL

CICS does not accept a user ID or password from clients. All requests run under the link user ID or the default user ID if there is no link user ID.

#### IDENTIFY

Incoming attach requests must specify a user identifier. Enter IDENTIFY when the connecting system has a security manager; for example, if it is another CICS system.

Client authentication must be in use or the connecting system must be in the same sysplex.

#### VERIFY

Incoming attach requests must specify a user identifier and a user password. Specify VERIFY when connecting systems are unidentified and cannot be trusted.

#### DEFAULTUSER

CICS does not accept a user ID and password from the partner system. All requests run under the default user ID.

For outbound requests, the level of user security is specified by the USERAUTH attribute of the IPCONN definition installed in the partner system. CICS sends a user ID when USERAUTH(IDENTIFY) is specified, but not when USERID(LOCAL) is specified. Because CICS does not send passwords to remote systems, USERAUTH(VERIFY) is not supported for communication between CICS TS for z/OS systems.

# Establishing a trust relationship when using USERAUTH(IDENTIFY)

Defining an IPCONN resource with USERAUTH(IDENTIFY) means that you are prepared to accept unauthenticated, or asserted, user identifiers on the connection; that is, you are trusting the partner system to transmit only user IDs that have already been authenticated in the partner system. CICS identifies two types of partner, with differing degrees of trust:

#### The partner is outside the local sysplex

If the partner is outside the local sysplex, CICS does not directly trust the partner to assert unauthenticated user IDs unless it identifies itself with a trusted digital certificate. Connections from such partners are therefore only accepted using a secure socket layer connection with client authentication. This type of connection is specified by the attribute SSL(CLIENTAUTH) on the TCPIPSERVICE definition.

If you do not require encryption over the connection, you can suppress the normal encryption that SSL provides by specifying only non-encrypting cipher suites on the attribute CIPHERS(0102) of the TCPIPSERVICE definition.

#### The partner is in the local sysplex

If the partner is in the local sysplex, CICS trusts the partner to assert unauthenticated user IDs without requiring a digital certificate. Connections from these partners are permitted without requiring an SSL connection.

Configure the TCP/IP network so that there is no proxy between CICS and the partner system. If there is a proxy, CICS might not be able to correctly detect if a partner is in the same sysplex. It is strongly recommended that you configure the netaccess security zones to control which other systems within the same sysplex are allowed to communicate with CICS. For further information on network access control, see the *z*/OS Communication Server: IP Configuration Guide. For further information on the **NETACCESS** configuration parameter, see the *z*/OS Communication Server: IP Configuration Reference.

Remote user sign-on status with IPIC I If the IPCONN resource specifies USERAUTH(IDENTIFY), the remote user remains I signed on after the conversation associated with the first attach request is I complete. CICS then accepts attach requests from the same user without a new sign-on until one of the following events occurs: The period specified in the system initialization parameter, USRDELAY, elapses after completion of the last transaction associated with the attach request for this T user. If you are using z/OS 1.11 or later, RACF notifies CICS with a RACF Event Т Notification (ENF) that the profile has been changed. If you alter the RACF profile of a signed-on remote user, CICS continues to use the 1 authorization established at the first attach request until one of the following I situations occurs: • The transaction performs a sync point. T • You are using a z/OS 1.11 system or above and the attach request ends. 1 You are using a system earlier than z/OS 1.11 and the user ID is unused for the 1 I time specified in the **USRDELAY** system initialization parameter.

### IPIC transaction, resource, and command security

As in a single-system environment, users must be authorized to:

- Attach a transaction (transaction security)
- Access all the resources that the transaction is programmed to use. These levels are called **resource security**, **surrogate user security**, and **command security**

### **Transaction security**

As in a single-system environment, the security requirements of a transaction are specified when the transaction is defined, as described in Chapter 5, "Transaction security," on page 81.

In an IPIC environment, two basic security requirements must be met before a transaction can be initiated:

- The link user ID must have sufficient authority to initiate the transaction (see "IPIC link security" on page 212).
- If anything other than USERAUTH(LOCAL) has been specified, user security is in force. The user who is making the request must therefore have sufficient authority to access the system and to initiate the transaction.

### **Resource and command security**

Resource and command security in an intercommunication environment are handled in much the same way as in a single-system environment. Resource and command security checking are performed only if the installed TRANSACTION definition specifies that they are required; for example, on the CEDA DEFINE TRANSACTION command, as shown in Figure 22.

```
CEDA DEFINE TRANSACTION
.
RESSEC(YES)
CMDSEC(YES)
.
```

Figure 22. Specifying resource and command security for transactions

If a TRANSACTION definition specifies resource security checking, using RESSEC(YES), both the link and the user must have sufficient authority for the resources that the attached transaction accesses.

If a TRANSACTION definition specifies command security checking, using CMDSEC(YES), both the link and the user must have sufficient authority for any of the system programming commands shown in Table 10 on page 121 that the attached transaction issues.

For further guidance on specifying resource and command security, see Chapter 6, "Resource security," on page 87 and Chapter 8, "CICS command security," on page 121.

### **CICS routing transaction, CRTE**

1

T

You can use the CICS routing transaction, CRTE, with IPIC, LU6.2, or MRO links to run transactions that are on a connected remote system, instead of defining these transactions as remote in the local system.

CRTE is particularly useful for infrequently used transactions, or for transactions such as CEMT that are on all systems.

Ensure that the terminal through which CRTE is started is defined on the remote system or is defined as shippable in the local system. The terminal operator needs RACF authority if the remote system is protected.

Security checking in the AOR for transactions that run under CRTE does not depend on what is specified on ATTACHSEC (for MRO and LU6.2 links) or USERAUTH (for IPIC links), nor does it depend on the user ID signed on in the TOR. Instead, security checking depends on whether the user signs on when using CRTE:

- If the user does *not* sign on, the surrogate terminal created is associated with the AOR default user. When a transaction is run, the security checks are carried out against this default user. A check is also made against the link user ID to see whether the routing application itself has authority to access the resource.
- If the user *does* sign on, using the CESN transaction while running CRTE, the surrogate points to the user ID of the signed-on user. For transactions attempting to access resources, security checking is made against the user ID of the signed-on user in the surrogate and the link user ID.

#### Related concepts:

Using the routing transaction, CRTE The routing transaction, CRTE, is a CICS-supplied transaction used by a terminal operator to call transactions that are owned by a connected CICS system.

### Security checking done in AOR with IPIC

This depends on how LINKAUTH, SECURITYNAME and USERAUTH are specified in the AOR.

The link user ID shown in the tables Table 29, Table 30 on page 218, and Table 31 on page 218 is determined from the values of LINKAUTH and SECURITYNAME on the IPCONN definition. If LINKAUTH(SECUSER) is specified, the link user ID is determined from the SECURITYNAME attribute. If LINKAUTH(CERTUSER) is specified, the link user ID is determined from the external security manager such as RACF which associates a user ID with the certificate passed by the TOR during SSL handshake. LINKAUTH(SECUSER) is the default. The default value for SECURITYNAME is the default user ID.

If the link user ID is the same as the region user ID for the AOR, then the link is deemed to have the same security as the AOR, and link security is omitted altogether. The effect of omitted link security depends on the value specified with the USERAUTH attribute for the IPCONN in the AOR:

- If USERAUTH(LOCAL) is specified, security checking is done using the link user ID only.
- If USERAUTH(DEFAULTUSER) is specified, only the default user ID for the AOR is used.
- If USERAUTH(IDENTIFY) or USERAUTH(VERIFY) is specified, the link user ID is not used. Only the user ID received from the TOR is used to determine security.

USERAUTH(LOCAL) is the default.

Neither the region user ID for the TOR, nor the link user ID associated with the TOR's IPCONN definition for the AOR, is relevant to security checking in the AOR.

The following table shows how checking is done when USERAUTH(LOCAL) is specified.

Region user ID for AOR	Link user ID	Checking in AOR
USERIDA	Not specified	Check against AOR DFLTUSER
USERIDA	USERIDA	Check against AOR DFLTUSER
USERIDA	USERIDB	Check against USERIDB

Table 29. USERAUTH(LOCAL)

The following table shows how checking is done when USERAUTH(DEFAULTUSER) is specified.

Table 30. USERAUTH(DEFAULTUSER)

Region user ID for AOR	Link user ID	Checking in AOR
USERIDA	Not specified	Check against AOR DFLTUSER
USERIDA	USERIDA	Check against AOR DFLTUSER
USERIDA	USERIDB	Check against USERIDB and AOR DFLTUSER

The following table shows how checking is done when USERAUTH(IDENTIFY) or USERAUTH(VERIFY) is specified.

Region user ID for AOR	Link user ID	Checking in AOR
USERIDA	Not specified	Transmitted user ID and AOR DFLTUSER
USERIDA	USERIDA	Transmitted user ID only
USERIDA	USERIDB	Transmitted user ID and USERIDB

Table 31. USERAUTH(IDENTIFY) and USERAUTH(VERIFY)

# Chapter 16. Implementing MRO security

This topic tells you how to implement CICS multiregion operation (MRO) security.

### Security implications of choice of MRO access method

Either MVS cross-memory services or the CICS Type 3 SVC can be used for interregion communication (function shipping, transaction routing, distributed transaction processing, and asynchronous processing).

If you use cross-memory services, you lose the total separation between systems that is normally provided by separate address spaces.

The risk of accidental interference between two CICS address spaces connected by a cross-memory link is small. However, an application program in either system could access the other system's storage (subject to key-controlled protection) by using a sequence of cross-memory instructions.

If this situation would create a security exposure in your installation, use the CICS type 3 SVC for interregion communication, rather than MVS cross-memory services.

For information about how to specify the access method for MRO, see the the *CICS Intercommunication Guide*.

### **Bind-time security with MRO**

The CICS interregion communication (IRC) facility supports MRO through the use of DFHAPPL.*applid* profiles in the FACILITY class.

There are two phases to bind security checking in DFHIRP, and these occur at:

- Logon time
- Connect time

These security checks, via RACROUTE calls to the SAF interface, are always performed, regardless of whether the or not MRO partner regions are running with external security active for CICS resource security checking (that is, for both SEC=YES and SEC=NO). In order for an MRO connection to be established between two regions, both the logon and connect security checks in both systems must be completed successfully.

### Logon security checking with MRO

Logon security checking is performed whenever a CICS region logs on to the CICS-supplied interregion communication (IRC) program, DFHIRP.

CICS interregion communication uses the external security manager to check that CICS regions logging on to IRC are the regions they claim to be.

Each region that uses the IRC access method must be authorized to RACF in a DFHAPPL.*applid* profile in the RACF FACILITY class. This requires the definition of a DFHAPPL.*applid* profile for each region that logs on to DFHIRP, and that each CICS region userid has UPDATE access to its own DFHAPPL.*applid* profile.

When a batch job connects to a CICS region using IRC, the CICS region logs on to IRC, and requires UPDATE access to its own DFHAPPL *applid* profile as described above.

See Figure 23 on page 221 for an illustration of logon checking.

### Connect security

To perform MRO connect security checking, DFHIRP checks that each CICS region in the connection has read access to its partner's DFHAPPL.*applid* profile.

When CICS Transaction Server for z/OS, Version 4 Release 1 DFHIRP is installed, all regions using earlier CICS releases in the MVS image use the DFHAPPL.*applid* form of MRO connect security. In addition, the SECURITYNAME parameter on the CONNECTION definition is not used for MRO and is ignored.

To authorize the MRO partner regions for bind security purposes, you must define the appropriate DFHAPPL profiles in the RACF FACILITY class. This means that each CICS region in an MRO interregion communication link must be given access to its partner's DFHAPPL.*applid* profile with READ access authority. For example, for the CICS TOR running under userid CICSRTOR (with APPLID CICSATOR), that connects to the AOR running under userid CICSRAOR (with APPLID CICSAAOR), the RACF commands to authorize the connections are shown in Figure 23 on page 221.

You cannot specify to CICS whether or not you want connect security checking for MRO connections—CICS always issues the RACROUTE calls.




Figure 23. Illustration of the DFHIRP logon and connect security checks.

This illustration shows a CICS terminal-owning region (TOR) and CICS application-owning region (AOR) logging on to DFHIRP, and connecting to one another:

- The TOR has an APPLID of CICSATOR and a region user ID of CICSRTOR.
- The AOR has an APPLID of CICSAAOR and a region user ID of CICSRAOR.

During the logon process, DFHIRP calls RACF to check that:

- 1. User ID CICSRTOR has UPDATE access to DFHAPPL.CICSATOR
- 2. User ID CICSRAOR has UPDATE access to DFHAPPL.CICSAAOR

During the connection process, DFHIRP calls RACF to check that:

- 1. User ID CICSRTOR has READ access to DFHAPPL.CICSAAOR
- 2. User ID CICSRAOR has READ access to DFHAPPL.CICSATOR

The TOR and AOR shown in Figure 23, running under region userids CICSRTOR and CICSRAOR respectively, with APPLIDs CICSATOR and CICSAAOR, require the following RACF definitions to authorize their logon to DFHIRP:

 For the MRO logon and connect process: RDEFINE FACILITY (DFHAPPL.CICSATOR) UACC(NONE) RDEFINE FACILITY (DFHAPPL.CICSAAOR) UACC(NONE)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRTOR) ACCESS(UPDATE) PERMIT DFHAPPL.CICSAAOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(UPDATE)
 For connection: PERMIT DFHAPPL.CICSAAOR CLASS(FACILITY) ID(CICSRTOR) ACCESS(READ) PERMIT DFHAPPL.CICSAAOR CLASS(FACILITY) ID(CICSRTOR) ACCESS(READ) PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR CLASS(FACILITY) ID(CICSRAOR) ACCESS(READ)
 PERMIT DFHAPPL.CICSATOR ACCESS(READ)

### Responses from the system authorization facility (SAF)

If the security profile for a specified resource is not retrieved, SAF neither grants nor refuses the access request. In this situation:

IRC rejects the logon or connect request if:

• A security manager was installed, but is either temporarily inactive or inoperative for the duration of the MVS image. This is a fail-safe action, on the grounds that, if the security manager was active, it might retrieve a profile that does not permit access.

IRC allows the logon or connect request if:

- · There is no security manager installed, or
- There is an active security manager, but the FACILITY class is inactive, or there is no profile in the FACILITY class. The logon is allowed in this case because there is no evidence that you want to control access to the CICS APPLID.

Any CICS region without a specific DFHAPPL.*applid* profile, or applicable generic profile, permits all logon and connect requests. No messages are issued to indicate this. To avoid any potential security exposures, you can use generic profiles to protect all, or specific groups of, regions before, or in parallel with, security measures for specific regions. For example, specifying RDEFINE FACILITY (DFHAPPL.*) UACC(NONE)

ensures that any region without a more specific profile is prevented from binding.

### Link security with MRO

Link security restricts the resources that a user can access, depending on the remote system from which they are accessed. The practical effect of link security is to prevent a remote user from attaching a transaction or accessing a resource for which the link userid has no authority.

Each link between systems is given an access authority defined by a link userid. A link userid for MRO is a userid defined on your sessions definition for this connection. Note that for MRO, unlike LU6.2, you can have only one sessions definition per connection, and there can be only one link userid per connection. If there is no preset session userid, the link userid is taken to be the region userid of the TOR region. The SECURITYNAME field on the connection definition is ignored for MRO.

You can never transaction route or function ship to CICS without having at least one security check, but the security checks done are minimized if the link userid matches the local region's userid.

- If the userids match, you will always only have one security check. This will be made either against the local region's default user (for ATTACHSEC=LOCAL) or against the userid in the received FMH-5 attach request (ATTACHSEC=IDENTIFY).
- If the userids do not match, then for ATTACHSEC=LOCAL, resource checks are done only against the link userid. For ATTACHSEC=IDENTIFY you will always have two resource checks. One check is against the link userid, and the other is against the userid received from the remote user in the attach request.

If a failure occurs in establishing link security, the link is given the same security authorization as defined for the local region's default user. This would happen, for example, if the preset session userid had been revoked.

Associate the SESSIONS definition with a RACF user profile that has access to any protected resource to which the inbound transaction needs access. See Chapter 2, "RACF facilities," on page 11 for guidance on defining profiles.

If the sign-on fails, a sign-on failure message is sent to the CSCS security destination, and the link is given the security of the DFLTUSER in the receiving system; that is, it is able to access only those resources to which the default user has access.

### Obtaining the CICS region userid

For the purposes of MRO logon and connect security checks, DFHIRP needs to know the CICS region userid under which the CICS job or task is running. DFHIRP obtains the CICS region's userid by issuing a RACROUTE REQUEST=EXTRACT macro.

If you are not using RACF as your external security manager, you must use the MVS security router exit, ICHRTX00, to customize the response from the RACROUTE REQUEST=EXTRACT macro.

CICS determines whether a security manager is present or not by examining the SAF response codes.

### Specifying link security for MRO connections

#### About this task

For MRO connections, all sessions have the same link userid. If you require more information about the SESSIONS resources, see the CICS Resource Definition Guide.

#### Procedure

Specify the link userid in the USERID attribute of the SESSIONS resource definition. The SECURITYNAME field on the CONNECTION resource definition is ignored for MRO connections.

### User security with MRO

User security causes CICS to make a second check against a user signed on to a terminal, in addition to the link security check described in "Link security with MRO" on page 222. You should consider whether you want the extra level of security checking that user security provides.

You can specify either LOCAL, in which case the user is not checked, or IDENTIFY, in which case a userid is required, but no password is sent.

You specify the sign-on support for each connection using the ATTACHSEC operand of CONNECTION definition, as described in "User security in link definitions" on page 224.

### User security in link definitions

The level of user security you require for a remote system is specified in the ATTACHSEC attribute of the CONNECTION resource definition.

CICS interprets the parameters of the ATTACHSEC attribute as described here. However, special rules apply for CICS transaction routing using CRTE, as described in "Transaction routing security with MRO" on page 227.

The ATTACHSEC attribute specifies the sign-on requirements for incoming requests. It has no effect on requests that are issued by your system to a remote system; these are dealt with by the remote system.

The following values of the ATTACHSEC attribute are valid with MRO:

#### LOCAL

specifies that a user identifier is not required from the remote system, and if one is received, it is ignored. Here, CICS makes the user security profile equivalent to the link security profile. You do not need to specify RACF profiles for the remote users. (LOCAL is the default value.)

Specify ATTACHSEC(LOCAL) if you think that the link security profile alone provides sufficient security for your system.

#### IDENTIFY

specifies that a user identifier is expected on every attach request. All remote users of a system must be identified to RACF.

Specify ATTACHSEC(IDENTIFY) when you know that CICS can trust the remote system to verify its users, when, for example, the remote system is another CICS.

The following rules apply to IDENTIFY:

- If a password is included in an attach request with a user identifier on a link with ATTACHSEC(IDENTIFY), CICS rejects the attach request and unbinds the session.
- If a null user identifier or an unknown user identifier is received, CICS rejects the attach request.
- If no user identifier is received, the attach is rejected unless USEDFLTUSER(YES) is specified on the connection. In this case CICS applies the security capabilities of the default user, as specified in the DFLTUSER system initialization parameter. For more information, see "The CICS default user ID" on page 7.

**Note:** In the case of distributed transaction processing (DTP) transactions, you must issue a BUILD ATTACH request before the MRO SEND or CONVERSE command to include the userid of the terminal user in an attach request.

#### Remote user sign-on status with MRO

With the ATTACHSEC(IDENTIFY) parameter, the remote user remains signed on after the conversation associated with the first attach request is complete.

CICS then accepts attach requests from the same user without a new sign-on until one of the following events occurs:

• The period specified in the **USRDELAY** USRDELAY system initialization parameter elapses after completion of the last transaction associated with the attach request for this user.

	<ul> <li>From z/OS 1.11 onwards, CICS is notified of certain changes in the RACF profile of a signed-on remote user or a signed-on user who is not directly using a physical terminal or console through a type 71 RACF Event Notification (ENF). For example, CICS is notified when you use the REVOKE option on the ALTUSER command, with no date specified, to revoke a user ID with immediate effect. However, CICS is not notified when a user ID expires. When a RACF profile change occurs and CICS receives a new attach request for a user ID, CICS performs an implicit sign-on for the user ID and the new RACF profile information is used. Existing tasks for that user continue with the RACF profile that was valid when the task was attached.</li> <li>The CICS region shuts down.</li> </ul>
   	If you alter the RACF profile of a signed-on remote user, CICS continues to use the authorization established at the first attach request until one of the following situations occurs:
I	The transaction performs a sync point.
I	• You are using a z/OS 1.11 system or above and the attach request ends.
1	• You are using a system earlier than z/OS 1.11 and the user ID is unused for the time specified in the <b>USRDELAY</b> system initialization parameter.

## Information about remote users

With MRO links, information about the user can be transmitted with the attach request from the remote system.

This means that you can protect your resources not only on the basis of which remote system is making the request, but also on the basis of which actual user at the remote system is making the request.

This section describes some of the concepts associated with remote-user security, and how CICS sends and receives user information.

You will have to define your users to RACF. If a remote user is not defined to RACF, any attach requests from that remote user are rejected.

CICS sends userids on ATTACHSEC(IDENTIFY) conversations. Table 32 shows how CICS decides which userid to send.

Characteristics of the local task	User identifier sent by the TOR to the AOR
Task with associated terminal—user identifier	Terminal user identifier
Task with associated terminal—no user signed on and no USERID specified in the terminal definition	Default user identifier from the TOR
Task with no associated terminal or USERID, started by interval control START command (if using function shipping or DTP)	User identifier for the task that issued the START command
Task started with USERID option	User identifier specified on the START command
CICS internal system task	CICS region userid

Table 32. MRO attach-time user identifiers

Table 32. MRO attach-time user identifiers (continued)

Characteristics of the local task	User identifier sent by the TOR to the AOR
Task with no associated terminal, started by transient data trigger	User identifier specified on the transient data destination definition that defines the queue
Task with associated terminal, started by transient data trigger	Terminal user identifier
Task started from PLTPI	User identifier specified by the PLTPIUSR system initialization parameter

### Transaction, resource, and command security with MRO

As in a single-system environment, users must be authorized to:

- Attach a transaction.
- Access all the resources that the transaction is programmed to use. This results in security levels called transaction security, resource security, and command security.

### Transaction security

As in a single-system environment, the security requirements of a transaction are specified when the transaction is defined, as described in Chapter 5, "Transaction security," on page 81.

In an MRO environment, two basic security requirements must be met before a transaction can be initiated:

- The link must have sufficient authority to initiate the transaction.
- The "user" who is making the request must have sufficient authority to access the system and to initiate the transaction.

### **Resource and command security**

Resource and command security in an intercommunication environment are handled in much the same way as in a single-system environment.

#### When resource and command security checking are performed

Resource and command security checking are performed only if the installed transaction definition specifies that they are required; for example, on the CEDA DEFINE TRANSACTION command, as shown in Figure 24.

```
CEDA DEFINE TRANSACTION
.
RESSEC(YES)
CMDSEC(YES)
.
```

Figure 24. Specifying resource and command security for transactions

If a transaction specifies resource security checking, using RESSEC(YES), both the link and the user must also have sufficient authority for the resources that the attached transaction accesses.

If a transaction specifies command security checking, using CMDSEC(YES), both the link and the user must also have sufficient authority for the commands (shown in Table 10 on page 121) that the attached transaction issues.

For further guidance on specifying resource and command security, see Chapter 6, "Resource security," on page 87 and Chapter 8, "CICS command security," on page 121.

#### **NOTAUTH exceptional condition**

If a transaction tries to access a resource, but fails the resource security checks, the NOTAUTH condition is raised.

When the transaction is the CICS mirror transaction, the NOTAUTH condition is returned to the requesting transaction, where it can be handled in the usual way.

### Transaction routing security with MRO

In transaction routing, the authority of a user to access a transaction can be tested in both the TOR and the AOR.

In the TOR, a normal test is made to ensure that the user has authority to access the transaction defined as remote, just as if it were a local transaction. This test determines whether the user is allowed to run the relay program.

In the AOR, the transaction has as its principal facility a remote terminal (the "surrogate" terminal) that represents the "real" terminal in the TOR. The way in which the remote terminal is defined (see *CICS Intercommunication Guide*) affects the way in which user security is applied.

- If the definition of the remote terminal does not specify the USERID parameter:
  - For links with ATTACHSEC(IDENTIFY), the transaction security and resource security of the user are established when the remote user is signed on. The userid under which the user is signed on, whether explicitly or implicitly (in the DFLTUSER system initialization parameter), has this security capability assigned in the remote system.
  - For links with ATTACHSEC(LOCAL), transaction security, command security, and resource security are limited by the authority of the link.

In both cases, tests against the link security are made as described in "Link security with MRO" on page 222.

**Note:** During transaction routing, the 3-character operator identifier from the TOR is transferred to the surrogate terminal entry in the AOR. This identifier is not used for security purposes, but it may be referred to in messages and audit trails.

When transaction routing a PSB request, the following conditions must both be satisfied:

- ATTACHSEC on the connection definition must not be LOCAL (that is, it can be IDENTIFY, PERSISTENT, MIXIDPE, or VERIFY).
- PSBCHK=YES must be specified as a system initialization parameter in the remote system.

### Preset-security terminals and transaction routing

Preset-security for a terminal is determined by the specification of the USERID parameter.

When considering the security aspects of transaction routing from a preset-security terminal, remember that preset-security is an attribute of the terminal rather than of the user who is performing the transaction routing request.

During transaction routing, CICS creates a surrogate terminal in the AOR to represent the terminal at which the transaction routing request was issued. Whether the surrogate terminal has preset- security or not depends upon a number of factors:

- If a remote terminal definition exists in the AOR for the terminal at the TOR, and specifies the USERID parameter, the surrogate terminal is preset with this userid. If the USERID parameter is not coded, the surrogate terminal does not have preset-security.
- If a remote terminal definition does not exist in the AOR, the preset-security characteristics of the surrogate terminal are determined from the terminal definition shipped from the TOR. If the shipped terminal definition has preset security, the surrogate also has preset security, unless the connection to the AOR is defined with ATTACHSEC=LOCAL, in which case any preset security information shipped to the AOR is ignored.

### **CICS** routing transaction, CRTE

You can use the CICS routing transaction, CRTE, with IPIC, LU6.2, or MRO links to run transactions that are on a connected remote system, instead of defining these transactions as remote in the local system.

CRTE is particularly useful for infrequently used transactions, or for transactions such as CEMT that are on all systems.

Ensure that the terminal through which CRTE is started is defined on the remote system or is defined as shippable in the local system. The terminal operator needs RACF authority if the remote system is protected.

Security checking in the AOR for transactions that run under CRTE does not depend on what is specified on ATTACHSEC (for MRO and LU6.2 links) or USERAUTH (for IPIC links), nor does it depend on the user ID signed on in the TOR. Instead, security checking depends on whether the user signs on when using CRTE:

- If the user does *not* sign on, the surrogate terminal created is associated with the AOR default user. When a transaction is run, the security checks are carried out against this default user. A check is also made against the link user ID to see whether the routing application itself has authority to access the resource.
- If the user *does* sign on, using the CESN transaction while running CRTE, the surrogate points to the user ID of the signed-on user. For transactions attempting to access resources, security checking is made against the user ID of the signed-on user in the surrogate and the link user ID.

#### **Related concepts:**

Using the routing transaction, CRTE The routing transaction, CRTE, is a CICS-supplied transaction used by a terminal operator to call transactions that are owned by a connected CICS system.

# Function shipping security with MRO

When CICS receives a function-shipped request, the transaction that is invoked is the **mirror transaction**.

|

T

The CICS-supplied definitions of the mirror transactions all specify resource security checking, but not command security checking. This means that you are prevented from accessing the remote resources if either the link or your user profile on the other system does not have the necessary authority.

If the CICS-supplied definitions of the mirror transactions are not what your security strategy needs, you can change them by copying the definitions in group DFHISC into your own group, changing them, and then reinstalling them. For more information, see "Category 2 transactions" on page 147.

If you include a remote resource in your resource definitions, you can arrange for security checking to be done locally, just as if the resource were a local one. Also, the system that owns the resource can be made to apply an independent check, if it is able to receive the user identifier. You can therefore choose to apply security restrictions on both sides, on either side, or not at all.

**Note:** If you specify the SYSID option on a function-shipped request, security checking is done in the remote system but is **bypassed in the local system**. Figure 25 on page 230 summarizes what happens.




Figure 25. Security checking done with and without SYSID.

This example illustrates what security checking is done when a transaction in an application-owning region issues a file control request against a remote file.

- In the application-owning region (AOR), file RFILE is defined as remote, with a name of LFILE in the file-owning region (FOR). Resource security checking is active for the transaction that issues the file control request.
- In the FOR, resource security checking is active for the mirror transaction.

There are two cases. In the first case:

- 1. The transaction in the AOR issues EXEC CICS READ FILE('RFILE'). Resource security checking is performed for file RFILE.
- 2. The request is transmitted to the FOR, where resource security checking is performed for file LFILE.

In the second case:

- 1. The transaction in the AOR issues EXEC CICS READ FILE('RFILE') *specifying the SYSID option*. Resource security checking *is not performed* for file RFILE.
- **2.** The request is transmitted to the FOR, where resource security checking is performed for file LFILE.

For programming information on specifying the SYSID option, see the CICS *Application Programming Reference* manual.

### Distributed program link security with MRO

The CICS distributed program link (DPL) facility enables a program (the client program) to call a CICS program (the server program) in a remote CICS region. The client program may be a CICS program or a non-CICS program.

A CICS client program uses DPL by specifying the SYSID option on the EXEC CICS LINK PROGRAM command, or omitting the SYSID option if the REMOTESYSTEM option of the program resource definition already specifies a

remote CICS region. When the SYSID option on the EXEC CICS LINK command specifies a remote CICS system, the client region does not perform any resource security checking, but leaves the resource check to be performed in the server region.

A non-CICS client program uses calls to DFHXCIS to open a line to the CICS system, and then to link to a CICS program. This is called the external CICS interface (EXCI). One of the parameters of the link call is the transaction identifier under which the server program is to run. Define this transaction to CICS as running program DFHMIRS and as using profile DFHCICSA. Another parameter of the link call is the client's userid, which is validated if the MRO connection has been defined with ATTACHSEC(IDENTIFY).

To use the userid parameter in the DFHXCIC call, the client program must have surrogate-user authority to the specified userid. For more information, see "Surrogate user checking for EXCI calls" on page 116.

The client program receives a USER_ERROR error if the external CICS interface command fails the security check. However, this error can have other causes; each reason code value for a USER_ERROR response indicates whether the command can be reissued directly, or whether the pipe being used has to be closed and reopened first.

The server program is executed by a mirror transaction, in a similar way to other function-shipped CICS requests. However, the transaction name associated with the mirror depends on how the program link is invoked in the client region. You must be aware of the transaction name because normal attach security applies to the mirror transaction:

- If a transaction identifier is specified on the link request, the specified transaction name is used for the mirror.
- If the transaction is omitted from the link request, but the TRANSID option is used in the program resource definition in the client region, the name for the mirror is taken from the program's TRANSID specification.
- Otherwise, the default name of CSMI is used for the mirror transaction.

Authorize users to access the transaction name that the mirror runs under. The userids to be authorized depend on whether LOCAL or IDENTIFY attach security is being used, and are described in "Security checking done in AOR with MRO" on page 232. If you define the mirror transaction with RESSEC(YES) in the server region, authorize these userids to access the server program that is being linked to by the mirror. If the server program accesses any CICS resources, authorize the same userids to access them. If the server program invokes any SP-type commands, and the mirror transaction is defined with CMDSEC(YES) in the server region, authorize the same userids to access the commands.

If the mirror transaction cannot be attached because of security reasons, the NOTAUTH condition is not raised, but the TERMERR condition is returned to the issuing application in the client region. If the mirror transaction is successfully attached, but it is not authorized to link to the distributed program in the server region, the NOTAUTH condition is raised. The NOTAUTH condition is also raised if the server program fails to access any CICS resources for security reasons.

The server program is restricted to a DPL subset of the CICS API commands when running in a server region. The commands that are not supported include some that return security-related information. For programming information about which commands are restricted, see the *CICS Application Programming Reference*. For further information about DPL, refer to CICS distributed program link*CICS Intercommunication Guide*.

# Security checking done in AOR with MRO

This section summarizes how security checking is done in the AOR.

The userid of the front-end CICS region is assigned as the default. However, if a USERID is specified on the SESSIONS definition, and a link check is done, the userid used is the one on the SESSIONS definition.

The region userid referred to in Table 33 through Table 34 is the USERID on the SESSIONS definition. The userid referred to in this case is the one under which the job is running. This userid is the one normally returned by the security manager domain.

### With ATTACHSEC(LOCAL) specified

Table 33 shows how checking is done in the AOR when ATTACHSEC(LOCAL) has been specified.

Region userid for AOR	Userid in session definition	Region userid for TOR	Checking in AOR
USERIDA	Not specified	USERIDA	Check against AOR DFLTUSER
USERIDA	USERIDA	Anything	Check against AOR DFLTUSER
USERIDA	Not specified	USERIDB	Check against USERIDB
USERIDA	USERIDB	Anything	Check against USERIDB

Table 33. Security checking done in AOR—ATTACHSEC(LOCAL) specified

### With ATTACHSEC(IDENTIFY) specified

Table 34 shows how checking is done in the AOR when ATTACHSEC(IDENTIFY) has been specified.

Table 34. Security checking done in AOR—ATTACHSEC(IDENTIFY) specified

Region userid for AOR	Userid in session definition	Region userid for TOR	Checking in AOR
USERIDA	Not specified	USERIDA	FMH-5 ATTACH check only
USERIDA	USERIDA	Anything	FMH-5 ATTACH check only
USERIDA	Not specified	USERIDB	FMH-5 ATTACH check and USERIDB
USERIDA	USERIDB	Anything	FMH-5 ATTACH check and USERIDB

# Chapter 17. Security for data tables

This topic describes how to provide security for CICS shared data tables and coupling facility data tables.

### Security for CICS shared data tables

To provide security for a shared data table when **cross-memory services** are used, ensure that:

- The file-owning region (FOR) that is acting as the shared data table server cannot be impersonated. See "SDT server authorization security check" on page 234 for details of how you ensure this.
- An application-owning region (AOR) cannot gain access to data that it is not meant to access. You can prevent this by checking at CONNECT time that the AOR is allowed access to the FOR and, if file security is in force, that the AOR is allowed access to the requested file.

These security checks are performed through the system authorization facility (SAF), to invoke RACF or an equivalent security manager.

**Note:** A region is still able to use data tables locally even if it does not have authority to act as a shared data table server.

The CICS shared data tables (SDT) facility reproduces the main characteristics of function-shipping security that operate at the region level, but note the following differences:

- SDT does not provide any mechanism for the FOR to perform security checks at the transaction level (there is no equivalent of ATTACHSEC(IDENTIFY) or ATTACHSEC(VERIFY)). Therefore, if you consider that the transaction-level checks performed by the AOR are inadequate for some files, ensure that those files are not associated with data tables in the FOR.
- SDT does not support any equivalent of preset security on SESSIONS, because no sessions are used.
- SDT does not pass any installation parameter list (INSTLN) information to the security user exits.

Security for CICS shared data tables is covered in the following topics:

- "Security checking for data tables"
- "SDT server authorization security check" on page 234
- "CONNECT security checks for AORs" on page 234.

### Security checking for data tables

You should consider the implications of the security checks before sharing a file that is associated with a data table.

SDT security makes use of existing CICS file security definitions, but it also relies on treating SDT server APPLIDs as protected resources. An SDT server's APPLID is represented by a DFHAPPL.*applid* profile in the RACF FACILITY resource class.

### SDT server authorization security check

When a region attempts to be an SDT server, it calls RACF to check whether its user ID has the required access authority to its APPLID.

If the call fails, the region cannot initialize the required SDT support to be a server. This minimizes the risk that an AOR might accept **counterfeit data records** from an FOR that is not properly authorized to act as an SDT server. This check is never bypassed, even when SEC=NO is specified at system initialization.

To act as a server for a protected APPLID, an SDT FOR's userid must have UPDATE (or higher) access to its DFHAPPL.*applid* profile in the FACILITY class. In the following example definitions, the APPLID of the FOR is CICSHF01, and its user ID is CICSSDT1:

RDEFINE FACILITY (DFHAPPL.CICSHF01) UACC(NONE)

PERMIT DFHAPPL.CICSHF01 CLASS(FACILITY) ID(CICSSDT1) ACCESS(UPDATE)

The above example authorizes one FOR to act as a server with APPLID CICSHF01, running under user ID CICSSDT1. The following example shows how to authorize a group of FORs, with user IDs defined as members of group SDTGRP1, to act as SDT servers using a generic profile in the FACILITY class:

RDEFINE FACILITY (DFHAPPL.CICSTST*) UACC(READ)

PERMIT DFHAPPL.CICSTST* CLASS(FACILITY) ID(SDTGRP1) ACCESS(UPDATE)

#### If SAF neither grants nor refuses an access request

If a security profile for a specified resource is not retrieved, SAF neither grants nor refuses the access request.

In this situation:

- The request fails if a security manager is installed but is either temporarily inactive or inoperative for the duration of this MVS IPL. This decision is made on the grounds that had the security manager been active it might have retrieved a profile that refuses access.
- The request succeeds if:
  - There is no security manager at all.
  - There is an active security manager but the FACILITY class is undefined or inactive.
  - There is no profile covering the APPLID in question.

The request is allowed in these cases because there is no evidence that you want to control access to the particular FOR APPLID.

### CONNECT security checks for AORs

The security checks performed at CONNECT time provide two levels of security:

- **Bind security** allows an FOR that runs without CICS file security to be able to restrict shared access to selected AORs. (Running without file security minimizes runtime overheads and the number of security definitions.)
- **File security** can be activated in the FOR if you want SDT to implement those checks that apply to the AOR as a whole.

Note that SDT provides no way of implementing those security checks that an FOR makes at the transaction level when ATTACHSEC(IDENTIFY) or ATTACHSEC(VERIFY) is used with function shipping.

### **Bind security**

To be allowed shared access to any of an FOR's data tables, an AOR's userid needs READ (or higher) access to the FOR's DFHAPPL.

*applid* in the FACILITY class. This check is never bypassed, even when SEC=NO is specified at system initialization. In the following example definitions, three CICS AORs (userids is CICSAOR1, CICSAOR2, and CICSAOR3) all require SDT access to the FOR represented by the DFHAPPL.CICSHF01 profile:

PERMIT DFHAPPL.CICSHF01 CLASS(FACILITY) ID(CICSAOR1 CICSAOR2 CICSAOR3) ACCESS(UPDATE)

Cases when SAF neither grants nor refuses access are resolved in the same way as for server LOGON (see "If SAF neither grants nor refuses an access request" on page 234). If the result is a refusal, CICS does not permit shared access by the AOR to the FOR's APPLID.

Note that controlling SDT server authorization security and bind security by using different (but hierarchical) levels of access to the same resource has the following consequences:

- Any region with the same userid as a server can always bind to that server.
- It is impossible to control which userids can bind to a given APPLID without also controlling which userids can log on as servers for that APPLID.

SDT bind-time security uses different definitions from those employed by ISC and (if using preset sessions) MRO. Therefore, unless you make them consistent, SDT access might be granted when function shipping attempts are rejected, or vice versa. Both MRO and SDT use the same class and so, with ISC only, SDT CONNECT security might react to changes in security definitions either earlier or later than function shipping.

If file security is not in force in the FOR (that is, if SEC=NO or XFCT=NO was specified at system initialization), an AOR that is allowed to bind to an FOR is also allowed to access all that FOR's shared data tables.

If file security is in force, an AOR that is allowed to bind is still allowed free access if the userids of the AOR and FOR are the same (undefined userids are not considered to be the same).

#### File security

After the bind-security check, and when file security is in force in the FOR, the FOR checks whether the AOR is authorized to "sign on" to the FOR.

This security check is optional, and applies only when the userid of the AOR is different from that of the FOR. It is the equivalent of ATTACHSEC(LOCAL) in an MRO environment (see "User security with MRO" on page 223). The AOR also requires READ authorization to the file it is trying to access in the FOR.

To implement file security checking by the FOR:

- Initialize the FOR with system initialization parameter SEC=YES
- Authorize the AOR with READ access to the FOR's APPLID profile in the APPL general resource class
- Specify the appropriate value on the XFCT system initialization parameter
- Authorize the AOR's region user ID with READ access to the required files in the file resource profiles named on the XFCT system initialization parameter.

For example, define the APPL profile for an FOR with APPLID CICSHF01, and the PERMIT command to enable the AORs with user IDs CICSAOR1 and CICSAOR2 to sign on to CICSHF01, as follows:

RDEFINE APPL CICSHF01 UACC(NONE) NOTIFY(sys_admin_userid) PERMIT CICSHF01 CLASS(APPL) ID(CICSAOR1 CICSAOR2) ACCESS(READ)

For information about authorizing access to files, see "Security for files" on page 97.

Cases when SAF neither grants nor refuses the request are resolved in the same way as for server LOGON (see "If SAF neither grants nor refuses an access request" on page 234).

If the userid is allowed to sign on to the FOR's application, the CONNECT request succeeds unless the AOR's userid is not allowed to read the specified file. Otherwise, the CONNECT request is treated in the same way as when the AOR's userid is undefined.

When file security is in force in an FOR, and the userid of the AOR is *undefined*, a CONNECT request fails unless the FOR's default userid (specified by the DFLTUSER system initialization parameter) is allowed to read the specified file.

Function shipping detects that an AOR's access to a file has been revoked when a rebuild of the file control resource class is completed in the FOR. However, if a valid connection already exists, SDT continues to allow access until something causes the connection to be broken. See "Refreshing resource profiles in main storage" on page 22.

**Caution:** If you use ISC instead of MRO for function shipping, ensure that the value of the SECURITYNAME parameter in the FOR is the same as the userid of the AOR. Otherwise, the SDT CONNECT and function shipping security checks will be inconsistent.

### Security for coupling facility data tables

CICS and MVS use RACF facilities to provide security for coupling facility data tables in the following areas:

- 1. Authorizing server access to a coupling facility list structure
- 2. Authorizing the server
- 3. Authorizing a CICS region's access to a coupling facility data table pool
- 4. Authorizing a CICS region to a CFDT
- 5. File resource security checking.

With the exception of items 4 and 5, which are optional, the other security checks are made automatically and are never bypassed. For items 2 and 3 in the above list, in cases when the system authorization facility (SAF) neither grants nor refuses access are resolved in the same way as the LOGON security check for CICS shared data table support (see "SDT server authorization security check" on page 234 for details).

An optional security check, which is controlled by server startup parameters, is provided for controlling access to specific tables within a coupling facility data table pool. This is described under "Authorizing a CICS region to a coupling facility data table" on page 237.

### Authorizing server access to a list structure

Each coupling facility data table server requires access to the coupling facility list structure that contains its pool of coupling facility data tables.

To permit access, give the server region user ID ALTER access to a FACILITY class general resource profile called IXLSTR.*structure_name*. Structure names for coupling facility data tables take the form DFHCFLS_*poolname*.

For example, if coupling facility data tables are defined in a pool called PRODCFT1, the list structure for this pool is named DFHCFLS_PRODCFT1 in the CFRM policy. To access this list structure, the server user ID for pool PRODCFT1 requires ALTER access to the IXLSTR profile, defined as follows:

RDEFINE FACILITY IXLSTR.DFHCFLS_PRODCFT1 UACC(NONE) PERMIT IXLSTR.DFHCFLS_PRODCFT1 CLASS(FACILITY) ID(server_userid) ACCESS(ALTER)

### Authorizing the server

When a CFDT server starts up for a given coupling facility data table pool CICS authorized cross-memory (AXM) services calls RACF to establish that it is authorized to act as a server for that pool. To authorize a coupling facility data table server to act as a server for its specified pool, give the server region user ID CONTROL access to a FACILITY class general resource profile called DFHCF.*poolname*.

For example, if the pool is PRODCFT1, define the profile and the required PERMIT statement as follows

RDEFINE FACILITY DFHCF.PRODCFT1 UACC(NONE) PERMIT DFHCF.PRODCFT1 CLASS(FACILITY) ID(server_userid) ACCESS(CONTROL)

### Authorizing a CICS region to a CFDT pool

Each CICS region requires authorization to connect to a coupling facility data tablepool. To authorize a CICS region to connect to a server and its pool, give the CICS region UPDATE access to the server's FACILITY class profile for the pool.

For example, if the pool is PRODCFT1, define the required PERMIT statement as follows:

PERMIT DFHCF.PRODCFT1 CLASS(FACILITY) ID(CICS_region_userid) ACCESS(UPDATE)

### Authorizing a CICS region to a coupling facility data table

In addition to controlling a CICS region's access to a coupling facility data table pool, you can optionally control access to each CFDT in the pool.

This security check, if active, is performed by the server each time a CICS region connects to a coupling facility data table for the first time. The resource security check is done as if for a CICS file owned by the coupling facility data table server region, using a profile defined in the general resource class specified on the SECURITYCLASS server initialization parameter. The default for this is the FCICSFCT class. For the profile name, use the table name as defined in the file resource definition.

You can optionally prefix the profile name using the server region user ID as the prefix by specifying SECURITYPREFIX=YES as a server initialization parameter. You can customize the prefix for this security check using the server initialization parameter SECURITYPREFIXID.

The coupling facility data table server performs the table security check by issuing a cross-memory mode FASTAUTH check, which requires the use of global in-storage security profiles. Access fails if a return code other than zero is received by the server in response to the FASTAUTH check. If the external security manager does not support cross-memory mode FASTAUTH or global in-storage profiles, coupling facility data table security checks are not possible and an error message is issued at server initialization time if table security checking is specified. For information about all server initialization parameters that can be specified, see the *CICS System Definition Guide* 

### File resource security checking

Normal CICS resource security for files is supported for coupling facility data tables. CICS performs the usual file resource security checks against signed-on users of transactions that access coupling facility data tables, using profiles defined in the general resource class named on the XFCT system initialization parameter.

See "Security for files" on page 97 for details of CICS file security.

# Part 4. Security for TCP/IP clients

This part discusses how you can secure your applications when CICS participates in a client-server configuration, using TCP/IP communication protocols.

# Chapter 18. About security for TCP/IP clients

TCP/IP connections between clients and servers — especially when they use the internet — are vulnerable to attack by malicious parties.

An attacker might attempt to:

- Read confidential information flowing between client and server. You can protect your system by encrypting data that flows between the client and server.
- Falsify information flowing between client and server.

You can protect your system by encrypting data that flows between the client and server, and by detecting data that has been tampered with.

• Impersonate a legitimate user of a client system.

You can protect your system by authenticating users.

CICS supports several schemes for authenticating users. See "Identification and authentication" on page 244 for more information.

CICS can use the Secure Sockets Layer (SSL) security protocol or the Transport Layer Security (TLS) protocol to support secure TCP/IP connections. See "Support for security protocols" on page 252 for more information.

### Message protection

*Message protection* is a term that describes the techniques used to ensure that a confidential message cannot be observed in transit, and cannot be illicitly changed.

The two aspects of message protection are:

#### Confidentiality

Protecting the message content from being intercepted

### Integrity

Protecting a message from illicit modification

*Confidentiality* is achieved by encrypting the message (or parts of it) using a public key encryption scheme, so that only the intended recipient of the message can read it.

*Integrity* is achieved by digitally signing the message, so that the intended recipient can be confident that the message has not been changed illicitly.

### Public key encryption

Public key encryption is a cryptographic system that uses two keys - a *public key* that is potentially known to everyone and a related *private key* that is known only to one party in an exchange of information.

The private and public keys used for public key encryption are related to each other in such a way that:

 It is not feasible to deduce the value of the private key from the public key, nor the public key from the private key. While the private key must be stored securely, and not made known to anyone but its owner, the public key can be made freely available to any user, with no risk of compromising the security of the private key.

• Information encrypted using the public key can be decrypted only with the private key.

Information can be encrypted by any user, and sent securely to the holder of the private key: data encrypted with the public key is readable by only the holder of the private key.

• Information encrypted using the private key can be decrypted only with the public key.

Only the holder of the private key can encrypt information that can be decrypted with the public key. Any party can use the public key to read the encrypted information; however, data that can be decrypted with the public key is guaranteed to originate with the holder of the private key.

Knowledge of a public key does not guarantee the identity of the owner of the corresponding private key, and so encryption of information with a public key cannot, on its own, prevent encrypted information falling into the wrong hands. Before a public key can be safely used to encrypt or decrypt information, the identity of the holder of the private key must be assured. This assurance is provided by a *digital certificate* which binds the public key to the identity of the private key's owner.

## Digital signatures

A digital signature is information that is attached to data to assure the recipients of the data that it has not been altered and has originated from the signer of the message. Digital signatures perform an equivalent function to a handwritten signature on a paper document.

A digital signature consists of a *message digest* encrypted with the message sender's private key. The message digest, which is much shorter than the original message, is created from the message using a process known as *hashing*. It is not possible to reconstruct the original message from the message digest. The message, when combined with the signature, is a *signed message*.

The receiver of a signed message attempts to decrypt the signature using the sender's public key, thus changing it back into a message digest. Success indicates that the message was signed by the sender, because only the sender has the private key. The receiver then hashes the document data into a message digest, and compares it with the message digest obtained by decrypting the signature. If both digests are the same, the receiver can be sure that the signed message has not been changed.

A digital signature does not provide confidentiality. In other words, data that is not encrypted data can bear a digital signature.

Knowledge of a public key does not guarantee the identity of the owner of the corresponding private key, and so encryption of information with a public key cannot, on its own, prevent encrypted information falling into the wrong hands. Before a public key can be safely used to encrypt or decrypt information, the identity of the holder of the private key must be assured. This assurance is provided by a *digital certificate* which binds the public key to the identity of the private key's owner.

# **Digital certificates**

A digital certificate is a digitally signed data structure that binds a public key to the identity of the private key's owner. The use of digital certificates ensures that the user of a public key can be confident of the ownership of the corresponding private key.

Digital certificates are issued by a trusted body, known as a Certificate Authority (CA), that is typically independent of the message sender and receiver (although if there is a trust relationship between the sender and the receiver, the certificate can be issued by one or the other). The certificate is encrypted with the CA's private key, and can be decrypted using the CA's public key, which is freely available to anyone who needs to read the certificate.

Following decryption, a valid certificate assures the reader that the certificate was indeed issued by the CA, and that the certificate has not been tampered with or forged.

A digital certificate contains information that identifies the certificate owner, and the certificate owner's public key, and is digitally signed by the CA. The receiver of a message containing a certificate uses the CA's public key to decrypt the certificate, verifies that it was issued by the CA and then obtains the sender's public key and identification information held within the certificate.

### X.509 Certificates

ITU-T recommendation X.509 defines a widely used format for digital certificates.

An X.509 certificate contains

- Two *distinguished names*, which uniquely identify the Certificate Authority (CA), that issued the certificate and the *subject* (the individual or organization to whom the certificate was issued). The distinguished names contain several optional components:
  - Common name
  - Organizational unit
  - Organization
  - Locality
  - State or Province
  - Country

• A digital signature. The signature is created by the certificate authority using the public-key encryption technique:

- 1. A secure hashing algorithm is used to create a digest of the certificate's contents.
- 2. The digest is encrypted with the certificate authority's private key.
- **3**. The signature is decrypted with the CA's public key.
- 4. A new digest of the certificate's contents is made, and compared with the decrypted signature. Any discrepancy indicates that the certificate may have been altered. The digital signature thus assures the receiver that no changes have been made to the certificate since it was issued.
- The subject's domain name. The receiver compares this with the actual sender of the certificate.
- The subject's public key.

# Identification and authentication

*Identification* is the process by which the identity of a user is established, and *authentication* is the process by which a service confirms the claim of a user to use a specific identity by the use of credentials (usually a password or a certificate).

# Identification

In CICS, identification can be accomplished in several ways:

• The client can supply a user ID directly. Typically this is done as part of the authentication process.

You can identify users in this way when you use basic authentication with the ECI and HTTP application protocols.

• The client can supply information other than a user ID (for example, an SSL client certificate) during the authentication process. The information is mapped to a user ID in the security manager.

You can identify users in this way when you use SSL client certificate authentication with the HTTP and IIOP application protocols.

- An intermediate server can establish the identity of the client, and pass it to the client. You can identify users in this way when you use asserted identity authentication with the IIOP application protocol.
- The user ID can be supplied in a user-replaceable program which is invoked for each inbound request.

In the HTTP application protocol, the analyzer program can supply a user ID. In the IIOP protocol, the program specified in the URM attribute of the TCPIPSERVICE resource definition can supply a user ID.

• The user ID can be supplied in a URIMAP definition for an inbound request. You can identify users in this way when you use URIMAP definitions to handle requests on the HTTP application protocol.

If you do not use one of these methods to supply a user ID, the default user ID is used.

### Identifying HTTP users About this task

For the HTTP application protocol, you can identify the user in the following ways:

- A user ID can be obtained from the Web client using HTTP basic authentication.
- If the Web browser sends a client certificate, you can use a user ID that is associated with the certificate.

You can associate a certificate with a RACF userid in two ways:

- You can use RACF commands to associate a certificate with a user ID.
- CICS can automatically issue the RACF commands to associate a certificate with a user ID (which is obtained from the Web client using HTTP basic authentication).

"Associating a RACF user ID with a certificate" on page 268 tells you how to do this.

For application-generated responses only, it is also possible for CICS to supply a user ID on behalf of the Web client:

• In an analyzer program that is used in the processing path for the request.

- In the USERID attribute of the URIMAP definition for a request.
- As the CICS default user ID.

T

L

L

It is important to note that if you use a URIMAP definition or analyzer program to set a user ID that has not been supplied by a client, or allow the CICS default user ID to be used, there is no authentication of the client's identity. You should only do this when communicating with your own client system, which has already authenticated its users, and communicates with the server in a secure environment.

When the HTTP response is to be provided by an application (an application-generated response), the order of precedence of user IDs is:

- 1. A user ID that you set using an analyzer program. This user ID can override a user ID obtained from the Web client or supplied by a URIMAP definition.
- 2. A user ID that you obtained from the Web client using basic authentication, or a user ID associated with a client certificate sent by the Web client. If authentication is required for the connection but the client does not provide an authenticated user ID, the request is rejected.
- 3. A user ID that you specified in the URIMAP definition for the request.
- 4. The CICS default user ID, if no other can be determined.

When the HTTP response is to be provided by a URIMAP definition that specifies a CICS document template or z/OS UNIX file (a static response), the user ID used for the Web client is a user ID that you obtained from the Web client using basic authentication, or a user ID associated with a client certificate sent by the Web client. For static responses, it is not possible to supply a user ID on behalf of the Web client, nor to override an authenticated user ID obtained from a Web client.

For static responses, CICS only makes use of a supplied user ID if you specify resource security checking for the transaction. No default user ID is required for static responses. If the Web client does not supply a user ID, no resource security checking is carried out, even if resource security is active for the transaction.

The method used to identify the user is determined by the AUTHENTICATE and SSL attributes of the TCPIPSERVICE definition:

AUTHENTICATE	SSL	How the user is identified	
NO	NO or YES	The client does not supply a user ID. It can be supplied by an analyzer program or URIMAP definition, or allowed to default to the CICS default user ID, if applicable.	
NO	CLIENTAUTH	If the client sends a certificate that is associated with a user ID, then that user ID applies, unless it is overridden by an analyzer program. If the client sends a certificate that is not associated with a user ID, a user ID can be supplied by an analyzer program or URIMAP definition, or allowed to default to the CICS default user ID, if applicable.	
BASIC	all values	A user ID is obtained from the client, using HTTP basic authentication. This can be overridden by an analyzer program.	

Table 35. How the user of an HTTP client is identified

UTHENTICATE	SSL	How the user is identified
CERTIFICATE	CLIENTAUTH	If the client sends a certificate that is associated with a user ID, then that user ID applies, unless it is overridden by an analyzer program.
		If the client sends a certificate that is not associated with a user ID, or does not send a certificate, then the connection is rejected.
AUTOREGISTER	CLIENTAUTH	If the client sends a certificate that is associated with a user ID, then that user ID applies, unless it is overridden by an analyzer program.
		If the client sends a certificate that is not associated with a user ID, then the user ID is obtained from th client, using HTTP basic authentication, and the use ID is registered to the certificate.
		If the client does not send a certificate, then the connection is rejected.
AUTOMATIC	NO or YES	A user ID is obtained from the client, using HTTP basic authentication. This can be overridden by an analyzer program.
AUTOMATIC	CLIENTAUTH	If the client sends a certificate that is associated wit a user ID, then that user ID applies, unless it is overridden by an analyzer program.
		If the client sends a certificate that is not associated with a user ID, then the user ID is obtained from the client, using HTTP basic authentication, and the use ID is registered to the certificate.
		If the client does not send a certificate, then the use ID is obtained from the client, using HTTP basic authentication.

Table 35. How the user of an HTTP client is identified (continued)

2. If HTTP basic authentication is used, CICS verifies the password. If the password is invalid, the connection is rejected.

For more information about CICS Web support architecture, see the CICS Internet Guide.

### Identifying IIOP users

If SSL client authentication does not provide a user ID, it is possible for CICS to supply a user ID on behalf of the client. The ID can be supplied by a user-replaceable program specified in the URM attribute of the TCPIPSERVICE resource definition.

#### About this task

For IIOP requests, SSL client authentication can be used to identify the user. When the client sends a client certificate, you can identify the user by a user ID that you have previously associated with the certificate. IIOP users cannot register certificates automatically. For more information, see "Associating a RACF user ID with a certificate" on page 268.

If neither of these mechanisms provides a user ID, the user ID can default to the CICS *default user identifier*.

The derived user ID is passed with the IIOP request to the request processor, for authentication of the request execution. If the request processor is executing in a different CICS region, the transmission of the user ID follows CICS rules for CONNECTION authentication.

The method used to identify the user is determined by the AUTHENTICATE and SSL attributes of the TCPIPSERVICE resource definition.

AUTHENTICATE	SSL	How the user is identified
NO	NO or YES	The user ID can be provided by the user-replaceable program specified in the URM attribute of the TCPIPSERVICE resource definition. Alternatively, it can be allowed to default to the CICS default user ID.
NO	CLIENTAUTH	If the client sends a certificate that is associated with a user ID, then that user ID applies.
		If the client does not send a certificate, or sends a certificate that is not associated with a user ID, then the user ID can be provided by the user-replaceable program or allowed to default to the CICS default user ID.
CERTIFICATE	CLIENTAUTH	If the client sends a certificate that is associated with a user ID, then that user ID applies.
		If the client does not send a certificate, or sends a certificate that is not associated with a user ID, then the connection is rejected.
		The user-replaceable program cannot be used when the CERTIFICATE option is specified.
ASSERTED	CLIENTAUTH	The client in this case is typically an intermediate server. If the client sends a certificate that is associated with a user ID, then it is trusted to identify and authenticate its own clients, and the user ID sent in the IIOP request applies.
		If the client does not send a certificate, or sends a certificate that is not associated with a user ID, then the connection is rejected.
		The user-replaceable program cannot be used when the ASSERTED option is specified.

Table 36. How the user of an IIOP client is identified

**Note:** This table does not list combinations of values for the AUTHENTICATE and SSL attributes which are invalid, and cannot be specified in the TCPIPSERVICE definition.

### **Identifying ECI users**

For the ECI protocol you can use basic authentication to identify the user.

Specify ATTACHSEC(VERIFY) in the TCPIPSERVICE definition for the ECI client. Specify ATTACHSEC(LOCAL) if you do not want to identify the user.

### Identifying IPIC users

For the IPIC protocol you can use basic authentication to identify the user. Specify USERAUTH(VERIFY) in IPCONN resource definitions. Specify USERAUTH(LOCAL) if you do not want to identify the user.

### Authentication

In many systems, the user's authenticity is verified by checking a password supplied by the user.

In a system in which there is no possibility of a password being intercepted, this level of authentication may be sufficient; however, in an insecure network, it is possible that passwords can be intercepted, and used to impersonate legitimate users of the system.

In an environment where your applications may be accessed by users across the internet, and by users who are outside the control of your organization, a more secure method of authentication is required.

On the other hand, there are situations where a limited level of authentication is sufficient. If you have a client system that authenticates its users, and communicates with a server in a secure environment, you may not need to authenticate end users at the server, but rely entirely on the client's authentication mechanisms.

CICS supports the following authentication schemes:

#### **Basic authentication**

The client's identity is authenticated by a password. This level of authentication is appropriate in an environment where passwords cannot be intercepted and used to impersonate an end user.

You can use basic authentication with the HTTP and ECI application protocols.

#### SSL client certificate authentication

The client's identity is authenticated with a client certificate issued by a trusted third party (or Certificate Authority). This level of authentication is appropriate in an environment where information flowing in the network could be intercepted, and used to impersonate an end user.

You can use SSL client certificate authentication with the HTTP and IIOP application protocols.

For more information about SSL, see "Support for security protocols" on page 252.

#### Asserted identity authentication

Asserted identity authentication can be used when an IIOP client communicates with the target server through an intermediate server, and both servers use the same security manager:

- 1. The intermediate server's identity is authenticated by the target server using SSL client certificate authentication.
- **2**. Through the security manager, the target server verifies that the intermediate server can be trusted to authenticate its clients.

- **3**. When the intermediate server receives a request, it authenticates the client using whatever authentication protocol is appropriate. If the client is successfully authenticated, the intermediate server passes the request to the target server
- 4. Because the target server trusts the intermediate server to authenticate the client, it makes no further checks of the client's authenticity before processing the client's request.

You can use asserted identity authentication with the IIOP application protocols. In CICS, a CorbaServer can be configured as an intermediate or target server.

### Authenticating HTTP users

You can use HTTP basic authentication or SSL client certificate authentication to authenticate HTTP users.

### About this task

The authentication scheme is specified by the AUTHENTICATE and SSL attributes of the TCPIPSERVICE definition:

Authentication scheme	AUTHENTICATE	SSL	Notes
HTTP with no authentication	NO	NO or YES	
HTTP with basic authentication	BASIC	NO, YES or CLIENTCERT	
HTTP with basic authentication	AUTOMATIC	NO, YES or CLIENTCERT	If SSL(CLIENTCERT) is specified, and the client sends a certificate, then SSL client certificate authentication is used.
HTTP with SSL client certificate authentication	CERTIFICATE or AUTOREGISTER	CLIENTCERT	If the client does not send a certificate, the connection is not established.
HTTP with SSL client certificate authentication	AUTOMATIC	CLIENTCERT	If the client does not send a certificate, then basic authentication is used.

### Authenticating IIOP users

The authentication scheme used by a port is specified by the AUTHENTICATE and SSL attributes of the TCPIPSERVICE resource definition which defines the characteristics of the port.

### About this task

For the IIOP application protocol, you can authenticate the user using SSL client certificate authentication or asserted identity authentication.

Authentication method	AUTHENTICATE	SSL	Associated CORBASERVER attribute
IIOP with no authentication	NO	NO	UNAUTH
IIOP with no authentication	NO	YES	SSLUNAUTH
IIOP with SSL client certificate authentication	CERTIFICATE	CLIENTCERT	CLIENTCERT
IIOP with asserted identity authentication	ASSERTED	CLIENTCERT	ASSERTED

A CorbaServer can support more than one authentication scheme. Each CORBASERVER resource definition is associated with one or more TCPIPSERVICE resource definitions, and each TCPIPSERVICE resource definition supports a different mechanism for authentication and identification.

• The UNAUTH attribute of the CORBASERVER resource definition names a TCPIPSERVICE resource definition for a port which is used for inbound IIOP with no authentication.

**Note:** You must specify a value for the UNAUTH attribute when you create a CORBASERVER resource definition, even if you intend that all inbound requests to this CorbaServer should be authenticated. This is because the PORTNUMBER attribute of the TCPIPSERVICE is required in order to construct IORs that are exported from this logical server.

- The SSLUNAUTH attribute of the CORBASERVER resource definition names a TCPIPSERVICE resource definition for a port which is used for inbound IIOP with SSL encryption but no client authentication.
- The CLIENTCERT attribute of the CORBASERVER resource definition names a TCPIPSERVICE resource definition for a port which is used for inbound IIOP with SSL client certificate authentication.
- The ASSERTED attribute of the CORBASERVER resource definition names a TCPIPSERVICE resource definition for a port which is used for inbound IIOP with asserted identity authentication.

To change the association between an installed CORBASERVER definition and its TCPIPSERVICE definitions, discard and reinstall the CORBASERVER definition.

The authentication protocols supported by an object are made known to clients in the IOR for the object:

- When CICS is the target server, the authentication protocols are specified in CORBASERVER resource definitions. When the Generic Factory Interoperable Object Reference (GenFacIOR) of the CorbaServer is published, the authentication protocols supported by each object are made known to clients in the GenFacIOR.
- When CICS is the intermediate server, it examines the IOR for the server object to determine which authentication protocols the object supports, and selects the protocol to use. If more than one protocol is supported, CICS selects the first supported protocol from:
  - 1. Asserted identity authentication
  - 2. SSL client certificate authentication

If these authentication protocols are not supported, no authentication is used.

CICS can use asserted identity authentication when communicating with WebSphere[®] Application Server for z/OS or with other CICS regions. Both the target server and the intermediate server must use the same security manager.

The protocol that a CICS CorbaServer uses for asserted identity authentication is the z/OS Secure Authentication Service (z/SAS) protocol. In WebSphere Application Server for z/OS Version 6.1 or later, this protocol is no longer available, but CICS is able to communicate with these product versions using a limited implementation of the Common Secure Interoperability Version 2 (CSIv2) protocol for identity assertion. (Release 6.1.0.13 or later of WebSphere Application Server for z/OS is required to support this function.) To enable this function in CICS, specify the system property **-Dcom.ibm.cics.iiop.CSIv2Enabled=true** in all of the JVM properties files used in the CICS region.

CICS only uses the CSIv2 protocol if WebSphere Application Server for z/OS requires that protocol; if the protocol is optional, CICS does not use it. When CICS is communicating with earlier versions of WebSphere Application Server for z/OS or with other CICS regions, CICS chooses the z/SAS protocol instead of the CSIv2 protocol whenever support for the z/SAS protocol is available.

### Authenticating ECI users

For the ECI protocol you can use basic authentication to authenticate the user.

Specify ATTACHSEC(VERIFY) in the TCPIPSERVICE definition for the ECI client. Specify ATTACHSEC(LOCAL) if you do not want to authenticate the user.

### Authenticating IPIC users

For IPIC connections, you can use basic user authentication. Specify USERAUTH(VERIFY) in the IPCONN resource definition. Specify USERAUTH(LOCAL) if you do not want to authenticate the user.

# Configuring CICS to use asserted identity authentication About this task

You can configure each CorbaServer in your CICS region as:

#### An intermediate server

The intermediate server authenticates a client using whatever authentication protocol is appropriate.

#### A target server

The target server trusts the intermediate server to authenticate the client, and does not perform its own authentication.

In either case, you must establish a trust relationship between the intermediate and target servers.

If a CICS CorbaServer needs to support asserted identity authentication for IIOP messages sent from WebSphere Application Server for z/OS Version 6.1 or later, you need to enable a suitable authentication protocol before completing the steps in these tasks. To do this, specify the system property

**-Dcom.ibm.cics.iiop.CSIv2Enabled=true** in all of the JVM properties files used in the CICS region. Release 6.1.0.13 or later of WebSphere Application Server for z/OS is required to support this function.

### Establishing a trust relationship between the servers

To establish a trust relationship between the intermediate and target servers, where the target server is a CICS CorbaServer, perform the following steps:

- 1. Configure your CICS region to use SSL authentication. See Chapter 19, "Configuring CICS to use SSL," on page 261 for more information.
- 2. Associate the intermediate server's client certificate with a RACF userid. For more information, see "Associating a RACF user ID with a certificate" on page 268.
- **3.** Create a profile named DFH.*applid.corbaserver*.ASSERTID in the SERVAUTH general resource class, where

```
applid
```

is the APPLID of the CICS region

```
corbaserver
```

is the name of the target CorbaServer

For example, use the following RACF command:

RDEFINE SERVAUTH DFH.applid.corbaserver.ASSERTID UACC(NONE)

4. Give the intermediate server's userid (established in step 2) READ authority to the profile. For example, use the following RACF command:

PERMIT DFH.applid.corbaserver.ASSERTID CLASS(SERVAUTH) ID(server_userid) ACCESS(READ)

For information about establishing a trust relationship where another product is the target server, see the documentation for the target server.

#### Configuring a CorbaServer as an intermediate server

To configure a CICS CorbaServer as an intermediate server, perform the following steps:

- 1. Configure your CICS region to use SSL authentication. See Chapter 19, "Configuring CICS to use SSL," on page 261 for more information.
- **2**. Specify the certificate that will authenticate this server in the CERTIFICATE attribute of the CORBASERVER resource definition.

### Configuring a CorbaServer as the target server

To configure a CICS Corbaserver as the target server, perform the following steps:

- 1. Configure your CICS region to use SSL authentication. See Chapter 19, "Configuring CICS to use SSL," on page 261 for more information.
- 2. Define and install a TCPIPSERVICE to define the characteristics of the port which is used for inbound IIOP with asserted identity authentication. Specify AUTHENTICATE(ASSERTED) when you define the TCPIPSERVICE.
- **3**. Define and install a CORBASERVER. Specify the name of the TCPIPSERVICE you defined in step 2 in the ASSERTED attribute.

# Support for security protocols

CICS supports two security protocols that can be used to provide secure communication over the Internet. The first is the Secure Sockets Layer (SSL) 3.0 protocol. The second is the Transport Layer Security (TLS) 1.0 protocol, which is the latest industry standard SSL protocol and is based on SSL 3.0. The TLS 1.0 specification is documented in RFC2246 and is available on the Internet at www.rfc-editor.org/rfcsearch.html. Any connections that require encryption will automatically use the TLS protocol, unless the client specifically requires SSL 3.0. **Note:** For clarity, the term SSL is used to refer to both protocols in the documentation, except where a specific point about either protocol is required.

The primary aim of TLS is to make the Secure Sockets Layer more secure and to make the specification of the protocol more precise and complete. TLS provides the following enhancements over SSL 3.0:

#### Key-Hashing for Message Authentication

TLS uses Key-Hashing for Message Authentication Code (HMAC), which ensures that a record cannot be altered while travelling over an open network such as the Internet. SSL Version 3.0 also provides keyed message authentication, but HMAC is considered more secure than the (Message Authentication Code) MAC function that SSL Version 3.0 uses.

#### **Enhanced Pseudorandom Function (PRF)**

PRF is used for generating key data. In TLS, the PRF is defined with the HMAC. The PRF uses two hash algorithms in a way that guarantees its security. If either algorithm is exposed then the data remains secure as long as the second algorithm is not exposed.

#### Improved finished message verification

Both TLS 1.0 and SSL 3.0 provide a finished message to both endpoints that authenticates that the exchanged messages were not altered. However, TLS bases this finished message on the PRF and HMAC values, which is more secure than SSL Version 3.0.

#### Consistent certificate handling

Unlike SSL 3.0, TLS attempts specify the type of certificate which must be exchanged between TLS implementations.

#### Specific alert messages

TLS provides more specific and additional alerts to indicate problems that either session endpoint detects. TLS also documents when certain alerts should be sent.

The main features of the security protocols are:

#### Privacy

The data to be exchanged between the client and the server is encrypted. See "SSL encryption" for more information.

#### Integrity

Data which is transmitted using the SSL protocols is protected against tampering by a **message authentication code** (MAC). The MAC is computed from the data contents using a secure hashing algorithm and transmitted with the data. It is computed again by the receiver, and compared with the value transmitted by the sender. A mismatch between the two values of the MAC indicates that the data may have been tampered with.

#### Authentication

SSL uses digital certificates to authenticate servers to clients, and — optionally — clients to servers. See "SSL authentication" on page 254 for more information.

### SSL encryption

The SSL protocol operates between the application layer and the TCP/IP layer. This allows it to encrypt the data stream itself, which can then be transmitted securely, using any of the application layer protocols.

SSL uses two encryption techniques:

- Public key cryptography standard (PKCS), which encrypts and decrypts certificates during the SSL handshake. Encryption keys are created in pairs, a public key and its associated private key. Data encrypted with a given public key can be decrypted only with the associated private key; this means that data is readable by only the intended recipient. Data encrypted with a given private key can be decrypted only with the associated public key; this means that authentication data is assured to originate from the owner of the private key.
- A mutually agreed symmetric encryption technique, such as DES (data encryption standard), or triple DES, is used in the data transfer following the handshake.

PKCS, as used by SSL, works briefly as follows:

- 1. When a certificate is created, an algorithm based on two random numbers is used to create a private key and public key for the certificate owner. The private and public keys which result are related to each other such that:
  - It is not feasible to deduce the value of the private key from the public key, nor the public key from the private key

The private key is stored securely, and is not made known to anyone but its owner. The public key can be made freely available to any user, with no risk of compromising the security of the private key.

• Information encrypted using the public key can be decrypted only with the private key

Information can be encrypted by any user, and sent securely to the holder of the private key. A third party cannot use the public key to read the information.

• Information encrypted using the private key can be decrypted only with the public key

Only the holder of the private key can encrypt information that can be decrypted with the public key. A third party cannot pose as the sender of the information.

## **SSL** authentication

To make an environment secure, you must be sure that any communication is with "trusted" sites whose identity you can be sure of. SSL uses certificates for authentication — these are digitally signed documents which bind the public key to the identity of the private key owner.

Authentication happens at connection time, and is independent of the application or the application protocol. Authentication involves making sure that sites with which you communicate are who they claim to be. With SSL, authentication is performed by an exchange of certificates, which are blocks of data in a format described in ITU-T standard X.509. The X.509 certificates are issued, and digitally signed by an external authority known as a certificate authority.

### A certificate contains

- Two **distinguished names**, which uniquely identify the **issuer** (the certificate authority that issued the certificate) and the **subject** (the individual or organization to whom the certificate was issued). The distinguished names contain several optional components:
  - Common name
  - Organizational unit

- Organization
- Locality
- State or Province
- Country
- A digital signature. The signature is created by the certificate authority using the public-key encryption technique:
  - 1. A secure hashing algorithm is used to create a digest of the certificate's contents.
  - 2. The digest is encrypted with the certificate authority's private key.

The digital signature assures the receiver that no changes have been made to the certificate since it was issued:

- 1. The signature is decrypted with the certificate authority's public key.
- 2. A new digest of the certificate's contents is made, and compared with the decrypted signature. Any discrepancy indicates that the certificate may have been altered.
- The subject's domain name. The receiver compares this with the actual sender of the certificate.
- The subject's public key.

Certificates are used to authenticate clients to servers, and servers to clients; the mechanism used is essentially the same in both cases. However, the server certificate is mandatory — that is, the server must send its certificate to the client — but the client certificate is optional: some clients may not support client certificates; other may not have certificates installed. Servers can decide whether to require client authentication for a connection.

# **Certificate authorities**

In order that one system can be assured that a certificate received from another system is genuine, a trusted third party that can vouch for the certificate is needed.

Certificate authorities are independent bodies who act as the trusted third parties, by issuing certificates for use by others. Before issuing a certificate, a certificate authority will examine the credentials of the person or organization that has requested the certificate. When the certificate has been issued, information about it is held on a publicly accessible repository. Users can consult the repository to check the status and validity of any certificates received.

Certificate authorities issue several levels of security certificates for different purposes. For example:

- Secure e-mail
- Client authentication
- Server authentication

CICS can check every certificate it receives from a client for a revoked status by using certificate revocation lists. A certificate revocation list details all the revoked certificates for a particular certificate authority. These lists are freely available to download from the Internet. If the certificate has a revoked status, CICS closes the SSL connection immediately. To find out how to set up certificate revocation lists, see "Using certificate revocation lists (CRLs)" on page 273.

## **Cipher suites**

There are many different algorithms which can be used for encrypting data, and for computing the message authentication code. Some provide the highest levels of security, but require a large amount of computation for encryption and decryption; others are less secure, but provide rapid encryption and decryption. The length of the key used for encryption affects the level of security - the longer the key, the more secure the data.

To allow users to select the level of security that suits their needs, and to enable communication with others who may have different needs, SSL defines **cipher suites**, or sets of ciphers. When an SSL connection is established, the client and server exchange information about which cipher suites they have in common. They then communicate using the common cipher suite that offers the highest level of security. If they do not have a cipher suite in common, then secure communication is not possible and CICS closes the connection.

Use the **ENCRYPTION** system initialization parameter to specify the level of encryption that CICS should use. The default is STRONG, which means that CICS can use all of the cipher suites to negotiate with clients. You can set a minimum as well as a maximum encryption level by editing the list of cipher suites in the CIPHERS attribute on the appropriate resource definition.

To specify the level of encryption required:

#### For inbound HTTP and IIOP

Use the CIPHERS attribute of the TCPIPSERVICE resource definition, which automatically defines the PRIVACY attribute.

#### For outbound HTTP and web service requests

Use the CIPHERS attribute of the URIMAP resource definition.

#### For outbound IIOP

Use the CIPHERS attribute of the CORBASERVER resource definition, which automatically defines the OUTPRIVACY attribute

#### For inbound IPIC

Use the CIPHERS attribute of the TCPIPSERVICE resource definition.

#### For outbound IPIC

Use the CIPHERS attribute of the IPCONN resource definition.

# For inbound CICSPlex SM Web User Interface requests and CMCI requests using CICSPlex SM

Use the **TCPIPSSLCIPHERS** Web User Interface server initialization parameter. This value has the same syntax as the CIPHERS attribute of the TCPIPSERVICE resource, but it is limited to a maximum of 22 cipher suites.

The PRIVACY and OUTPRIVACY attributes are no longer supported, except in compatibility mode. The values are determined by the list of ciphers in the CIPHERS attribute as follows:

#### NOTSUPPORTED

Specified when the list of ciphers in the CIPHERS attribute only includes ciphers with no encryption. For example, cipher suites 01 and 02.

#### REQUIRED

Specified when the list of ciphers in the CIPHERS attribute only includes cipher suites with encryption. For example, if ENCRYPTION=STRONG is

|

specified, the full list of cipher suites are listed in the CIPHERS attribute. If you remove 01 and 02, the PRIVACY attribute changes to REQUIRED.

### SUPPORTED

Specified when the list of ciphers in the CIPHERS attribute includes 01 and 02 in combination with any other cipher suites.

The cipher suites supported by z/OS Versions 1.6 and 1.7 and CICS are shown in Table 37. More cipher suites are supported by later versions of z/OS.

Cipher suite	Encryption algorithm	Key length	MAC algorithm	Key Exchange	Certificate
00		None	None	RSA	
01		None	MD5	RSA	
02		None	SHA-1	RSA	
03	RC4	40 bits	MD5	RSA	
04	RC4	128 bits	MD5	RSA	
05	RC4	128 bits	SHA-1	RSA	
06	RC2	40 bits	MD5	RSA	
09	DES	56 bits	SHA-1	RSA	
0A	Triple DES	168 bits	SHA-1	RSA	
0C	DES	56 bits	SHA-1	fixed Diffie- Hellman	DSS
0D	Triple DES	168 bits	SHA-1	fixed Diffie- Hellman	DSS
0F	DES	56 bits	SHA-1	fixed Diffie- Hellman	RSA
10	Triple DES	168 bits	SHA-1	fixed Diffie- Hellman	RSA
12	DES	56 bits	SHA-1	ephemeral Diffie- Hellman	DSS
13	Triple DES	168 bits	SHA-1	ephemeral Diffie- Hellman	DSS
15	DES	56 bits	SHA-1	ephemeral Diffie- Hellman	RSA
16	Triple DES	168 bits	SHA-1	ephemeral Diffie- Hellman	RSA
2F	AES	128 bits	SHA-1	RSA	
30	AES	128 bits	SHA-1	fixed Diffie- Hellman	DSS

Table 37. Cipher suites supported by z/OS and CICS

Cipher sui	te Encryption algorithm	Key length	MAC algorithm	Key Exchange	Certificate
31	AES	128 bits	SHA-1	fixed Diffie- Hellman	RSA
32	AES	128 bits	SHA-1	ephemeral Diffie- Hellman	DSS
33	AES	128 bits	SHA-1	ephemeral Diffie- Hellman	RSA
35	AES	256 bits	SHA-1	RSA	
36	AES	256 bits	SHA-1	fixed Diffie- Hellman	DSS
37	AES	256 bits	SHA-1	fixed Diffie- Hellman	RSA
38	AES	256 bits	SHA-1	ephemeral Diffie- Hellman	DSS
39	AES	256 bits	SHA-1	ephemeral Diffie- Hellman	RSA
Terms used	in this table are:			1	
AES Ad	dvanced encryptic	on Standard			
DES Da	Data Encryption Standard				
<b>Triple DES</b> DI	ES applied three t	imes.			
DSS Di	Digital Signature Standard				
MD5 M	Message Digest algorithm				
RC Ri	Rivest encryption				
RSA Ri	vest, Shamir, Adle	eman public key	<i>.</i>		
SHA Se	Secure Hash algorithm				

# The SSL handshake

The *SSL handshake* is an exchange of information that takes place between the client and the server when a connection is established. It is during the handshake that client and server negotiate the encryption algorithms that they will use, and authenticate one another.

The main features of the SSL handshake are:

- The client and server exchange information about the SSL version number and the cipher suites that they both support.
- The server sends its certificate and other information to the client. Some of the information is encrypted with the server's private key. If the client can successfully decrypt the information with the server's public key, it is assured of the server's identity.

- If client authentication is required, the client sends its certificate and other information to the server. Some of the information is encrypted with the client's private key. If the server can successfully decrypt the information with the client's public key, it is assured of the client's identity.
- The client and server exchange random information which each generates and which is used to establish session keys: these are symmetric keys which are used to encrypt and decrypt information during the SSL session. The keys are also used to verify the integrity of the data.

# The SSL cache

The SSL cache is used to store session ids from the negotiation between clients and CICS.

The SSL cache allows CICS to perform partial handshakes with clients that it has previously authenticated. In a local CICS region, the SSL cache is part of the enclave for the S8 TCBs. You have the option of sharing the SSL cache across a sysplex if this is appropriate for your CICS system. You can use sysplex caching if you have multiple CICS socket-owning regions that accept SSL connections at the same IP address.

If you want to share the cache between regions, activate the system SSL started task GSKSRVR and use the system initialization parameter SSLCACHE. The default is to use the local region cache, but you can change this by specifying the option SYSPLEX. CICS will use the SSL cache in the coupling facility instead to store session ids.

### The SSL pool

CICS uses the open transaction environment (OTE) to manage SSL connections and requests to LDAP using the DFHDDAPX XPI interface.

To improve the number and performance of SSL connections in CICS, each SSL connection uses an S8 TCB from the SSL pool. The S8 TCBs run as UNIX pthreads and are owned by an open mode TCB called SP. The SP TCB owns a single enclave, in which all the S8 TCBs run. This enclave also includes the SSL cache. This provides the benefit of saving storage below the line, allowing many more simultaneous SSL connections in CICS.

The S8 TCBs are contained in an SSL pool, which is managed by the CICS dispatcher. The S8 TCBS are allocated from the new SSL pool, but are only locked to a transaction for the period that it needs to perform SSL or LDAP functions. After the SSL or LDAP request is complete, the TCB is released back into the SSL pool to be reused. The MAXSSLTCBS system initialization parameter specifies the maximum number of S8 open TCBs in the SSL pool. The default value is 8, but you can specify up to 1024.

You can monitor the performance of the SSL pool and the S8 TCBs using the dispatcher reports from DFH0STAT and DFHSTUP. The statistics include information on how often the maximum number of S8 TCBs are reached, the delay before a TCB is allocated and the actual number of TCBs in the SSL pool.

# Chapter 19. Configuring CICS to use SSL

CICS can use the Secure Sockets Layer (SSL) or the Transport Layer Security (TLS) security protocols to support secure TCP/IP connections. To authenticate servers to clients, create certificates and key rings in RACF and ensure that the CICS region and resources are correctly configured to support security.

### Before you begin

Before you begin to configure CICS, decide which type of certificates to use in SSL handshakes.

### About this task

You can use RACF to create certificates, but you must configure your clients to ensure that they can recognize the RACF server certificate. If you cannot configure your clients in this way, for example when clients are external to your organization, use a certificate signed by an external certificate authority.

Complete the following tasks to configure CICS to use SSL:

### Procedure

- 1. Set the correct authorizations in RACF to create a key ring, create a signing certificate (certificate authority certificate), and to add certificates to the key ring.
- 2. Optional: If you decide to use a certificate from a certificate authority, create a certificate request using RACF and send it to the certificate authority. You might have to wait a number of days to receive a signing certificate from the certificate authority. If your chosen certificate authority does not have its certificate built in to RACF, you might have to import it.
- **3**. Create a key ring. You must create a key ring in the RACF database. The key ring contains:
  - Your public and private keys
  - Your server certificates
  - Signing certificates for the server certificates
  - Signing certificates for any client certificates owned by clients with which you expect CICS to communicate using client authentication.
- 4. Create the certificates and add them to the key ring.
- 5. Ensure that the CICS region has access to the z/OS system SSL library SIEALNKE. You can use STEPLIB or JOBLIB statements, or use the system link library.
- 6. Define the CICS system initialization parameters that are related to security. In particular, specify the name of the key ring that you created in the **KEYRING** system initialization parameter.
- 7. Define TCPIPSERVICE resources.

### Example

CICS supplies a sample REXX program, DFH\$RING, that contains all of the RACF commands to create a key ring, create a signing certificate, create additional

certificates, and add them to the key ring. DFH\$RING contains sample values which are suitable for building a test key ring only. You must edit all the values if you want to create a key ring that is suitable for a production environment.

## Authorizing users to administer certificates in the key ring

You must grant access to the appropriate profiles in the FACILITY class in RACF to build a key ring in the RACF database, create a signing certificate, and administer certificates in the key ring.

### About this task

You must grant this access only to users who administer CICS regions and not to general CICS users. The following profiles are available:

Access level	Profile	Description
CONTROL	IRR.DIGTCERT.GENCERT	Allow certificates to be signed by a CERTAUTH certificate.
	IRR.DIGTCERT.ADD Allow a CERTAUTH certificate to be general first execution.	
	IRR.DIGTCERT.CONNECT	Connect CERTAUTH certificates for other users.
UPDATE	IRR.DIGTCERT.CONNECT	Connect CERTAUTH certificates to your key ring.
	IRR.DIGTCERT.*	Manage certificates for other users.
READ	IRR.DIGTCERT.*	Manage certificates for your own user ID.

IRR.DIGTCERT.* contains the wildcard asterisk and is intended as a generic profile.

CICS provides a sample REXX program, DFH\$RING, which you can edit to create a key ring, signing certificate, and other certificates as appropriate. The default values are suitable only for a test key ring and not for production. To run DFH\$RING, you must have the required authorization access in RACF.

### Procedure

1. To allow generic profiles to be created in the FACILITY class, issue the following command:

SETROPTS GENERIC(FACILITY)

2. Issue the following commands:

```
RDEFINE FACILITY(IRR.DIGTCERT.*)
RDEFINE FACILITY(IRR.DIGTCERT.ADD)
RDEFINE FACILITY(IRR.DIGTCERT.CONNECT)
RDEFINE FACILITY(IRR.DIGTCERT.GENCERT)
```

**3**. Depending upon whether the FACILITY class is RACLISTed or not, issue one of the following commands:

SETROPTS RACLIST(FACILITY) REFRESH SETROPTS GENERIC(FACILITY) REFRESH 4. Give a user ID or group, *ringuser*, authority to use the RACF commands to create and manage certificates. Issue the following commands:

PERMIT IRR.DIGTCERT.* CLASS(FACILITY) ID(ringuser) ACCESS(READ) PERMIT IRR.DIGTCERT.CONNECT CLASS(FACILITY) ID(ringuser) ACCESS(UPDATE) (for self) PERMIT IRR.DIGTCERT.CONNECT CLASS(FACILITY) ID(ringuser) ACCESS(CONTROL) (for another user) PERMIT IRR.DIGTCERT.GENCERT CLASS(FACILITY) ID(ringuser) ACCESS(CONTROL)

5. Give a user ID, *certauser*, authority to create a signing certificate (certificate authority certificate). RACF uses this certificate to sign all the other certificates. Issue the following command:

PERMIT IRR.DIGTCERT.ADD CLASS(FACILITY) ID(certauser) ACCESS(CONTROL)

If you plan to use the DFH\$RING program, your user ID must have CONTROL access to create the signing certificate the first time you run the program. After you have created the signing certificate, you require only UPDATE access.

### Results

You can add certificate information for your own user ID if you have READ access to the IRR.DIGTCERT.ADD profile in the FACILITY class. You can add certificate information for other user IDs if you have UPDATE access to the IRR.DIGTCERT.ADD profile in the FACILITY class. If you have SPECIAL authority, you can run RACDCERT ADD for any user ID. You can also generate a digital certificate for any RACF-defined user or for any certificate authority or site certificate with SPECIAL authority.

### What to do next

If you want to use a certificate from a certificate authority to authenticate with a client, create a certificate request using RACF and send it to the certificate authority. If you want to use RACF certificates only, you can build a key ring.

### Requesting a certificate from a certificate authority

You can use RACF to request a signing certificate (certificate authority certificate) from a certificate authority such as Verisign. Use an external certificate to authenticate your server to clients that cannot recognize RACF certificates.

### Before you begin

You must have authorization to use the **RACDCERT** command. This command installs and maintains digital certificates, key rings, and digital certificate mappings in RACF.

### Procedure

1. Create a self-signed certificate in RACF as a placeholder:

```
RACDCERT ID(foruser) GENCERT,

SUBJECTSDN(CN('username')

T ('username''s certificate')

OU('department')

O ('organization')

L ('city')

SP('state')

C ('country'))
```

```
NOTBEFORE(DATE(start) TIME(00:00:00))
NOTAFTER (DATE(finish) TIME(23:59:59))
WITHLABEL(self-signed-certlabel)
SIZE (1024)
```

**2**. Generate a certificate request, based on the placeholder certificate, to send to your external certificate authority. Use the **RACDCERT GENREQ** command:

```
RACDCERT ID(cics-region-userid) GENREQ(LABEL('label'))
DSN('request.dataset')
```

where *label* is the placeholder self-signed certificate. RACF saves the certificate request in the data set specified in the **DSN** parameter.

- **3**. Send the certificate request to the certificate authority, using a method that the certificate authority accepts.
- 4. When you receive the certificate, save it in a new data set.
- 5. Optional: If you are using a certificate authority that is not one of the default certificate authorities, for which certificates are already stored in the key database, you must import the certificate authority's certificate into your RACF database. See Importing a certificate from a file as a trusted CA certificate in the z/OS information center.
- 6. Replace the self-signed certificate with your new CA-signed certificate: RACDCERT ID(*cics-region-userid*) ADD('*response.dataset*') TRUST

### What to do next

Create the key ring in the RACF database and add your CA-signed certificate.

# Building a key ring manually

In CICS, the required server certificate and related information about certificate authorities are held in a *key ring* in the RACF database. The key ring contains your system's private and public key pair, together with your server certificate and the certificates for all the certificate authorities that might have signed the certificates you receive from your clients.

### Before you begin

Before you can use SSL with CICS, you must create a key ring that contains a private and public key pair and a server certificate. To create a key ring you must have UPDATE authority to the IRR.DIGTCERT.ADDRING resource in the FACILITY class. If you want to share certificates in a key ring between CICS regions, the CICS regions must have the same user ID and the user ID must own the key ring.

### About this task

The **RACDCERT** command installs and maintains public key infrastructure (PKI) private keys and certificates in RACF. You can either manually issue the **RACDCERT** command to create a new key ring or you can use the DFH\$RING sample program.

To create a key ring manually, follow these steps:

### Procedure

Issue the following RACDCERT command: RACDCERT ID(cics-region-userid) ADDRING(ringname)

The key ring must be associated with the CICS region user ID.

### Results

RACF creates the key ring in the RACF database. If there is a key ring of the same name already in the RACF database, it is replaced with the new key ring.

### What to do next

Create a signing certificate (certificate authority certificate) and add it to the key ring.

### Building a key ring with certificates using DFH\$RING

DFH\$RING is a sample REXX program that builds a key ring, creates a signing certificate (certificate authority certificate), creates additional certificates, and adds the certificates to the key ring.

### Before you begin

You must have the required authorization to run the RACF commands. Your user ID must have CONTROL access to create the signing certificate the first time your run the program. If you run the program again, you require only UPDATE access.

### About this task

DFH\$RING is in library CICSTS41.CICS.SDFHSAMP. Edit the values in DFH\$RING to create a suitable key ring and certificates:

### Procedure

- 1. Enter values for the *firstname*, *lastname*, and *hostname* variables. The *firstname* and *lastname* values are concatenated together to form the name of the key ring. Enter the host name of your Web server for the *hostname* variable.
- 2. Optional: Enter a value for the *FORUSER* variable if you are building a key ring for a different user ID, such as a CICS region user ID.
- **3**. If you have a signing certificate (certificate authority certificate), enter the label in the *certifier* variable.
- 4. If you do not have a signing certificate, replace the variables for the **RACDCERT CERTAUTH GENCERT** command with suitable values and RACF can create it for you:

```
"RACDCERT CERTAUTH GENCERT",
" SUBJECTSDN(CN('CICS Sample Certification Authority' ) ",
                                                              ۳,
             "OU('"department"'
             "O ('"organization"'
"L ('"city"'
                                                            ) ",
                                                            ) ",
) ",
))",
))",
             "SP('"state"'
             "C ('"country"'
" NOTBEFORE(DATE("start") TIME(00:00:00)
" NOTAFTER (DATE("finish") TIME(23:59:59)
                                                             ۱) ۳
" WITHLABEL("certifier"
                                                             )"
" SIZE
            (768
```

These values define appropriate fields in the distinguished names of the generated certificates. The country code for the *country* variable must be an ISO 3166-1 code. For a list of valid codes, see http://www.iso.org/iso/ country_codes/iso_3166_code_lists.htm. *start* and *finish* determine the validity of the certificate. *certifier* is the label of the self-signed Certificate Authority certificate that is used to sign the other certificates. The **SIZE** parameter specifies the size, in bits, of the private key that is associated with the certificate. The larger the size, the more secure the key. The most common size is 1024.

DFH\$RING creates the signing certificate only if it does not already exist.

- 5. Edit the variables for the **RADCERT GENCERT** RACF commands to create appropriate certificates to add to your key ring. DFH\$RING has four examples that you can edit, add to, or remove. Ensure that the *certifier* variable on the **SIGNWITH** parameter matches the label of your signing certificate.
- 6. Edit the labels for the **RACDCERT CONNECT** RACF commands to match your certificates. Ensure that the signing certificate is added to the key ring first, because it signs all the other certificates.
- 7. Run DFH\$RING to create the key ring and certificates as follows: EXEC 'CICSTS41.CICS.SDFHSAMP(DFH\$RING)' 'firstname lastname webservername [ FORUSER(useric

where *userid* is the CICS region user ID.

### **Results**

The DFH\$RING program creates a key ring with name *firstname.lastname* which is owned by the *userid* user ID. Any existing key ring with that name is replaced. If you omit the **FORUSER** parameter, the key ring is owned by the user ID that you used to run the program. DFH\$RING creates a signing certificate if required and adds it to the key ring, followed by the other certificates.

### Example

If you run DFH\$RING with the default values, DFH\$RING creates certificates with the following labels:

#### lastname-Web-Server

This certificate can be used in the CERTIFICATE attribute of TCPIPSERVICEs with PROTOCOL(HTTP). The distinguished name within the certificate has a common name of *webservername*, which must be the same as the host name associated with the connection. Web browsers usually check that the common name in the certificate matches the host name of the server from which it is received.

#### lastname-EJB-Container

This certificate can be used in the CERTIFICATE attribute of a CORBASERVER definition.

### lastname-IP-CONNECTION

This certificate can be used for IP interconnectivity (IPIC). It can be used in CERTIFICATE attributes of resource definitions that are required for a CICS region to use IPIC. This sample certificate is for a CICS region to use as a client certificate and as a server certificate during an SSL handshake that occurs when an IPCONN is acquired. It can be used in the CERTIFICATE attribute of an IPCONN definition for a client certificate and the CERTIFICATE attribute of a TCPIPSERVICE definition with PROTOCOL(IPIC) for a server certificate.

#### lastname-Default-Certificate

This certificate is marked as the default certificate for the key ring and is the one that is used for all TCPIPSERVICEs and CORBASERVERs that do not specify a CERTIFICATE attribute. This certificate also contains a common name of *webservername*.

#### Verisign Class 1 Primary CA

#### Verisign Class 2 Primary CA

### IBM World Registry CA

These certificates are required to validate client certificates that you might receive that have been signed by these Certificate Authorities. If you intend to accept client certificates signed by other Certificate Authorities, or certificates that you have created yourself, you will have to add their certificates to the key ring manually, using the **RACDCERT CONNECT** command. When you add a certificate to the key ring in this way, you must specify USAGE(PERSONAL).

### What to do next

You can create and add further certificates to the key ring.

## **Creating new RACF certificates**

Use the **RACDCERT** command to create and add new certificates to a key ring.

### About this task

The certificates in the key ring must be associated with the CICS region user ID. The key ring must be owned by the CICS region user ID that is making use of it.

### Procedure

1. Create a certificate, specifying the CICS region user ID. Enter the **RACDCERT GENCERT** command as follows:

```
RACDCERT ID (foruser) GENCERT

SUBJECTSDN(CN('username')

T ('username''s certificate')

OU('department')

O ('organization')

L ('city')

SP('state')

C ('country'))

NOTBEFORE(DATE(start) TIME(00:00:00))

NOTAFTER (DATE(finish) TIME(23:59:59))

SIGNWITH (CERTAUTH LABEL('certifier'))

WITHLABEL('certlabel')

SIZE (1024)
```

Provide values for the variables. The country code for the *country* variable must be an ISO 3166-1 code. For a list of valid codes, see http://www.iso.org/iso/country_codes/iso_3166_code_lists.htm. The value of *certifier* is the label of the signing certificate in the key ring.

- 2. Add the certificate to the key ring using the RACDCERT CONNECT command.
  - a. If you want to share the certificate across multiple CICS regions, add it to the key ring specified in the **KEYRING** system initialization parameter for that CICS region and specify USAGE(PERSONAL). Any CICS region that has the same region user ID and is using the same key ring can access the certificate.

RACDCERT ID(foruser) CONNECT( RING(ringname) LABEL('label') USAGE('PERSONAL'))

b. If you want to add a certificate to the key ring as the default certificate, add it to the key ring specified in the KEYRING system initialization parameter for that CICS region and specify DEFAULT.

RACDCERT ID(foruser) CONNECT( RING(ringname) LABEL('label') DEFAULT)

When a client or server requests a certificate from CICS, the default certificate is used unless you have specified otherwise:

- For inbound HTTP and IIOP requests, specify the certificate in the TCPIPSERVICE resource definition.
- For outbound IIOP requests, specify the certificate in the CORBASERVER resource definition.
- **3**. After running any of the RACDCERT commands that update certificates or key rings, if the DIGTCERT and DIGTRING classes are RACLISTed, you must issue the following command:

SETROPTS RACLIST (DIGTCERT DIGTRING) REFRESH

4. After you have performed a key ring update, restart the CICS region to pick up the changes.

### Associating a RACF user ID with a certificate

The client certificate can only be used to determine the user ID for the CICS transaction if the certificate is associated with a RACF user ID.

You can associate a certificate with a RACF user ID in two ways:

• Users can register their certificates online through their browser program. You enable clients to register their certificates themselves by specifying AUTHENTICATE(AUTOREGISTER) on the TCPIPSERVICE definition. Users connecting to CICS through such a TCPIPSERVICE must have a client certificate. If that certificate is already registered to a user ID, then that user ID is used; if not, the client is prompted for a user ID and password with HTTP basic authentication. If the client then enters a valid user ID and password, that user ID is registered to the certificate, and the client will not be prompted for a password again. The rules are summarized in "Identifying HTTP users" on page 244.

Once a certificate has been registered in this way, it can be used for all inbound TCP/IP connections. For example, the same certificate can be used to authenticate and identify users of IIOP requests as well as HTTP requests.

• You can use the RACDCERT command. If you do not want to allow your clients to register their own certificates, you must register them with the RACDCERT command. Before executing RACDCERT, you must download the certificate that you want to process into an MVS sequential file with RECFM=VB that is accessible from TSO. The syntax of RACDCERT is:

RACDCERT ADD('datasetname') TRUST [ ID(userid) ]

where *datasetname* is the name of the data set containing the client certificate, and *userid* is the user ID that is to be associated with the certificate. If the optional ID(userid) parameter is omitted, the certificate is associated with the user issuing the RACDCERT command.

You can add certificate information for your own user ID if you have READ access to the IRR.DIGTCERT.ADD profile in the FACILITY class. You can add certificate

information for other user IDs if you have UPDATE access to the IRR.DIGTCERT.ADD profile in the FACILITY class or if you have RACF SPECIAL authority.

For further information on the RACDCERT command, including the format of data allowed in the downloaded certificate data set, see *z*/OS Security Server RACF Command Language Reference

# Making a certificate untrusted

If a certificate has been registered in the RACF database, but you do not want it to be used by clients, you can mark it as UNTRUSTED using the RACDCERT command.

### About this task

To make a certificate untrusted, follow these steps:

### Procedure

- 1. Enter the command RACDCERT ID(*userid*) LIST to find the label associated with the certificate.
- 2. Enter the command RACDCERT ID (*userid*) ALTER(LABEL(*label*)) NOTRUST to mark the certificate as untrusted.

### Results

Clients are prevented from establishing CLIENTAUTH connections with this certificate.

## System initialization parameters for SSL

The following system initialization parameters relate to SSL:

#### CRLPROFILE

Specifies the name of the profile that authorizes CICS to access certificate revocation lists that are stored in an LDAP server. For more information about certificate revocation lists and setting up this profile, see "Configuring an LDAP server for CRLs" on page 274.

#### ENCRYPTION

Specifies the cipher suites that CICS uses for secure TCP/IP connections. When a secure connection is established between a pair of processes, the most secure cipher suite supported by both is used. For more information about cipher suites, see "Cipher suites" on page 256.

#### KEYRING

Specifies the name of a key ring in the RACF database that contains keys and certificates used by CICS. It must be owned by the CICS region userid. You can create an initial key ring with the DFH\$RING exec in CICSTS41.CICS.SDFHSAMP.

#### MAXSSLTCBS

Specifies the maximum number of S8 TCBs that are available to CICS to process secure sockets layer connections and requests to LDAP using the DFHDDAPX XPI interface. This value is a number in the range 0 through 999, and has a default value of 8. The S8 TCBs are created and managed in the SSL

pool. An S8 TCB is used by a task only for the duration of the SSL or LDAP processing. This parameter replaces the obsolete SSLTCBS system initialization parameter.

#### SSLCACHE

Specifies whether CICS should use the local SSL cache in the CICS region, or share the cache across multiple CICS regions by using the coupling facility. Caching across a sysplex can only take place when the regions accept SSL connections at the same IP address.

#### SSLDELAY

Specifies the length of time in seconds for which CICS retains session IDs for secure socket connections in a local CICS region. Session IDs are tokens that represent a secure connection between a client and an SSL server. While the session ID is retained by CICS within the SSLDELAY period, CICS can continue to communicate with the client without the significant overhead of an SSL handshake. The value is a number of seconds in the range 0 through 86400. The default value is 600.

See CICS System Definition Guide for details of the system initialization parameters.

# Defining TCPIPSERVICE resources for SSL

### About this task

The following attributes of the TCPIPSERVICE resource relate to SSL. For a full description of the TCPIPSERVICE resource, see the *CICS Resource Definition Guide*.

#### AUTHENTICATE

specifies the authentication and identification scheme to be used for inbound TCP/IP connections for the HTTP and IIOP protocols. Each protocol supports a different set of authentication schemes.

#### When PROTOCOL(HTTP) is specified:

**NO** The client is not required to send authentication or identification information.

#### BASIC

HTTP basic authentication is used to obtain a user ID and password from the client.

#### CERTIFICATE

SSL client certificate authentication is used to authenticate and identify the client.

#### AUTOREGISTER

SSL client certificate authentication is used to authenticate the client. If the client sends a valid certificate that is not registered to the security manager, then CICS will register the certificate.

### AUTOMATIC

If the client sends a certificate, SSL client certificate authentication is used to authenticate the client. If the client sends a valid certificate that is not registered to the security manager, then CICS will register the certificate. If the client does not send a certificate, then HTTP Basic authentication is used to obtain a user ID and password from the client.

### When PROTOCOL(IIOP) is specified:

**NO** The client is not required to send authentication or identification information.

### CERTIFICATE

SSL client certificate authentication is used to authenticate and identify the client.

#### ASSERTED

Asserted identity authentication is used to authenticate and identify the client.

#### CERTIFICATE

specifies the label of the server certificate used during the SSL handshake. If this attribute is omitted, the default certificate defined in the key ring for the CICS region user ID is used.

#### CIPHERS

L

L

L

Т

Specifies a string of up to 56 hexadecimal digits that is interpreted as a list of up to 28 2-digit cipher suite codes. When you use the CEDA transaction to define the resource, CICS automatically initializes the attribute with a default list of acceptable codes. For CICS to initialize the attribute, the KEYRING system initialization parameter must be specified in the CICS region where you are running CEDA. If KEYRING is not set, CICS does not initialize the attribute. The default list of codes depends on the level of encryption that is specified by the ENCRYPTION system initialization parameter.

- For ENCRYPTION=WEAK, the default value is 03060102.
- For ENCRYPTION=MEDIUM, the initial value is 0903060102.
- For ENCRYPTION=STRONG, the initial value is 050435363738392F303132330A1613100D0915120F0C03060201.

You can reorder the cipher codes or remove them from the initial list. However, you cannot add cipher codes that are not in the default list for the specified encryption level. To reset the value to the default list of codes, delete all of the cipher suite codes. The field is automatically repopulated with the default list.

See the CICS RACF Security Guide for more information.

#### PORTNUMBER

specifies the number of the port on which CICS is to listen for incoming client requests. The well known ports for SSL services supported by CICS are:

443 HTTP with SSL

684 IIOP with SSL

#### SSL

specifies whether the TCP/IP service is to use SSL for encryption and authentication:

- NO SSL is not to be used.
- **YES** An SSL session is to be used; CICS will send a server certificate to the client.

#### **CLIENTAUTH**

An SSL session is to be used; CICS will send a server certificate to the client, and the client must send a client certificate to CICS.

# Customizing encryption negotiations

You can select the cipher suites that are used in the encryption negotiation process to set a minimum level as well as a maximum level of encryption.

### About this task

The CIPHERS attribute on the resource definitions TCPIPSERVICE, CORBASERVER and URIMAP specifies the cipher suites that can be used for each encryption level. The default value of the attribute is the list of 2-digit cipher codes that are used in encryption negotiations. You have the option of customizing this list of cipher suites to include your order of preference for the encryption levels at which CICS should negotiate with clients. You can also choose to remove cipher suites from the list. This is particularly useful if you want to ensure that only a very high level of encryption is used. You can do this as follows:

### Procedure

- 1. Select the resource definition that you want to change.
- 2. The CIPHERS attribute displays the default value. For example, if the system initialization parameter ENCRYPTION=STRONG, the default value is 0504352F0A0903060201. For CICS to display the default value, the KEYRING system initialization parameter must be specified in the CICS region where you are working with the resource definition.
- **3**. Edit the attribute value to remove and reorder the cipher suites. For example, you could specify 352F0A0504.
- 4. Save the resource definition.

### Results

Specifying 352F0A0504 means that CICS will not negotiate below 128-bit encryption for connections using this resource. Each of the 2-digit codes in the attribute, for example 35, 2F, 0A and so on, refer to cipher suites that have at least a 128-bit encryption. CICS will start by trying to negotiate using the AES cipher suites 35 and 2F, because these are first in the list of cipher codes. If the client does not have this level of encryption, CICS will close the connection.

Note that you cannot include cipher suites that are not in the default values for that level of encryption. For example, if you have a MEDIUM level of encryption specified, you cannot add the AES cipher suites 35 and 2F to the CIPHERS attribute. For a complete list of cipher suites for each level of encryption, see The ENCRYPTION system initialization parameter.

# Configuring LDAP for CICS use

You can use LDAP for storing CRLs (certificate revocation lists) or Basic Authentication credentials. When certificate revocation lists or credentials are stored in the LDAP server, you must authorize CICS to access them.

### About this task

Certificate revocation lists and passwords are stored in the LDAP server with an access class of *critical* and can only be accessed by a user who has provided authentication credentials at LDAP bind time. These credentials are a user's distinguished name and an associated password. You can save these details in a

specialized profile in the LDAPBIND RACF class. To set up the profile, follow these steps:

### Procedure

- 1. The password that is used in the profile must be encrypted before it is stored in the RACF database. To encrypt the password, you must store a password encryption key in the KEYSMSTR RACF class by issuing one of the following RACF commands:
  - RDEFINE KEYSMSTR LDAP.BINDPW.KEY OWNER(userid) SSIGNON(KEYENCRYPTED(keyvalue))

Use this command when the password encryption key is stored by the integrated cryptographic service facility (ICSF).

 RDEFINE KEYSMSTR LDAP.BINDPW.KEY OWNER(userid) SSIGNON(KEYMASKED(keymask))

Use this command when ICSF is not active.

2. Create the profile using the following RACF command:

RDEFINE LDAPBIND profile-name PROXY(LDAPHOST(ldap-url) BINDDN('ldap-distinguished-name') BINDPW(password)) UACC(NONE)

where:

#### profile-name

is the name of the RACF profile whose PROXY segment contains the following LDAP bind parameters.

#### ldap-url

is a fully qualified URL of the LDAP server to be accessed; for example, LDAP://EXAMPLE.COM:3389.

#### ldap-distinguished-name

is the distinguished name of an LDAP user authorized to inquire on certificate revocation list attributes from the server; for example, CN=LDAPADMIN.

#### password

is the password that authenticates the LDAP user. The password is case-sensitive.

**3**. Authorize each CICS region user ID to access appropriate bind credentials in the LDAPBIND class by issuing one or more commands of the following form:

PERMIT profile-name CLASS(LDAPBIND) ACCESS(READ) ID(region-userid)

# Using certificate revocation lists (CRLs)

You can configure CICS to use certificate revocation lists (CRLs) to check the validity of client certificates being used in SSL negotiations.

### Before you begin

To use certificate revocation lists, you must install and configure an LDAP server. Details on how to perform these tasks can be found in *z*/OS V1R4.0 Security Server LDAP Server Admin and Use.

### About this task

A certificate revocation list details the revoked certificates from a certificate authority. Certificate authorities keep these lists in CRL repositories that are available on the World Wide Web and can be downloaded and stored in an LDAP server. To populate the LDAP server and update certificate revocation lists, use the CICS-supplied transaction CCRL. You also need to authorize CICS to access the LDAP server. To use CRLs, follow these steps:

# Configuring an LDAP server for CRLs

To use certificate revocation lists (CRLs), you must have an LDAP server running. You will also need to perform some configuration steps before you download the CRLs.

### Before you begin

If you need to install and configure an LDAP server, read the *z*/OS V1R4 Security Server LDAP Server Admin and Use manual.

### About this task

### Procedure

- 1. Ensure that the LDAP server is running. The default started task name is LDAPSRV.
- 2. In the file system in etc/ldap, edit the configuration file slapd.conf as follows:
  - a. Create an administrator distinguished name and password, by providing values for adminDN and adminPW. The CICS-supplied CCRL transaction requires this information to update the LDAP server with the certificate revocation lists.
  - b. Create a suffix entry for every certificate authority that you want to download CRLs from using CCRL. For each suffix, use the syntax "O=*certificate authority*". The suffix is comprised of the Certificate Authority's distinguished name that contains the organization or "O=" keyword, together with any other keywords to the right of this. If the suffix contains any of the special characters <,+;>\" you must escape them by using two backslash characters. If you are using the z/OS LDAP server and the suffix contains any characters that are not in the required 1047 code page, the characters should be escaped by encoding them as the 3-digit octal number of their Unicode representation, preceded by an ampersand.

### Example

For example you could specify the following suffixes in the file slapd.conf:

```
suffix "0=CompanyName"
suffix "0=CompanyName plc"
suffix "0=CompanyName,L=CompanyLocation,ST=CompanyArea,C=CompanyCountry"
suffix "0=CompanyName\\, Inc."
suffix "0=CompanyName\\, Inc.,C=CompanyCountry"
```

### What to do next

When you have configured the LDAP server to include all of your certificate authorities, run the CCRL transaction. For details, see "Running the CCRL transaction" on page 275.

# **Running the CCRL transaction**

The CICS-supplied transaction CCRL allows you to download and store certificate revocation lists (CRLs) that can be used in the SSL handshake to determine if client certificates are valid.

# Before you begin

You need to configure an LDAP server to specify which certificate authorities you want to use and to create an administrator id and password. See "Configuring an LDAP server for CRLs" on page 274 for detailed instructions.

## About this task

Certificate revocation lists are available from certificate authorities such as Verisign. They are kept in CRL repositories that are available on the World Wide Web and can be downloaded and stored in an LDAP server. To populate the LDAP server and update certificate revocation lists, use the CICS-supplied transaction CCRL. You can run the CCRL transaction from a terminal or using a **START** command. Use the **START** command to schedule regular updates.

## Procedure

- 1. Specify the name of the profile that authorizes CICS to access the LDAP server in the **CRLPROFILE** system initialization parameter.
- 2. Run the CCRL transaction using either of the following methods:
  - Run the transaction from a terminal. See "Running CCRL from a terminal".
  - Run the transaction using a command. See "Running CCRL from a START command" on page 276.

## Running CCRL from a terminal

You can run the CICS-supplied transaction CCRL using a terminal to download certificate revocation lists (CRLs).

#### Before you begin

Read "Running the CCRL transaction" to find out about the prerequisites before running this transaction from a terminal.

#### Procedure

- 1. From a terminal, enter the command CEOT TRANIDONLY so that you can enter the list of URLs in mixed case.
- 2. Enter CCRL *url-list*, where *url-list* is the URL that specifies the location of the certificate revocation list file that you want to download. You can specify more than one URL by leaving a space between each URL in the list. For example, you could specify: CCRL http://crl.verisign.com/ATTClass1Individual.crl http://crl.verisign.com/ATTClass2Individual.crl.
- **3**. You are prompted to enter the administrator distinguished name and password for the LDAP server. This allows CICS to update the LDAP server with the CRLs that it downloads. The administrator name and password are specified in the file slapd.conf. For more information about configuring this file, see "Configuring an LDAP server for CRLs" on page 274

## Results

CICS downloads the CRLs from the URLs that you have specified and store them in the LDAP server. You will receive confirmation that all of the lists were downloaded. If CICS experiences a problem, for example the URL is not valid, you will receive an error message.

### What to do next

To set up regular updates, you can use a START command. See "Running CCRL from a START command."

## **Running CCRL from a START command**

You can schedule the CCRL transaction to run at regular intervals using a START command.

### Before you begin

Read "Running the CCRL transaction" on page 275 to find out about the prerequisites before running this transaction from a terminal.

### Procedure

To use a START command, enter EXEC CICS START TRANSID(CCRL) FROM (admin://adminDN:adminPW url-list) LENGTH (url-list-length) [INTERVAL(hhmmss)]TIME(hhmmss)] where url-list is a space-delimited list of URLs from where certificate revocation lists can be downloaded, url-list-length is the length of the URL list (including admin://), and hhmmss is the interval or expiration time at which the CCRL transaction is to be scheduled. For example, you could specify:

EXEC CICS START TRANSID(CCRL)

```
FROM('admin://cn=ldapadmin:cics31ldap http://crl.verisign.com/ATTClass1Individual.crl http
LENGTH(124) INTERVAL(960000)
```

This would schedule the CCRL transaction to run in 96 hours.

# Part 5. Security for enterprise beans

This describes how you can use RACF to provide security for enterprise beans.

# Chapter 20. Managing security for enterprise beans

The security mechanisms, Java2 security, Secure Sockets Layer (SSL) security, MRO security, and Security Roles can be used with enterprise beans.

You can implement any combination of these.

#### Java security

This form of security control is implemented by the Java Virtual Machine (JVM) and can be used with any Java program that executes under JVM control. See "Protecting Java applications in CICS by using the Java security policy mechanism" for guidance on using this type of security control.

#### Secure Sockets Layer (SSL) security

The Secure Sockets Layer (SSL) is a security protocol that provides privacy and authentication between clients and servers communicating using TCP/IP. For more information about SSL, see Support for security protocols, in the *CICS RACF Security Guide*. For information about using SSL with enterprise beans see Authentication of IIOP requests.

#### MRO security

After the request receiver has established a CICS USERID to be associated with the request, it may need to be routed to an application-owning-region (AOR). If the routing mechanism uses a multiple region operation (MRO) connection, the transmission of the userid is subject to MRO security rules. See Link security with MRO, in the *CICS RACF Security Guide*.

#### Security roles

A security role represents a type of user of an application in terms of the permissions that the user must have to successfully use the application. See "Security roles" on page 287.

# Protecting Java applications in CICS by using the Java security policy mechanism

The security of the enterprise beans container environment is protected by the Java security policy mechanism and is independent of CICS security. The security policy mechanism is one of the components that make up the Java security model.

The security policy mechanism is used to enforce the restrictions in the EJB specification concerning Java functions that may not be issued by enterprise beans. By default, Java applications have no security restrictions placed on activities requested of the Java API; the Java API does whatever it is asked. To use Java security to protect a Java application or enterprise bean from performing potentially unsafe actions, you enable a security manager for the Java Virtual Machine (JVM) in which the application or enterprise bean runs. If no security manager is enabled, the JVM runs without Java security by default. A default security manager is supplied with the Java platform. To prevent unauthorized access to system resources by enterprise beans, you are recommended to enable the default security manager.

The security manager enforces a security policy, which is a set of permissions (system access privileges) that are assigned to code sources. Every time the JVM executes code in a class, the JVM determines the code source for the class and

consults the security policy before granting the class the appropriate permissions. Thus, if a piece of code requests access to a particular system resource while a security manager is active, the JVM grants the code access to that resource only if such an access is a privilege associated with that class.

When a JVM starts up, its security manager determines the security policy for the JVM by looking at one or more *policy files* that you have specified. The policy files contain details of the permissions that are granted to particular code sources. A default policy file is supplied with the Java platform. If you enable the default security manager for a JVM, but do not specify any policy files, the security manager determines a security policy using the permissions given in the default policy file. You can specify one or more additional policy files containing permissions that you want to grant, and the security manager adds these permissions to the security policy. So, although only one security policy is in effect for the JVM at any given time, this security policy can be the result of processing one or more policy files.

To enable Java applications and enterprise beans to run successfully in CICS when Java security is active, you specify, as a minimum, an additional policy file that gives CICS the permissions it needs to run the enterprise beans container and gives applications the permissions outlined in the *Enterprise JavaBeans* specification, Version 1. The CICS-supplied enterprise beans policy file, dfjejbpl.policy, contains the permissions for this purpose. You specify this additional policy file for each kind of JVM that has a security manager enabled.

You enable the security manager for a JVM, and specify additional policy files, using the security system properties for the JVM.

If you need more information about Java security than is provided here, refer to the Java documentation.

### Java security with JDBC or SQLJ

To use JDBC or SQLJ from enterprise beans that run in a JVM with a Java security policy mechanism active, you must use the JDBC 2.0 driver provided by DB2. The JDBC 1.2 driver provided by DB2 does not support Java security and will fail with a security exception unless you disable the mechanism (by deactivating the security manager for the JVM). You must also modify your additional policy file to grant permissions to the JDBC driver.

# Enabling a Java security manager and specifying policy files for a JVM

To enable a Java security manager for a JVM and specify additional policy files that you want the security manager to use, you need to customize the security system properties for the JVM.

For each JVM profile that your Java applications and enterprise beans request, if you want JVMs with that profile to run with Java security, you need to enable the default security manager and specify a suitable policy file. For each JVM profile that you want to use Java security, customize the following system properties in either the JVM profile or a JVM properties file:

#### -Djava.security.manager

This system property indicates the Java security manager to be enabled for the JVM. To enable the default Java security manager, include this system property in one of the following formats:

```
-Djava.security.manager=default
```

or

```
-Djava.security.manager=""
```

or

|

Т

L

I

|

T

1

1

T

1

L

|

I

|

1

L

L

T

I

|

I

-Djava.security.manager=

All these statements have the effect of enabling the default security manager. If you do not include the **-Djava.security.manager** system property, then the JVM runs without Java security enabled. If you need to disable Java security for a JVM, comment out this system property.

#### -Djava.security.policy

This system property describes the location of additional policy files that you want the security manager to use to determine the security policy for the JVM. A default policy file is provided with the JVM in /usr/lpp/java/J6.0/lib/ security/java.policy, where java/J6.0 is your install location for the IBM 31-bit SDK for z/OS, Java Technology Edition. The default security manager always uses this default policy file to determine the security policy for the JVM, and you can use the **-Djava.security.policy** system property to specify any additional policy files that you want the security manager to take into account as well as the default policy file.

To enable CICS Java applications and enterprise beans to run successfully when Java security is active, you need to specify, as a minimum, an additional policy file that gives CICS the permissions it needs to run the enterprise beans container, and gives applications the permissions outlined in the *Enterprise JavaBeans* specification, Version 1. If you do not provide these permissions, then the container code may become inaccessible, preventing CorbaServers from being initialized. The CICS-supplied enterprise beans policy file, dfjejbpl.policy, contains the permissions that you need. To specify this policy file, include the system property:

-Djava.security.policy=/usr/lpp/cicsts/cicsts41/lib/security/dfjejbpl.policy

where *cicsts41* is your chosen value for the USSDIR installation parameter that you defined when you installed CICS TS. "The CICS-supplied enterprise beans policy file" on page 283 has more information about dfjejbpl.policy.

If you need to give any of your applications further permissions, you can modify the CICS-supplied enterprise beans policy file, or create and specify your own additional policy file. Policy files are stored in text format, so you can display or modify them using any standard text editing tool. In particular, if you want to use JDBC or SQLJ from enterprise beans, you need to modify the enterprise beans policy file that you have specified, to grant permissions to the JDBC driver. Requirements to support Java programs in the CICS DB2 environment, in the *CICS DB2 Guide*, tells you how to do this.

It is recommended that policy files are made secure, with update authority restricted to system administrators.

When you specify a policy file in the JVM properties file, the policy file is used for JVMs that are built using JVM profiles which reference that JVM properties file. As an alternative, you can specify a policy file to be used for **all** the JVMs in your system for which you have enabled a Java security manager, whatever JVM properties file they might have. For example, you could specify the CICS-supplied enterprise beans policy file, dfjejbpl.policy, to be used for all your JVMs. To do this, instead of including the **-Djava.security.policy** system property, use the

alternative method described in "Specifying policy files to apply to all JVMs." If you specify a policy file to be used for all JVMs, remember that to activate Java security for your JVMs, you still need to add the **-Djava.security.manager** system property to your JVM profile or optional JVM properties files to enable a Java security manager.

# Specifying policy files to apply to all JVMs

As an alternative to using the **-Djava.security.policy** system property to specify additional policy files, you can name the additional policy files in the JVM default **security properties file**, which applies to all JVMs.

This file is where the default Java security manager looks for the name of the default policy file, which it always uses to determine the security policy for a JVM.

The default security properties file is called java.security and is provided in: /usr/lpp/java/J6.0/lib/security/java.security

where the java/J6.0 subdirectory names are your install location for the IBM 31-bit SDK for z/OS, Java Technology Edition on z/OS UNIX.

The default security properties file already includes the name of the default policy file, /usr/lpp/java/J6.0/lib/security/java.policy. You can add the names of additional policy files, and the security manager will then use these files, as well as the default policy file, to determine the security policy for **all** JVMs. The security manager will also refer to any policy files that you have specified in the JVM profile or optional JVM properties file for a particular type of JVM.

In the default security properties file java.security, policy files are specified in the form:

policy.url.n=URL

where n represents the precedence number for the order in which the policies should be loaded. The location of a policy file is specified as a URL, so policy files do not need to be stored in the local file system.

Note that the precedence numbers must be serial and continuous. For example, if policy.url.1 and policy.url.3, are present, but policy.url.2 is missing, then policy.url.3 is ignored and only policy.url.1 is considered.

The default security properties file java.security contains these two entries: policy.url.1=file:\${java.home}/lib/security/java.policy policy.url.2=file:\${user.home}/.java.policy

To specify the CICS-supplied enterprise beans policy file, dfjejbpl.policy, as an additional policy file to be used for all JVMs, add the entry: policy.url.3=file:/usr/lpp/cicsts/*cicsts41*/lib/security/dfejbpl.policy

where *cicsts41* is your chosen value for the USSDIR installation parameter that you defined when you installed CICS TS. It is specified as policy.url.3 because two other policy files are already specified. You can substitute the path to your own policy file in place of dfjejbpl.policy, or add further entries to specify additional policy files.

It is possible to bypass the default security properties file java.security for a JVM. You can do this by specifying your own policy file on the **-Djava.security.policy**  system property for the JVM, and inserting a double equals sign (= =). For example, if you include the system property: -Djava.security.policy=/usr/lpp/cicsts/cicsts41/lib/security/dfejbpl.policy

then the security manager ignores any policy files that are specified in the java.security file, and uses only dfjejbpl.policy to determine the security policy for the JVM. However, you should bear in mind that if you bypass the default security properties file, the security manager will not grant any permissions that are specified in that file; it will only grant the permissions that are specified in your own policy file.

# The CICS-supplied enterprise beans policy file

The CICS-supplied enterprise beans policy file, dfjejbpl.policy, is based on the Java security policy mechanism.

The Java security policy mechanism is described in the Sun Microsystems *Enterprise JavaBeans Specification, Version 1.1,* which is available at http://www.javasoft.com/products/ejb. The sample policy file is shown in Figure 26 on page 284.

In Java, the security policy is defined in terms of protection domains which map permissions to code sources. A protection domain contains a code source with a set of associated permissions.

The CICS-supplied enterprise beans policy file defines two protection domains, which do the following:

- 1. Grants the required permissions to the CICS enterprise beans Container code source for execution. See the 'grant codeBase' block in Figure 26 on page 284.
- Grants any code source only the permissions outlined in the *Enterprise JavaBeans* specification, Version 1. See the default 'grant' block in Figure 26 on page 284:
  - To allow anyone to initiate a print job request.
  - To allow outbound connection on any TCP/IP ports.
  - To allow all system properties to be read.

Remember that if you want to use JDBC or SQLJ from enterprise beans, you need to amend the CICS-supplied enterprise beans policy file to grant permissions to the JDBC driver. Requirements to support Java programs in the CICS DB2 environment, in the CICS DB2 Guide, tells you how to do this.

```
// permissions granted to CICS enterprise beans Container codesource protection
//domain
grant codeBase "file:usr/lpp/cicsts/cicsts41//-" {
    permission java.security.AllPermission;
};
// default EJB 1.1 permissions granted to all protection domains
grant {
    // allows anyone to initiate a print job request
    permission java.lang.RuntimePermission "queuePrintJob";
    // allows outbound connection on any TCP/IP ports
    permission java.net.SocketPermission "*:0-65535", "connect";
    // allows anyone to read properties
    permission java.util.PropertyPermission "*", "read";
};
```

Figure 26. Sample CICS enterprise beans security policy

# Using enterprise bean security

The EJB 1.1 specification defines the following security APIs to allow enterprise beans to make application decisions based on their callers' security details.

```
java.security.Principal getCallerPrincipal()
```

This method is used to determine who invoked the current bean method. The getCallerPrincipal method is fully supported in CICS. Details of the way that the identity of the current caller is determined are shown in "Deriving distinguished names" on page 286.

```
boolean isCallerInRole(String SecurityRoleReference)
```

This method is used to test whether the current caller is assigned to a security role that is linked to the security role reference specified on the method call.

CICS will throw a runtime exception (which conforms to the EJB 1.1 specification) if the following deprecated EJB 1.0 security APIs are used.

- java.security.Identity getCallerIdentity()
- boolean isCallerInRole(java.security.Identity role)

**Note:** Note that enterprise beans developed to the Enterprise JavaBeans (EJB) 1.0 specification need to be upgraded to the Enterprise JavaBeans 1.1 specification level, using the supplied development tools.

- See The deployment tools for enterprise beans in a CICS system for information about deployment tools.
- See Writing enterprise beans for information about writing enterprise beans.
- See Java Applications in CICS for more information.
- See The deployment tools for enterprise beans in a CICS system for information about deployment tools.
- See Writing enterprise beans for information about writing enterprise beans.

# Defining file access permissions for enterprise beans

To successfully run enterprise beans in CICS, the CICS region userid must be permitted to access the files used by the enterprise logic.

These file permissions are required to run enterprise beans, regardless of the level of security implemented. See also the *CICS Transaction Server for z/OS Installation Guide*.

# Access to z/OS UNIX files used by enterprise beans

These file permissions are required to run enterprise beans.

File/Directory structure	Minimum permission	Comments
CORBASERVER Shelf directory (for example, /var/cicsts/ )	Read, write and execute	The shelf is accessed during CORBASERVER and DJAR installation, and each CICS needs to create unique subdirectories (see note 1).
/usr/lpp/cicsts/cicsts41 directory structure and classes	Read and execute	Contains the CICS-supplied Java code (see note 2).
/usr/lpp/java/J6.0/bin and /usr/lpp/java/J6.0/bin/classic directories	Read and execute	Contain the IBM JVM code (see note 3).
CICS working directory	Read, write and execute	Used to create stdin files (see note 4).
Deployed jar file	Read	Used during DJAR installation by the deployment process.
Security policy file (if required)	Read	Required if the <b>-Djava.security.policy</b> property is specified in the JVM system properties file.
System properties file	Read	Optional when creating a JVM (see note 5).

Table 38. File access permissions required for CICS enterprise beans

#### Note:

|

L

- 1. /var/cicsts/ is the default SHELF directory name when you define a CORBASERVER resource definition. Each CICS region creates a unique subdirectory in this shelf when it installs the resource definition
- **2**. *cicsts41* is your chosen value for the USSDIR installation parameter that you defined when you installed CICS TS.
- **3**. java/J6.0 is your install location for the IBM 31-bit SDK for z/OS, Java Technology Edition.
- 4. The CICS working directory is defined by the WORK_DIR parameter in the JVM profile.
- 5. The optional system properties directory and file name are named on the JVMPROPS option in the JVM profile.

File ownership and permissions may be defined using the **chmod** and **chown** commands. For more information, see *z*/OS UNIX System Services Command *Reference*.

#### Access to data sets used by enterprise beans

Before CORBASERVERs can be installed in a CICS region, the following two data sets must be created with UPDATE access, defined to CICS and installed. These files can be VSAM data sets or coupling facility data tables.

Figure 27 shows an example of RACF commands to access data sets with the necessary authorization.

**Note:** These files are used internally by CICS, so no users should be given resource level security access to them. This will prevent VSAM applications from accessing the data in these files.

#### DFHEJDIR

This data set contains a request streams directory which is shared by the listener regions and AORs comprising a CICS IIOP server. The file must be recoverable.

#### **DFHEJOS**

DFHEJOS is a data set containing passivated stateful session beans. It is shared by all the AORs comprising a CICS IIOP server. This file must not be recoverable.

Figure 27. An example of RACF commands used to authorize access to CICS data sets

See Authorizing access to CICS data sets, in the CICS RACF Security Guide, for more information about authorizing access to CICS data sets.

# **Deriving distinguished names**

Enterprise beans can identify their end-user, or client, by means of a *Principal* object.

The getCallerPrincipal method returns a Principal object representing the client, and that Principal object contains methods that can be invoked to return information about the client. In particular, the getName method of the Principal object returns a String that contains the "distinguished name" of the client. The distinguished name, or DN, is a sequence of keyword and value pairs, known as relative distinguished names, or RDNs, and forms part of the X.500 recommendation (Standard ISO/IEC 9594). The string representation of a distinguished name is suggested by RFC2253, *LDAP V3: UTF-8 String Representation of Distinguished Names*.

**Note:** CICS Transaction Server for z/OS, Version 4 Release 1 does not verify that a stateful session bean instance is used only by the same principal that created it. Therefore the principal's userid and distinguished name may be different after a bean instance has been reactivated.

If the bean's client has been identified and authenticated by means of a client certificate using the secure sockets layer protocol, the distinguished name is always obtained from that certificate. However, if the bean's client has not provided a certificate, the distinguished name is obtained by invoking the DFHEJDNX user-replaceable module. The inputs to the DFHEJDNX module are the title, organizational unit, organization, locality, state, and country, obtained from the server certificate whose label is specified in the CERTIFICATE option of the CORBASERVER definition, and the userid and common name associated with the user ID of the user executing the bean, but if SEC=NO is specified, the CICS region

userid is used. The common name is derived by transforming the username for that user to a mixed-case string.) The certificate label specifies a certificate within the key ring identified by the KEYRING system initialization parameter. If the CERTIFICATE option is omitted, information is obtained from the default certificate in the key ring. If the KEYRING parameter is omitted, no certificate information is passed to DFHEJDNX, and only the common name RDN is available.

The CICS-supplied version of DFHEJDNX accepts the inputs derived from the CORBASERVER certificate and the username, and formats them into a distinguished name in the following style:

T=CICS EJB Container,CN=Louise Peters,OU=CICS/390 Development, O=IBM,L=Hursley,ST=Hampshire,C=GB

CICS-supplied samples of DFHEJDNX are located in the SDFHSAMP library, *CICSTS41.CICS.SDFHSAMP*, as:

- DFHEJDN1 for Assembler language
- DFHEJDN2 for C language

# Security roles

Access to enterprise bean methods is based on the concept of security roles.

A security role represents a type of user of an application in terms of the permissions that the user must have to successfully use the application. For example, in a payroll application:

- A manager role could represent users who are permitted to use all parts of the application
- A team_leader role could represent users who are permitted to use the administration functions of the application
- A data_entry role could represent users who are permitted to use the data entry functions of the application

The security roles for an application are defined by the application assembler, and are specified in the bean's deployment descriptor. For more information, see "Security roles in the deployment descriptor" on page 291

The security roles that are permitted to execute a bean method are also specified in the bean's deployment descriptor, again by the application assembler. In the example, methods which update the hours worked by employees each week might be assigned to the data_entry role, while methods which delete an employee from the payroll might be assigned to the team_leader role.

To distinguish similarly named security roles in different applications, or in different systems, the security roles specified in the bean's deployment descriptor can be given a one- or two-part qualifier when the bean is deployed in a CICS system. For example:

- Security role with no qualifiers: team_leader
- Security role with one qualifier: payroll.team_leader
- Security role with two qualifiers: test.payroll.team_leader

A security role with its qualifiers is known as a **deployed security role**. For more information, see "Deployed security roles."

The mapping of security roles to individual users is done in the external security manager. The mapping is not necessarily one-to-one. For example, several users might be assigned to the data_entry role, while a some users might be assigned to both the team_leader role and the data_entry role. For more information, see "Implementing security roles" on page 293.

The security role and display name in the deployment descriptor can contain any ASCII or Unicode character. This is not so for names used in RACF, which are restricted to characters in EBCDIC code page 037. In addition, some characters — the asterisk (*) for example — have special meaning when used in RACF commands. Therefore, when CICS constructs the deployed security role from its components, some characters are replaced with a different character, and others are replaced with an escape sequence. For details, see "Character substitution in deployed security roles" on page 290.

# Deployed security roles

A direct mapping between the security roles specified in a bean's deployment descriptor and individual users may not adequately control access to bean methods.

For example

- Two applications, provided by different suppliers, might use similar names for security roles. In your enterprise, the users of each application might be different.
- A bean could be used in more than one application. A user may be entitled to use a particular method in one application, but not in the other.
- An application could be deployed in a test system and a production system. Members of the test department may be permitted to use all bean methods in the test system, but not in the production system.

To provide the degree of control that is needed in these and other cases, you can qualify the security roles at the application level and the system level. A security role with its qualifiers is known as a **deployed security role**. Here is an example of a role name which is qualified at both levels:

test.payroll.team_leader

- payroll qualifies the security role at the application level, and is used to distinguish between the team_leader role in the payroll application and the team_leader role in other applications.
- test qualifies the security role at the system level, and is used to distinguish between the payroll.team_leader role in the test system and the payroll.team_leader role in other systems.

At the application level, security roles are qualified by the **display name**, if one is specified in the deployment descriptor. If a display name is not specified, the security roles are not qualified at the application level. If an application level qualifier is used, a period (.) is used as the delimiter; if no qualifier is used, there is no delimiter.

At the system level, security roles are optionally qualified with a prefix which is specified in the EJBROLEPRFX system initialization parameter. If EJBROLEPRFX is

not specified, the security roles are not qualified at the system level. If a system level qualifier is used, a period (.) is used as the delimiter; if no qualifier is used, there is no delimiter.

This example shows how security roles defined in a bean's deployment descriptor can be qualified:

- A bean contains three security roles: manager, team_leader, and data_entry
- The bean is used in a payroll application, with a display name of payroll. The bean is also part of a test application, which does not have a display name.
- The payroll application is used on two production systems: the first does not specify a prefix, while the second specifies a prefix of executive.
- The test application is used on a test system with a prefix of test1.

When the two levels of qualification are applied to the security roles specified in the deployment descriptor, the deployed security roles are:

payroll.manager	executive.payroll.manager	test1.manager
payroll.team_leader	executive.payroll.team_leader	<pre>test1.team_leader</pre>
payroll.data_entry	executive.payroll.data_entry	test1.data_entry

Each of these deployed roles can be mapped to individual users (or groups of users) to suit the security need of the enterprise.

If a security role is not qualified at the application level, or at the system level, then the deployed security role is the same as the security role defined in the deployment descriptor. For example, if the bean in the previous example is used in an application which does not have a display name, and the application is used in a system that does not specify EJBROLEPRFX, then the deployed security roles are:

manager team_leader data_entry

# Enabling and disabling support for security roles

By default, CICS support for security roles is enabled.

You can use the XEJB system initialization parameter to disable (or explicitly enable) support for security roles. If you disable the support:

- CICS does not perform method authorization checks: all users are permitted to use all bean methods.
- The isCallerInRole() method returns true for all users.

## Security role references

Within an application, the isCallerInRole() method can be used to determine if the user of the application is defined to a given role.

The method takes a **security role reference** as an argument, rather than a security role. The security role references coded in the bean are defined by the bean provider, and declared in the bean's deployment descriptor.

For more information, see "Security roles in the deployment descriptor" on page 291

Each security role reference is linked to a security role by the application assembler; the linkage is declared in the deployment descriptor for the bean. For

example, the security role reference of administrator used within the bean's code might be linked, in the deployment descriptor, to the team_leader role.

For more information, see "Security roles in the deployment descriptor" on page 291

# Character substitution in deployed security roles

The security role and display name in the deployment descriptor can contain any ASCII or Unicode character.

The character set which can be used in deployed security roles is more restricted:

- Profile names used in RACF are restricted to characters in EBCDIC code page 037.
- Some characters the asterisk (*) for example have special meaning when used in RACF commands, and cannot be used in a profile name.

When Unicode characters in the security role and display name cannot be used directly in the deployed security role, they are replaced by the escape sequences shown in Table 39. Substitution occurs:

- when the EJBROLE generator utility (dfhreg) processes the deployment descriptor to generate RACF commands
- · when CICS maps a security role to a RACF user ID

Table 39. Escape sequences used in security roles

Character	Description	ASCII/Unicode	EBCDIC code page 037	Escape sequence
	le values whose eq e are replaced with			
	blank	X'20'	X'40'	¢
¢	cent	X'A2'	X'4A'	\A2
\	backslash	X'5C'	X'E0'	\5C
*	asterisk	X'2A'	X'5C'	\2A
&	ampersand	X'26'	X'50'	\26
%	per cent	X'25'	X'6C'	\25
,	comma	X'2C'	X'6B'	\2C
(	left parenthesis	X'28'	X'4D'	\28
)	right parenthesis	X'29'	X'5D'	\29
;	semicolon	X'3B'	X'5E'	\3B
Unicode values w	hich do not have a	n equivalent in FB	CDIC code page ()	37 are replaced

Unicode values which do not have an equivalent in EBCDIC code page 037 are replaced with the Unicode escape sequence: a character with a Unicode representation of X'yyyy' is replaced by \uyyyy. For example:

€	Euro symbol	X'20AC'	not supported	\u20AC
	Hiragana Ki	X'304D'	not supported	\u304D
α	alpha	X'03B1'	not supported	\u03B1

Here are two examples that illustrate the way that characters are substituted:

#### Example 1

• The EJBROLEPRFX has a value of test

- The display name in the deployment descriptor has a value of year.end.processing
- The security role in the deployment descriptor has a value of auditor 1

In this example, when the deployed security role is constructed:

- 1. Each space is replaced with ¢
- 2. The deployed security role is composed from the EJBROLEPRFX value, the display name, and the security role; a period is used as the delimiter.

The resulting deployed security role is:

test.year.end.processing.auditor¢1

#### Example 2

- The EJBROLEPRFX has a value of test
- The display name in the deployment descriptor has a value of  $\alpha\beta$ 32. The Unicode encoding is X'03B1 03B2 0033 0034'.
- The security role in the deployment descriptor has a value of auditor 1

In this example, when the deployed security role is constructed:

- 1. Each Unicode character that has an equivalent in EBCDIC code page 037 is replaced accordingly: In the display name, X'0033 0034' is replaced by 34.
- 2. Each Unicode character that does *not* have an equivalent in EBCDIC code page 037 is replaced with the corresponding escape sequence. In the display name, X'03B1 03B2' is replaced by \u03B1\u03B2
- **3**. Each space is replaced with ¢
- 4. The deployed security role is composed from the EJBROLEPRFX value, the display name, and the security role; a period is used as the delimiter.

The resulting deployed security role is: test.\u03B1\u03B234.auditor¢1

# Security roles in the deployment descriptor

This shows a fragment of a deployment descriptor. It includes the following security role information.

- 1 A display name of payroll.
- 2 The security role reference of administrator which is linked to the team_leader role.
- 3 A security role of team_leader.
- 4 A method permission that allows a user defined in the team_leader role to invoke the create() method.

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE ejb-jar PUBLIC
"-//Sun Microsystems, Inc.//DTD Enterprise JavaBeans 1.1//EN"
"http://java.sun.com/j2ee/dtds/ejb-jar 1 1.dtd">
  <ejb-jar id="ejb-jar ID">
    <display-name>payroll</display-name>
                                                  1
      <enterprise-beans>
        <session id="Session 1">
          <security-role-ref id="SecurityRoleRef 1">
            <role-name>administrator</role-name>2
            <role-link>team leader</role-link>
          </security-role-ref>
        </session>
      </enterprise-beans>
      <assembly-descriptor id="AssemblyDescriptor 1">
        <security-role id="SecurityRole 1">
          <role-name>team_leader</role-name>
                                                  3
        </security-role>
        <method-permission id="MethodPermission 1">
          <description>team leader:+:</description>
          <role-name>team leader</role-name>
                                                  4
          <method id="MethodElement_01">
            <ejb-name>Managed</ejb-name>
            <method-intf>Home</method-intf>
            <method-name>create</method-name>
            <method-params>
            </method-params>
          </method>
           .
        </method-permission>
      </assembly-descriptor>
     </ejb-jar>
```

Figure 28. Example of a deployment descriptor containing security roles

If an application with this deployment descriptor is used in a CICS system with the following system initialisation parameters:

SEC=YES XEJB=YES EJBROLEPRFX='test'

- The deployed security role of test.payroll.team_leader must be defined to RACF.
- Users that have READ access to that deployed security role will be permitted to invoke the create() method.
- isCallerInRole('administrator') will return true for users defined in the deployed security role of test.payroll.team_leader, and false for other users.

For detailed information about the contents of the deployment descriptor, refer to *Enterprise JavaBeans Specification, Version 1.1.* 

To view the contents of a deployment descriptor, you can use the Assembly Toolkit (ATK). For more information about ATK, see The enterprise bean deployment tool, ATK, in the *CICS Operations and Utilities Guide*.

# Implementing security roles

Access to enterprise bean methods is based on the concept of security roles.

#### About this task

These are described in "Security roles" on page 287.

To implement the use of security roles in a CICS enterprise bean environment, you must:

- 1. Determine which security roles are defined in the application's deployment descriptor.
- 2. Determine the display names associated with the security roles in the application's deployment descriptor. The display name qualifies the security role at the application level.
- **3**. Decide whether you need to qualify the security role name at the system level, and if you do the value of the prefix which you will use in each system where the application executes.
- 4. Using the information gathered in steps 1 through 3, determine the names of the deployed security roles used by the application in each system. Characters in the security role and display name that do not have a direct equivalent in EBCDIC code page 37 (and some other characters) must be replaced with a different character or an escape sequence when constructing the deployed security role. See "Character substitution in deployed security roles" on page 290 for more information.
- 5. Using the information gathered in steps 1 through 3, define RACF profiles for the deployed security roles. See the *Java Applications in CICS* manual"Defining security roles to RACF" on page 295 for more information.
- 6. Associate individual users or groups of users with each deployed security role in RACF. See the *Java Applications in CICS* manual"Defining security roles to RACF" on page 295 for more information.
- 7. Specify these system initialization parameters:
  - SEC=YES
  - XEJB=YES. This is the default value, so you do not need to specify it explicitly.
- 8. For those systems where the deployed security roles contain a system level qualifier (see step 3), specify the EJBROLEPRFXEJBROLEPRFX system initialization parameter.

# Using the RACF EJBROLE generator utility

The RACF EJBROLE generator utility (dfhreg) is a Java application program that extracts security role information from deployment descriptors, and generates a REXX program which can be used to define security roles to RACF.

The REXX program that dfhreg generates contains the RACF commands that define security roles as members of a profile in the GEJBROLE class. Before you run the REXX program, you will need to modify it, in order to change the name of the profile that is defined.

The dfhreg invocation scripts for USS (dfhreg) and for Windows (dfhreg.bat) are in the CICS_HOME/lib/security directory. The implementation of dfhreg (dfhreg.jar) is also in this directory. The other JAR files required to run dfhreg (dfjcsi.jar, dfjejbdd.jar, and dfjorb.jar) are in the CICS_HOME/lib directory. CICS_HOME is the z/OS UNIX directory in which you have installed the USS components of CICS.

You can execute dfhreg on any platform that supports Java; however, you must execute the resulting REXX program against the RACF database on the z/OS system where you want to define the security roles. When you run dfhreg:

1. Your classpath must contain:

dfhreg.jar dfjcsi.jar dfjejbdd.jar dfjorb.jar

2. You must be using a 1.4 or later version of the Java 2 SDK.

The REXX program which the utility generates is in the code page of the platform where the utility executes. If you run the utility on a platform that uses an ASCII code page, you must convert the REXX program to the EBCDIC code page used on the target z/OS system.

# Executing the utility About this task

To execute the utility enter the following on the command line: dfhreg [options] inputfiledesc

# The full syntax is

```
dfhreg [-secprfx secprfx]
    [-out outputfiledesc]
    [-f | -force]
    [-v | -verbose]
    [-? | -help]
    inputfiledesc
```

where

```
-secprfx secprfx
```

Specifies the name used to qualify the security role name at system level. The value you specify must match the value of the EJBROLEPRFXEJBROLEPRFX system initialization parameter for the CICS system where the security roles will be used

out outputfiledesc

Specifies the file which to which the utility writes its output. If you do not specify a file, output will be written to standard output.

inputfiledesc

Specifies the input file containing the deployment descriptor. The file must be a Java archive file (file type jar).

-f | -force

Specifies that the utility will overwrite an existing output file.

-v | -verbose

Specifies that processing messages will be written to standard output.

-? | -help

Displays a summary of the syntax for the utility.

```
All options are case sensitive; the keywords (-secprfx, -out, -force, -f, -verbose, -v, -help) must be entered in lower case.
```

If the utility encounters an error, it generates one or more messages. These are described in the *CICS Messages and Codes* manual.

# Defining security roles to RACF

In RACF, deployed security roles are managed as general resources. To define the deployed security roles, define profiles in the GEJBROLE or EJBROLE resource classes, with appropriate access lists.

For example, to use the following commands to define deployed security roles deployed_security_role_land deployed_securityrole_2 as members of the securityrole_group profile in the GEJBROLE class, and give READ access to user1 and user2:

```
RDEFINE GEJBROLE securityrole_group UACC(NONE)
ADDMEM(deployed_security_role_1, deployed_securityrole_2, ...)
NOTIFY(sys_admin_userid)
PERMIT securityrole_group CLASS(GEJBROLE) ID(user1, user2) ACCESS(READ)
```

Alternatively, use the following commands to define deployed security roles in the EJBROLE class, and to give users READ access to each deployed security role:

PERMIT deployed_security_role1 CLASS(EJBROLE) ID(user1, user2) ACCESS(READ) PERMIT deployed_security_role2 CLASS(EJBROLE) ID(user1, user2) ACCESS(READ)

#### Note:

- 1. The security role you specify is the deployed security role, and not the unqualified security role which is defined in the deployment descriptor.
- 2. To execute a bean method, or to receive a true response from the isCallerInRole() method, a user requires READ access.

# Part 6. Identity propagation and distributed security

Identity propagation provides a mechanism to allow a user identity from an external security realm to be preserved, regardless of where the identity information was created, strengthening accountability across distributed environments.

In an external computing environment, for example, WebSphere Application Server, the identity of a user is authenticated using a user identification that applies to that environment. Applications like WebSphere Application Server often use a separate, shared external security manager user ID when communicating with a CICS system. The original identity of the user is not passed to CICS and therefore cannot be passed onto the external security manager, making it difficult to determine the initial user identity and impacting the audit trail of the request.

In the identity propagation topics, RACF represents the external security manager. If you are not using RACF with CICS, consult your system administrator to configure the settings for your external security manager.

The term *distributed identity* represents user identity information, for example, an X.500 distinguished name and associated LDAP realm, that originates from a remote system. The distributed identity is created in one system and is passed to one or more other systems over a network. A distributed identity originates outside of CICS only; CICS is never the source of a distributed identity, but is capable of propagating the distributed identity onwards.

When a distributed identity enters the sysplex over MRO and IPIC connections, it is automatically propagated in the sysplex, regardless of connection settings. CICS security handles the distributed identity as additional information relating to the user ID, and a distributed identity cannot exist without a user ID.

Outside the sysplex, the distributed identity can be propagated on, depending on support. Receipt of a distributed identity by another party depends on whether the party is participating in identity propagation. See "Support and requirements for identity propagation" on page 299.

Identity propagation allows the distributed identity to be preserved, regardless of where the identity information was created, for use during authorization and for auditing purposes. The distributed identity is part of the identity context that is carried with a request from the external client application to the server, and it is incorporated in the access control of the server as part of the authorization process; for example, using RACF. CICS receives and processes the distributed identity, which is sent by another application; for example, CICS Transaction Gateway on behalf of WebSphere Application Server.

The diagram shows how the X.500 distinguished name and associated LDAP realm which identify the user externally are passed with the request from WebSphere Application Server to a CICS system. The distinguished name and realm, which are known in CICS as a distributed identity when they are transmitted across a network, are propagated into the z/OS security context and are associated with the RACF user ID. With the z/OS RACF command, **RACMAP**, you can use mapping filters to correlate the distinguished name and realm to a RACF user ID, preserve the distributed credential information and fulfill governance and auditing

|

I

L

1

1

1

Т

I

1

|

1

I

|

1

1

1


|

I

1

I

 requirements. RACF provides information to CICS about the distinguished name and realm, allowing retrieval in CICS of the identity of the initial user.



"Sample network topologies for using identity propagation" on page 301 expands on this diagram and shows how different network and product combinations provide support for distributed identities.

#### Related concepts:

|

|

T

1

1

T

|

Identity propagation scenario

Follow this scenario to get the best out of CICS support for identity propagation. The scenario provides you with step-by-step instructions to set up identity propagation, using Websphere DataPower[®] and CICS.

# Chapter 21. Preparing for identity propagation

L

   	To participate in identity propagation, ensure that you have the correct infrastructure and that you complete your RACF changes before updating CICS settings.
Suppor	t and requirements for identity propagation
   	CICS provides support for identity propagation between a range of products. Make sure that you meet these requirements to allow participation in identity propagation.
1	Summary of identity propagation participation
	Identity propagation is a form of asserted identity and as a result, participation requires a number of factors:
 	<ul><li>All parties involved must be able to process distributed identities</li><li>A trusted connection must connect all external parties</li></ul>
	If a system does not participate in identity propagation, distributed identity information is ignored, and user ID information is used as before.
	For propagation, the outbound request must be made from a participating task, that is; a task whose user ID has an associated distributed identity.
I	Support for identity propagation
I	CICS provides support for identity propagation in the following situations:
	<ul> <li>Inbound requests to CICS from WebSphere Application Server using the CICS ECI resource adapters over an IPIC connection.</li> </ul>
 	<ul> <li>Using a WS-Security Header element in a Web service request. Routed inbound Web service requests do not support identity propagation.</li> </ul>
   	• Using IPIC and MRO connections between CICS systems. The distributed identity is used by CICS only if it is passed to the MRO or IPIC connection from a participating task.
	• Function shipping of <b>START</b> commands and local <b>START</b> commands do not inherit the distributed identity.
   	Sample network topologies for using identity propagation provides diagrams and examples to explain how user security information is passed using the supported requests and connections.
I	Software requirements for identity propagation
	Each host system participating in identity propagation requires the following minimum software:
I	• z/OS, Version 1 Release 11.
	<ul> <li>CICS TS for z/OS, Version 4.1 with the following enabling APARs. Perform an initial start after applying these APARs:</li> </ul>
	<ul> <li>PK95579 and PM01622, which supply updates to Security domain to provide new functions that call new RACF functions for identity propagation support</li> </ul>

   	<ul> <li>and updates to Security domain callers (Web services, IPIC, and MRO) to call the new functions for identity propagation support.</li> <li>PK83741, to enable identity propagation support if z/OS 1.11 is present.</li> <li>PK98426, to enable CICSPlex SM updates for identity propagation.</li> </ul>
1	All supported levels of WebSphere Application Server support identity propagation.
   	If you are using Websphere DataPower, you require one of the following Websphere DataPower appliances and minimum software: • Websphere DataPower XI50, Version 3.8 • or Websphere DataPower XS40, Version 3.8
 	If you are using CICS Transaction Gateway, you require the following minimum software: • CICS Transaction GatewayVersion 8.0.
I	<b>RACF</b> requirements for identity propagation
   	You must configure your RACF settings for the RACMAP and SETR RACLIST(IDIDMAP) commands before you update clients and CICS configuration definitions for identity propagation.
I	CICS requirements for identity propagation
	<ul> <li>CICS has a number of requirements to allow distributed identities to flow:</li> <li>Security must be enabled, by specifying the SEC=YES system initialization parameter.</li> <li>The external security manager, for example, RACF, must be configured to accept distributed identities.</li> <li>All partner systems must be able to process distributed identities.</li> <li>CICS supports distinguished names up to 246 bytes in length, and realm names up to 252 bytes in length.</li> <li>IPIC connections are limited to supporting identity contexts (ICRX identity tokens), the total size which must not exceed 2000 bytes.</li> </ul>

#### Related tasks:

|

I

I

1

1

1

T

|

I

L

1

I

1

I

I

1

1

L

I

"Configuring RACF for identity propagation" on page 305 Use the RACF **RACMAP** command to create, delete, and list a distributed identity filter. Use the RACF **SETR RACLIST (IDIDMAP)** command to refresh the IDIDMAP resource profile that contains the distributed identity filter. You must configure your RACF settings for identity propagation before you update clients and CICS configuration definitions.

"Configuring IPIC connections for identity propagation" on page 306 You define an IPCONN resource in a receiving CICS region to enable processing of incoming distributed identity information and you define an IPCONN resource in a sending region to specify whether a distributed identity is transmitted outside a sysplex.

"Configuring provider mode Web services for identity propagation" on page 308 Identity propagation with a Web service request relies on trust-based configurations; for example, using a client-certified SSL connection from a Websphere DataPower integration appliance. In this task, you configure a PIPELINE resource to expect an ICRX identity token in the WS-Security header, sent from a trusted client.

### Related reference:

"Sample network topologies for using identity propagation" Identity propagation is supported on network topologies that use either IPIC connections or Web service requests to CICS. Use these sample topologies to help you plan your configuration.

# Sample network topologies for using identity propagation

Identity propagation is supported on network topologies that use either IPIC connections or Web service requests to CICS. Use these sample topologies to help you plan your configuration.

# Sample configuration using an IPIC connection and CICS Transaction Gateway

If you are using IPIC connections into CICS, you might be using CICS Transaction Gateway as an interface between WebSphere Application Server and the CICS ECI resource adapters. If CICS Transaction Gateway and any communicating CICS systems are not on the same sysplex, SSL is also required. The following sample topology shows how the X.500 distinguished name and associated LDAP realm are passed with the request from WebSphere Application Server through CICS Transaction Gateway over an IPIC connection to a CICS system on the same sysplex. The distinguished name and realm, which are known in CICS as a distributed identity when they are transmitted across a network, are then passed between CICS systems using either MRO or IPIC in a sysplex or between CICS systems in different sysplexes using IPIC over SSL. The multiple CICS systems shown in this scenario show how you can connect CICS systems in and outside of a sysplex, however multiple CICS systems are not a required part of the configuration to allow identity propagation. The distributed identity is propagated into the z/OS security context, also known as the Accessor Environment Element (ACEE), and is associated with the RACF user ID using the mapping rules specified in the RACF RACMAP command. RACF provides information to CICS about the distinguished name and realm as well as the RACF user ID, allowing retrieval in CICS of the identity of the initial user.




Figure 29. Example of identity propagation using WebSphere Application Server and CICS Transaction Gateway, communicating with CICS over an IPIC connection.


For more information about CICS Transaction Gateway and identity propagation, see the CICS Transaction Gateway V8.0 information center.

# Sample configuration using a Web service request and Websphere DataPower

If you are sending Web service requests to CICS, you might be using Websphere DataPower as an interface between WebSphere Application Server and CICS. You can use the Websphere DataPower appliance with CICS Web services WS-Security support to process the XML digital signature and perform mappings to a predefined RACF user ID.

The following sample topology shows how the X.500 distinguished name and associated LDAP realm are passed with the request from WebSphere Application Server through Websphere DataPower. The distinguished name and realm are sent in the Extended Identity Context Reference (ICRX) WS-Security Header element of a Web service request to a CICS system. For more information about ICRX identity tokens, see *z/OS Security Server RACF Data Areas*. The distinguished name and realm, which are known in CICS as a distributed identity when they are transmitted across a network, are then passed between CICS systems using either MRO or IPIC in a sysplex or between CICS systems in different sysplexes using IPIC over SSL. The multiple CICS systems shown in this scenario show how you can connect CICS systems in and outside of a sysplex, however multiple CICS systems are not a required part of the configuration to allow identity propagation. The distributed identity is propagated into the *z*/OS security context, also known as the Accessor Environment Element (ACEE), and is associated with the RACF

user ID using the mapping rules specified in the RACF RACMAP command. RACF provides information to CICS about the distinguished name and realm as well as the RACF user ID, allowing retrieval in CICS of the identity of the initial user.



I I

I I

Figure 30. Example of identity propagation using WebSphere Application Server and Websphere DataPower, communicating with CICS using a Web service request.

   	For more information about Websphere DataPower, see the Websphere DataPower scenario: Configuring identity propagation for Web service requests into CICS using WebSphere DataPower.
	Related concepts:
	Identity propagation scenario
I	Follow this scenario to get the best out of CICS support for identity propagation.
I	The scenario provides you with step-by-step instructions to set up identity
	propagation, using Websphere DataPower and CICS.
I	

# Chapter 22. Configuring identity propagation

Configuring RACF for identity propagation

connections or from Web service requests.

specified, but no other configuration changes are required.

|

I

1

1

T

1

You must configure RACF to be able to map distributed identities. You can

configure your CICS system to accept distributed identity information from IPIC

If you are using MRO connections, you can accept distributed identity information between CICS systems only. You must ensure that ATTACHSEC(IDENTIFY) is

Use the RACF **RACMAP** command to create, delete, and list a distributed identity

filter. Use the RACF SETR RACLIST (IDIDMAP) command to refresh the IDIDMAP I resource profile that contains the distributed identity filter. You must configure 1 I your RACF settings for identity propagation before you update clients and CICS configuration definitions. Before you begin T I Ensure that you have the required access to update RACF profiles for your z/OSsystem. I About this task I RACF uses the term *distributed identity filter* to describe a mapping association between a RACF user ID and one or more distributed identities. When you define I the filter using the **RACMAP** command, you associate (or map) a distributed identity with a RACF user ID. If the distributed identity is not mapped in the **RACMAP** command, the default CICS user ID is not used and a security error is issued. Each distributed identity filter is stored in a general resource profile in the IDIDMAP class. The owner of an IDIDMAP profile is the user ID of the RACMAP MAP command I issuer. When the SETR RACLIST (IDIDMAP) command is issued, the IDIDMAP class becomes active. When a distributed user is authenticated and the supported transaction is sent to the z/OS system, RACF receives the distinguished name and realm of the user as character strings of UTF-8 data. RACF has a number of restrictions as a result of UTF-8 data encoding; for example, if the distinguished name exceeds 246 I bytes or the realm exceeds 252 bytes, the RACMAP MAP command fails. See the topic about restrictions for UTF-8 data values in the z/OS Security Server RACF Security Administrator's Guide. I 1 RACF uses the distinguished name and realm to search IDIDMAP profiles for the 1 distributed identity filter that contains the name values best matching the data. When the best matching filter is found, RACF assigns a RACF user ID. T Procedure I I 1. Create a generic profile called IRR.IDIDMAP.* in the FACILITY class in RACF.

. Grant UPDATE access to your user group to enable general access to this
profile. Here is an example, using dev as the name of the user group:
RDEFINE FACILITY IRR.IDIDMAP.** OWNER(cpssing) PERMIT IRR.IDIDMAP.** CLASS(FACILITY) ID(dev) ACCESS(UPDATE) SETROPTS RACLIST(FACILITY) REFRESH
5. You can grant specific users authority to manage the IDIDMAP class by granting CLAUTH access. Here is an example, using usera, userb, and userc as the users that are granted access:
ALTUSER (usera,userb,userc) CLAUTH(IDIDMAP)
. Issue the following command to activate the changes:
SETROPTS CLASSACT(IDIDMAP) RACLIST(IDIDMAP)
5. If you are changing RACMAP definitions on a running system, the cached copy might not map to the same user ID as the new RACMAP definition. To reset the mapping you must wait until the cached copy is deleted. The copy is deleted if the distinguished name and realm pair (the distributed user ID) is not used for the length of time that is specified in the USRDELAY SIT parameter. For performance reasons, CICS caches distinguished names and realms so that the first requests only from a distinguished name and realm require RACF to build an ACEE using the RACMAP definitions.
Results
The distributed user information is mapped in RACF. RACF is configured to map the distributed identity to a RACF user ID.
Vhat to do next
You are now ready to configure your IPIC or Web service connections to CICS. For more information about the RACF <b>RACMAP</b> and <b>SETR RACLIST(IDIDMAP)</b> commands, ee the information about distributed identity filters in the <i>z</i> / <i>OS Security Server</i> <i>RACF Security Administrator's Guide</i> .
Related tasks:
Configuring IPIC connections for identity propagation" 'ou define an IPCONN resource in a receiving CICS region to enable processing of ncoming distributed identity information and you define an IPCONN resource in sending region to specify whether a distributed identity is transmitted outside a ysplex.
Configuring provider mode Web services for identity propagation" on page 308 dentity propagation with a Web service request relies on trust-based onfigurations; for example, using a client-certified SSL connection from a Vebsphere DataPower integration appliance. In this task, you configure a PIPELINE resource to expect an ICRX identity token in the WS-Security header,

You define an IPCONN resource in a receiving CICS region to enable processing of incoming distributed identity information and you define an IPCONN resource in a sending region to specify whether a distributed identity is transmitted outside a sysplex.

|

1

1

Τ

L

I

L

# Before you begin

L

I

I

I

|

|

Т

I

1

I

|

|

1

1

I

I

1

I

1

I

T

Т

L

Т

You must configure your RACF RACMAP settings before you configure your IPIC connections, even if you have IDPROP(OPTIONAL) set in your IPCONN resource definition. Otherwise, you receive the RACF ICH408I message for every unmapped request that is sent to RACF.

# About this task

Identity propagation over an IPIC connection relies on trusted connections between CICS and a security manager; for example, CICS Transaction Gateway over an SSL connection, if CICS Transaction Gateway and CICS are not in the same sysplex. An ICRX identity token identifies the distributed identity of a user, and can be sent to CICS as part of a message.

If CICS receives an ICRX in a message that is sent over an IPIC connection, USERAUTH(IDENTIFY) must be defined for the IPCONN resource in the receiving CICS region to allow processing of the ICRX. If USERAUTH(IDENTIFY) is defined, CICS attempts to map the ICRX to an external security manager (ESM) user ID, for example, a RACF user ID. If the mapping is successful, the ESM user ID is used as the security context for the task that is attached to process the incoming message. If the ICRX cannot be mapped to an ESM user ID, because it is not defined to the external security manager, the message is processed as if it did not contain an ICRX. Local and remote START commands over an IPIC connection do not support identity propagation.


## Procedure

- 1. Specify USERAUTH(IDENTIFY) in the IPCONNresource definition of the receiving CICS system. The IDENTIFY attribute specifies that incoming requests must include a user identifier, which can be provided in the form of an ICRX, but that client authentication is being managed by the security manager that is sending the request. If you are using CICS Transaction Gateway, you must specify USERAUTH(IDENTIFY) to allow CICS Transaction Gateway to pass the distributed identity to CICS. For more information about the IPCONN resource, see the *CICS Resource Definition Guide*. For more information about identity propagation with CICS Transaction Gateway, see the CICS Transaction Gateway information center.
- 2. Specify IDPROP(REQUIRED) in the IPCONN resource definition of the sending CICS system. The REQUIRED attribute specifies that a distributed identity is required for requests using this connection, instead of a user ID. The attribute has no meaning if the connection is contained in a single sysplex or if either or both regions cannot support identity propagation. If the connection is between systems in the same sysplex, the connection operates as if IDPROP(OPTIONAL) is specified and ignores any other setting. The receiving CICS system must have USERAUTH(IDENTIFY) specified in the IPCONN resource to be able to process the distributed identity information. For more information about the IPCONN resource, see the *CICS Resource Definition Guide*.

# Results

The distributed identity of a user can now be received in requests from a trusted security manager, for example, CICS Transaction Gateway, that are sent over an IPIC connection.

	<b>Related tasks</b> : "Configuring RACF for identity propagation" on page 305 Use the RACF <b>RACMAP</b> command to create, delete, and list a distributed identity filter. Use the RACF <b>SETR RACLIST (IDIDMAP)</b> command to refresh the IDIDMAP resource profile that contains the distributed identity filter. You must configure your RACF settings for identity propagation before you update clients and CICS configuration definitions.
	"Configuring provider mode Web services for identity propagation" Identity propagation with a Web service request relies on trust-based configurations; for example, using a client-certified SSL connection from a Websphere DataPower integration appliance. In this task, you configure a PIPELINE resource to expect an ICRX identity token in the WS-Security header, sent from a trusted client.
I	Configuring provider mode Web services for identity propagation
     	Identity propagation with a Web service request relies on trust-based configurations; for example, using a client-certified SSL connection from a Websphere DataPower integration appliance. In this task, you configure a PIPELINE resource to expect an ICRX identity token in the WS-Security header, sent from a trusted client.
Ι	Before you begin
   	You must configure your RACF RACMAP settings before you configure your Web service connections, otherwise you receive the RACF ICH408I message for every unmapped request that is sent to RACF. For more information about configuring the RACF <b>RACMAP</b> command, see Configuring RACF for identity propagation.
	It is a brighter to see Course a functional in the transmitter Without and DetaDenser
	It is advisable to configure a <i>trust</i> relationship between the Websphere DataPower appliance and CICS, for example, using SSL client certification between Websphere DataPower and CICS. The digital certificate that Websphere DataPower uses to identify itself must be associated with a user ID, and that user ID must be granted surrogate authority to assert identities. For more information about surrogate authority, see Chapter 7, "Surrogate user security," on page 113.
	appliance and CICS, for example, using SSL client certification between Websphere DataPower and CICS. The digital certificate that Websphere DataPower uses to identify itself must be associated with a user ID, and that user ID must be granted surrogate authority to assert identifies. For more information about surrogate
	appliance and CICS, for example, using SSL client certification between Websphere DataPower and CICS. The digital certificate that Websphere DataPower uses to identify itself must be associated with a user ID, and that user ID must be granted surrogate authority to assert identifies. For more information about surrogate authority, see Chapter 7, "Surrogate user security," on page 113.



Websphere DataPower acts as an intermediary between CICS and other applications. Remote Web service requester applications connect to the Websphere DataPower appliance using the SOAP protocol. Websphere DataPower authenticates the credentials supplied by the remote client and maps the credentials to a z/OS ICRX identity token, which identifies the distributed identity of a user. The SOAP message is then forwarded to CICS over the trusted SSL connection with an ICRX identity token in a WS-Security header. For more information about ICRX identity tokens, see *z/OS Security Server RACF Data Areas*.

CICS receives the SOAP message from Websphere DataPower. The PIPELINE configuration file specifies *blind* trust, because the only possible client is the Websphere DataPower appliance, and Websphere DataPower is communicating with CICS over a secure SSL connection. Therefore, you do not need to specify additional authentication in the PIPELINE configuration file. The WS-Security handler program locates the first ICRX found in the WS-Security header and uses the ICRX to identify the user.

#### Procedure

1. Create a PIPELINE resource, or edit an existing PIPELINE resource to specify the basic-ICRX mode, which allows the PIPELINE to receive an ICRX. The most typical combination is the blind trust with the basic-ICRX mode. For more information about the PIPELINE resource element, see the topic about <a href="https://www.authentications.com">authentications</a> elements in the *CICS Web Services Guide*.

Here is an example PIPELINE configuration file, showing blind trust with the basic-ICRX mode:

1

1

I

1

```
<terminal_handler>
<cics_soap_1.2_handler>
</terminal_handler>
</service>
<apphandler>DFHPITP</apphandler>
</provider pipeline>
```

Here is an example SOAP message with an ICRX identity, using blind trust:

```
<?xml version="1.0" encoding="UTF-8"?>
<SOAP-ENV:Envelope
xmlns:SOAP-ENV="http://schemas.xmlsoap.org/soap/envelope/">
<SOAP-ENV:Header>
<soAP-ENV:Header>
xmlns:wsse="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-wssecurity-secext-1.0.xsd"
SOAP-ENV:mustUnderstand="1">
```

<wsse:BinarySecurityToken EncodingType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss
-soap-message-security-1.0#Base64Binary"</pre>

wsu:Id="ICRX"

xmlns:wsu="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wsswssecurity-utility-1.0.xsd"
ValueType="http://www.IBM.com/xmlns/prod/zos/saf#ICRXV1">

#### ICRX IS HERE

</wsse:BinarySecurityToken>

</wsse:Security> </SOAP-ENV:Header> <SOAP-ENV:Body>

#### APPLICATION SPECIFIC XML IS HERE

</SOAP-ENV:Body> </SOAP-ENV:Envelope>

2. If you have not already configured Websphere DataPower to be able to send ICRX information, see this scenario: Configuring identity propagation for Web service requests into CICS using WebSphere DataPower.

## Results

Web service requests from Websphere DataPower with an ICRX identity token in the WS-Security header, connected over a client-certified SSL connection, can now flow.

#### **Related tasks:**

Configuring identity propagation for Web service requests into CICS using WebSphere DataPower

In this scenario, you will configure identity propagation for Web service requests sent from WebSphere Application Server to CICS from a WebSphere DataPower XI50, Version 3.8 integration appliance.

"Configuring RACF for identity propagation" on page 305

Use the RACF **RACMAP** command to create, delete, and list a distributed identity filter. Use the RACF **SETR RACLIST (IDIDMAP)** command to refresh the IDIDMAP resource profile that contains the distributed identity filter. You must configure your RACF settings for identity propagation before you update clients and CICS configuration definitions.

"Configuring IPIC connections for identity propagation" on page 306 You define an IPCONN resource in a receiving CICS region to enable processing of incoming distributed identity information and you define an IPCONN resource in a sending region to specify whether a distributed identity is transmitted outside a sysplex.

# Part 7. Customization

This part tells you how to customize the interface between CICS and the External Security Manager.

# Chapter 23. Customizing security processing

This topic describes the interface between CICS and RACF interface, and how you can customize security processing using RACF exit programs.


This topic contains Product-sensitive Programming Interface and Associated Guidance Information.

# **Overview of the CICS-RACF interface**

In CICS Transaction Server for z/OS, Version 4 Release 1, the only form of security CICS supports is that provided by an external security manager (ESM), such as RACF. CICS uses, by means of the RACROUTE macro, the MVS system authorization facility (SAF) interface to route authorization requests to RACF.

Figure 32 shows how the MVS router exit and RACF user exits are invoked when CICS issues a RACROUTE macro.

See the *z/OS Security Server RACROUTE Macro Reference* for information on how



#### Figure 32. MVS router exit.

- 1. CICS issues the RACROUTE macro, which invokes the MVS router.
- 2. The MVS router calls the MVS router exit (ICHRTX00)
- **3**. If the MVS router exit's return code is zero, the MVS router calls the RACF router; the RACF router calls the external security manager (RACF in this example). The security manager may call its own user exits.
- 4. The MVS router returns control to CICS.

the RACROUTE macro is coded.

The control points at which CICS issues a RACROUTE macro to route authorization requests are described in "CICS security control points" on page 315.

#### The MVS router

The system authorization facility (SAF) provides your installation with centralized control over security processing by using a system service called the *MVS router*. The MVS router provides a common system interface for all products providing and requesting resource control. The resource-managing components and

subsystems (such as CICS) call the MVS router as part of certain decision-making functions in their processing, such as access control checking and authorization-related checking. These functions are called **control points**. This single SAF interface encourages the use of common control functions shared across products and across systems.

If RACF is available in the system, the MVS router may pass control to the RACF router, which in turn invokes the appropriate RACF function. (The parameter information and the RACF router table, which associates router invocations with RACF functions, determine the appropriate function.) However, before calling the RACF router, the MVS router calls an optional installation-supplied security-processing exit, if one has been installed.

The system authorization facility and the SAF router are present on all MVS systems, even if RACF is not installed. Although the SAF router is not part of RACF, many system components and programs, such as CICS, invoke RACF through the RACROUTE macro and SAF. Therefore, installations can modify RACF parameter lists and do customized security processing within the SAF router. For information about how to code a SAF router exit, see the *z*/*OS Security Server RACF Messages and Codes*.

### How ESM exit programs access CICS-related information

When CICS invokes the ESM, it passes information about the current CICS environment, for use by an ESM exit program, in an **installation data parameter list**. How your exit programs access the installation data parameter list depends on the ESM you are using. The ICHxxxxx interfaces defined in Table 40 apply only to RACF. For programming information on non-RACF interfaces, see the *CICS Customization Guide*.

# The RACF user exit parameter list

If you write RACF user exits, you can find the address of the installation data parameter list directly from the RACF user exit parameter list.

The name of the relevant field in the user exit parameter list varies according to the RACROUTE REQUEST type and the RACF user exit that is invoked. The relationships between REQUEST type, exit name, and field name are shown in Table 40.

RACROUTE REQUEST type	RACF exit	Exit list mapping macro	Parameter list field name (see Notes 1 and 2.)
VERIFY	ICHRIX01	ICHRIXP	RIXINSTL
	ICHRIX02	ICHRIXP	RIXINSTL
AUTH	ICHRCX01	ICHRCXP	RCXINSTL
	ICHRCX02	ICHRCXP	RCXINSTL
FASTAUTH	ICHRFX01	ICHRFXP	RFXANSTL
	ICHRFX02	ICHRFXP	RFXANSTL
LIST	ICHRLX01	ICHRLX1P	RLX1INST
	ICHRLX02	ICHRLX2P	RLX2PRPA

Table 40. Obtaining the address of the installation data parameter list

#### Note:

- 1. The 'xxxINSTL' field points to the installation parameter list only if you code ESMEXITS=INSTLN in the CICS system initialization parameters. The default value for this parameter is NOINSTLN, which means that no installation data is passed. (Note that ESMEXITS cannot be coded as a SIT override.)
- RLX2PRPA contains the address of the ICHRLX01 user exit parameter list (RLX1P). Field RLX1INST of RLX1P points to the installation data parameter list.
- **3**. There is no RACF user exit for REQUEST=EXTRACT, and no installation parameter data is passed. Any customization must be done using the MVS router exit, ICHRTX00.

For brief descriptions of RACF exits and their functions, see the *z*/OS Security Server RACF Security Administrator's Guide. For full descriptions of the RACF exit parameter lists, see the *z*/OS Security Server RACF System Programmer's Guide.

### The installation data parameter list

The installation data parameter list gives your ESM exit programs access to the following information:

- CICS security event being processed
- Details of the current CICS environment, as available
  - APPLID of the CICS region
  - Common work area
  - Transaction being invoked
  - Program being executed
  - CICS terminal identifier
  - VTAM LUname
  - Terminal user area
  - An 8-byte communication area, whose usage is described in the CICS *Customization Guide*.

For programming information about user-written ESMs, see the *CICS Customization Guide*.

# **CICS** security control points

RACROUTE macros are used to start the ESM. Theses macros are issued at a number of control points.

Some calls might not always be issued, because CICS reuses entries for users already signed on.

#### RACROUTE

This macro is the "front end" to the macros described below; the macro calls the MVS router.

#### **RACROUTE REQUEST=VERIFY**

This macro is issued at operator sign-on, with the parameter ENVIR=CREATE, and at sign-off, with the parameter ENVIR=DELETE. This macro creates or destroys an ACEE (access control environment element). This macro is issued, with the parameter ENVIR=VERIFY, early in normal sign-on through the **EXEC CICS SIGNON** command, but the command is ignored by RACF.

This macro is issued at the following CICS control points. Each of the following control points relates to ENVIR=CREATE:

• Normal sign-on through EXEC CICS SIGNON.

- Sign-on of the default user ID DFLTUSER.
- Sign-on of preset-security terminal.
- Sign-on of MRO session.
- Sign-on of LU6.1 session.
- Sign-on of LU6.2 session.
- Sign-on for XRF tracking of any of the above.
- Sign-on associated with the user ID on an attach request, for all operands of ATTACHSEC except LOCAL.

Each of the following control points relates to ENVIR=DELETE:

- Normal sign-off through EXEC CICS SIGNOFF.
- Sign-off when deleting a terminal.
- Sign-off when TIMEOUT expires.
- Sign-off when USRDELAY expires.
- Sign-off of MRO session.
- Sign-off of LU6.1 session.
- Sign-off of LU6.2 session.
- Sign-off for XRF tracking of any of the above.
- Sign-off associated with the user ID on an attach request, for all operands of ATTACHSEC except LOCAL.
- If you are using a z/OS 1.11 system or above, sign-off because RACF notifies CICS of changes to a user profile, and an attached request associated with that signed-on user ID completes, for all operands of ATTACHSEC except LOCAL.
- If you are using a z/OS 1.11 system or above, sign-off because RACF notifies CICS of changes to a user profile, and a new attach request is made and the value in the **USRDELAY** system initialization parameter has not expired. This sign-off is followed by a sign-on.

#### **RACROUTE REQUEST=VERIFYX**

Т

Т

Т

1

T

1

T

This macro creates and deletes an ACEE in a single call. This macro is issued at the following control points:

- Sign-on, as an alternative to VERIFY, when an optimized sign-on is performed for subsequent attach sign-ons across an LU6.2 link with ATTACHSEC(VERIFY) or ATTACHSEC(PERSISTENT).
- When an invalid password or PassTicket is presented.
- When a login process involving password verification, such as the EXEC CICS VERIFY PASSWORD command, is used to log in a user, and the original attempt to verify the password using the RACROUTE VERIFY=EXTRACT macro has failed.

#### RACROUTE REQUEST=FASTAUTH

This macro is issued during resource checking, on behalf of a user who is identified by an ACEE. This macro is the high-performance form of REQUEST=AUTH, using in-storage resource profiles, which does not cause auditing to be performed. This macro is issued at the following CICS control points:

- When attaching a local transaction
- When checking link security for transaction attach
- Transaction validation for an MRO task
- CICS resource checking
- Link security check for a CICS resource
- Transaction validation for EDF
- Transaction validation for the transaction being tested (by EDF)
- DBCTL PSB scheduling resource security check
- DBCTL PSB scheduling link security check
- Remote DL/I PSB scheduling resource check

- When checking a surrogate user authority
- QUERY SECURITY with the RESTYPE option
- When an enterprise bean calls the isCallerInRole() method
- When checking the authority of a user to call an enterprise bean method

#### RACROUTE REQUEST=AUTH

This macro provides a form of resource checking with a larger pathlength and causes auditing to be performed. This macro is used as follows:

- After a call to FASTAUTH indicates an access failure that requires logging.
- When a QUERY SECURITY request with the RESCLASS option is used. This option indicates a request for a resource for which CICS has not built in-storage profiles.

#### RACROUTE REQUEST=LIST

This macro is issued to create and delete the in-storage profile lists needed by REQUEST=FASTAUTH. One REQUEST=LIST macro is required for each resource class. This macro is issued at the following CICS control points:

- When CICS security is being initialized
- When an EXEC CICS PERFORM SECURITY REBUILD command is issued
- · When XRF tracks either of these events

#### RACROUTE REQUEST=EXTRACT

L

I

L

This macro is issued when a login process involving password verification, such as the EXEC CICS VERIFY PASSWORD command, is used to log in a user. If the password cannot be verified using this macro, CICS subsequently issues the RACROUTE REQUEST=VERIFYX macro.

The RACROUTE REQUEST=EXTRACT macro is also issued, with the SEGMENT=CICS,CLASS=USER parameters, and with the SEGMENT=BASE,CLASS=USER parameters to obtain the national language and user name, at all of the following control points:

- Normal sign-on through EXEC CICS SIGNON
- Sign-on of the default user ID DFLTUSER
- Sign-on of preset security terminal
- Sign-on of MRO session
- Sign-on of LU6.1 session
- Sign-on of LU6.2 session
- Sign-on for XRF tracking of any of the above
- Sign-on associated with the user ID on an attach request, for all operands of ATTACHSEC except LOCAL

This macro can be used to verify the password of the user when an entry in the user table is reused within the USRDELAY period.

This macro is also issued, with the SEGMENT=SESSION,CLASS=APPCLU parameters, during verification of LU6.2 bind security, at the CICS control point for bind of an LU6.2 sessions.

The REQUEST=EXTRACT parameter has no associated RACF user exit, and no installation parameter data is passed. You use the MVS router exit, ICHRTX00, for customization.

For a detailed description of these macros, see the *z*/OS Security Server RACROUTE Macro Reference.

# Determining the userid of the CICS region

CICS makes use of the userid of the region in which it runs for the following purposes:

- To prefix resource names if SECPRFX=YES is specified. For more information about the SECPRFX system initialization parameter, see "Security-related system initialization parameters" on page 55.
- As the user to be checked for category 1 transactions. For more information, see "Category 1 transactions" on page 144.
- As the default PLTPI user for PLTPI non-terminal security, if a PLTPIUSR is not specified in the system initialization parameter.
- For SURROGAT checking (for example, authority to use the PLTPI and default userids).
- For MRO bind security. For more information, see Chapter 16, "Implementing MRO security," on page 219.

CICS obtains the region userid by invoking the external security manager, which extracts it from the RACF control blocks relevant for the job. The security domain and MRO-bind security each obtain the region userid by issuing a RACROUTE REQUEST=EXTRACT macro. To customize the response from this macro, and thus the security identification of a CICS region, use the MVS security router exit, ICHRTX00.

# Specifying user-defined resources to RACF

If you want to use the QUERY SECURITY command with the RESCLASS option, you may need to create user-defined resources within user-defined classes to represent the non-CICS resources that you want to query. To do this, add entries to the RACF class descriptor table (CDT) and to the RACF router table. Then, you must activate the new classes, define your resources in the new classes, and finally grant your users access to the resources. To improve the performance of QUERY SECURITY, also consider loading the new resource profiles into virtual storage.

### Adding new resource classes to the class descriptor table

The RACF class descriptor table has a system-defined part, and an installation-defined part named ICHRRCDE.

You add new resource classes to ICHRRCDE by coding the ICHERCDE macro.

Specify the length of the resource name in the MAXLNTH. Specify a length sufficient to contain:

- An eight-character prefix
- A period (.)
- The name of the resource type.

Thus for RDO resources, with resource type names of up to 12 characters, specify MAXLNTH=23.

**Remember:** For RDO resources, the name of the resource type can be up to 12 characters long, even though the name of the resource itself is shorter. For example, "PARTITIONSET" contains 12 characters, but the names of PARTITIONSET resources are restricted to eight characters in length. Thus for RDO resources, with resource type names of up to 12 characters, specify MAXLNTH=23.

For example, to add to the CDT a new class \$FILEREC, and a corresponding (optional) group class \$GILEREC, add the following macros to ICHRRCDE:

· 1 /		8	
\$FILEREC	ICHERCDE CLASS=\$FILEREC, GROUP=\$GILEREC, ID=192, MAXLNTH=17, RACLIST=ALLOWED, FIRST=ALPHANUM, OTHER=ANY, POSIT=42, OPER=N0,	Entity or Member class	* * * * * * * *
	DFTUACC=NONE		
\$GILEREC	ICHERCDE CLASS=\$GILEREC,	Group class	*
	MEMBER=\$FILEREC,		*
	ID=191,		*
	MAXLNTH=17,		*
	FIRST=ALPHANUM,		*
	OTHER=ANY,		*
	POSIT=42,		*
	OPER=NO, DFTUACC=NONE		*

Add the same classes to the RACF router table, ICHRFR01, by coding the ICHRFRTB macro:

ICHRFRTB CLASS=\$FILEREC,ACTION=RACF ICHRFRTB CLASS=\$GILEREC,ACTION=RACF

Both the ICHERCDE and ICHRFRTB macros are described in the *z*/OS Security Server RACF Macros and Interfaces manual.

When you have recreated the two modules ICHRRCDE and ICHRFR01, re-IPL your MVS system to bring them into use.

#### Activating the user-defined resource classes

Once you have installed the new classes in your system, it is necessary to activate them in RACF before they can be used.

This has to be done by a user with system-SPECIAL authority, who enters the following commands under TSO: SETROPTS CLASSACT(\$FILEREC) SETROPTS GENERIC(\$FILEREC)

To improve the performance of QUERY SECURITY, you should load the new resource profiles into virtual storage by using the RACLIST option. The RACLIST option is **required** if you are using the group class, because the connection between the group class and the entity class is resolved by RACLIST: SETROPTS RACLIST(\$FILEREC)

You need to issue the SETROPTS commands for the entity class \$FILEREC, because the group class \$GILEREC has the same POSIT number.

#### Defining resources within the new class

Resources within the new classes have to be defined by a user with system-SPECIAL authority, or with CLAUTH authority in the new class.

CLAUTH authority is granted by issuing the following TSO command: ALTUSER userid CLAUTH(\$FILEREC)

If you have the required authority, you can create the new resources by issuing the following TSO commands:

RDEFINE \$FILEREC PAYFILE.SALARY UACC(NONE) RDEFINE \$FILEREC PAYFILE.TAXBAND UACC(NONE) RDEFINE \$GILEREC PERSONAL.DETAILS ADDMEM( PERSONAL.DEPT, + PERSONAL.MANAGER, + PERSONAL.PHONE) + UACC(READ)

Now you are ready to authorize users to use the new resources. Assume that PAYROLL is the name of a group of users who are to be permitted to update all the pay and personal details fields in an employee record. The following TSO commands grant UPDATE access to all users in the group:

PERMIT PAYFILE.SALARY CLASS(\$FILEREC) ID(PAYROLL) ACCESS(UPDATE) PERMIT PAYFILE.TAXBAND CLASS(\$FILEREC) ID(PAYROLL) ACCESS(UPDATE) PERMIT PERSONAL.DETAILS CLASS(\$FILEREC) ID(PAYROLL) ACCESS(UPDATE)

If you had previously loaded the profiles by using the RACLIST option, refresh the profiles in virtual storage by issuing the command: SETROPTS RACLIST(\$FILEREC) REFRESH

#### Designing applications to use the user-defined resources

This topic gives an example of how you might design applications to make use of the user-defined resources.

Your applications use CICS file control in the normal way to read records from the pay and personal details file. Because you are controlling individual fields within each record, you may not need to apply resource security at the file level, so your transactions can be defined with RESSEC(NO). After reading the file record, but before displaying the results, you use QUERY SECURITY to determine whether the user has the authority to access the particular field within the record. For instance, before displaying the salary amount, you issue:

```
EXEC CICS QUERY SECURITY RESCLASS('$FILEREC')
RESID('PAYFILE.SALARY')
RESIDLENGTH(14)
READ(read_cvda)
```

Then, depending on the value returned in read_cvda, your application either displays the salary or a message stating that the user is not authorized to display it. Likewise, as part of a transaction that updates a person's telephone number, you issue:

```
EXEC CICS QUERY SECURITY RESCLASS('$FILEREC')
RESID('PERSONAL.PHONE')
RESIDLENGTH(14)
UPDATE(update_cvda)
```

If the value returned in update_cvda indicates that the user has UPDATE access, the transaction can continue and update the telephone number in the file. Otherwise, it should indicate that the user is not authorized to update the telephone number.

# Suppressing attach checks for non-terminal transactions

CICS always performs a transaction-attach security check for each transaction attach, even when the transaction has no associated terminal. The following suggests how you can bypass transaction-attach security checks for non-terminal transactions while continuing to keep full transaction-attach security for terminal-attached transactions.

CICS always performs the transaction-attach resource check using RACROUTE REQUEST=FASTAUTH, so you need only to provide an ICHRFX01 user exit. The ICHRFX01 routine must issue a zero return code to indicate that the resource check processing is to continue, or a return code of 8 to indicate that the check is to be regarded as successful.

So that the ICHRFX01 exit can determine the circumstances under which it is called, specify the ESMEXITS=INSTLN system initialization parameter for the CICS regions for which you want to control transaction-attach security. Then your ICHRFX01 routine should do the following:

- 1. Obtain the address of the CICS installation data parameter list, as described in "How ESM exit programs access CICS-related information" on page 314. If this address is zero, either the caller of the RACROUTE macro is not CICS, or it is a CICS region whose behavior you do not want to modify; so exit with a return code of zero.
- 2. Use the DFHXSUXP macro to map the fields in the installation data parameter list.
- **3**. Confirm that the installation data was created by CICS, by checking that UXPDFHXS is equal to 'DFHXS'. If it is not, exit with a return code of zero.
- 4. Examine field UXPPHASE in the installation data. If it is not equal to USER_ATTACH_CHECK (X'40'), this is not a transaction attach, so exit with a return code of zero.
- 5. Examine field UXPTERM in the installation data. If it is nonzero, this is a terminal-related transaction attach, so exit with a return code of zero.
- 6. If UXPPHASE is USER_ATTACH_CHECK and UXPTERM is zero, then a non-terminal transaction is being attached. Exit with a return code of 8 to indicate to RACF that this check is successful. The function RACROUTE REQUEST=FASTAUTH then completes with a return code of zero, and CICS continues with the attach of the non-terminal transaction.

# Global user exits in signon and signoff

CICS provides the XSNON global user exit in EXEC CICS SIGNON processing and the XSNOFF global user exit in EXEC CICS SIGNOFF processing.

These exits do not allow you to affect the result of the sign-on or sign-off, but notify you when the userid associated with a terminal changes. The exits are further described in the *CICS Customization Guide*.

# Part 8. Problem determination

This part explains how to determine the cause of security-related problems in CICS.

# Chapter 24. Problem determination in a CICS-RACF security environment

This topic provides information to help you find the causes of access authority problems.

# Resolving problems when access is denied incorrectly

When a user requires access to a protected resource (such as a CICS transaction) and RACF denies the requested access, you will often have to analyze the problem before deciding what action to take.

The basic points to ensure are that:

- CICS is using RACF for this particular kind of resource.
- You know which profile RACF is using to check the user's authority.
- You know which userid CICS is using for the authorization check.

For each security violation, up to three messages are issued:

- CICS issues an authority message to the terminal user (or returns a "not authorized" return code to an application).
- CICS sends a message DFHXS1111 to the CSCS transient data destination.
- RACF sends an ICH408I message to the CICS region's job log and to the security console.

For a brief description of message ICH4081, see "RACF message ICH4081" on page 329. For complete descriptions of this and all other RACF messages, see *z*/*OS Security Server RACF Messages and Codes*.

If message ICH408I is issued for an authorization failure, RACF is active. The message text itself indicates the userid for which the authorization check was done and the name of the RACF profile that was used for the check.

When issued because of a CICS-originated authorization check, the RACF sends the ICH408I message to the CICS region's job log. Most CICS authorization messages also go to the CSCS transient data queue, except DFHIR and DFHZC messages, which go to the CSMT transient data queue.

**Note:** You can use the CICS-supplied message domain global user exit, XMEOUT, to reroute CICS-issued authorization messages. (For example, you can send them to the same console as the ICH408I messages.) For programming information about using XMEOUT, see the *CICS Customization Guide*.

If no profile exists for a particular resource, RACF returns a "profile not found" indication to CICS. CICS issues message DFHXS1111 with a SAF return code of X'00000004' and an ESM code of X'00000000'. **No ICH408I message is issued in this case.** The RLIST command issues a message stating that no profile was found.

#### Note:

- The RLIST command shows the profile as it exists in the RACF database, which might not necessarily be the same as the in-storage copy that CICS uses.
- When you have determined which RACF profile is denying access, see the *z/OS Security Server RACF Security Administrator's Guide*for a description of

authorization checking for RACF-protected resources. The following describe some further steps to take in resolving "access denied" problems.

# Is CICS using RACF for this particular kind of resource?

Make sure that CICS is using an ESM. If it is not using an ESM, it issues message DFHXS1102.

- Is CICS using an external security manager (ESM)?
- Is security checking done for the particular general resource class? Message DFHXS1105 tells you if the class named on an *Xname* parameter has been initialized.

**Note:** If message DFHXS1105 is not there, ensure that the SEC=YES system initialization parameter is specified for the region.

Check the appropriate CICS initialization parameter for the resource. For example: for transactions, this is the XTRAN parameter.

# Which profile is RACF using?

- Check the RACF message ICH408I for the name of the profile that RACF used.
- If CICS prefixing is in effect for the CICS region involved, the prefix specified is used as the first qualifier of RACF resource profiles (or member names).
  - Make sure that you have specified the correct prefix as part of resource profile names (on the RDEFINE command) and as member names on the ADDMEM operand.
  - Make sure the CICS job is running under the correct prefix if SECPRFX=*prefix* or SECPRFX=YES is specified. The name of the resource in message ICH408I includes the prefix if one of these parameter values is specified in the system initialization parameters.
  - Make sure that an installation-written SAF exit is not changing the effective userid under which the CICS region is running.
- Is CICS using current copies of the RACF resource profiles?

If you have created, changed, or deleted a resource profile, the in-storage profile does not reflect the change until one of the following is completed:

- SETROPTS GENERIC(*class-name*) REFRESH (a generic profile has been changed).
- SETROPTS RACLIST(classname) REFRESH

For more information about refreshing resource profiles, see "Refreshing resource profiles in main storage" on page 22.

• You can use the TSO RLIST command to determine which profile (or profiles) protect the resource. See "Which profile is used to protect the resource?" on page 327.

# Which userid did CICS supply for the authorization check?

Check to see if the user reporting the problem has signed on to CICS.

If the user has not signed on to CICS, one of the following could be occurring:

- If you are using preset-terminal security, the authorization could be related to that terminal's userid.
- The user could be trying to operate as the CICS default user (without signing on to CICS).

- If the transaction was initiated by a START command, the userid could be inherited from the transaction issuing the START, or specified on the START command itself.
- If the transaction was initiated as the trigger transaction associated with a transient data queue, the userid could have been specified in the transient data destination definition for the queue.
- If the program is running as a PLTPI program, the userid could be specified in the PLTPIUSR system initialization parameter.

**Note:** RACF message ICH408I identifies the userid, as supplied by CICS to RACF, for which the authorization failed.

For help in identifying the user, see "CICS users" on page 4.

#### Which profile is used to protect the resource?

If you are using generic profiles (and you are **not** using resource group profiles), only the most specific profile is used.

For example, if the following profiles exist:

** C* CE* CEDA

CEDA is the profile that is used to control access to the CEDA transaction. If you delete profile CEDA and refresh the in-storage copies, CE* is used.

**Note:** This assumes CICS prefixing is not used and generic profile checking **is** used. (That is, that the RACF command SETROPTS GENERIC(*class_name*) has been issued for the class.)

If resource group profiles have been defined in the relevant class (for example, profiles in the GCICSTRN class), it is possible that more than one profile is used in determining a user's access. To determine which profiles protect the resource, enter the RLIST command with the RESGROUP operand. Be sure to specify the **member class** on the RLIST command. For example:

RLIST TCICSTRN transaction-name RESGROUP

If prefixing is in effect for this CICS region, include the prefix on the resource name specified on the RLIST command:

RLIST TCICSTRN prefix.transaction-name RESGROUP

Note that these examples use the member class TCICSTRN, not the resource group class GCICSTRN.

The AUDITOR attribute enables users to list all profiles that are defined, but does not authorize them to change those profiles. We recommend you give AUDITOR access to system programmers who need to see all profiles (for example, those who are doing problem determination) instead of system-SPECIAL access.

As a result of issuing RLIST with RESGROUP, you might see:

• A brief listing of the resource group profile that protects the resource. See Figure 33 on page 328.

- A slightly longer listing showing the member profile as well as the resource group profile. See Figure 34.
- A "profile not found" message, if no profile is found that protects the resource. See Figure 35 on page 329.
- A "not authorized" message, if If a profile exists, but you are not authorized to list the profile. See Figure 36 on page 329.

```
rlist tcicstrn cemt resgroup
CLASS NAME
TCICSTRN CEMT
GROUP CLASS NAME
GCICSTRN
RESOURCE GROUPS
CAT2
```

Figure 33. Output of RLIST command with RESGROUP: resource group profile

rlist tcicstrn cem CLASS NAME	t resgroup			
TCICSTRN CEMT GROUP CLASS NAME				
GCICSTRN RESOURCE GROUPS				
CICSCAT2A LEVEL OWNER	UNIVERSAL ACCESS	YOUR ACCESS	WARNING	
00 PUB01 INSTALLATION DATA	NONE	ALTER		
NONE APPLICATION DATA				
NONE AUDITING				
FAILURES(READ) NOTIFY				
NO USER TO BE NOT	IFIED			

Figure 34. Output of RLIST command with RESGROUP: several profiles

**Note:** When you are using resource group profiles, more than one profile might be used at the same time. If the resource is protected by more than one profile, you are strongly urged to delete all other occurrences of the resource name. Use the DELMEM operand on the RALTER command to remove the resource name from existing resource group profiles. Use the RDELETE command with care to delete profiles from the member class.

```
rlist tcicstrn dfhcicsm.cemt resgroup
ICH13003I DFHCICSM.CEMT NOT FOUND
```

Figure 35. Output of RLIST command with RESGROUP: profile not found

**Note:** If you get the "profile not found" message, make sure that generic profile processing is in effect for the specified class. (SETROPTS LIST will show this.) If, indeed, no profile exists, create a suitable profile and ensure that the appropriate users and groups have access.

```
rlist tcicstrn dfhcicsm.cemt resgroup
ICH13002I NOT AUTHORIZED TO LIST DFH*
```

Figure 36. Output of RLIST command with RESGROUP: authorization message

The "not authorized" message identifies the name of the profile preventing you from having access. You can ask the RACF security administrator (who has the system-SPECIAL attribute and can therefore list the profile) to investigate the problem.

Some possible solutions are:

- The profile is not needed and can be deleted.
- You can be made OWNER of the profile.
- A more specific generic profile can be created, and you or your group can be made OWNER of the new profile.
- If the profile is a discrete profile, you can be given ALTER access to the profile.
- You can be assigned the AUDITOR attribute.

For a description of the authority needed to list a general resource profile, see the description of the RLIST command in the *z/OS Security Server RACF Command Language Reference*.

#### RACF message ICH408I

For a complete description of RACF message ICH408I, see the *z*/OS Security Server RACF Messages and Codes manual.

The first line of message ICH408I identifies a user who had an authorization problem. The other lines of the message describe the request the user was issuing and the reason for the failure.

Consider the following example:

```
ICH408I USER(JONES ) GROUP(DEPT60 ) NAME(M.M.JONES )
ICH408I FLA32 CL(FCICSFCT)
ICH408I INSUFFICIENT ACCESS AUTHORITY
ICH408I FROM F%A* (G)
ICH408I ACCESS INTENT(UPDATE ) ACCESS ALLOWED(READ )
```

This message can be interpreted as follows:

User JONES, a member of group DEPT60, whose name is M.M.JONES, had INSUFFICIENT ACCESS AUTHORITY to resource FLA32, which is in class FCICSFCT.

**Note:** If the class shown is a resource group class, the profile might be in the class shown or in the related member class. For example, if GCICSTRN appears, check TCICSTRN also. If HCICSFCT appears, check FCICSFCT also. For a list of all the IBM-supplied class names, see Table 2 on page 23. For a list of the installation-defined class names that are in use on your installation, see your RACF system programmer, or issue the SETROPTS LIST command.

The RACF profile protecting the resource is  $F\%A^*$ . "(G)" indicates that  $F\%A^*$  is a generic profile.

The access attempted by user JONES was UPDATE, but the access allowed by RACF was READ. Therefore, user JONES was denied access.

A DFHXS1111 message would also be issued for this access attempt:

DFHXS1111 26/09/95 15:34:01 CICSSYS1 Security violation by user JONES at netname D2D1 for resource FLA32 in class TCICSTRN. SAF codes are (X'00000008',X'00000000'). ESM codes are (X'00000008',X'00000000').

The SAF and ESM codes come from RACROUTE REQUEST=AUTH.

To find the cause of the violation, issue the RLIST command with AUTHUSER specified to list the profile indicated in the ICH408I message. The AUTHUSER operand displays the access list, as shown in Figure 37.

```
rlist fcicsfct f%a* authuser
CLASS NAME
____
        ____
FCICSFCT F%A* (G)
GROUP CLASS NAME
----- -----
HCICSFCT
            UNIVERSAL ACCESS YOUR ACCESS WARNING
LEVEL OWNER
-----
             -----
00 CICSADM
              NONE
                            ALTER
                                     NO
                     •
                     •
                     .
USER
      ACCESS
____
       _____
       UPDATE
DEPTA
JONES
       READ
GROUPX
       NONF
SYSPROG
       ALTER
```

Figure 37. Requesting a display of the access list

In this profile, user JONES has an explicit entry in the access list. If the userid itself does not appear in the access list, check for one of JONES's connect groups. To list the groups to which JONES is connected, issue LISTUSER JONES Other specifications in the profile (such as security level or security category) might cause access to be denied. For a complete description, see the *z*/*OS Security Server RACF Security Administrator's Guide*.

**Note:** If NOTIFY(CICSADM) were specified in this profile, TSO userid CICSADM would receive immediate notification of failed attempts to access resources protected by the profile.

### Resolving problems when access is allowed incorrectly

There could be many reasons why a user might have access to a protected resource, even when you think that the user should **not** have that access.

Here are some checks that you can make to investigate this kind of situation:

- Confirm which userid the user is signed on as. (Make sure the user has signed on and is not acting as the CICS default user.) You can ask the user to sign off, then sign on again. You can also ask the user to issue EXEC CICS ASSIGN or EXEC CICS INQUIRE TERMINAL, which can be issued with the CECI transaction (or a user-written transaction).
- Make sure that the SEC system initialization parameter is SEC=YES for the CICS region the user is signed on to.

If SEC=NO is specified, users can access any resource.

- If the user is running a transaction that communicates with other regions such as application-owning regions (AORs) or file-owning regions (FORs), make sure that the SEC system initialization parameter is SEC=YES for those regions.
- Is prefixing correct?
  - Has the CICS JOB been submitted by the correct USER?
  - Is SECPRFX set correctly?
  - Has an installation-written SAF exit been used to return a different CICS region userid when RACROUTE=EXTRACT has been specified?
- Depending on the resource, make sure that RESSEC(YES) is specified for each transaction that might access that resource.
- Is the appropriate Xname CICS system initialization parameter correctly set?

For example, if it is a file control request, is XFCT=YES or XFCT=*value* specified? If the *Xname* parameter specifies a value other than YES or NO, does the value show the correct installation-defined class name?

- Is the transaction exempt from transaction security? (For information on transactions that may have been defined in this way, see "Category 3 transactions" on page 154.)
- Does the transaction have the correct RESSEC and CMDSEC options?
- Check that the RESSEC setting on the MIRROR transaction is correct.
- If the resource is temporary storage, are you using the correct TST? Check:
  - The DFHTST TYPE=SECURITY entry in the TST
  - That TST entries are in the correct order

If you are using TSMODEL resource definition, check the SECURITY option of the model.

- If intersystem communication is involved, check the following:
  - Is a SECURITY REBUILD required (on this or on the remote system)?
  - If ATTACHSEC=LOCAL is specified, does the SECURITYNAME userid have access to the resource?
  - Is ATTACHSEC=IDENTIFY specified?
  - Is link security being bypassed because the link userid matches the local region userid?
  - Is the remote system using the same RACF database?
- Do you have any RACF installation exits?
- To check the profile that you think protects the resource, use the checklist provided in the *z/OS Security Server RACF Security Administrator's Guide*.

# CICS initialization failures related to security

If SEC=YES is specified, external security is *required*. If external security cannot be provided, CICS cannot be initialized.

Figure 38 on page 333 shows an example of a failure to initialize.

If security initialization fails:

• Examine the DFHXS1106 message return codes. In the example shown in Figure 38 on page 333, SAF return code X'00000004' and reason code X'00000000' were issued:

A return code of X'00000004' indicates that an error occurred in the MVS security router (RACROUTE). See the RACROUTE macro reference in "CICS security control points" on page 315.

- Check the CICS startup options, in particular the *Xname* system initialization parameters. Make sure that:
  - The class is defined to RACF and is active (use the SETROPTS LIST command to check this).
  - The class is defined in the router table. To do this, examine the installation source for ICHRFR01 for any installation-defined classes. (The description of the ICHFRTB macro in *z/OS Security Server RACF Macros and Interfaces* includes a listing of the IBM-supplied module, ICHRFR0X.)

Figure 38 on page 333 shows that XPPT=UNKNOWN has been specified. This causes CICS to try to use a class called MUNKNOWN. MUNKNOWN has not been defined to the MVS router, or to the RACF CDT.

# **RACF** abends

If a RACF abend occurs, see *z*/OS Security Server RACF Messages and Codes and *z*/OS Security Server RACF Diagnosis Guide for further guidance.

### SAF or RACF installation exits

Check if any SAF or RACF installation exits are causing initialization (RACLIST requests to fail.

### CICS default user fails to sign on

The following example shows a CICS job log when the DFLTUSER fails to sign on. CICS is started with SEC=YES and DFLTUSER=ORMAN. User profile ORMAN has not been defined to RACF.

This CICS region cannot be initialized because, with SEC=YES specified, external security is required and the default user must be defined to RACF.

```
DFHPA1927 IYCTZCCA AKPREQ=0
DFHPA1927 IYCTZCCA APPLID=IYCTZCCA
DFHPA1927 IYCTZCCA CSDFRLOG=NO
DFHPA1927 IYCTZCCA CSDRECOV=NONE
DFHPA1927 IYCTZCCA FCT=NO
DFHPA1927 IYCTZCCA SIT=6$
DFHPA1927 IYCTZCCA START=INITIAL
DFHPA1927 IYCTZCCA GMTEXT='SSYS NOOR CIC5100M SYSTEM with RACF'
DFHPA1927 IYCTZCCA GRPLIST=USERLIST
DFHPA1927 IYCTZCCA PLTPI=NO
DFHPA1927 IYCTZCCA SEC=YES
DFHPA1927 IYCTZCCA XCMD=NO
DFHPA1927 IYCTZCCA XFCT=1CVFFCT
DFHPA1927 IYCTZCCA XJCT=1CVFJCT
DFHPA1927 IYCTZCCA XPCT=1CVFPCT
DFHPA1927 IYCTZCCA XPPT=UNKNOWN
DFHPA1927 IYCTZCCA XPSB=N0
DFHPA1927
          IYCTZCCA XTST=1CVFTST
DFHPA1927 IYCTZCCA XTRAN=1CVFTRN
DFHPA1927 IYCTZCCA CICSSVC=212
DFHPA1927 IYCTZCCA SRBSVC=211
DFHPA1927 IYCTZCCA .END
DFHPA1103 IYCTZCCA END OF FILE ON SYSIN.
+DFHTR0103 TRACE TABLE SIZE IS 64K
+DFHSM0122I IYCTZCCA Limit of DSA storage below 16MB is 5,120K.
+DFHSM0123I IYCTZCCA Limit of DSA storage above 16MB is 20M.
+DFHSM0113I IYCTZCCA Storage protection is not active.
+DFHSM0126I IYCTZCCA Transaction isolation is not active.
+DFHDM0101I IYCTZCCA CICS is initializing.
+DFHLG0101I IYCTZCCA Log manager domain initialization has started.
+DFHSI1500 IYCTZCCA CICSTS41.CICS. Startup is in progress.
+DFHXS1100I IYCTZCCA Security initialization has started.
+DFHDU0304I IYCTZCCA Transaction Dump Data set DFHDMPA opened.
+DFHSI1501I IYCTZCCA Loading CICS nucleus.
+DFHXS1105 IYCTZCCA Resource profiles for class A1CVFPCT have been built.
+DFHDU03041 IYCTZCCA Transaction Dump Data set DFHDMPA opened.
+DFHXS1105 IYCTZCCA Resource profiles for class F1CVFFCT have been built.
+DFHXS1105 IYCTZCCA Resource profiles for class J1CVFJCT have been built.
+DFHXS1106 IYCTZCCA
 Resource profiles could not be built for class MUNKNOWN. CICS is
 terminated. SAF codes are (X'00000004',X'00000000'). ESM codes are
 (X'0000000',X'0000000').
+DFHDU0303I IYCTZCCA Transaction Dump Data set DFHDMPA closed.
+DFHKE1800 IYCTZCCA ABNORMAL TERMINATION OF CICSTS41.CICS IS COMPLETE.
IEF450I SSYTZCCA CICS - ABEND=S000 U1800 REASON=00000000
                          TIME=13.55.26
$HASP395 SSYTZCCA ENDED
```

Figure 38. Security initialization failure

```
DFHPA1927 IYCTZCCE SEC=YES
DFHPA1927 IYCTZCCE XUSER=YES
DFHPA1927 IYCTZCCE DFLTUSER=ORMAN
DFHPA1927 IYCTZCCE XCMD=NO
DFHPA1927 IYCTZCCE XFCT=1CVFFCT
DFHPA1927 IYCTZCCE XJCT=1CVFJCT
DFHPA1927 IYCTZCCE XPCT=1CVFPCT
DFHPA1927 IYCTZCCE XFCT=1CVFPPT
DFHPA1927 IYCTZCCE XPSB=NO
DFHPA1927 IYCTZCCE XTST=1CVFTST
DFHPA1927 IYCTZCCE XTRAN=1CVFTRN
DFHPA1927 IYCTZCCE CICSSVC=212
DFHPA1927 IYCTZCCE SRBSVC=211
DFHPA1927 IYCTZCCE .END
DFHPA1103 IYCTZCCE END OF FILE ON SYSIN.
+DFHTR0103 TRACE TABLE SIZE IS 64K
+DFHSM0122I IYCTZCCE Limit of DSA storage below 16MB is 5,120K.
+DFHSM0123I IYCTZCCE Limit of DSA storage above 16MB is 20M.
+DFHSM0113I IYCTZCCE Storage protection is not active.
+DFHSM0126I IYCTZCCE Transaction isolation is not active.
+DFHDM0101I IYCTZCCE CICS is initializing.
+DFHLG0101I IYCTZCCE Log manager domain initialization has started.
+DFHSI1500 IYCTZCCE CICSTS41.CICS Startup is in progress
+DFHXS1100I IYCTZCCE Security initialization has started.
+DFHDU0304I IYCTZCCE Transaction Dump Data set DFHDMPA opened.
+DFHSI1501I IYCTZCCE Loading CICS nucleus.
+DFHXS1105 IYCTZCCE Resource profiles for class A1CVFPCT have been built.
+DFHXS1105 IYCTZCCE Resource profiles for class F1CVFFCT have been built.
+DFHXS1105 IYCTZCCE Resource profiles for class J1CVFJCT have been built.
+DFHXS1105 IYCTZCCE Resource profiles for class M1CVFPPT have been built.
+DFHXS1105 IYCTZCCE Resource profiles for class S1CVFTST have been built.
+DFHXS1105 IYCTZCCE Resource profiles for class T1CVFTRN have been built.
+DFHXS1105 IYCTZCCE Resource profiles for class SURROGAT have been built.
ICH4081 USER(ORMAN ) GROUP(
                                   ) NAME(???
  LOGON/JOB INITATION - USER AT TERMINAL
                                              NOT RACF-DEFINED
IRR012I VERIFICATION FAILED. USER PROFILE NOT FOUND.
+DFHXS1104 IYCTZCCE
Default security could not be established for userid ORMAN. The
 security domain cannot continue, so CICS is terminated. SAF codes are
 (X'00000004',X'00000000'). ESM codes are (X'00000004',X'00000000').
+DFHDU0303I IYCTZCCE Transaction Dump Data set DFHDMPA closed.
+DFHKE1800 IYCTZCCE ABNORMAL TERMINATION OF CICSTS41.CICS IS COMPLETE.
IEF450I SSYTZCCE CICS - ABEND=S000 U1800 REASON=00000000
                          TIME=13.55.26
$HASP395 SSYTZCCE ENDED
```

Figure 39. Example of CICS job log if DFLTUSER fails to sign on

### Revoked user attempting to sign on

The following example sequence illustrates what happens when a revoked user attempts to sign on:

- 1. User USR001 attempts to sign on using CESN. However, the user is revoked. The user sees the following on the terminal:
  - DFHCE3546 Your signon userid has been revoked. Signon is terminated.
- A RACF ICH408I message is sent to the CICS region's job log: ICH408I USER(USR001 ) GROUP(GRP001 ) NAME(AUSER ) LOGON/JOB INITIATION - REVOKED USER ACCESS ATTEMPT

This message indicates that user USR001, whose name as recorded in the RACF user profile is AUSER, and whose current RACF connect group is GRP001, attempted to sign on.

 A CICS message is sent to the CSCS transient data queue: DFHSN1120 26/09/95 12:20:24 CICSSYS1 Signon at netname D2D1 with userid USR001 failed because the userid has been revoked.

# User has insufficient authority to access a resource

Now let us consider user USR001, who has signed on successfully with current connect group GRP001. User USR001 attempts unsuccessfully to use transaction CEMT, which is protected by profile CAT2 in class GCICSTRN (the resource group class for CICS transactions), because XTRAN=YES is specified in the CICS system initialization parameters.

1. The terminal user received the following CICS message:

DFHAC2033 26/09/95 15:18:44 CICSSYS1 You are not authorized to use transaction CEMT. Check that the transaction name is correct.

2. A RACF ICH408I message is sent to the CICS region's job log:

ICH408I USER(USR001 ) GROUP(GRP001 ) NAME(AUSER ICH408I CEMT CL(TCICSTRN) ICH408I INSUFFICIENT ACCESS AUTHORITY ICH408I ACCESS INTENT(READ ) ACCESS ALLOWED(NONE )

This message indicates that user USR001, whose name as recorded in the RACF user profile is AUSER, and whose current RACF connect group is GRP001, attempted to use the CEMT transaction. To do this, AUSER needs to have at least READ access to the profile protecting the CEMT transaction. However, RACF determined that AUSER had **no** access authority.

)

3. A CICS message is sent to the CSCS transient data queue:

DFHXS1111 26/09/95 13:30:41 CICSSYS1 CEMT Security violation by user USR001 at netname D2D1 for resource CEMT in class TCICSTRN. SAF codes are (X'00000008',X'00000000'). ESM codes are (X'00000008',X'00000000').

The following message is also sent to the CSMT transient data queue: DFHAC2003 26/09/95 15:18:44 CICSSYS1 Security violation has been detected term id = D2D1, trans id = CEMT, userid = USR001.

4. Which profile protects CEMT?

It appears from the ICH408I message that profile CEMT in class TCICSTRN protects CEMT. However, this is not necessarily the case. A resource group profile (in class GCICSTRN) might protect CEMT. In fact, in this case, there is no profile named CEMT. If a system-SPECIAL or AUDITOR user issues the SEARCH command with CLASS(TCICSTRN) specified, no profile named CEMT would appear.

To determine which profile was used, you must issue the RLIST command with the RESGROUP operand as follows:

RLIST member-class resource-name RESGROUP

In this case, issue the following: RLIST TCICSTRN CEMT RESGROUP

**Note:** If prefixing is used for this CICS region, specify the prefix on the resource-name in the RLIST command.

RACF displays the following:

```
CLASS NAME
TCICSTRN CEMT
GROUP CLASS NAME
GCICSTRN
RESOURCE GROUPS
CAT2
```

The profiles in class GCICSTRN that protect CEMT are shown under RESOURCE GROUPS in the command output. In this case, only one profile (CAT2) protects profile CEMT.

**Note:** If a profile in class TCICSTRN protected CEMT, that profile's contents would be added to the output of RLIST.

 To determine how profile CAT2 protects CEMT, list that profile with the AUTHUSER operand specified on the RLIST command: RLIST GCICSTRN CAT2 AUTHUSER

RACF displays the following: CLASS NAME ____ ____ GCICSTRN CAT2 MEMBER CLASS NAME ----- ----- ----TCICSTRN RESOURCES IN GROUP ----- -- -----CDBC CDBI CBRC CEDA CEMT CETR LEVEL OWNER UNIVERSAL ACCESS YOUR ACCESS WARNING NOTIFY _____ NO USER TO BE NOTIFIED USER ACCESS ACCESS COUNT DEPTA ALTER 000000 USR001 NONE 000000

NO ENTRIES IN CONDITIONAL ACCESS LIST

#### CICS region user ID access problem

CICS security initialization can fail if the CICS region user ID does not have access to the necessary Category 1 transactions.

A message similar to the following is shown: DFHXS1103I CICSAPPL Default security for userid CICSUSER has been established. DFHDU0304I CICSAPPL Transaction dump data set DFHDMPA opened. DFHXS1111 CICSAPPL 01/18/99 16:05:15 CICSAPPL ???? Security violation by user TESTRGN for resource CATA in class TCICSTRN.SAF codes are (X'00000004',X'00000000').ESM codes are (X'00000004',X'00000000'). DFHXS1113 CICSAPPL The region userid cannot access system transaction CATA. CICS will terminate. SAF codes are (X'00000004',X'00000000').ESM codes are (X'00000004',X'00000000').

When this occurs the SAF and return codes (X'00000004') indicate that no profile in the TCICSTRN (or GCICSTRN) class is protecting the resource CATA. To resolve this a suitable profile for CATA must be defined in the TCICSTRN (or GCICSTRN) class, and CICS region user ID TESTRGN must be given at least READ access. For guidance you can use example CLIST DFH\$CAT1 which is in library CICSTS41.CICS.SDFHSAMP (see "Category 1 transactions" on page 144).

After adding a suitable profile, you must issue the command: SETROPTS RACLIST (TCICSTRN) REFRESH

Even if you have also added the profile to the GCICSTRN class, you still only issue this command for TCICSTRN. If you do NOT issue this SETROPTS command, and you restart CICS, initialization will fail again with the same error, because RACF will not be using the updated definitions.

#### Password expiry management problem determination

If you are running a CICS-APPC PEM environment, and are not receiving the expected responses, check the following possible sources of errors in the sign-on transaction program:

- The function management header (FMH) may be in error; check that:
  - The conversation type being used is **basic**.
  - The XTRANID in the CICS TRANSACTION definition for CLS4 is X'06F3F0F1'. (See "Setting up the PEM client" on page 192.)
  - The CICS PEM server sign-on transaction is running as a synclevel 0 transaction. (See "Setting up the PEM client" on page 192.)
- The user data may be in error; check that:
  - Valid lengths are being sent. (See "PEM client input and output data" on page 194 and "Format of user data" on page 193.)
  - Userids and passwords are sent in uppercase EBCDIC. (See "Setting up the PEM client" on page 192.)
  - GDS variables (required in basic conversations) are being used: (See "Format of user data" on page 193.)

**Note:** If the CICS PEM server receives an error in the FMH or user data, it sends an ISSUE ERROR to the PEM requester, and terminates without an abend. If this happens, it is likely that there is an error in the flow. For examples of valid flows, see "PEM client input and output data" on page 194.

# Execution diagnostic facility (EDF)

The execution diagnostic facility (EDF) **cannot** be used to check DFHCLS4, for security reasons, because user passwords would be displayed on the EDF screens.

# Part 9. CICSPlex SM security

This part describes how to implement security for CICSPlex SM.

# **Chapter 25. Implementing CICSPlex SM security**

To implement CICSPlex SM security using RACF, you must determine who needs access to the various CICSPlex SM functions. You must also perform a number of tasks to define CICSPlex SM class names and resource names, as well as activating security and refreshing RACF profiles.

#### About this task

If you are using a SAF-compliant external security manager (ESM) other than RACF, refer to Chapter 26, "Invoking a user-supplied external security manager," on page 375. The following steps summarize how to set up security for CICSPlex SM. Each of the steps are explained in detail in the subsequent topics.

#### Procedure

- 1. Decide who needs access to CICSPlex SM.
- 2. Review the general security requirements for CICSPlex SM.
- 3. Create RACF profiles for the CICSPlex SM data sets.
- 4. Define the CICSPlex SM started tasks to RACF.
- 5. If CICS transaction security is active in a CMAS, define the CICSPlex SM transactions to RACF.
- 6. If CICS transaction security is active in a MAS, define the CICSPlex SM transactions to RACF.
- 7. Create RACF profiles for the CICSPlex SM views.
- 8. Create RACF profiles for the CICSPlex SM Web User Interface resources. See the *CICSPlex System Manager Web User Interface Guide* for more information.
- **9**. Optional: Optionally, you can activate simulated security checking using the CICSSYS, CPLEXDEF, or MAS views
- **10**. Activate security in the CMASs and MASs using the CICSPlex SM and CICS security-related system initialization parameters

# Determining who requires access to CICSPlex SM resources

To determine who requires access to the CICSPlex SM resources, answer the questions and complete the matrix. You can then use the results to create the PERMIT statements that are required in RACF to control access to the resources.

#### About this task

You can control access to CICSPlex SM resources in two ways:

- By restricting access to the objects managed by CICSPlex SM views. This restriction does not affect access to the views themselves, but it prevents them from displaying any data.
- By restricting access to Web User Interface view sets, menus and the View Editor. This restriction does not affect access to the objects being managed but prevents access to the view sets, menus and View Editor themselves.

#### Procedure

1. Answer the following questions to determine who requires access to the CICSPlex SM resources:

#### What groups of users will use CICSPlex SM?

Your enterprise probably already has several user groups defined to RACF. The groups that typically require access to CICSPlex SM include systems programming, operations, the help desk, applications programming, and performance monitoring. These groups are used as column headings in the security matrix. You can supply their corresponding RACF group IDs. (If necessary, you can ignore, replace, or add groups to the matrix as appropriate for your enterprise.)

#### Which CICSPlex SM views will each group need to use?

CICSPlex SM manages CICS resources using views. Views are grouped by functionality: configuration, topology, workload management, real-time analysis, operations, monitoring, business application services, and CICSplex management. Not all view groups are appropriate for all users. Certain groups of users will only use a subset of views. For example, the systems programming group might need to work with all views, while the help desk group might only need to use one or two. The view groups are listed vertically on the left side of the matrix, along with the high-level qualifier of their CICSPlex SM resource names.

#### What type of access does each RACF group need?

After deciding who needs to use what, stop universal access to all of the objects managed by all of the views. You can then selectively permit read, update, or alter access to specific view groups. To complete the matrix, specify READ, UPDATE, or ALTER access for each RACF group that needs access to a group of views.

- Specify READ access to allow a user to inquire on a resource.
- Specify UPDATE access to allow a user to change a value, using the SET or UPDATE command, or perform an action. The user can also create or remove a definition, such as a BAS resource object.
- Specify ALTER access to allow a user to discard an installed resource from CICS and allow a user to install a BAS resource object.

# Which CICSPlex SM Web User Interface views, menus will each group need access to?

Web User Interface views and menus are usually user-defined but like Web User Interface views are most likely grouped by functionality. Not all view sets and menus are appropriate for all users. Certain groups of users require access to a subset of views. For example, the systems programming group might require access to all views and to the View Editor, while the help desk group might not need to use the View Editor or those views that manage the definition of CICSPlex SM resources.

2. Fill out the security matrix when you have answered the questions.

Table 41. Security matrix

RACF group → CICSPlex SM view group ↓	System Programming ID( )	Operations ID( )	Help Desk ID( )	Application Programming ID( )	Performance ID( )
Configuration CONFIG					

Table 41. Security matrix (continued)

RACF group → CICSPlex SM view group ↓	System Programming ID( )	Operations ID( )	Help Desk ID( )	Application Programming ID( )	Performance ID( )
Topology TOPOLOGY					
Workload Management WORKLOAD					
Real-Time Analysis ANALYSIS					
Operations OPERATE					
Monitor MONITOR					
Business Application Services BAS					

Table 42 is a sample of a completed security matrix for a production CICSplex:

Table 42. Sample security matrix

RACF group → CICSPlex SM view group ↓	System Programming ID(SYSPGRP)	Operations ID(OPSGRP)	Help Desk ID(HELPGRP)	Application Programming ID(APPLGRP)	Performance ID(PERFGRP)
Configuration CONFIG	UPDATE				
Topology TOPOLOGY	UPDATE	UPDATE	READ		
Workload Management WORKLOAD	UPDATE			READ	
Real-Time Analysis ANALYSIS	UPDATE	UPDATE	READ		READ
Operations OPERATE	ALTER	UPDATE	READ	READ	READ
Monitor MONITOR	UPDATE	READ			READ
Business Application Services BAS	ALTER	ALTER		UPDATE	

**3**. Ensure that the CPSMOBJ class is active and that generic profiles can be defined:

SETROPTS CLASSACT(CPSMOBJ) SETROPTS GENERIC(CPSMOBJ) SETROPTS GENCMD(CPSMOBJ)

4. Create a RACF profile to protect all of the views and action commands for all CICSPlex SM functions:

RDEF CPSMOBJ ** UACC(NONE) OWNER(admin_group) NOTIFY(admin_user)

CPSMOBJ is the CICSPlex SM member class. The double asterisks indicate that all of the CICSPlex SM views are included in this RDEF statement.

5. Using the information in the sample matrix, you can permit access to the specific view groups. For example, the systems programming group requires update access to all of the view groups and ALTER access to the BAS views. You can define this with just three PERMIT statements:

PERMIT ** CLASS(CPSMOBJ) ID(SYSPGRP) ACCESS(UPDATE) PERMIT BAS.** CLASS(CPSMOBJ) ID(SYSPGRP) ACCESS(ALTER)

The double asterisks indicate that all of the CICSPlex SM views are affected by this PERMIT statement.

The following PERMIT statements grant the appropriate access to all of the topology views for the operations and help desk groups:

PERMIT TOPOLOGY.** CLASS(CPSMOBJ) ID(OPSGRP) ACCESS(UPDATE) PERMIT TOPOLOGY.** CLASS(CPSMOBJ) ID(HELPGRP) ACCESS(READ)

For the workload management views:

PERMIT WORKLOAD.** CLASS(CPSMOBJ) ID(APPLGRP) ACCESS(READ)

For the real-time analysis views:

PERMIT ANALYSIS.** CLASS(CPSMOBJ) ID(OPSGRP) ACCESS(UPDATE) PERMIT ANALYSIS.** CLASS(CPSMOBJ) ID(HELPGRP) ACCESS(READ) PERMIT ANALYSIS.** CLASS(CPSMOBJ) ID(PERFGRP) ACCESS(READ)

For the operations views:

PERMIT OPERATE.** CLASS(CPSMOBJ) ID(OPSGRP) ACCESS(UPDATE) PERMIT OPERATE.** CLASS(CPSMOBJ) ID(HELPGRP) ACCESS(READ) PERMIT OPERATE.** CLASS(CPSMOBJ) ID(APPLGRP) ACCESS(READ) PERMIT OPERATE.** CLASS(CPSMOBJ) ID(PERFGRP) ACCESS(READ)

For the monitor views:

PERMIT MONITOR.** CLASS(CPSMOBJ) ID(APPLGRP) ACCESS(READ)
PERMIT MONITOR.** CLASS(CPSMOBJ) ID(PERFGRP) ACCESS(READ)

For the business application services views:

PERMIT BAS.** CLASS(CPSMOBJ) ID(OPSGRP) ACCESS(ALTER)
PERMIT BAS.** CLASS(CPSMOBJ) ID(APPLGRP) ACCESS(UPDATE)

#### Results

For simplicity, these PERMIT statements grant access to broad groups of views by using the double asterisks in the resource names. However, if required, you can use more specific resource names in your PERMIT statements. Refer to "Specifying CICSPlex SM resource names in profiles" on page 349 for details.

#### What to do next

Using your own completed security matrix and the information in the remainder of this section, you can create as many profiles as required for your enterprise. Chapter 27, "Example tasks: security," on page 379 provides detailed profile examples.

#### General requirements for CICSPlex SM security

Review your RACF configurations to ensure that your systems meet the minimum requirements.

- The IDs for all users expected to use CICSPlex SM must be defined to RACF in each MVS system in which there is a CMAS. For each individual user, the ID must be the same for each MVS system.
- User access authority to CICSPlex SM definitions and CICS commands and resources must be defined to RACF in a consistent manner in all MVS systems used by CICSPlex SM.

In addition, in the CMAS address space, a security environment is created for the user specified in the **DFLTUSER** system initialization parameter associated with the MAS.

# Creating profiles for the CICSPlex SM data sets

#### About this task

You should restrict access to CICSPlex SM data sets using RACF data set protection. Use the following guidelines:

#### Procedure

- 1. Prohibit universal access by specifying UACC(NONE).
- 2. Ensure that minimum access to the data sets is authorized for the RACF USERID assigned to each of the following:
  - Every CMAS job or started task.
  - Every MAS.
  - All individuals allowed to use CICSPlex SM from the CICSPlex SM WUI and API (both system administrators and end users).

Table 43 lists the CICSPlex SM data sets and the minimum access that should be granted to each type of user ID.

#### Table 43. Access by user ID for CICSPlex SM data sets

Data set name	CMAS	MAS	System Admin.	Individual User
SYS1.CICSTS41.CPSM.SEYULPA	NONE	READ	UPDATE	NONE
SYS1.CICSTS41.CPSM.SEYULINK	READ	NONE	UPDATE	NONE
CICSTS41.CPSM.SEYUAUTH	READ	READ	UPDATE	READ
CICSTS41.CPSM.SEYULOAD	READ	READ	UPDATE	NONE
CICSTS41.CPSM.SEYUPARM	READ	READ	UPDATE	NONE
CICSTS41.CPSM.SEYUCMOD	NONE	NONE	UPDATE	NONE
CICSTS41.CPSM.SEYUCOB	NONE	NONE	UPDATE	READ
CICSTS41.CPSM.SEYUC370	NONE	NONE	UPDATE	READ
CICSTS41.CPSM.SEYUDEF	READ	READ	UPDATE	READ
CICSTS41.CPSM.SEYUCLIB	NONE	NONE	UPDATE	READ
CICSTS41.CPSM.SEYUMLIB	NONE	NONE	UPDATE	READ
CICSTS41.CPSM.SEYUPLIB	NONE	NONE	UPDATE	READ
CICSTS41.CPSM.SEYUTLIB	NONE	NONE	UPDATE	READ
CICSTS41.CICS.SDFHINST	NONE	NONE	UPDATE	NONE
CICSTS41.CPSM.SEYUMAC	NONE	NONE	UPDATE	READ
CICSTS41.CPSM.SEYUOS2	NONE	NONE	UPDATE	NONE
CICSTS41.CPSM.SEYUPL1	NONE	NONE	UPDATE	READ
CICSTS41.CPSM.SEYUPROC	NONE	NONE	UPDATE	READ
CICSTS41.CPSM.SEYUSAMP	NONE	NONE	UPDATE	READ
CICSTS41.CPSM.EYUSDEF	NONE	NONE	UPDATE	UPDATE
CICSTS41.CPSM.EYUDREP	UPDATE	NONE	UPDATE	NONE
CICSTS41.CPSM.EYUIPRM	NONE	NONE	UPDATE	NONE

#### What to do next

If you require more details about RACF data set protection, see the *z*/OS Security Server RACF Security Administrator's Guide.

#### Defining the CICSPlex SM started tasks

When you run a CMAS as a started task, you must associate the appropriate procedure names with a suitably authorized USERID.

#### About this task

This is usually achieved using the STARTED general resource class or the RACF ICHRIN03 tables. The names of the associated USERIDs need not match the names of the procedures. Each USERID must have the appropriate level of access to all of the data sets referenced in the cataloged procedures.

For additional information about the STARTED class, see the *z*/OS Security Server RACF Security Administrator's Guide. For more information about ICHRIN03, see the *z*/OS Security Server RACF System Programmer's Guide.

**Note:** If the USERID and group name that you assign are not defined to RACF, the started tasks will execute with only the limited authority of an undefined user. In this case, the address space will be able to access protected resources only if the universal access authority (UACC) for the resource is sufficient to allow the requested operation.

#### Defining the CICSPlex SM transactions in a CMAS

If transaction–attach security is active in a CMAS (that is, SEC=YES and XTRAN=YES|*classname* are specified in the system initialization parameters), you must define to RACF the CICSPlex SM transactions that run in a CMAS.

#### Procedure

1. You must define the following CICSPlex SM transactions to RACF:

BMLT	LPLT	PRLT	WMWC
LCPP	LPRT	PRPR	WMWD
LCMU	LPSC	PSLT	WMWT
LECI	LPSM	TICT	WSCL
LECR	LRLT	TIRT	WSLW
LECS	LSGT	TIST	XDBM
LEEI	LSRT	TSMH	XDNC
LEER	LWTM	TSPD	XDND
LEMI	MCCM	TSSC	XDNE
LEMS	MCTK	TSSJ	XDNR
LENS	MMEI	WMCC	XDNS
LMIR	MMIS	WMGR	XDSR
LNCI	MMST	WMLA	XLEV
LNCS	PEAD	WMQB	XLNX
LNMI	PELT	WMQM	XLST
LNMS	PMLT	WMQS	XMLT
LPDG	PNLT	WMSC	XQST
LPLK	PPLT		XZLT

T

A list of these transactions is also contained in the EYU\$CDEF member of SEYUSAMP sample library.

- a. If the CMAS is started by a PLT program, ensure that the region user ID , and any user ID that might be specified on the PLTPIUSR system initialization parameter, has authority to attach these transactions.
- b. Depending on the security attributes specified for any CMTCMDEF or CMTPMDEF, ensure that any user IDs that might flow from connected CMASs have the authority to attach these transactions. Note that the CICS default user ID might flow if the connected CMAS or MASs are defined as equivalent systems.
- 2. Define the following debugging transactions to RACF if transaction security is active, regardless of the CICS release running as the CMAS:
  - CODB
  - COD0
  - COD1
  - COD2
  - COLU

|

L

These transactions are associated with a terminal and are supplied for debugging purposes under the guidance of IBM support personnel. Authority to initiate these transactions must be restricted to only those users who might become involved in working with IBM to resolve CICSPlex SM problems.

- **3**. Give users access to the CESD shutdown-assist transaction. Users who can attach CICSPlex SM transactions or define debugging transactions need access to CESD in case of CMAS failure.
- Allow only users who might need to shut down a CMAS to access the COSD transaction. The COSD transaction allows a terminal user to shut down a CMAS.

## Defining the CICSPlex SM transactions in a managed CICS region

For CICS regions that are capable of running with an external security manager, it might be necessary to define the CICSPlex SM transactions that run in a CICS region managed by CICSPlex SM to the ESM.

## About this task

If transaction–attach security is active in a CICS region (that is, SEC=YES and XTRAN=YES | *classname* are specified in the system initialization parameters), you must define the following transactions to RACF in the appropriate class:

COHT COIE COIR COI0 CONA COND CONH CONL CONM

## COWC

The region userid, and any userid that may be specified on the **PLTPIUSR** system initialization parameter, should be given READ access to these transactions.

Users who might initiate the agent code using transaction COLM for a local managed CICS region should also be given access to these transactions. If your CICS system performs surrogate user checks (that is, the **XUSER** system initialization parameter has a value of YES), then the CICS region userid should be a surrogate of the user of the COLM transaction.

For details of the **PLTIPUSR** and **XUSER** system initialization parameters, see the *CICS System Definition Guide*.

Users who can enter dynamic transactions in a CICSPlex SM workload management requesting region must have READ access to the COWC transaction.

Users who might invoke the CICSPlex SM debugging transactions should be given READ access to the following transactions:

CODB COD0 COD1 COD2 COLU

The security attributes of the CONNECTION/SESSION pair defined for the link to the CMAS define which users are authorized to run these transactions. See Chapter 11, "Overview of intercommunication security," on page 159 for information on intercommunication security.

The COSH transaction allows a terminal user to stop agent code execution. Access to this transaction should be restricted to those users who might need to stop the agent code in this way.

## Defining the CICSPlex SM transactions for a WUI

For Web User Interface (WUI) regions that are capable of running with an external security manager (ESM) such as RACF, it is necessary to define the CICSPlex SM transactions that run in the region to the ESM.

## Before you begin

This is necessary when transaction attach security is active in the WUI region, where SEC=YES and XTRAN=YES system initialization parameters are specified.

#### Procedure

- 1. Create the same definitions as you would for a MAS region. See "Defining the CICSPlex SM transactions in a managed CICS region" on page 347.
- 2. Define READ access to the COVG and COVC transactions for the following user IDs:
  - The region user ID
  - All user IDs that are specified on the **PLTPIUSR** system initialization parameter for the region
  - All WUI system administrators.

- **3**. Define READ access to the COVE, COVP, and COVU transactions for the WUI default user ID.
- 4. Define READ access to the COVA transaction for all WUI end users.

#### Example

A list of these transactions is also contained in the CSD group EYU\$WDEF.

# Specifying CICSPlex SM resource names in profiles

You can create RACF profiles for CICSPlex SM views for a specific CICS system, a group of CICS systems, or all systems comprising a CICSplex.

## About this task

This section provides the resource names for CICSPlex SM views to be used in RACF profiles. Refer to Chapter 27, "Example tasks: security," on page 379 for profile examples.

CICSPlex SM views are divided into groups that reflect the functions they perform. Within each functional group, the views are divided by their type. Functional groups can be even further qualified with the addition of a context and, for some groups, a scope. You can control access to a specific set of views (and their associated action commands) by identifying the set in a profile, using one of the following resource name formats:

function.type.context

function.type.context.scope

where:

function

I

5		
	is the	name of the CICSPlex SM function to be affected:
	ANAI	YSIS
		Real-time analysis
	BAS	Business application services
	CONF	
		CMAS configuration
	CSD	CICS System Definition
	MON	5
		Resource monitoring
	OPER	0
		Operations
	ТОРО	LOGY
		CICSplex configuration
	WORI	KLOAD
		Workload management
type	is the	specific or generic name of an area that qualifies the CICSPlex SM
	functio	on to be affected. The specific names are:
	AIMC	
		CICS AIMODEL
	BRFA	CIL
		Link3270 Bridge Facility
	CONN	· ·
		CICS connections
	DB2D	BCTL
		DB2/DBCTL resources and subsystems

DEF **CICSPlex SM definitions** DOCTEMP Document templates ENQMODEL CICS global enqueue models ENTJAVA CorbaServers and deployed DJARs EXIT CICS exits FEPI CICS FEPI resources FILE CICS files **IPCONN IPIC** connections **JOURNAL** Journal models PARTNER CICS partners PROCTYPE CICS BTS Process types PROFILE CICS profiles PROGRAM CICS programs REGION CICS region data RQMODEL CICS request models TASK CICS active tasks TCPIPS TCP/IP services **TDOUEUE** CICS transient data queues **TERMINAL** CICS terminals **TRAN** CICS transactions **TSQUEUE** CICS temporary storage queues **UOW** CICS units of work

The type must be valid for the specified function. Table 44 on page 352 lists the valid function.type combinations.

#### context

is the specific or generic name of the CMAS or CICSplex to be affected by the designated function and type. If the function is CONFIG or TOPOLOGY, the context must be a CMAS. For all other functions, the context must be a CICSplex.

**scope** is the specific or generic name of a CICS system in the CICSplex identified as the context. Do not specify scope when the context is a CMAS or the type is DEF, except when you are handling CSD resources. If you are handling CSD resources you must specify the scope.

#### Note:

In this section only, the term scope means CICS systems. It does *not* mean the scope (CICS system groups) you have defined as part of the CICSplex environment, nor does it refer to a BAS logical scope.

T

Т

Т

1

I

**2**. To include all of the systems comprising a CICS system group when their names do not match a generic system name, you must establish a profile for each system.

# Using asterisks in resource names

To reduce the number of profiles you need to define, you can use * (one asterisk) and ** (two consecutive asterisks) to represent one or more entries. Use of one or two asterisks is optional.

**Note:** Before using asterisks in profile definitions, ensure that generics have been activated for the relevant class:

SETROPTS GENERIC (CPSMOBJ, CPSMXMP)

The following examples demonstrate how asterisks can be used:

#### **OPERATE.*.EYUPLX01.EYUPLX01**

Indicates that all views and action commands associated with any type valid within the OPERATE function are to be recognized when the context and scope are EYUPLX01.

#### OPERATE.PROGRAM.**

Indicates that all views and action commands associated with the PROGRAM type within the OPERATE function are to be recognized, regardless of the current context and scope.

#### OPERATE.**

|

I

Indicates that all views and action commands associated with any type valid within the OPERATE function are to be recognized, regardless of the current context and scope.

****** Indicates that *all* views and action commands associated with *any* type valid within *any* function are to be recognized, regardless of the current context and scope.

## Valid resource name combinations

You can use valid function and type combinations when creating profiles to control access to resource tables using the CICSPlex SM API or WUI.

Table 44 on page 352 lists the valid function and type combinations and the resource names associated with each combination. If you are using the WUI, note that the resource name is given at the foot of the views in the corresponding view set.

Table 44. Function and type combinations for resources accessible using CICSPlex SM

Function.Type	Resource Table Name and Usage
ANALYSIS.DEF	ACTION
	Create, display, and maintain action definitions.
	APACTV
	Display analysis definitions associated with an analysis point specification.
	APSPEC
	Create, display, and maintain analysis point specifications.
	CMDMPAPS Identify the role of a primary CMAS.
	CMDMSAPS
	Identify the role of a secondary CMAS.
	EVALDEF
	Create, display, and maintain evaluation definitions.
	EVENT
	Display changes in the status of a CICSplex. EVENTDTL
	Display evaluation definitions associated with an analysis definition that
	caused an event.
	LNKSRSCG
	Describe the link between a CICS system group and an analysis specification
	LNKSRSCS
	Describe the link between a CICS system and an analysis specification.
	<b>RTAACTV</b> Display analysis and status definitions in CICS systems.
	RTADEF
	Create, display, and maintain analysis definitions.
	RTAGROUP
	Create, display, and maintain analysis groups.
	RTAINAPS
	Display analysis groups in analysis point specifications. <b>RTAINGRP</b>
	Display analysis and status definitions in analysis groups.
	RTAINSPC
	Display analysis groups in analysis specifications.
	RTASPEC
	Create, display, and maintain analysis specifications.
	STATDEF
	Create, display, and maintain status definitions. STAINGRP
	Identify the membership relation of a status definition in an RTAGROUP.
BAS.APPLICTN	BUNDDEF
	Install applications that are deployed as bundles.
BAS.CONNECT	CONNDEF
	Install ISC/MRO connection definitions.
	IPCONDEF
	Install IPIC connection definitions.
	SESSDEF Install session definitions.
BAS.DB2DBCTL	DB2CDEF
DIGDDZDDCTL	Install DB2 connection definitions.
	DB2EDEF
	Install DB2 entry definitions.
	DB2TDEF
	Install DB2 transaction definitions.

| |

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

| | |

| |

| | |

Function.Type	Resource Table Name and Usage
BAS.DEF	ATOMDEF
	Create, display, and maintain Atom service definitions.
	<b>BUNDDEF</b> Create, display, and maintain bundle definitions.
	CONNDEF
	Create, display, and maintain MRO and ISC over SNA connection definitions
	DB2CDEF Create, display, and maintain DB2 connection definitions.
	DB2EDEF
	Create, display, and maintain DB2 entry definitions. <b>DB2TDEF</b>
	Create, display, and maintain DB2 transaction definitions.
	DOCDEF
	Create, display, and maintain document template definitions. EJCODEF
	Create, display, and maintain CorbaServer definitions.
	EJDJDEF
	Create, display, and maintain deployed JAR file definitions. ENQMDEF
	Create, display, and maintain enqueue models definitions.
	FENODDEF Create, display, and maintain FEPI node definitions.
	FEPOODEF
	Create, display, and maintain FEPI pool definitions.
	FEPRODEF Create, display, and maintain FEPI property set definitions.
	FETRGDEF
	Create, display, and maintain FEPI target definitions. FILEDEF
	Create, display, and maintain file definitions.
	FSEGDEF
	Create, display, and maintain OS/2 key file segment definitions. IPCONDEF
	Create, display, and maintain IPIC connection definitions.
	JRNMDEF
	Create, display, and maintain journal model definitions. JVMSVDEF
	Create, display, and maintain JVM server definitions.
	LIBDEF Create, display, and maintain LIBRARY definitions.
	LSRDEF
	Create, display, and maintain LSR pool definitions.
	MAPDEF Create, display, and maintain mapset definitions.
	MQCONDEF
	Create, display, and maintain WebSphere MQ connection definitions.
	MQCINGRP Display WebSphere MQ connection definitions in groups.
	PARTDEF
	Create, display, and maintain partner definitions. PIPEDEF
	Create, display, and maintain pipeline definitions.
	PROCDEF
	Create, display, and maintain process type definitions.

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Function.Type	Resource Table Name and Usage
BAS.DEF (continued)	PROFDEF
	Create, display, and maintain profile definitions.
	PROGDEF
	Create, display, and maintain program definitions.
	PRTNDEF
	Create, display, and maintain partition set definitions.
	RASGNDEF
	Create, display, and maintain resource assignments. RASINDSC
	Display resource assignments in descriptions.
	RASPROC
	Display resource assignment process.
	RDSCPROC
	Display resource description process.
	RESDESC
	Create, display, maintain, and install resource descriptions.
	RESGROUP
	Create, display, maintain, and install resource groups.
	RESINDSC
	Display resource groups in descriptions.
	RESINGRP
	Display resource definitions in groups.
	RQMDEF
	Create, display, and maintain request model definitions.
	SESSDEF
	Create, display, and maintain session definitions.
	SYSRES
	Display CICS system resources.
	TCPDEF
	Create, display, and maintain TCP/IP service definitions.
	<b>TDQDEF</b> Create, display, and maintain transient data queue definitions.
	TERMDEF
	Create, display, and maintain terminal definitions.
	TRANDEF
	Create, display, and maintain transaction definitions.
	TRNCLDEF
	Create, display, and maintain transaction class definitions.
	TYPTMDEF
	Create, display, and maintain typeterm definitions.
	URIMPDEF
	Create, display, and maintain URI map definitions.
	WEBSVDEF
	Create, display, and maintain Web services definitions.

Function.Type **Resource Table Name and Usage BAS.DEF** (continued) ATMINGRP Describe the membership of an Atom service definition in a resource group. **BUNINGRP** Describe the membership of a bundle definition in a resource group. CONINGRP Describe the membership of an MRO or ISC over SNA connection definition in a resource group. DOCINGRP Describe the membership of a document template definition in a resource group. **D2CINGRP** Describe the membership of a DB2 connection definition in a resource group. **D2EINGRP** Describe the membership of a DB2 entry definition in a resource group. **D2TINGRP** Describe the membership of a DB2 transaction definition in a resource group. EJCINGRP Describe the membership of a CorbaServer definition in a resource group. **EJDINGRP** Describe the membership of a deployed JAR file definition in a resource group. ENQINGRP Describe the membership of an ENQ/DEQ model definition in a resource group. FILINGRP Describe the membership of a file definition in a resource group. **FNOINGRP** Describe the membership of a FEPI node definition in a resource group. **FPOINGRP** Describe the membership of a FEPI pool definition in a resource group. FPRINGRP Describe the membership of a FEPI property set definition in a resource group. FSGINGRP Describe the membership of a file key segment definition in a resource group. FTRINGRP Describe the membership of a FEPI target definition in a resource group. **IPCINGRP** Describe the membership of an IPIC connection definition in a resource group. **JMSINGRP** Describe the membership of a JVM server definition in a resource group. **JRMINGRP** Describe the membership of a journal model definition in a resource group. LIBINGRP Describe the membership of a LIBRARY definition in a resource group. LSRINGRP Describe the membership of an LSR pool definition in a resource group. MAPINGRP Describe the membership of a map set definition in a resource group. PARINGRP Describe the membership of a partner definition in a resource group. PGMINGRP Describe the membership of a program definition in a resource group. PIPINGRP Describe the membership of a pipeline definition in a resource group. PRCINGRP Describe the membership of a process type definition in a resource group. Chapter 25. Implementing CICSPlex SM security 355 PRNINGRP Describe the membership of a partition set definition in a resource group.

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

1

L

T

1

PROINGRP

Describe the membership of a profile definition in a resource group.

Function.Type	Resource Table Name and Usage
BAS.DEF (continued)	SESINGRP
	Describe the membership of a session definition in a resource group. <b>TCLINGRP</b>
	Describe the membership of a transaction class definition in a resource
	group.
	TCPINGRP
	Describe the membership of a TCPIP Service definition in a resource group. <b>TDQINGRP</b>
	Describe the membership of a transient data queue definition in a resource
	group.
	<b>TRMINGRP</b> Describe the membership of a terminal definition in a resource group.
	TRNINGRP
	Describe the membership of a transaction definition in a resource group.
	<b>TSMINGRP</b> Describe the membership of a temporary storage model definition in a
	resource group.
	TYPINGRP
	Describe the membership of a typeterm definition in a resource group.
	<b>URIINGRP</b> Describe the membership of a URI map definition in a resource group.
	WEBINGRP
	Describe the membership of a web service definition in a resource group.
BAS.DOCTEMP	DOCTEMP Install document template definitions.
BAS.ENQMODEL	ENQMDEF
~	Install enqueue model definitions.
BAS.ENTJAVA	EJCODEF
	Install CorbaServer definitions. EJDJDEF
	Install deployed JAR file definitions.
	JVMSVDEF
	Install JVM server definitions.
BAS.FILE	FILEDEF Install file definitions.
BAS.JOURNAL	JRNMDEF
	Install journal model definitions.
BAS.PARTNER	PARTDEF
BAS.PROCTYPE	Install partner definitions. PROCDEF
	Install BTS Process type definitions.
BAS.PROFILE	PROFDEF
	Install profile definitions.
BAS.PROGRAM	LIBDEF Install LIBRARY definitions.
	MAPDEF
	Install map set definitions.
	PROGDEF Install program definitions.
	PRTNDEF
	Install partition set definitions.

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

| |

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Function.Type	Resource Table Name and Usage
BAS.REGION	LSRDEF
	Install LSR pool definitions.
	MQCONDEF
	Install WebSphere MQ connection definitions.
	TRNCLDEF
	Install transaction class definitions.
BAS.TCPIPS	ATOMDEF
	Install Atom service definitions.
	PIPEDEF
	Install pipeline definitions.
	TCPDEF
	Install TCPIP service definitions.
	URIMPDEF
	Install URI map definitions.
	WEBSVDEF
	Install Web services definitions.
BAS.TDQUEUE	TDQDEF
	Install transient data queue definitions.
BAS.TERMINAL	TERMDEF
	Install terminal definitions.
	TYPTMDEF
	Install typeterm definitions.
BAS.TRAN	TRANDEF
	Install transaction definitions.
CONFIG.DEF	CICSPLEX
	Display and manage CMAS in CICSplex.
	CMAS Display and manage active CMASs.
	CMASLIST
	Describe a CMAS and its connection to characteristics.
	CMASPLEX
	Display CICSplexes for a CMAS.
	CMTCMDEF
	Create, display, and maintain CMAS links.
	CMTCMLNK Dieplay active CMAS links
	Display active CMAS links. CMTPMLNK
	Display an active CMAS-to-MAS link.
	CPLEXDEF
	Create, display, and maintain CICSplex definitions.
	CPLXCMAS
	Display CMAS to CICSplex.

| |

Function.Type Resource Table Name and Usage CSD.DEF ATOMDEF Create, install, display, and maintain Atom service definitions. **BUNDDEF** Create, install, display, and maintain bundle definitions. CONNDEF Create, install, display, and maintain MRO and ISC over SNA connection definitions. CSDGROUP Create, install, display, and maintain CSD resource group definitions. CSDINGRP Describe the membership of a CSD resource group. CSDINLST Describe the membership of a CSD resource group list. CSDLIST Create, install, display, and maintain CSD resource group list definitions. **DB2CDEF** Create, install, display, and maintain DB2 connection definitions. **DB2EDEF** Create, install, display, and maintain DB2 entry definitions. **DB2TDEF** Create, install, display, and maintain DB2 transaction definitions. DOCDEF Create, install, display, and maintain document template definitions. EJCODEF Create, install, display, and maintain CorbaServer definitions. EIDIDEF Create, install, display, and maintain deployed JAR file definitions. ENQMDEF Create, install, display, and maintain enqueue models definitions. FILEDEF Create, install, display, and maintain file definitions. FSEGDEF Create, install, display, and maintain OS/2 key file segment definitions. **IPCONDEF** Create, install, display, and maintain IPIC connection definitions. JRNMDEF Create, install, display, and maintain journal model definitions. **JVMSVDEF** Create, install, display, and maintain JVM server definitions. LIBDEF Create, install, display, and maintain LIBRARY definitions. LSRDEF Create, install, display, and maintain LSR pool definitions. MAPDEF Create, install, display, and maintain mapset definitions. MOCONDEF Create, install, display, and maintain WebSphere MQ connection definitions. PARTDEF Create, install, display, and maintain partner definitions. PIPEDEF Create, install, display, and maintain pipeline definitions. PROCDEF Create, install, display, and maintain process type definitions. PROFDEF Create, install, display, and maintain profile definitions. PROGDEF Create, install, display, and maintain program definitions. PRTNDEF Create, install, display, and maintain partition set definitions. 358 CICS TS for z/OS 4.1: RACE Service Guide Create, install, display, and maintain request model definitions.

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Т

T

Т

Т

Т

Т

Т

Т

SESSDEF

Create, display, and maintain session definitions

Function.Type	Resource Table Name and Usage
MONITOR.CONNECT	MCONNECT
	ISC and MRO connections
	MMODENAME LU 6.2 modenames
MONITOR.DB2DBCTL	MDB2THRD
Mortifoldbbbbere	DB2 threads
MONITOR.DEF	LNKSMSCG
	Describe the link between a CICS system group and a monitor specification.
	LNKSMSCS
	Describe the link between a CICS system and a monitor specification. MONDEF
	Create, display, and maintain monitor definitions.
	MONGROUP
	Create, display, and maintain monitor groups.
	MONINGRP
	Create, display, and maintain monitor definitions in monitor groups. MONINSPC
	Create, display, and maintain monitor groups in monitor specifications.
	MONSPEC
	Create, display, and maintain monitor specifications.
	POLMON
MONITOR FEDI	Describe a monitor definition in a specific CICS system.
MONITOR.FEPI	MFEPICON FEPI connections
MONITOR.FILE	MCMDT
	Data tables
	MLOCFILE
	Local files
	MREMFILE Remote files
MONITOR.JOURNAL	MJOURNL
	Journals
	MJRNLNAM
	Journal names
MONITOR.PROGRAM	MPROGRAM
MONITOR.REGION	Programs MCICSDSA
WICH TOR. REGION	Dynamic storage areas
	MCICSRGN
	CICS systems
	MLSRPBUF
	LSRPOOL buffer pool MLSRPOOL
	LSRPOOL
	MTRANCLS
	Transaction classes
MONITOR.TDQUEUE	MINDTDQ
	Indirect transient data queues MNTRATDQ
	Intrapartition transient data queues
	MREMTDQ
	Remote transient data queues
	MTDQGBL
	Global intrapartition transient data queues MXTRATDQ
	Extrapartition transient data queues
L	

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Function.Type	Resource Table Name and Usage
MONITOR.TERMINAL	MTERMNL
	Terminals
MONITOR.TRAN	MLOCTRAN
	Local transactions
	MREMTRAN
	Remote transactions
MONITOR.TSQUEUE	MTSQGBL
~~~~	Global temporary storage queues
OPERATE.AIMODEL	AIMODEL
	Autoinstall models
	CRESAIMD
	Describe an instance of an autoinstalled terminal model in a CICS system.
OPERATE.APPLICTN	BUNDLE
	Application bundles
	CRESBUND
	Describe an instance of a bundle in a CICS system.
	CRESXMLT
	Describe an instance of an XMLTRANSFORM resource in a CICS system.
	EVCSPEC
	A CICS resource object that provides information about capture
	specifications.
	EVNTBIND
	A CICS resource object that provides information about event bindings.
	EVNTGBL
	A CICS resource object that provides information about event processing.
	XMLTRANS
	XMLTRANSFORM resources.
OPERATE.BRFACIL	BRFACIL
	LINK3270 bridge facility
OPERATE.CONNECT	CONNECT
	MRO and ISC over SNA connections
	CRESCONN
	Describe an instance of an MRO or ISC over SNA connection in a CICS
	system.
	CRESIPCN
	Describe an instance of an IPIC connection in a CICS system.
	CRESMODE
	Describe an instance of an LU6.2 modename in a CICS system.
	IPCONN
	IPIC connections
	MODENAME
	LU 6.2 modenames

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Function.Type	Resource Table Name and Usage
OPERATE.DB2DBCTL	CRESDB2C
	Describe an instance of a DB2 connection in a CICS system.
	CRESDB2E
	Describe an instance of a DB2 entry in a CICS system.
	CRESDB2T
	Describe an instance of a DB2 transaction in a CICS system.
	DB2CONN
	DB2 connection
	DB2ENTRY
	DB2 entry DB2TRN
	DB2 transaction
	DBCTLSS
	DBCTL subsystem
	DB2SS DB2 subsystem
	DB2THRD
	DB2 threads
	DB2TRAN
	DB2 transactions
OPERATE.DOCTEMP	CRESDOCT
	Describe an instance of a document template in a CICS system.
	DOCTEMP
	Document templates
OPERATE.ENQMODEL	CRESENQM
	Describe an instance of an ENQ/DEQ model in a CICS system.
	ENQMODEL Enqueue models
OPERATE.ENTJAVA	CLCACHE
	Shared class caches
	CRESJVMS
	Describe an instance of a JVM server in a CICS region.
	EJDJBEAN
	Enterprise beans in a CICS-deployed JAR file
	EJCOBEAN
	Enterprise beans in CorbaServers
	EJCOSE
	CorbaServers
	EJDJAR Deployed JAR files
	JVM Java virtual machines
	JVMPOOL
	JVM pools
	JVMPROF
	JVM profiles
	JVMSERV
	JVM servers
OPERATE.EXIT	CRESGLUE
	Describe an instance of a global user exit in a CICS system.
	CRESTRUE
	Describe an instance of a task-related user exit in a CICS system.
	EXITGLUE Global user exits
	EXITTRUE
	Task-related user exits
	EXTGLORD
	Ordered global user exits
	0

| |

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Resource Table Name and Usage Function.Type OPERATE.FEPI **CRESFECO** Describe an instance of a FEPI connection in a CICS system. CRESFEND Describe an instance of a FEPI node in a CICS system. **CRESFEPO** Describe an instance of a FEPI pool in a CICS system. CRESFETR Describe an instance of a FEPI target in a CICS system. **FEPICONN FEPI** connections **FEPINODE** FEPI nodes **FEPIPOOL** FEPI pools **FEPIPROP** FEPI property sets FEPITRGT FEPI targets OPERATE.FILE **CFDTPOOL** Coupling facility data tables pools **CMDT** Data tables CRESDSNM Describe an instance of a data set in a CICS system. CRESFILE Describe an instance of a file in a CICS system. **DSNAME** Data sets LOCFILE Local files REMFILE Remote files OPERATE.JOURNAL CRESJRNL Describe an instance of a journal in a CICS system. CRESJRNM Describe an instance of a journal name in a CICS system. **JRNLMODL** Journal models **JRNLNAME** System logs and general logs **STREAMNM** MVS log streams OPERATE.PARTNER CRESPART Describe an instance of a partner table in a CICS system. PARTNER CICS partners OPERATE.PROCTYPE CRESPRTY Describe an instance of a process type in a CICS system. PROCTYP Process types OPERATE.PROFILE CRESPROF Describe an instance of a profile in a CICS system. PROFILE CICS profiles

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Function.Type	Resource Table Name and Usage
OPERATE.PROGRAM	CRESPRGM
	Describe an instance of a program in a CICS system.
	PROGRAM
	Programs
	LIBDSN
	LIBRARY data set names
	LIBRARY
	LIBRARY data sets
	RPLLIST
	DFHRPL data sets

Function.Type	Resource Table Name and Usage
OPERATE.REGION	CICSDSA
	Dynamic storage areas
	CICSPAGP
	CICS page pools
	CICS systems
	CICS Systems
	All CICS dynamic storage areas
	CRESSDMP
	Describe an instance of a system dump code in a CICS system.
	CRESTDMP
	Describe an instance of a transaction dump code in a CICS system. DOMSPOOL
	CICS storage domain subpools
	DSPGBL
	Global CICS dispatcher
	DSPMODE
	CICS dispatcher TCB mode
	DSPPOOL
	CICS Dispatcher TCB pool ENQUEUE
	CICS enqueues
	LOADACT
	CICS Loader activity by dynamic storage area
	LOADER
	CICS loader activity
	LSRPBUF
	Buffer usage for LSR pools
	LSRPOOL
	LSR pools MASHIST
	MAS history
	MONITOR
	CICS monitoring and statistics
	MQCON
	WebSphere MQ connection
	MQCONN
	WebSphere MQ connection statistics MQINI
	WebSphere MQ initiation queue
	MVSESTG
	MVS storage element
	MVSTCB
	MVS TCB
	MVSTCBGL
	Global MVS TCB
	MVSWckload manager
	MVS workload manager RECOVERY
	CICS recovery manager
	REQID Timed requests
	SYSDUMP
	System dump codes
	SYSPARM
	System initialization parameters
	TRANCLAS
	Transaction classes TRANDUMP
	Transaction dump codes
364 CICS TS for z/OS 4.	1: RACF Security Guide

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

|

| |

Function.Type	Resource Table Name and Usage
OPERATE.RQMODEL	CRESRQMD
	Describe an instance of a request in a CICS system.
	RQMODEL
	Request models
OPERATE.TASK	EXCI
	HTASK Completed task
	TASK Active tasks
	TASKESTG
	Task storage element
	TASKFILE
	Task file usage
	TASKRMI
	RMI usage by individual task
	TASKTSQ
	TSQ usage by individual task
	TSKSPOLS All task subpools
	TSKSPOOL
	Task storage subpools
	WORKREQ
	EJB work requests
OPERATE.TCPIPS	ATOMSERV
	Atom services
	CRESATOM
	Describe an instance of an Atom service in a CICS system.
	CRESTCPS
	Describe an instance of a TCPIP service in a CICS system.
	HOST URI Host IPFACIL
	IPIC connection sessions
	PIPELINE
	Pipelines
	TCPIPGBL
	TCP/IP global statistics
	TCPIPS
	TCP/IP services
	URIMAP
	URI maps URIMPGBL
	URI map global statistics
	WEBSERV
	Web services
OPERATE.TDQUEUE	CRESTDQ
	Describe an instance of a transient data queue in a CICS system.
	EXTRATDQ
	Extrapartition transient data queues
	INDTDQ
	Indirect transient data queues
	INTRATDQ
	Intrapartition transient data queues
	REMTDQ Remote transient data queues
	Remote transient data queues TDQGBL Intrapartition transient data queue usage

| | |

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Function.Type	Resource Table Name and Usage
OPERATE.TERMINAL	CRESTERM
	Describe an instance of a terminal in a CICS system.
	TERMNL
	Terminals
OPERATE.TRAN	CRESTRAN
	Describe an instance of a transaction in a CICS system.
	LOCTRAN
	Local transactions
	REMTRAN
	Remote transactions
	TASKASSC
	Task association data
OPERATE.TSQUEUE	CRESTSMD
	Describe an instance of a temporary storage queue in a CICS system.
	TSQUEUE
	Temporary storage queues
	TSMODEL
	Temporary storage models
	TSPOOL
	Temporary storage pools
	TSQGBL
	Global temporary storage queues
	TSQSHR
	Shared temporary storage queues
	TSQNAME
	Long temporary storage queues
OPERATE.UOW	UOWDSNF
	Display shunted units of work
	UOWENQ
	Display enqueues for executing units of work
	UOWLINK
	Display links for unit of work
	UOW Display executing units of work
TOPOLOGY.DEF	CSYSGRP
	Create, display, and maintain CICS system groups.
	CSYSDEF
	Create, display, and maintain CICS systems.
	CSGLCGCG
	Describe the link of a CICS system group to an outer system group.
	CSGLCGCS
	Describe the link of a CICS system to a system group.
	MAS Display CICS systems in a CICSplex.
	MASSTAT
	Display CICS systems in a CICSplex by CMAS.
	PERIODEF
	Display period definitions.
	SYSLINK Display information about the links that exist between CICS systems.

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Function.Type	Resource Table Name and Usage
WORKLOAD.DEF	DTRINGRP
Weldteend 221	Display transactions in transaction groups.
	LNKSWSCG
	Describe the link between a CICS system group and a workload
	specification.
	LNKSWSCS
	Describe the link between a CICS system and a workload specification.
	TRANGRP
	Create, display, and maintain transaction groups.
	WLMATAFF
	Display and discard active affinities.
	WLMATGRP
	Display and discard active transaction groups
	WLMATRAN
	Display and discard transaction directory.
	WLMAWAOR
	Display active AORs in a workload.
	WLMAWDEF
	Display and discard active workload definitions.
	WLMAWORK
	Display active workloads.
	WLMAWTOR
	Display active AORs in a workload.
	WLMDEF
	Create, display, and maintain workload definitions.
	WLMGROUP
	Create, display, and maintain workload groups.
	WLMINGRP
	Display workload definitions in groups.
	WLMINSPC
	Display workload groups in workload specifications. WLMSPEC
	Create, display, and maintain workload specifications.

Table 44. Function and type combinations for resources accessible using CICSPlex SM (continued)

Activating simulated CICS security

When you create RACF profiles using the CICSPlex SM resource classes to permit access to the operations and monitoring views, CICSPlex SM determines which views a user can access. However, CICSPlex SM cannot determine if that user is authorized to access the CICS resources represented within the view.

About this task

You can enhance the security provided by your CICSPlex SM profiles by activating *simulated CICS security checking*. Simulated security uses your existing RACF profiles to control access to CICS resources and/or CICS commands. It is available only for the operations and monitor views. When using this combination of profiles, your CICSPlex SM profiles determine which sets of views can be accessed and your CICS resource profiles determine which resources within the view can be accessed. For example, you can create a CICSPlex SM profile that allows a user to issue the file view commands and any associated action commands, and then have CICS simulated security determine which files the user is authorized to access.

To activate or deactivate simulated security checking, use the CSYSDEF view (for a single CICS system) or CPLEXDEF view (for multiple systems). You can indicate whether you want CICS resource checking, CICS command checking, or both, to occur. CICS resource checking controls which resources are displayed in a view. CICS command checking controls what commands can be used within the view. The CSYSDEF and CPLEXDEF views are described in *CICSPlex System Manager Administration*.

To activate or deactivate simulated security checking temporarily for an active CICS system, use the MAS view (as described in *CICSPlex System Manager Administration*).

Note:

- 1. Refer to "Activating security parameters" on page 369 for important information on how the CICSPlex SM and CICS security parameters can affect simulated security.
- **2**. Simulated security involves significantly more processing overhead than using only CICSPlex SM profiles and will have a negative impact on performance.

Exempting users and resources from security checking

There might be certain individuals who do not require security checking. There might also be certain CICS resources that are sufficiently protected by CICSPlex SM profiles and, therefore, do not need to be involved in security checking.

You can exempt these individuals and resources from simulated CICS security checking using the CICSPlex SM CPSMXMP resource class. Exemption bypasses only the simulated CICS security checks, not the basic CICSPlex SM resource checks.

For example, if a user does not have RACF authority to issue the CICS command CEMT INQ FILE, you can enable that user to achieve the same result by creating a profile in the exemption class that allows the user to issue the equivalent CICSPlex SM command LOCFILE.

To create exemption profiles:

- 1. Decide which resource you want to exempt and specify this on the **PERMIT** command. Use the resource name format described in "Specifying CICSPlex SM resource names in profiles" on page 349.
- **2**. Specify the class name CPSMXMP. This RACF class controls exemption from simulated security checking.
- 3. Specify the type of access that you require.
 - If you do not want to bypass security checking, specify ACCESS(NONE).
 - If you want to bypass security checking of INQUIRE level commands, specify ACCESS(READ).
 - If you want to bypass security checking of INQUIRE, SET, and PERFORM level commands, specify ACCESS(UPDATE).
 - If you want to bypass security checking of all commands, including DISCARD level commands, specify ACCESS(ALTER).
- 4. Specify the user or the group that you want the exemptions to apply to.

The following example shows how you could define an exemption profile that allows the individuals comprising the group EYUGRP2 to bypass security checking for all views and action commands associated with the TERMINAL type within the MONITOR function, when the context is EYUPLX01 and the scope is EYUMAS1A:

PERMIT	MONITOR.TERMINAL.EYUPLX01.EYUMAS1A	/*	Resource name	*/+
	CLASS(CPSMXMP)	/*	Class name	*/+
	ACCESS(UPDATE)	/*	Access	*/+
	ID(EYUGRP2)	/*	User or group	*/+
		/*	granted access	*/

Activating security parameters

About this task

To activate security for CICSPlex SM, you must:

- Specify the CICSPlex SM parameter SEC in the EYUPARM data set or member defined in the JCL used to start the CMAS and MAS, as described in the CICS *Transaction Server for z/OS Installation Guide*.
- Specify the CICS parameter SEC= in the CICS system initialization parameters used to start the MAS, as described in the*CICS Transaction Server for z/OS Installation Guide*.

Together these parameters determine what security checking is performed. Table 45 explains the possible parameter combinations.

Table 45. Parameters controlling security checking

CMAS (CICSPlex SM parameter)	MAS (CICS system initialization parameter)	Explanation
SEC(YES)	SEC=YES	Both view selection checking and simulated security checking can occur, depending on the settings in the CICSSYS and CPLEXDEF views. This means that after CICSPlex SM determines whether a user can display a particular view, simulated security determines what information can be provided in the view.
SEC(YES)	SEC=NO	View selection occurs; simulated security checking does not occur even if it is requested in the CICSSYS or CPLEXDEF views. This means that after CICSPlex SM determines whether a user can display a designated view, no simulated security checking is performed to determine what information is to be provided in that view.
SEC(NO)	SEC=YES	CICSPlex SM does not allow the MAS to connect to the CMAS. This prevents a MAS that has requested security from connecting to a CMAS that cannot provide security.

Note: CICSPlex SM honors any of the system initialization parameters XCMD, XDB2, XDCT, XFCT, XHFS, XJCT, XPCT, XPPT, and XRES; that is, CICSPlex SM includes or excludes the designated commands and resources from security checking. For each MAS, you can specify YES, NO, or CLASS NAME for these system initialization parameters. However, for the CMAS, you *must* specify NO for each of these system initialization parameters.

Refreshing RACF profiles for CICSPlex SM

CICSPlex SM uses a cached copy of RACF information in order to reduce unnecessary I/O to the RACF database. When you change a RACF definition, you will, in some situations, need to force the CMAS to refresh the cached information.

Refreshing general resource profiles in the cache About this task

A CMAS requests RACF to create a cached copy of its general resource profiles during initialization:

- During CMAS initialization, global copies of the RACF profiles in the CPSMOBJ (including GCPSMOBJ) and CPSMXMP are created.
- During MAS initialization, the MAS determines which CICS security classes are in use, using the information specified in the XCMD, XDB2, XDCT, XFCT, XJCT, XPCT and XPPT system initialization parameters. This information is passed to the CMAS where it is used to create global copies of the relevant RACF profiles.

Perform the following steps to refresh the general resource profiles in the cache.

Procedure

- 1. To identify the profiles for which global copies exist, issue the RACF command **SETROPTS LIST**. The "GLOBAL=YES RACLIST ONLY" section of the output shows which general resource classes have been globally copied.
- 2. Whenever a change is made to one of these classes (for example, with the **RALTER**, **RDEFINE**, **RDELETE** or **PERMIT** commands), you must refresh the cache. Use the following RACF command:

SETR RACLIST(classname) GENERIC(classname) REFRESH

In a multi-CMAS environment, this command will refresh the cache only on the MVS images that share the same RACF database.

3. If other CMASes run on other MVS images that do not share the same RACF database, repeat the **SETR** command on the other images.

Refreshing user profiles in the cache About this task

A CMAS stores security information for a userid in the cache when it performs a security check. By default, the information is retained in the cache until the user has remained inactive in the CMAS for the time specified by the **SECTIMEOUT** CICSPlex SM parameter, and the CMAS has performed a userid timeout check.

Whenever a change is made to a userid (for example, with the **CONNECT**, **REMOVE**, **ALTUSER**, or **DELUSER** commands), the change becomes visible when the CMAS discards security information for the user form the cache.

Procedure

- To force a CMAS to discard security information from the cache before timeout processing has occurred, use one the following actions.
 - For a single CMAS, use the **RESET USERID** action on the CMAS object.
 - For more than one CMAS, use the **RESET USERID** action on the CMASLIST object.

Both actions are available from the WUI and the API. Perform the action when a user has previously used the CMAS and you do not want to wait for normal timeout processing to occur.

- To force a CMAS to immediately check for userids that are eligible for timeout, use one of the following actions.
 - For a single CMAS, use the **PURGE** action on the CMAS object.
 - For more than one CMAS, use the **PURGE** action on the CMASLIST object.

Both actions are available from the WUI and the API.

CICSPlex SM security checking sequence

A user can issue a single CICSPlex SM command that causes data to be gathered about or an action to be performed against one or more CICS systems comprising a CICSplex. These CICS systems can reside in different MVS images.

When a user issues a request, the request is directed to the CMAS that manages the target CICS system or systems. Figure 40 on page 373 and Figure 41 on page 374 are flowcharts showing the procedure followed by CICSPlex SM to evaluate the security requirements of a request from a user. Here is a description of that procedure:

- 1. CICSPlex SM determines whether CICSPlex SM rules allow the request to be processed.
 - If not, CICSPlex SM terminates the request and issues an error message.
- **2**. CICSPlex SM determines whether simulated CICS security checking is to be performed.
 - If not, processing continues at 9.
- **3**. CICSPlex SM determines whether the user is exempt from simulated CICS security checking.
 - If so, processing continues at 9.
- 4. CICSPlex SM determines whether simulated CICS command checking is to be performed.
 - If not, processing continues at 6.
- 5. CICSPlex SM determines whether the user is allowed to process the command.
 - If not, CICSPlex SM terminates the request and issues an error message.
- 6. CICSPlex SM determines whether the request is an action (not a request for information).
 - If not, processing continues at 9.
- 7. CICSPlex SM determines whether simulated CICS resource checking is to be performed.
 - If not, processing continues at 9.
- 8. CICSPlex SM determines whether the user is allowed access to information about the resource.
 - If not, CICSPlex SM terminates the request and issues an error message.
- 9. CICSPlex SM performs the action or gets the information.
- **10**. CICSPlex SM determines whether the request is an action (not a request for information).
 - If so, CICSPlex SM returns the results of the action.
- 11. CICSPlex SM determines whether simulated CICS security checking is to be performed.

- If not, CICSPlex SM returns the requested information in the appropriate view.
- **12.** CICSPlex SM determines whether the user is exempt from simulated CICS security checking.
 - If so, CICSPlex SM returns the requested information in the appropriate view.
- **13**. CICSPlex SM determines whether simulated CICS resource checking is to be performed.
 - If not, CICSPlex SM returns the requested information in the appropriate view.
- 14. CICSPlex SM determines whether the user is allowed access to information about the resource.
 - If not, CICSPlex SM excludes the requested information from the appropriate view.
- **15.** CICSPlex SM determines whether information for another resource is requested.
 - If so, processing continues at 14.
 - Otherwise, CICSPlex SM returns the requested information in the appropriate view.

No further security checking is required.




Figure 40. Flowchart of CICSPlex SM security checking sequence - part 1




Figure 41. Flowchart of CICSPlex SM security checking sequence - part 2

Chapter 26. Invoking a user-supplied external security manager

CICSPlex SM provides an interface to an external security manager (ESM), which can be user-supplied or can be Resource Access Control Facility (RACF).

On the return from any user-supplied program, CICSPlex SM must always receive control in primary-space translation mode, with the original contents of all access registers restored, and with all general-purpose registers restored (except for those which provide return codes or linkage information). For information about translation modes, refer to the *z*/*Architecture Principles of Operation* manual.

Note: This information is intended primarily for non-RACF users. For information about security processing using RACF, refer to Chapter 25, "Implementing CICSPlex SM security," on page 341.

An overview of the CICSPlex SM ESM interface

CICSPlex SM security uses the RACROUTE macro to get the MVS system authorization facility (SAF) interface to route authorization requests to the ESM.

Usually, if RACF is present, the MVS router passes control to it. However, you can modify the action of the MVS router by invoking the router exit. The router exit can be used, for example, to pass control to a user-supplied or vendor-supplied ESM. If you want to use your own security manager, you must supply an MVS router exit routine.

The control points at which CICSPlex SM issues a RACROUTE macro to route authorization requests are described in "CICSPlex SM security control points" on page 377.

Using the MVS router

SAF provides your installation with centralized control over security processing, by using a system service called the MVS router. The MVS router provides a common system interface for all products providing resource control.

The resource-managing components and subsystems (such as CICSPlex SM) call the MVS router as part of certain decision-making functions in their processing, such as access control checking and authorization-related checking. These functions are called control points. This single SAF interface encourages the use of common control functions shared across products and across systems.

If RACF is available in the system, the MVS router may pass control to the RACF router, which in turn invokes the appropriate RACF function. (The parameter information and the RACF router table, which associates router invocations with RACF functions, determine the appropriate function.) However, before calling the RACF router, the MVS router calls an optional, installation-supplied security-processing exit, if one has been installed.

The MVS router exit

The MVS router provides an optional installation exit that is invoked whether or not RACF is installed and active on the system. If your installation does not use RACF, you can use the router exit to pass control to your own ESM. If you do use RACF, you could use the exit for preprocessing before RACF is invoked.

The MVS router exit routine is invoked whenever CICSPlex SM (or another component of your system) issues a RACROUTE macro. The router passes a parameter list (generated by the RACROUTE macro) to the exit routine. In addition, the exit receives the address of a 150-byte work area.

On entry to the exit routine, register 1 contains the address of the area described in Table 46.

Offset	Length	Description
0	4	Parameter list address: points to the MVS router parameter list. (See "The MVS router parameter list.")
4	4	Work area address: points to a 150-byte work area that the exit can use.

Table 46. Area addressed by register 1, on entry to exit routine

The exit must be named ICHRTX00 and must be located in the link pack area (LPA).

The MVS router parameter list

The MVS router parameter list is generated when the RACROUTE macro is issued, and describes the security processing request by providing the request type.

If the router exit routine exists, the router passes the parameter list to this exit. (If it does not exist, and if RACF is active, the router passes the parameter list to the RACF router.)

You can map the MVS router parameter list using the ICHSAFP macro. Its format is shown in the *MVS/ESA Diagnosis: Data Areas* manual.

Router exit return codes

Your exit routine must return a return code in register 15.

The hexadecimal values of the return code are shown in the following table.

Code	Meaning
0	The exit has completed successfully. Control proceeds to the RACF frontend routine for further security processing and an invocation of RACF.
C8	The exit has completed successfully. The MVS router translates this return code to a router return code of '0' and returns control to the issuer of the RACROUTE macro (CICSPlex SM), bypassing RACF processing. (See the next section.)
CC	The exit has completed successfully. The MVS router translates this return code to a router return code of '4' and returns control to CICSPlex SM, bypassing RACF processing. (See the next section.)

Table 47. MVS router exit return codes

Table 47. MVS router exit return codes (continued)

Code	Meaning
D0	The exit has completed successfully. The MVS router translates this return code to a router return code of '8' and returns control to CICSPlex SM, bypassing RACF processing. (See the next section.)
Other	If the exit routine sets any return code other than those described above, the MVS router returns control directly to CICSPlex SM and passes the untranslated code as the router return code. Further RACF processing is bypassed.

Passing control to a user-supplied ESM

Usually, a caller (such as CICSPlex SM) invokes the MVS router and passes it request type, requester, and subsystem parameters via the RACROUTE exit parameter list. Using these parameters, the MVS router calls the router exit which, on completing its processing, passes a return code to the router.

If the return code is '0', the router invokes RACF. RACF reports the result of that invocation to the router by entering return and reason codes in register 15 and register 0 respectively. The router converts the RACF return and reason codes to router return and reason codes and passes them to the caller. The router provides additional information to the caller by placing the unconverted RACF return and reason codes in the first and second words of the router input parameter list.

If your installation does not use RACF, you can make the MVS router exit pass control to an alternative ESM. However, if you do so you must still provide CICSPlex SM with the RACF return and reason codes that it expects to receive. You set the router exit return code, as defined in Table 47 on page 376, so that RACF is not invoked; and you simulate the results of a RACF invocation by coding the exit so that it places the RACF return and reason codes in the first and second fullwords of the router input parameter list. RACF return and reason codes are documented in the *z/OS MVS Assembler Programming Reference*.

CICSPlex SM security control points

All RACROUTE macros are issued from a CMAS. Macros required to support simulated CICS security checking are issued from the CMAS to which the target MAS is connected.

The following list summarizes the RACROUTE macros used by CICSPlex SM to invoke the ESM, and the control points at which they are issued.

RACROUTE

The "front end" to the macros described below, it invokes the MVS router. If RACF is not present on the system, RACROUTE can route to an alternative ESM, via the MVS router exit.

RACROUTE REQUEST=VERIFY

Issued at user signon (with the parameter ENVIR=CREATE), and at user sign-off (with parameter ENVIR=DELETE) to a CMAS. For ISPF end-user interface requests, signon calls are made during window creation in the CMAS that supports the named context. Sign-off calls are made when the window is closed. This macro creates or destroys an access control environment element (ACEE). It is issued at the following CICSPlex SM CMAS control points:

ISPF end-user interface user connection to a CMAS API CONNECT thread creation Single system image command routing ISPF end-user interface user disconnect from a CMAS API DISCONNECT thread termination

RACROUTE REQUEST=FASTAUTH

Issued during resource checking, on behalf of a user who is identified by an ACEE. It is the high-performance form of REQUEST=AUTH, using in-storage resource profiles, and is issued at the following CICSPlex SM CMAS control points:

Simulated CICS security checking View selection / API security

RACROUTE REQUEST=AUTH

This is a higher path length form of resource checking and is issued during CAS / PLEXMGR security checking. It may also be called to perform logging and auditing after a REQUEST=FASTAUTH.

RACROUTE REQUEST=LIST

Issued to create and delete the in-storage profile lists needed by REQUEST=FASTAUTH. (One REQUEST=LIST macro is required for each resource class.) It is issued at the following CICSPlex SM CMAS control points: When CICSPlex SM security is being initialized for a MAS When the CMAS or CMASD security action command (SEC) is issued.

For a detailed description of these macros, see the *z*/OS Security Server RACF Macros and Interfaces manual.

Chapter 27. Example tasks: security

The following information provides examples of typical security setup tasks that you can use as a model for your own.

Here are some general points that apply to all of the RACF examples:

- Each RACF command shown in these task examples must be issued once against every RACF database in your CICSPlex SM configuration. So, if there are two unconnected RACF databases, one on MVS1 and one on MVS2, each RACF command must be issued twice (once on each system).
- In all of the RACF command examples, strings in lowercase must be replaced by values suitable for your own enterprise. For example, you must replace the string admin_user with the USERID of the administrator responsible for security of the relevant CICSPlex SM resources.
- All of the RACF task examples use the enhanced generic naming facility (**) of RACF. If you do not use this convention at your enterprise, see the RACF documentation for information about creating equivalent profiles.
- Operations and administration RACF groups have been used in these examples: we recommend that you create such groups.

The first example describes creating some RACF profiles to protect all CICSPlex SM functions and resources. The next step is to permit access selectively to particular users of particular resources.

Example: Protecting all CICSPlex SM resources

To create the RACF profile to protect all CICSPlex SM resources, do the following:

1. Ensure that the CPSMOBJ class is active and that generic profiles can be defined:

SETROPTS CLASSACT(CPSMOBJ) GENERIC(CPSMOBJ)

2. Create a RACF profile to protect all views and action commands for all CICSPlex SM functions:

RDEF CPSMOBJ ** UACC(NONE) OWNER(admin group) NOTIFY(admin user)

This command defines a profile (**) that RACF treats as matching all CPSMOBJ resource entity names, and which therefore protects all CICSPlex SM resources; it also specifies that admin_user is to be notified of any violations.

3. The next step is very similar to Step 2: we define one RACF profile for each CICSplex in the configuration. Each profile will protect all CICSPlex SM functions and resources for that CICSplex. The purpose of doing this is to give you more flexibility in granting access to CICSplex-specific resources. In this example, we have two CICSplexes, and so create two RACF profiles:

```
RDEF CPSMOBJ *.*.PLXPROD1.* UACC(NONE) OWNER(admin_group) +
    NOTIFY(admin_user)
RDEF CPSMOBJ *.*.PLXPROD2.* UACC(NONE) OWNER(admin_group) +
    NOTIFY(admin_user)
```

Note that you can't replace Step 2 with multiple CICSplex-specific profiles: such profiles won't necessarily protect CICSplexes that you create later, nor can they protect CICSPlex SM functions whose context is the CMAS rather than the CICSplex. For example, the CONFIG views would be left unprotected if you didn't also perform Step 2.

4. In Step 3 on page 379 we protected all CICSPlex SM functions and resources at the CICSplex level. In this step, we're going to define profiles to control access to the CICSPlex SM CONFIG and TOPOLOGY definition functions, so that we can selectively permit any "special" users, such as administrators, the access they need. (Anyone who has update access to these two functions can alter the CICSplex configuration, and so access must be limited.)

RDEF CPSMOBJ CONFIG.DEF.** UACC(NONE) OWNER(admin_group)
RDEF CPSMOBJ TOPOLOGY.DEF.** UACC(NONE) OWNER(admin_group)

Now that we've controlled access to CICSPlex SM functions and resources, we can begin to grant access to particular users or groups of users.

Example: Giving CICSPlex SM operators appropriate authorizations

CICSPlex SM operators need access, at least, to all of the operations views. In this example, we'll show you how to give CICSPlex SM operators update access to all operations views and read access to the monitoring views. This will allow operators to look at monitor data, but not to create or change monitor definitions.

1. Give CICSPlex SM operators update access to the OPERATE views:

RDEF CPSMOBJ OPERATE.** OWNER(admin_group) UACC(NONE) PE OPERATE.** CLASS(CPSMOBJ) ID(ops_group) A(UPDATE)

2. Give CICSPlex SM operators read access to the MONITOR views:

RDEF CPSMOBJ MONITOR.** UACC(NONE) OWNER(admin_group) PE MONITOR.** CLASS(CPSMOBJ) ID(ops_group) A(READ)

In both steps, you can see that we begin by creating a RACF profile to protect the resource, and then grant access to users in group ops_group.

Example: Giving a user read access to all transactions on MVS system A

In this example, we show you how to give user PAYUSR1 read access to all transactions running on CICS systems on MVS system A.

In the example, we have three CICS systems (say, CICSAA01, CICSAA02, and CICSAA03) which all belong to CICSplex PLXPROD1.

1. Define the appropriate RACF profile:

 Give user PAYUSR1 read access to all transactions on MVS system A: PE OPERATE.TRAN.PLXPROD1.CICSAA0* CLASS(CPSMOBJ) I(PAYUSR1) A(READ)
 Part 10. Appendixes

Appendix A. National Language

This section contains the language codes with which the user can specify a preferred language if that language is defined in their CICS system.

Specify a language request is specified in the following RACF command: ALTUSER userid LANGUAGE(PRIMARY(language-code) SECONDARY(language-code))

For PRIMARY or SECONDARY, you can specify one of the language codes under "IBM code" in Table 48.

CICS attempts to use the PRIMARY language for a user if it corresponds to a language suffix in the NATLANG system initialization parameter. Otherwise it attempts to use the SECONDARY language. If neither the PRIMARY nor the SECONDARY language corresponds to a NATLANG value, the language must be provided from elsewhere. See "Obtaining CICS-related data at signon" on page 76.

Note: CICS ignores the RACF default national language defined by the command: SETROPTS LANGUAGE(PRIMARY(...) SECONDARY(...))

In CICS, you can use only the languages listed in Table 48. Languages other than ENU, CHNS, and JPN are available only if you provide translated message tables for them, using the message editing utility program, and then specify the CICS language suffix in the NATLANG system initialization parameter. See the CICS Operations and Utilities Guide for information on creating translated message tables.

Suffix	IBM Code	Language name
А	ENG	United Kingdom English
В	РТВ	Brazilian Portuguese
С	CHS	Simplified Chinese
D	DAN	Danish
Е	ENU	US English
F	FRA	French
G	DEU	German
Н	KOR	Korean
Ι	ITA	Italian
J	ISL	Icelandic
K	JPN	Japanese
L	BGR	Bulgarian
М	MKD	Macedonian
N	NOR	Norwegian
0	ELL	Greek
Р	PTG	Portuguese
Q	ARA	Arabic
R	RUS	Russian

Table 48. CICS language suffixes

Suffix	IBM Code	Language name
S	ESP	Spanish
Т	CHT	Traditional Chinese
U	UKR	Ukrainian
V	SVE	Swedish
W	FIN	Finnish
Х	HEB	Hebrew
Y	SHC	Serbo-Croatian (Cyrillic)
Z	THA	Thai
1	BEL	Byelorussian
2	CSY	Czech
3	HRV	Croatian
4	HUN	Hungarian
5	PLK	Polish
6	ROM	Romanian
7	SHL	Serbo-Croatian (Latin)
8	TRK	Turkish
9	NLD	Dutch

Table 48. CICS language suffixes (continued)

Appendix B. Resource and command check cross reference

Use this cross reference to check commands against resources.

Table 49. Resource and command check cross reference

EXEC CICS COMMAND	RESOURCE CHECK			CHECK CLASS=XCMD	
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE
ABEND					
ACQUIRE				UPDATE	TERMINAL
ACQUIRE FOR BTS	XFCT	UPDATE	BTS REPOSITORY FILE		
See note 9 on page 398					
ADDRESS					
ALLOCATE					
ASKTIME					
BIF DEEDIT					
BIF DIGEST					
BUILD ATTACH					
CANCEL	XPCT	READ	TRANSID		
See note 1 on page 397					
CANCEL FOR BTS	XFCT	UPDATE	BTS REPOSITORY FILE		
CHANGE PASSWORD					
CHANGE TASK					
COLLECT STATISTICS				READ	STATISTICS
COLLECT STATISTICS FILE	XFCT	READ	FILE	READ	STATISTICS
COLLECT STATISTICS JOURNALNAME	ХЈСТ	READ	JOURNAL	READ	STATISTICS
COLLECT STATISTICS JOURNALNUM	ХЈСТ	READ	JOURNAL	READ	STATISTICS
COLLECT STATISTICS PROGRAM	XPPT	READ	PROGRAM	READ	STATISTICS
COLLECT STATISTICS TDQUEUE	XDCT	READ	TDQUEUE	READ	STATISTICS
COLLECT STATISTICS TRANSACTION	ХРСТ	READ	TRANSID	READ	STATISTICS
CONNECT PROCESS					
CONVERSE					
CREATE ATOMSERVICE	XRES	ALTER	ATOMSERVICE.resource_name	ALTER	ATOMSERVICE
CREATE BUNDLE	XRES	ALTER	BUNDLE.resource_name	ALTER	BUNDLE

Table 49. Resource and command check cross reference (continued)

EXEC CICS COMMAND	RESOURCE CHECK			CHECK CLASS=XCMD	
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE
CREATE CONNECTION				ALTER	CONNECTION
See note 2 on page 397					
CREATE CORBASERVER				ALTER	CORBASERVER
CREATE DB2CONN		ALTER			DB2CONN
See note 3 on page 397					
CREATE DB2ENTRY	XDB2	ALTER	DB2ENTRY	ALTER	DB2ENTRY
See note 3 on page 397					
CREATE DB2TRAN	XDB2	ALTER	DB2TRAN	ALTER	DB2TRAN
See note 3 on page 397 CREATE DJAR				ALTER	DJAR
CREATE	XRES	ALTER	DOCTEMPLATE.resource_nam		DOCTEMPLATE
DOCTEMPLATE	ARES	ALIEK	DOCTEMPLATE.resource_num	ALIEK	DOCTEMPLATE
CREATE ENQMODEL				ALTER	ENQMODEL
CREATE FILE	XFCT	ALTER	FILE	ALTER	FILE
CREATE IPCONN				ALTER	IPCONN
CREATE JOURNALMODEL				ALTER	JOURNALMODEL
CREATE JVMSERVER	XRES	ALTER	JVMSERVER.resource_name	ALTER	JVMSERVER
CREATE LSRPOOL				ALTER	LSRPOOL
CREATE LIBRARY				ALTER	LIBRARY
CREATE MAPSET	XPPT	ALTER	MAPSET	ALTER	MAPSET
CREATE MQCONN				ALTER	MQCONN
CREATE PARTITIONSET	XPPT	ALTER	PARTITIONSET	ALTER	PARTITIONSET
CREATE PIPELINE				ALTER	PIPELINE
CREATE PARTNER				ALTER	PARTNER
CREATE PROCESSTYPE				ALTER	PROCESSTYPE
See note 10 on page 398					
CREATE PROFILE				ALTER	PROFILE
CREATE PROGRAM	XPPT	ALTER	PROGRAM	ALTER	PROGRAM
CREATE REQUESTMODEL				ALTER	REQUESTMODEL
CREATE SESSIONS				ALTER	SESSIONS
See note 3 on page 397					
CREATE TCPIPSERVICE				ALTER	TCPIPSERVICE

Table 49. Resource and command check cross reference (continued)

EXEC CICS COMMAND	RESOURCE CHECK			CHEC	CHECK CLASS=XCMD	
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE	
CREATE TDQUEUE	XDCT	ALTER	TDQUEUE	ALTER	TDQUEUE	
See note 3 on page 397						
CREATE TERMINAL				ALTER	TERMINAL	
See note 3 on page 397						
CREATE TRANCLASS				ALTER	TCLASS	
CREATE TRANSACTION	ХРСТ	ALTER	TRANSID	ALTER	TRANSACTION	
CREATE TSMODEL				ALTER	TSMODEL	
CREATE TYPETERM				ALTER	TYPETERM	
CREATE URIMAP				ALTER	URIMAP	
CREATE WEBSERVICE				ALTER	WEBSERVICE	
CSD ADD				UPDATE	CSD	
CSD ALTER				UPDATE	CSD	
CSD APPEND				UPDATE	CSD	
CSD COPY				UPDATE	CSD	
CSD DEFINE				UPDATE	CSD	
CSD DELETE				UPDATE	CSD	
CSD DISCONNECT				READ	CSD	
CSD ENDBRGROUP				READ	CSD	
CSD ENDBRLIST				READ	CSD	
CSD ENDBRRSRCE				READ	CSD	
CSD GETNEXTGROUP				READ	CSD	
CSD GETNEXTLIST				READ	CSD	
CSD GETNEXTRSRCE				READ	CSD	
CSD INQUIREGROUP				READ	CSD	
CSD INQUIRELIST				READ	CSD	
CSD INQUIRERSRCE				READ	CSD	
CSD INSTALL				ALTER	CSD	
CSD LOCK				UPDATE	CSD	
CSD REMOVE				UPDATE	CSD	
CSD RENAME				UPDATE	CSD	
CSD STARTBRGROUP				READ	CSD	
CSD STARTBRLIST				READ	CSD	
CSD STARTBRRSRCE				READ	CSD	
CSD UNLOCK				UPDATE	CSD	
CSD USERDEFINE				UPDATE	CSD	

Table 49. Resource and command check cross reference (continued)

EXEC CICS COMMAND		RESO	URCE CHECK	CHEC	CHECK CLASS=XCMD	
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE	
DEFINE ACTIVITY	XFCT	UPDATE	BTS REPOSITORY FILE			
See notes 7 on page 398 and 9 on page 398						
DEFINE PROCESS	XFCT	UPDATE	BTS REPOSITORY FILE			
See notes 7 on page 398 and 9 on page 398						
DELAY						
DELETE	XFCT	UPDATE	FILE			
DELETE ACTIVITY	XFCT	UPDATE	BTS REPOSITORY FILE			
See note 9 on page 398						
DELETEQ TD	XDCT	UPDATE	TDQUEUE			
DELETEQ TS	XTST	UPDATE	TSQUEUE			
See note 4 on page 398						
DEQ						
DISABLE PROGRAM	XPPT	UPDATE	PROGRAM	UPDATE	EXITPROGRAM	
DISCARD ATOMSERVICE	XRES	ALTER	ATOMSERVICE.resource_name	ALTER	ATOMSERVICE	
DISCARD AUTINSTMODEL				ALTER	AUTINSTMODEL	
DISCARD BUNDLE	XRES	ALTER	BUNDLE.resource_name	ALTER	BUNDLE	
DISCARD CONNECTION						
DISCARD CORBASERVER				ALTER	CORBASERVER	
DISCARD DB2CONN				ALTER	DB2CONN	
DISCARD DB2ENTRY	XDB2	ALTER	DB2ENTRY	ALTER	DB2ENTRY	
DISCARD DB2TRAN	XDB2	ALTER	DB2TRAN	ALTER	DB2TRAN	
DISCARD DJAR				ALTER	DJAR	
DISCARD DOCTEMPLATE	XRES	ALTER	DOCTEMPLATE.resource_name	ALTER	DOCTEMPLATE	
DISCARD ENQMODEL				ALTER	ENQMODEL	
DISCARD EVENTBINDING	XRES	ALTER	EVENTBINDING.resource_nam		EVENTBINDING	
DISCARD FILE	XFCT	ALTER	FILE	ALTER	FILE	
DISCARD IPCONN				ALTER	IPCONN	
DISCARD JOURNALMODEL				ALTER	JOURNALMODEL	
DISCARD JOURNALNAME	XJCT	ALTER	JOURNAL	ALTER	JOURNALNAME	
DISCARD JVMSERVER	XRES	ALTER	JVMSERVER.resource_name	ALTER	JVMSERVER	

|

L

T

Table 49. Resource an	d command check	cross reference	(continued)
-----------------------	-----------------	-----------------	-------------

I

EXEC CICS COMMAND		RESO	URCE CHECK	CHECK CLASS=XCMD		
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE	
DISCARD LIBRARY				ALTER	LIBRARY	
DISCARD MQCONN				ALTER	MQCONN	
DISCARD PARTNER				ALTER	PARTNER	
DISCARD PIPELINE				ALTER	PIPELINE	
DISCARD PROCESSTYPE				ALTER	PROCESSTYPE	
See note 10 on page 398						
DISCARD PROFILE				ALTER	PROFILE	
DISCARD PROGRAM	XPPT	ALTER	PROGRAM	ALTER	PROGRAM	
DISCARD REQUESTMODEL				ALTER	REQUESTMODEL	
DISCARD TCPIPSERVICE				ALTER	TCPIPSERVICE	
DISCARD TDQUEUE	XDCT	ALTER	TDQUEUE	ALTER	TDQUEUE	
DISCARD TERMINAL				ALTER	TERMINAL	
DISCARD TRANCLASS				ALTER	TCLASS	
DISCARD FRANSACTION	XPCT	ALTER	TRANSID	ALTER	TRANSACTION	
DISCARD TSMODEL				ALTER	TSMODEL	
DISCARD URIMAP				ALTER	URIMAP	
DISCARD WEBSERVICE				ALTER	WEBSERVICE	
DOCUMENT CREATE	XRES	READ	DOCTEMPLATE.resource_nam	ę		
DOCUMENT INSERT	XRES	READ	DOCTEMPLATE.resource_name	ę		
			See note 13			
DUMP TRANSACTION	VDDT		DROCRAN			
ENABLE PROGRAM	XPPT	UPDATE	PROGRAM	UPDATE	EXITPROGRAM	
See note 5 on page 398						
ENQ						
ENTER TRACENUM						
EXTRACT						
EXTRACT EXIT	XPPT	READ	PROGRAM	UPDATE	EXITPROGRAM	
EXTRACT STATISTICS				READ	STATISTICS	
FEPI					FEPI	
FORMATTIME						
FREE						
FREEMAIN						
GDS						

Table 49. Resource and command check cross reference (continued)

EXEC CICS COMMAND	RESOURCE CHECK			CHECK CLASS=XCMD	
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE
GETMAIN					
HANDLE ABEND PROGRAM	XPPT	READ	PROGRAM		
HANDLE AID					
HANDLE CONDITION					
IGNORE CONDITION					
INQUIRE ASSOCIATION				READ	ASSOCIATION
INQUIRE ACTIVITYID	XFCT	READ	BTS REPOSITORY FILE		
See note 9 on page 398					
INQUIRE ATOMSERVICE	XRES	READ	ATOMSERVICE.resource_name	READ	ATOMSERVICE
INQUIRE AUTINSTMODEL				READ	AUTINSTMODEL
INQUIRE AUTOINSTALL				READ	AUTOINSTALL
INQUIRE BEAN				READ	BEAN
INQUIRE BRFACILITY				READ	BRFACILITY
INQUIRE BUNDLE	XRES	READ	BUNDLE.resource_name	READ	BUNDLE
INQUIRE BUNDLEPART	XRES	READ	BUNDLE.resource_name	READ	BUNDLEPART
INQUIRE CAPTURESPEC	XRES	READ	EVENTBINDING.resource_nam	ıÆEAD	CAPTURESPEC
INQUIRE CFDTPOOL				READ	CFDTPOOL
INQUIRE CLASSCACHE				READ	CLASSCACHE
INQUIRE CONNECTION				READ	CONNECTION
INQUIRE CORBASERVER				READ	CORBASERVER
INQUIRE CONTAINER	XFCT	READ	BTS REPOSITORY FILE		
See note 9 on page 398					
INQUIRE DB2CONN				READ	DB2CONN
INQUIRE DB2ENTRY	XDB2	READ	DB2ENTRY	READ	DB2ENTRY
INQUIRE DB2TRAN	XDB2	READ	DB2TRAN	READ	DB2TRAN
INQUIRE DELETSHIPPED				READ	DELETSHIPPED
INQUIRE DJAR				READ	DJAR
INQUIRE DOCTEMPLATE	XRES	READ	DOCTEMPLATE.resource_name		DOCTEMPLATE
INQUIRE DSNAME				READ	DSNAME

Table 49.	Resource	and	command	check	cross	reference	(continued)
-----------	----------	-----	---------	-------	-------	-----------	-------------

EXEC CICS COMMAND	RESOURCE CHECK			CHECK CLASS=XCMD		
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE	
INQUIRE DUMPDS				READ	DUMPDS	
INQUIRE ENQMODEL				READ	ENQMODEL	
INQUIRE EXCI				READ	EXCI	
INQUIRE EVENT	XFCT	READ	BTS REPOSITORY FILE			
See note 9 on page 398						
INQUIRE EVENTBINDING	XRES	READ	EVENTBINDING.resource_nam	IREAD	EVENTBINDING	
INQUIRE EVENTPROCESS	XRES	READ	EVENTPROCESS.resource_nam	ÆEAD	EVENTPROCESS	
INQUIRE EXITPROGRAM	XPPT	READ	PROGRAM	READ	EXITPROGRAM	
INQUIRE FILE	XFCT	READ	FILE	READ	FILE	
INQUIRE HOST				READ	HOST	
INQUIRE IPCONN				READ	IPCONN	
INQUIRE IRC				READ	IRC	
INQUIRE JOURNALMODEL				READ	JOURNALMODEL	
INQUIRE JOURNALNAME	ХЈСТ	READ	JOURNAL	READ	JOURNAL	
INQUIRE JVM				READ	JVM	
INQUIRE JVMPOOL				READ	JVMPOOL	
INQUIRE JVMPROFILE				READ	JVMPROFILE	
INQUIRE JVMSERVER	XRES	READ	JVMSERVER.resource_name	READ	JVMSERVER	
INQUIRE LIBRARY				READ	LIBRARY	
INQUIRE MODENAME				READ	MODENAME	
INQUIRE MONITOR				READ	MONITOR	
INQUIRE MQCONN				READ	MQCONN	
INQUIRE MQINI	XRES	READ	MQINI.resource_name	READ	MQINI	
INQUIRE MVSTCB				READ	MVSTCB	
INQUIRE NETNAME				READ	TERMINAL	
INQUIRE PARTNER				READ	PARTNER	
INQUIRE PIPELINE				READ	PIPELINE	
INQUIRE PROCESS	XFCT	READ	BTS REPOSITORY FILE			
See note 9 on page 398						
INQUIRE PROCESSTYPE	XPTT			READ	PROCESSTYPE	
See note 10 on page 398						
INQUIRE PROFILE				READ	PROFILE	
INQUIRE PROGRAM	XPPT	READ	PROGRAM	READ	PROGRAM	

Table 49. Resource and command check cross reference (continued)

EXEC CICS COMMAND		RESO	URCE CHECK	CHEC	CHECK CLASS=XCMD		
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE		
INQUIRE REQID	ХРСТ	READ	TRANSID	READ	REQID		
See note 8 on page 398							
INQUIRE REQUESTMODEL				READ	REQUESTMODEL		
INQUIRE RRMS				READ	RRMS		
INQUIRE STATISTICS				READ	STATISTICS		
INQUIRE STORAGE				READ	STORAGE		
INQUIRE STREAMNAME				READ	STREAMNAME		
INQUIRE SUBPOOL				READ	SUBPOOL		
INQUIRE SYSDUMPCODE				READ	SYSDUMPCODE		
INQUIRE SYSTEM				READ	SYSTEM		
INQUIRE TASK				READ	TASK		
INQUIRE TCLASS				READ	TCLASS		
INQUIRE TCPIP				READ	TCPIP		
INQUIRE TCPIPSERVICE				READ	TCPIPSERVICE		
INQUIRE TDQUEUE	XDCT	READ	TDQUEUE	READ	TDQUEUE		
INQUIRE TERMINAL				READ	TERMINAL		
INQUIRE TIMER	XFCT	READ	BTS REPOSITORY FILE				
See note 9 on page 398							
INQUIRE TRACEDEST				READ	TRACEDEST		
INQUIRE TRACEFLAG				READ	TRACEFLAG		
INQUIRE TRACETYPE				READ	TRACETYPE		
INQUIRE TRANCLASS				READ	TCLASS		
INQUIRE TRANDUMPCODE				READ	TRANDUMPCODE		
INQUIRE TRANSACTION	ХРСТ	READ	TRANSID	READ	TRANSACTION		
INQUIRE TSMODEL				READ	TSMODEL		
INQUIRE TSPOOL				READ	TSPOOL		
INQUIRE TSQUEUE	XTST	READ	TSQUEUE	READ	TSQUEUE		
See note 4 on page 398							
INQUIRE TSQNAME	XTST	READ	TSQNAME	READ	TSQUEUE		
See note 4 on page 398							
INQUIRE UOW				READ	UOW		
INQUIRE UOWDSNFAIL				READ	UOWDSNFAIL		

Table 49	Resource	and	command	check	cross	reference	(continued)
----------	----------	-----	---------	-------	-------	-----------	-------------

EXEC CICS COMMAND		RESO	URCE CHECK	CHECK CLASS=XCMD	
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE
INQUIRE UOWENQ				READ	UOWENQ
INQUIRE UOWLINK				READ	UOWLINK
INQUIRE URIMAP				READ	URIMAP
INQUIRE VTAM				READ	VTAM
INQUIRE WEB				READ	WEB
INQUIRE WEBSERVICE				READ	WEBSERVICE
INQUIRE WORKREQUEST				READ	WORKREQUEST
INQUIRE XMLTRANSFORM	XRES	READ	XMLTRANSFORM.resource_na	nREAD	XMLTRANSFORM
ISSUE					
LINK	XPPT	READ	PROGRAM		
LINK ACQPROCESS See note 9 on page 398	XFCT	UPDATE	BTS REPOSITORY FILE		
LINK ACTIVITY / ACQACTIVITY	XFCT	UPDATE	BTS REPOSITORY FILE		
See note 9 on page 398					
LOAD	XPPT	READ	PROGRAM		
MONITOR					
PERFORM CLASSCACHE				UPDATE	CLASSCACHE
PERFORM CORBASERVER				UPDATE	CORBASERVER
See note 12 on page 398					
PERFORM DELETSHIPPED				UPDATE	DELETSHIPPED
PERFORM DJAR				UPDATE	DJAR
PERFORM DUMP				UPDATE	DUMP
PERFORM PIPELINE				UPDATE	PIPELINE
PERFORM RESETTIME				UPDATE	RESETTIME
PERFORM SECURITY				UPDATE	SECURITY
PERFORM SHUTDOWN				UPDATE	SHUTDOWN
PERFORM STATISTICS				UPDATE	STATISTICS
POINT					
POP HANDLE					
POST					
PURGE MESSAGE					
PUSH HANDLE					

Table 49. Resource and command check cross reference (continued)

EXEC CICS COMMAND		RESO	URCE CHECK	CHEC	CK CLASS=XCMD
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE
QUERY SECURITY					
See note 6 on page 398					
READ	XFCT	READ	FILE		
READ PREV					
See note 5 on page 398					
READ NEXT					
See note 5 on page 398					
READQ TD	XDCT	UPDATE	TDQUEUE		
READQ TS	XTST	READ	TSQUEUE		
	A131				
See note 4 on page 398					
RECEIVE					
RELEASE	XPPT	READ	PROGRAM		
RESET ACTIVITY	XFCT	UPDATE	BTS REPOSITORY FILE		
See note 9 on page 398					
RESET ACQPROCESS	XFCT	UPDATE	BTS REPOSITORY FILE		
See note 9 on page 398					
RESETBR					
See note 5 on page 398					
RESYNC ENTRYNAME				UPDATE	EXITPROGRAM
RETRIEVE					
RETURN / RETURN ENDACTIVITY	XFCT	UPDATE	BTS REPOSITORY FILE		
See note 9 on page 398 and 11 on page 398					
REWRITE	XFCT	UPDATE	FILE		
ROUTE					
RUN	XFCT	UPDATE	BTS REPOSITORY FILE		
See note 9 on page 398 and 11 on page 398					
RUN / ASYNCH SYNC	XFCT	UPDATE	DFHLRQ FILE		
See note 9 on page 398					
SEND					
SET ATOMSERVICE	XRES	UPDATE	ATOMSERVICE.resource_name	UPDATE	ATOMSERVICE
SET AUTOINSTALL				UPDATE	AUTOINSTALL
SET BRFACILITY				UPDATE	BRFACILITY
SET BUNDLE	XRES	UPDATE	BUNDLE.resource_name	UPDATE	BUNDLE

Т

L

Table 49. Resource	and command	check cross	reference	(continued)
				(

EXEC CICS COMMAND		RESO	URCE CHECK	CHEC	CK CLASS=XCMD
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE
SET CLASSCACHE				UPDATE	CLASSCACHE
SET CONNECTION				UPDATE	CONNECTION
SET CORBASERVER				UPDATE	CORBASERVER
SET DB2CONN				UPDATE	DB2CONN
SET DB2ENTRY	XDB2	UPDATE	DB2ENTRY	UPDATE	DB2ENTRY
SET DB2TRAN	XDB2	UPDATE	DB2TRAN	UPDATE	DB2TRAN
SET DELETSHIPPED				UPDATE	DELETSHIPPED
SET DOCTEMPLATE	XRES	UPDATE	DOCTEMPLATE.resource_nam	UPDATE	DOCTEMPLATE
SET DSNAME				UPDATE	DSNAME
SET DUMPDS				UPDATE	DUMPDS
SET ENQMODEL				UPDATE	ENQMODEL
SET EVENTBINDING	XRES	UPDATE	EVENTBINDING.resource_nam	UPDATE	EVENTBINDING
SET EVENTPROCESS	XRES	UPDATE	EVENTPROCESS.resource_nam	d UPDATE	EVENTPROCESS
SET FILE	XFCT	UPDATE	FILE	UPDATE	FILE
SET HOST				UPDATE	HOST
SET IPCONN				UPDATE	IPCONN
SET IRC				UPDATE	IRC
SET JOURNALNAME	ХЈСТ	UPDATE	JOURNAL	UPDATE	JOURNAL
SET JVMPOOL				UPDATE	JVMPOOL
SET JVMSERVER	XRES	UPDATE	JVMSERVER.resource_name	UPDATE	JVMSERVER
SET LIBRARY				UPDATE	LIBRARY
SET MODENAME				UPDATE	MODENAME
SET MONITOR				UPDATE	MONITOR
SET MQCONN See note 14 on page 398				UPDATE	MQCONN
SET NETNAME				UPDATE	TERMINAL
SET PIPELINE				UPDATE	PIPELINE
SET PROCESSTYPE	XPTT			UPDATE	PROCESSTYPE
See note 10 on page 398					
SET PROGRAM	XPPT	UPDATE	PROGRAM	UPDATE	PROGRAM
SET STATISTICS				UPDATE	STATISTICS
SET SYSDUMPCODE				UPDATE	SYSDUMPCODE
SET SYSTEM				UPDATE	SYSTEM
SET TASK				UPDATE	TASK
SET TCLASS				UPDATE	TCLASS
SET TCPIP				UPDATE	TCPIP
SET TCPIPSERVICE				UPDATE	TCPIPSERVICE

Table 49. Resource and command check cross reference (continued)

EXEC CICS COMMAND		RESO	URCE CHECK	CHEC	CK CLASS=XCMD
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE
SET TDQUEUE	XDCT	UPDATE	TDQUEUE	UPDATE	TDQUEUE
See note 3 on page 397					
SET TERMINAL				UPDATE	TERMINAL
SET TRACEDEST				UPDATE	TRACEDEST
SET TRACEFLAG				UPDATE	TRACEFLAG
SET TRACETYPE				UPDATE	TRACETYPE
SET TRANCLASS				UPDATE	TCLASS
SET TRANDUMPCODE				UPDATE	TRANDUMPCODE
SET TRANSACTION	ХРСТ	UPDATE	TRANSID	UPDATE	TRANSACTION
SET TSQNAME	XTST	UPDATE	TSQUEUE	UPDATE	TSQUEUE
See note 4 on page 398					
SET TSQUEUE	XTST	UPDATE	TSQNAME	UPDATE	TSQUEUE
-	X101				
See note 4 on page 398					
SET UOW				UPDATE	UOW
SET UOWLINK				UPDATE	UOWLINK
SET URIMAP				UPDATE	URIMAP
SET VTAM				UPDATE	VTAM
SET WEB				UPDATE	WEB
SET WEBSERVICE				UPDATE	WEBSERVICE
SET WORKREQUEST				UPDATE	WORKREQUEST
SET XMLTRANSFORM	XRES	UPDATE	XMLTRANSFORM.resource_	_nantePDATE	XMLTRANSFORM
SIGNOFF					
SIGNON					
SPOOLCLOSE					
SPOOLOPEN					
SPOOLREAD					
SPOOLWRITE					
START	ХРСТ	READ	TRANSID		
See note 7 on page 398					
STARTBR	XFCT	READ	FILE		
STARTBROWSE ACTIVITY	XFCT	READ	BTS REPOSITORY FILE		
See note 9 on page 398					
STARTBROWSE CONTAINER (BTS) See note 9 on page 398	XFCT	READ	BTS REPOSITORY FILE		

T

Table 49. Resource and command check cross reference (continued)

EXEC CICS COMMAND		RESO	URCE CHECK	CHECK	CLASS=XCMD
	CLASS	ACCESS	RESOURCE	ACCESS	RESOURCE
STARTBROWSE EVENT	XFCT	READ	BTS REPOSITORY FILE		
See note 9 on page 398					
STARTBROWSE PROCESS	XFCT	READ	BTS REPOSITORY FILE		
See note 9 on page 398					
SUSPEND	XFCT	UPDATE	BTS REPOSITORY FILE		
See note 9 on page 398					
SYNCPOINT					
TCPIP					
UNLOCK					
VERIFY PASSWORD					
WAIT					
WAIT JOURNALNAME	XJCT	READ	JOURNAL		
WAIT JOURNALNUM	XJCT	READ	JOURNAL		
WAITCICS					
WEB					
WRITE	XFCT	UPDATE	FILE		
WRITE JOURNALNAME	ХЈСТ	UPDATE	JOURNAL		
WRITE JOURNALNUM	XJCT	UPDATE	DFHJNN		
WRITE OPERATOR					
WRITEQ TD	XDCT	UPDATE	TDQUEUE		
WRITEQ TS	XTST	UPDATE	TSQUEUE TSQNAME		
See note 4 on page 398					
XCTL	XPPT	READ	PROGRAM		

Note:

- 1. The **CANCEL** command can perform two checks. One check is performed against the transaction specified on the **CANCEL** command. The other check is performed against the transaction associated with the REQID that you are canceling where applicable.
- 2. The **CREATE CONNECTION** command is subject to command security checking when you define a CONNECTION; for example, **CREATE CONNECTION(CON1)** *ATTRIBUTE(...)*. However, when you use the **CREATE CONNECTION COMPLETE** or **CREATE CONNECTION DISCARD** command, no command security checking is performed unless you have been authorized to use **COMPLETE** and **DISCARD** commands. COMPLETE and DISCARD commands can be used only by those authorized to perform **CREATE CONNECTION(CON1)** and **CREATE SESSIONS(SES1)** commands. Otherwise, ILLOGIC is returned.
- 3. An install surrogate user check can also occur.

- 4. A security check is performed when a DFHTST TYPE=SECURITY macro has been coded in the TST with a name that matches the TSname, or, when RDO is in use for TST and TSMODELS, and security is active for the model that matches that queue.
- 5. No security check is performed, because the **STARTBR** command must be issued before this command. A security check is issued on the **STARTBR** command.
- 6. The **QUERY SECURITY** command is not controlled by resource or command checks, but it can cause them to be issued.
- 7. A start surrogate user check can also occur.
- **8**. The resource check for the transid is performed only if the REQID is associated with a transaction.
- 9. CICS BTS API commands.
- **10.** CICS BTS commands that are subject to command security. All other CICS BTS commands are not subject to command-level security.
- 11. Any BTS commands that use timing operands will access the BTS LRQ file.
- **12.** In addition to UPDATE access to the CORBASERVER resource, ALTER access to the associated DJAR resource is required for the **PERFORM CORBASERVER SCAN** command.
- 13. The **EXEC CICS DOCUMENT CREATE** and **INSERT** commands reference document templates using the 48-character name of the template as specified in the TEMPLATENAME attribute of the DOCTEMPLATE resource definition. However, security checking for these commands uses the name of the DOCTEMPLATE resource definition that corresponds to the TEMPLATENAME attribute.
- 14. When command security is active for your CICS region, to use the **EXEC CICS SET MQCONN** command to start or stop the connection to WebSphere MQ users must have authority to use not only the **EXEC CICS SET MQCONN** command, but also the **EXEC CICS EXTRACT EXIT** command. If a user attempts to start or stop the connection without the authority to use the EXEC CICS EXTRACT EXIT command, CICS issues messages DFHXS1111 and DFHMQ0302.

Related tasks:

1

T

T

T

T

"Security using the XRES resource security parameter" on page 87 Use the XRES system initialization parameter to security check the following CICS resources: ATOMSERVICE, BUNDLE, DOCTEMPLATE, EVENTBINDING, JVMSERVER, and XMLTRANSFORM. An example of how to implement resource security for CICS document templates, the DOCTEMPLATE resource, is provided.

Appendix C. The sign-on table migration utility

The sign-on table migration utility, DFHSNMIG, is provided to help you migrate security information defined in an SNT to the CICS segment of a RACF user's profile. For each user entry in the SNT it creates a CLIST of RACF commands, generating either an ADDUSER or an ALTUSER command as appropriate for each SNT user entry.

Because the DFHSNT macro is not supported in CICS TS, you must assemble your SNT using an earlier version of CICS.

DFHSNMIG can be found as an APF-authorized program in CICSTS41.CICS.SDFHAUTH, and must be run from an APF-authorized library. If you invoke the program from TSO, add its name to the list of authorized program names in the AUTHPGM NAMES section in the IKJTSOxx member of SYS1.PARMLIB.

The DFHSNMIG utility creates a CLIST of ADDUSER and ALTUSER commands to define CICS users to RACF. These commands do not specify the default RACF group each user should belong to. You might want to edit the CLIST created by DFHSNMIG to add DFLTGRP information. See "Defining terminal users and user groups to RACF" on page 77 for an example of specifying DFLTGRP on the ADDUSER command.

Figure 42 shows an example sign-on table entry. In this example, OLDUSER is an existing RACF-defined userid, and NEWUSER is a userid that has not previously been defined to RACF. DFHSNT TYPE=(ENTRY, DEFAULT) is a default entry, for which DFHSNMIG will *not* create an entry.

SNT *	DFHSNT	TYPE=INITIAL	
	DFHSNT	TYPE=ENTRY,	*
		USERID=OLDUSER,	*
		OPIDENT=OLD,	*
		OPPRTY=255,	*
		OPCLASS=(1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,17,18,	*
		19,20,21,22,23,24),	*
		NATLANG=K,	*
		XRFSOFF=FORCE	
*			
	DFHSNT	TYPE=ENTRY,	*
		USERID=NEWUSER,	*
		OPIDENT=NEW,	*
		OPPRTY=100,	*
		TIMEOUT=20,	*
		OPCLASS=(10)	
*			
	DEHSNI	TYPE=(ENTRY, DEFAULT),	*
		OPIDENT=XXX,	*
		TIMEOUT=10	
*	DELICAT		
	END	TYPE=FINAL	

Figure 42. Sample sign-on table entry

Figure 43 shows an example of output from DFHSNMIG, which has changed the SNT shown in Figure 42 on page 399 into entries for the RACF database.

	*/
	*/
Migration of DFHSNT. (Created by DFHSNMIG utility.	
This CLIST will add CICS attributes into your RACF	
database. Please note that keywords are for RACF and will not work against earlier versions of RACF	
and will not work against earlier versions of RACF	• */ */
You may need to edit this file before executing the	-
CLIST under a TSO userid that has SPECIAL authorit;	
	,•
ADDUSER: Asks RACF to create a new entry for the us	-
ALTUSER: Adds CICS attributes to an existing RACF	
	*/
Userid – Identifier for user.	*/
LANGUAGE - Preferred language: ENU = English (US)	*/
JPN = Japanese	*/
The CICS attributes are:	*/
OPCLASS - Operator Class	*/
OPIDENT - Operator Identifier	*/
OPPRTY – Operator Priority TIMEOUT – Timeout Value	*/
	*/
XRFSOFF - FORCE or NOFORCE	*/
	*/
Details for OLDU	'
TUSER OLDUSER LANGUAGE(PRIMARY(JPN))	
TUSER OLDUSER LANGUAGE(PRIMARY(JPN)) CICS(
LANGUAGE(PRIMARY(JPN))	7,18,
LANGUAGE(PRIMARY(JPN)) CICS(7,18,
LANGUAGE(PRIMARY(JPN)) CICS(OPCLASS(1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,1 19,20,21,22,23,24) OPIDENT(OLD)	7,18,
LANGUAGE(PRIMARY(JPN)) CICS(OPCLASS(1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,1 19,20,21,22,23,24) OPIDENT(OLD) OPPRTY(255)	7,18,
LANGUAGE(PRIMARY(JPN)) CICS(OPCLASS(1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,1 19,20,21,22,23,24) OPIDENT(OLD) OPPRTY(255) TIMEOUT(0)	7,18,
LANGUAGE(PRIMARY(JPN)) CICS(OPCLASS(1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,1 19,20,21,22,23,24) OPIDENT(OLD) OPPRTY(255) TIMEOUT(0) XRFSOFF(FORCE))	7,18,
LANGUAGE(PRIMARY(JPN)) CICS(OPCLASS(1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,1 19,20,21,22,23,24) OPIDENT(OLD) OPPRTY(255) TIMEOUT(0) XRFSOFF(FORCE))	*/
LANGUAGE(PRIMARY(JPN)) CICS(OPCLASS(1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,1 19,20,21,22,23,24) OPIDENT(OLD) OPPRTY(255) TIMEOUT(0) XRFSOFF(FORCE))	*/ SER */
LANGUAGE(PRIMARY(JPN)) CICS(OPCLASS(1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,12 19,20,21,22,23,24) OPIDENT(OLD) OPPRTY(255) TIMEOUT(0) XRFSOFF(FORCE)) Details for NEWU DUSER NEWUSER	*/ SER */
LANGUAGE(PRIMARY(JPN)) CICS(OPCLASS(1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,12 19,20,21,22,23,24) OPIDENT(OLD) OPPRTY(255) TIMEOUT(0) XRFSOFF(FORCE)) Details for NEWUSER CICS(*/ SER */
LANGUAGE (PRIMARY (JPN)) CICS (OPCLASS (1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,12 19,20,21,22,23,24) OPIDENT (OLD) OPPRTY (255) TIMEOUT (0) XRFSOFF (FORCE)) 	*/ SER */
LANGUAGE (PRIMARY (JPN)) CICS (OPCLASS (1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,12 19,20,21,22,23,24) OPIDENT (OLD) OPPRTY (255) TIMEOUT (0) XRFSOFF (FORCE)) 	*/ SER */
LANGUAGE (PRIMARY (JPN)) CICS (OPCLASS (1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,12 19,20,21,22,23,24) OPIDENT (OLD) OPPRTY (255) TIMEOUT (0) XRFSOFF (FORCE)) 	*/ SER */
LANGUAGE (PRIMARY (JPN)) CICS (OPCLASS (1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,12 19,20,21,22,23,24) OPIDENT (OLD) OPPRTY (255) TIMEOUT (0) XRFSOFF (FORCE)) 	*/ SER */
LANGUAGE (PRIMARY (JPN)) CICS (OPCLASS (1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,12 19,20,21,22,23,24) OPIDENT (OLD) OPPRTY (255) TIMEOUT (0) XRFSOFF (FORCE)) 	*/ SER */
LANGUAGE (PRIMARY (JPN)) CICS (OPCLASS (1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,12) 19,20,21,22,23,24) OPIDENT (OLD) OPPRTY (255) TIMEOUT (0) XRFSOFF (FORCE)) Details for DUSER NEWUSER CICS (OPCLASS (1,10) OPIDENT (NEW) OPPRTY (100) TIMEOUT (20) XRFSOFF (NOFORCE))	*/ SER */ */
LANGUAGE (PRIMARY (JPN)) CICS (OPCLASS (1,2,3,4,5,6,7,8,9,10,11,12,13,14,15,16,12 19,20,21,22,23,24) OPIDENT (OLD) OPPRTY (255) TIMEOUT (0) XRFSOFF (FORCE)) 	*/ SER */ */

Figure 43. Example of output from DFHSNMIG

Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive Armonk, NY 10504-1785 U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation Licensing 2-31 Roppongi 3-chome, Minato-ku Tokyo 106, Japan

The following paragraph does not apply in the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore this statement may not apply to you.

This publication could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Licensees of this program who want to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact IBM United Kingdom Laboratories, MP151, Hursley Park, Winchester, Hampshire, England, SO21 2JN. Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Programming License Agreement, or any equivalent agreement between us.

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at Copyright and trademark information at www.ibm.com/legal/copytrade.shtml.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Microsoft, Windows, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Bibliography

CICS books for CICS Transaction Server for z/OS

General

- CICS Transaction Server for z/OS Program Directory, GI13-0536
- CICS Transaction Server for z/OS What's New, GC34-6994
- CICS Transaction Server for z/OS Upgrading from CICS TS Version 2.3, GC34-6996
- CICS Transaction Server for z/OS Upgrading from CICS TS Version 3.1, GC34-6997
- CICS Transaction Server for z/OS Upgrading from CICS TS Version 3.2, GC34-6998
- CICS Transaction Server for z/OS Installation Guide, GC34-6995

Access to CICS

CICS Internet Guide, SC34-7021

CICS Web Services Guide, SC34-7020

Administration

- CICS System Definition Guide, SC34-6999
- CICS Customization Guide, SC34-7001
- CICS Resource Definition Guide, SC34-7000
- CICS Operations and Utilities Guide, SC34-7002
- CICS RACF Security Guide, SC34-7003
- CICS Supplied Transactions, SC34-7004

Programming

- CICS Application Programming Guide, SC34-7022
- CICS Application Programming Reference, SC34-7023
- CICS System Programming Reference, SC34-7024
- CICS Front End Programming Interface User's Guide, SC34-7027
- CICS C++ OO Class Libraries, SC34-7026
- CICS Distributed Transaction Programming Guide, SC34-7028
- CICS Business Transaction Services, SC34-7029
- Java Applications in CICS, SC34-7025

Diagnosis

- CICS Problem Determination Guide, GC34-7034
- CICS Performance Guide, SC34-7033
- CICS Messages and Codes, SC34-7035
- CICS Diagnosis Reference, GC34-7038
- CICS Recovery and Restart Guide, SC34-7012
- CICS Data Areas, GC34-7014
- CICS Trace Entries, SC34-7013
- CICS Supplementary Data Areas, GC34-7015
- CICS Debugging Tools Interfaces Reference, GC34-7039

Communication

CICS Intercommunication Guide, SC34-7018 CICS External Interfaces Guide, SC34-7019

Databases

CICS DB2 Guide, SC34-7011

CICS IMS Database Control Guide, SC34-7016

CICSPlex SM books for CICS Transaction Server for z/OS

General

CICSPlex SM Concepts and Planning, SC34-7044 CICSPlex SM Web User Interface Guide, SC34-7045

Administration and Management

CICSPlex SM Administration, SC34-7005 CICSPlex SM Operations Views Reference, SC34-7006 CICSPlex SM Monitor Views Reference, SC34-7007 CICSPlex SM Managing Workloads, SC34-7008 CICSPlex SM Managing Resource Usage, SC34-7009 CICSPlex SM Managing Business Applications, SC34-7010

Programming

CICSPlex SM Application Programming Guide, SC34-7030 CICSPlex SM Application Programming Reference, SC34-7031

Diagnosis

CICSPlex SM Resource Tables Reference, SC34-7032 CICSPlex SM Messages and Codes, GC34-7035 CICSPlex SM Problem Determination, GC34-7037

Other CICS publications

The following publications contain further information about CICS, but are not provided as part of CICS Transaction Server for z/OS, Version 4 Release 1.

Designing and Programming CICS Applications, SR23-9692

CICS Application Migration Aid Guide, SC33-0768

CICS Family: API Structure, SC33-1007

CICS Family: Client/Server Programming, SC33-1435

CICS Family: Interproduct Communication, SC34-6853

CICS Family: Communicating from CICS on System/390, SC34-6854

CICS Transaction Gateway for z/OS Administration, SC34-5528

CICS Family: General Information, GC33-0155

CICS 4.1 Sample Applications Guide, SC33-1173

CICS/ESA 3.3 XRF Guide, SC33-0661

Other IBM publications

The following publications contain information about related IBM products.

z/OS Security Server

z/OS Security Server RACF Auditor's Guide, SA22-7684 *z/OS Security Server RACF Command Language Reference*, SA22-7687 *z/OS Security Server RACF Messages and Codes*, SA22-7686 *z/OS Security Server RACF Data Areas*, GA22-7680 *z/OS Security Server RACF Diagnosis Guide*, GA22-7689 *z/OS Security Server RACF General User's Guide*, SA22-7685 *z/OS Security Server RACF Macros and Interfaces*, SA22-7682 *z/OS Security Server RACF Messages and Codes*, SA22-7686 *z/OS Security Server RACF Security Administrator';s Guide,* SA22-7683 *z/OS Security Server Network Authentication Service Administration,* SC24-5926 *z/OS Security Server RACF System Programmer's Guide,* SA22-7681 *z/OS Security Server RACF Security Administrator's Guide,* SA22-7683

Systems Network Architecture (SNA)

SNA Reference: Peer Protocols, SC31-6808

z/OS

z/OS MVS Planning: Operations, SA22-7601 *z/OS MVS System Codes,* SA22-7626 *z/OS MVS Initialization and Tuning Guide,* SA22-7591

z/OS System Secure Sockets Layer

z/OS System Secure Sockets Layer Programming, SC24-5901

Accessibility

Accessibility features help a user who has a physical disability, such as restricted mobility or limited vision, to use software products successfully.

You can perform most tasks required to set up, run, and maintain your CICS system in one of these ways:

- using a 3270 emulator logged on to CICS
- using a 3270 emulator logged on to TSO
- using a 3270 emulator as an MVS system console

IBM Personal Communications provides 3270 emulation with accessibility features for people with disabilities. You can use this product to provide the accessibility features you need in your CICS system.

Index

Special characters

-ESM interface MVS router 375 overview 375 RACROUTE macros 377 * 21 ** (double asterisk)

in data set profile names 21 % 21 47

Α

access allowed incorrectly resolving 331 access authorization levels 89, 97, 108 access control HFS files 106 z/OS UNIX files 105 access lists avoiding with UACC(READ) 83 conditional, for transaction profiles 84 PERMIT command to create 28 ACEE (accessor environment element) (access control environment element) 315 ACICSPCT general resource class 99 activating RACF classes 29 activating security parameters 369 activating user-defined RACF classes 319 ADDUSER command defining the userid for CICS to RACF 39 administration 11 Advanced Encryption Standard encryption algorithm 257 algorithms encryption 257 APPC PEM (password expiration management) APPC PEM (password expiration management) 183 ATTACH security fields 193 benefits 183 buffer size 193 CICS activity 187 data from CICS to PEM client 195 EBCDIC for userids and passwords 193 information on passwords 183 overview of processing 187 permitted userid and password length 193 processing done by CICS PEM server 187 processing required by PEM client 187 PROFILE option 193

APPC PEM (password expiration management) (continued) sample configuration 184 setting up the PEM client 192 sign-on data sent to CICS PEM server 195 sign-on input data sent by PEM client 195 sign-on request, formatting errors 198 sign-on status 183 unsuccessful sign-on with PV 191 using with persistent verification (PV) 187 APPCLU general resource class 24 defining profiles 164 APPL general resource class 24 controlling access to CICS region 51 application program security access authorization levels 103 defining resource classes 102 MCICSPPT general resource class 102 NCICSPPT general resource class 102 QUERY SECURITY command 8, 133 asserted identity authentication 249 ATTACHSEC attribute 224 ATTACHSEC operand 170, 206 IDENTIFY parameter 171 LOCAL parameter 171 MIXIDPE parameter 171 PERSISTENT parameter 171 VERIFY parameter 171 auditing bind security failure 166 requested by CICS on authorization requests 94 second request to RACF to write log data 85 SMF type 80 log records 85 AUTHID surrogate security 116 authorization failures access is denied incorrectly 325 CICS resources 94 command security 131 error messages 84 ICH408I, RACF message 84, 329 is CICS using RACF for resource? 326 problem determination in-storage profiles 326 which profile is RACF is using? 326 which profile is used to protect the resource? 327 which userid supplied by CICS for authorization check? 326 authorizing CICS region userid as surrogate user 54 authorizing CICS users to RACF 77

authorizing SYS1.PARMLIB libraries data sets 345 autoinstall models 74

В

backup while open (BWO) 46 batch access to CSD, restricting 73 batch call interface 231 BCICSPCT general resource class 99 bind-time security 163, 205, 219 for IPCONN 211 for IPIC connections 211 introduction 160 MRO links 220 overview 160 BINDSECURITY option 165 BMS commands 92 BUILD ATTACH command 224 building a keyring 264 BWO (backup while open) 46

С

CADP transaction 151 CATA transaction 145 cataloged procedures authorizing CICS as a started task 37 CATD transaction 145 categories of CICS-supplied transactions 143 CATR transaction 154 CBAM transaction 151 CCICSCMD general resource class 129, 140 CCIN transaction 154 CCRL running from a START command 276 running from a terminal 275 CCRL transaction 151 CDBC transaction 151 CDBD transaction 145 CDBF transaction 145 CDBI transaction 151 CDBM transaction 151 CDBO transaction 145 CDBQ transaction 145 CDBT transaction 151 CDFS transaction 151 CDST transaction 151 CDT (class descriptor table) 139 IBM-supplied default classes 31 resource length 139 setting up installation-defined classes 31, 318 CDTS transaction 145 CEBR transaction 151 CEBT transaction 84 CECI transaction 151

CECS transaction 151 CEDA LOCK command 73 CEDA transaction 72, 151 CEDB transaction 151 CEDC transaction 151 CEDF transaction 109, 129, 151 CEDX transaction 151 CEGN transaction 154 CEHP transaction 151 CEHS transaction 151 CEJR transaction 154 CEMN transaction 151 CEMT transaction 152 CEMT, master terminal transaction and CRTE 175, 177, 216, 228 considerations for command security 130 resource names 131 system programming commands 121 CEOT transaction 152 CEPD transaction 145 CEPH transaction 152 CEPM transaction 145 CEPQ transaction 152 CEPT transaction 152 certificate 243, 254 certificate authorities 255 certificate authority 243, 254 certificate revocation list 273, 274 certificates, creating new 267 CESC transaction 145 CESD transaction 152 CESF transaction 154 CESN CICS-supplied sign-on transaction 63 CESN transaction 154 CEST transaction 152 CETR transaction 152 CEX2 transaction 145 CFCL transaction 145 CFDT server authorization 237 CFOR transaction 145 CFQR transaction 145 CFQS transaction 145 CFRM policy 237 CFTL transaction 145 CFTS transaction 145 CGRP transaction 145 CICS command security 121 CICS commands and resources creating security profiles with RACF 349 controlling access to resources 349 CICS JOB statement, PASSWORD parameter 39 CICS JOB statement, USER parameter 39 CICS load libraries, protecting 36 CICS region access to 51 access to APPL class profiles 52 remote 52 userid as security token 54 CICS region user ID access problem 336 CICS region userid 36, 144 in started jobs 38

CICS resources protecting 23 CICS security, controlling 367 CICS segment 15 CICS SIT parameters security-related 369 CICS source libraries, protecting 36 CICS system definition file (CSD), restricting batch access to 73 CICS user restart program, PLTPI 85 CICS users 4 CICS-RACF security interface CICS security control points 315 how ESM exit programs access CICS-related information 314 installation data parameter list 315 interface to external manager 313 RACF user exit parameter list 314 RACROUTE macros 315 system authorization facility (SAF) 313 The MVS router 313 CICS-supplied RACF dynamic parse validation routines 35 CICS-supplied transactions security 143 CICS-supplied transactions, categories 143 CICSPlex SM authorizing libraries 345 procedures 346 protecting with another ESM 375 with RACF 341 resource names 349 CICSPlex SM definitions, protecting adding SAF resource classes 349 CICSPlex SM resource classes controlling access to 349 CICSPlex SM security profiles creating 345 CIDP transaction 152 CIEP transaction 154 CIND transaction 152 CIOD transaction 145 CIOF transaction 145 CIOR transaction 145 cipher suites 256 restricting with CIPHERS attribute 256 supported by z/OS and CICS 257 **CIPHERS** attribute CORBASERVER resource 256 TCPIPSERVICE resource 256 URIMAP resource 256 CIRP transaction 152 CIRR transaction 145 CIS4 transaction 145 CISB transaction 145 CISC transaction 145 CISD transaction 146 CISE transaction 146 CISM transaction 146 CISQ transaction 146 CISR transaction 146 CISS transaction 146 CIST transaction 146

CISU transaction 146 CISX transaction 146 CITS transaction 146 CIGC transaction 146 CJPI transaction 146 CISR transaction 146 CJTR transaction 146 CKAM transaction 152 CKBM transaction 152 CKBP transaction 152 CKCN transaction 152 CKDL transaction 152 CKDP transaction 152 CKRS transaction 152 CKRT transaction 152 CKSD transaction 152 CKSQ transaction 152 CKTI transaction 152 class descriptor table (CDT) 139 class, resource 13 class, resource grouping 14 classification of data and users 30 CLAUTH (class authority) attribute in CICS-related general resource classes 12 in user's profile 12 installation-defined classes 31, 319 CLDM transaction 152 CLQ2 transaction 154 CLR1 transaction 154 CLR2 transaction 154 CLS1 transaction 154 CLS2 transaction 154 CLS3 transaction 154 CLS4 transaction 154 XTRANID X'06F3F0F1' 193 CMAC transaction 152 CMDSEC operand of DEFINE TRANSACTION 216 CMDSEC system initialization parameter 129 CMDSEC, command security parameter 129 CMPX transaction 154 CMSG transaction 153 CMTS transaction 146 COMAUTHID surrogate security 116 command security 121 authorization failures 131 CCICSCMD general resource class 129 CEMT considerations 130 CICS resources subject to 122 for IPIC connections 215 for ISC over TCP/IP connections 215 QUERY SECURITY command 133 resource names for CEMT 131 specifying 128 VCICSCMD general resource class 128 XCMD parameter 58, 91 XUSER parameter 73 Common Secure Interoperability Version 2 (CSIv2) 249 conditional access lists 84 conditional access processing 69

CONSOLE general resource class 24, 69 description 69 coupling facility data table pool 236 coupling facility data tables security 236 COVR transaction 146 CPCT transaction 154 CPIH transaction 153 CPIL transaction 153 CPIQ transaction 153 CPIR transaction 146 CPIS transaction 146 CPLT transaction 113, 146 CPMI transaction 153 CPSMOBJ general resource class 23 CPSMXMP general resource class 24 CPSS transaction 154 CQPI transaction 154 CQPO transaction 155 CQRY transaction 155 CREA transaction 153 CREC transaction 153 CRL (certificate revocation list) 273 CRLR transaction 146 CRMD transaction 146 CRMF transaction 146 CRPA transaction 153 CRPC transaction 153 CRPM transaction 153 CRSQ transaction 146 CRSR transaction 155 CRSY transaction 146 CRTE transaction 146, 153 CRTE, routing transaction 175, 177, 216, 228 CRTX transaction 153 CSAC transaction 155 CSCS transient data destination 70 CSCY transaction 155 CSD (CICS system definition file), restricting batch access to 73 CSD definitions, locking 72 CSFE transaction 153 CSFR transaction 147 CSFU transaction 147 CSGM transaction 153 CSHA transaction 147 CSHQ transaction 147 CSHR transaction 153 CSIv2 249 CSKP transaction 147 CSM1 transaction 153 CSM2 transaction 153 CSM3 transaction 153 CSM5 transaction 153 CSMI transaction 153 CSNC transaction 147 CSNE transaction 147 CSOL transaction 147 CSPG transaction 155 CSPK transaction 155 CSPP transaction 155 CSPQ transaction 147 CSPS transaction 155 CSQC transaction 147 CSRK transaction 155 CSRS transaction 155 CSSF transaction 155

CSSY transaction 147 CSTE transaction 147 CSTP transaction 147 CSZI transaction 147 CTIN transaction 153 CTSD transaction 147 customizing security checking changing level of security checking 141 field-level file security 141 notification of userid change 321 which transactions to offer a user 141 customizing the CICS-RACF interface CICS security control points 315 determining userid of CICS region 318 ESMEXITS parameter 57, 315 installation data parameter list 315 introduction 313 RACF user exit parameter list 314 RACROUTE macros 315 CVMI transaction 153 CW2A transaction 153 CWBA transaction 153 CWBG transaction 147 CWTO transaction 153 CWWU transaction 153 CWXN transaction 147 CWXU transaction 147 CXCU transaction 147 CXRE transaction 147 CXRT transaction 155

D

Data Encryption Standard encryption algorithm 257 data for default user 76 data set profile 13 data set profiles enhanced generic naming 21 SETROPTS EGN command 21 data set security access to CICS data sets 43 access to user data sets 46 APPLID parameter 45 CICS installation requirements 35 CICS system 36 MVS library lookaside (LLA) facility 46 data tables bind security 235 CONNECT security checks 234 coupling facility 236 file security 235 security checking 233 server authorization security check 234 date subfields, format 197 DB2ENTRY resource classes 27 DCICSDCT general resource class 95 defining profiles 95 default user 113 default user, CICS defining 41 DFLTUSER parameter 56

default user, CICS (continued) EJBROLEPRFX parameter 56 specifying on SIT 56 DEFINE CONNECTION ATTACHSEC attribute 224 ATTACHSEC operand 170, 206 BINDSECURITY operand 165 SECURITYNAME option 165 DEFINE TRANSACTION CMDSEC operand 216 RESSEC operand 176, 207, 216, 227 defining profiles APPCLU general resource class 164 defining to RACF groups 77 users 77 users, example 78 definitions, protecting controlling access to resources 349 delegation of RACF administrative responsibility 12 DELMEM operand 68 deployed security roles 288 DES encryption algorithm 257 DES (data encryption standard) 254 DFH\$RACF 32, 61 DFHEJDIR, EJB request streams directory file 286 DFHEJDNX user-replaceable module 286 DFHEJOS, EJB passivated session beans file 286 DFHEXCI surrogate profile 118 DFHINSTL surrogate profile 117 DFHSNMIG, SNT migration utility program description 399 example output 400 migration 399 DFHSNT macro sample sign-on table entry 399 DFHSNxxxx messages 70 DFHSTART surrogate profile 117 DFHTST TYPE=SECURITY 103 DFHXCIS 231 DFHXCOPT, EXCI options table 116 dfjejbpl.policy, enterprise beans security policy 283 DFLTUSER parameter definition 18 obtaining user data 76 DFLTUSER SIT parameter creating a security environment 345 DFLTUSER, system initialization parameter 56 DIGTCERT general resource class 24 discrete profile 13, 14 distinguished names deriving 286 obtaining 286 distributed program link (DPL) with LU6.2 179 with MRO 230 document template security access authorization levels 89 defining resource classes 87

document template security *(continued)* RCICSRES resource class 87 WCICSRES grouping class 87 XRES parameter 87, 92 DSNC transaction 153 dynamic parse validation routines 35

Ε

EBCDIC, for PEM userids and passwords 193 ECICSDCT general resource class 95 defining profiles 95 EJBROLE general resource class 24 EJBROLE, RACF security role generator utility 293 EJBROLEPRFX, system initialization parameter 56 encryption 254 public key 253 encryption algorithms 257 enhanced generic naming data set profile names 21 SETROPTS EGN command 21 enterprise beans deployment descriptor 291 deriving distinguished names 286 file access permissions 285 security 284 security policy 283 security roles 284 defining to RACF 295 implementing 293 **RACF EJBROLE** generator utility 293 ESDSs, VSAM, access to 46 ESM (external security manager) EBCDIC for userids and passwords 193 invoking another MVS router 375 overview of interface 375 RACROUTE macros 377 sample configuration 184 sign-on data from CICS to PEM client 195 user profile 196, 197 using RACF 341 controlling CICS security 367 creating profiles 345, 349 ESMEXITS, system initialization parameter 57, 315 evaluation sequence, security 371 event binding user ID 118 EVENTBINDING user ID surrogate security 117 example tasks security 379 EXCI security 231 EXEC CICS commands QUERY SECURITY 8 QUERY SECURITY command 133 EXEC CICS SET TRQUEUE ATIUSERID 116 execution diagnostic facility(EDF) 339

exits ESM, accessing CICS-related information 314 ESMEXITS parameter 315 ICHRTX00, MVS router exit 313 installation, SAF 313 RACF user exit parameter list 314 explicit sign-on 63 external call interface 231 External CICS interface (EXCI) and surrogate checking 116 external security manager (ESM) invoking another MVS router 375 overview of interface 375 RACROUTE macros 377 using RACF 341 controlling CICS security 367 creating profiles 345, 349

F

FACILITY general resource class 26 FCICSFCT general resource class 97 FEPIRESOURCE resource name 121 FIELD general resource class 18, 25 file access permissions for CICS enterprise beans 285 file resource security checking 238 file security access authorization levels 97 data set profiles 21 defining resource classes 97 FCICSFCT general resource class 97 field-level file security 141 generic data set profiles 21 HCICSFCT general resource class 97 XEJB parameter 58, 91 XFCT parameter 58, 91, 97 files processed by CICS 97 flows, examples 188 FMH (function management header) attach 195 attach FMH5 and data 194 FMH5 attach header 194 possible errors in 337 user data following 194 function shipping mirror transaction 178, 207, 229 **RESSEC** operand of DEFINE TRANSACTION 176, 207, 227

G

GCICSTRN general resource class 56, 81, 100 GCPSMOBJ resource group class 23 GDS (generalized data stream) GDS LL length 194 variables to pass data 194 GEJBROLE resource group class 24 general resource class APPCLU defining profiles 164 general resource classes ACICSPCT 99

general resource classes (continued) APPCLU 24 APPL 24 BCICSPCT 99 CCICSCMD 129 CONSOLE 24 CPSMOBJ 23 CPSMXMP 24 DIGTCERT 24 EJBROLE 24 FACILITY 26, 219 FIELD 18, 25 for protecting CICS resources 23 for protecting resources 23 for protecting system resources 24 JCICSJCT 98 JESSPOOL 25, 54 KCICSJCT 98 LOGSTRM 25 MCICSPPT 102 NCICSPPT 102 OPERCMDS 25,74 PCICSPSB 108 PROGRAM 25 PROPCNTL 25, 53 PTKTDATA 25 OCICSPSB 108 SCICSTST 103 SERVAUTH 25 STARTED 25 SUBSYSNM 25 SURROGAT 25, 53 TERMINAL 25 UCICSTST 103 user-defined 318 VCICSCMD 128 VTAMAPPL 26, 52 general resource profile 13 general resource profiles refreshing 370 generating and using RACF PassTickets 10 generic profile 13, 14 generic profiles SETROPTS command 30 SETROPTS GENERIC 13, 21, 32, 67 generic resource names (VTAM) VTAM generic resource 51 generic resource profiles 110 global security parameters 369 global user exits XSNOFF signoff exit 321 XSNON signon exit 321 goodnight transaction 66 group identifier 63 group profile 13 group profiles 19 GROUP special command SEARCH command warning 29 group-SPECIAL attribute 11 grouping class, resource 14 GTERMINAL definition 67 GTERMINL resource group class 25

Η

HCICSFCT general resource class 97

HFS file security XHFS parameter 91, 106

IBM-supplied classes example for files 60, 61 example for PSBs 60, 61 example for transactions 60, 61 example for user-defined resources 320 ICH408I, RACF message 84 ICHERCDE macro 12, 318 ICHRFR01 (RACF router table) 319 ICHRFRTB macro 319 ICHRFX01 RACF user exit 321 ICHRIN03 started procedures table 346 ICHRIN03, RACF started task table 37 ICHRRCDE (installation-defined class descriptor table) 318 ICHRTX00, MVS router exit 313, 318 **IDENTIFY** parameter, ATTACHSEC operand 171 identifying remote users 171, 215, 224 in-storage profiles and XCMD resource class 129 GTERMINL profiles 67 QUERY SECURITY RESCLASS 317 reducing need for 24 refreshing 20 installation-defined classes 61 example for files 61 example for PSBs 61 example for transactions 61 example for user-defined resource 318 intersystem communication (ISC) security coding ATTACHSEC 170, 224 intrapartition transient data resources 115 **IPCONNs** link security 212 IPIC bind-time security 211 **IPIC** connections command security 215 how security is implemented 211 resource security 215 transaction security 215 user security 213 IPIC security CRTE 175, 177, 216, 228 introduction 9 IRR.DIGTCERT.ADD profile 268 ISC over SNA security APPC (LU6.2) session security 9 ISC over TCP/IP connections command security 215 resource security 215 transaction security 215

J

Java Security 279 Java security manager 280 JCICSJCT general resource class 98 JES spool protection 54 JESSPOOL general resource class 25, 54 job submission, surrogate 53 journal security access authorization levels 99, 102 defining resource classes 98 XJCT parameter 58, 91, 98 journals and log streams journal access authorization levels 98

Κ

KCICSJCT general resource class 98 key rings 264 keyring building 264

L

labels, RACF security 30 language segment PRIMARY language parameter 19 SECONDARY language parameter 19 system defaults 19 user profile 19 LDAP server configuring 274 levels, RACF security 30 libraries, CICSPlex SM protecting with RACF 341 link security 167, 205 for IPCONNs 212 introduction 160 load libraries, protecting 36 LOCAL parameter, ATTACHSEC operand 171 LOCK command, CEDA 73 log records SMF type 80 85, 94 log streams authorizing access to 42 LOGSTRM general resource class 42 logging security events QUERY SECURITY 140 RACF audit messages in SMF 94 requested by CICS on authorization requests 94 sign-on and sign-off activity 70 LOGSTRM general resource class 25 LU6.1 links 205 LU6.1 security 205 LU6.2 (APPC) session security introduction 9, 163 XAPPC parameter 57, 60, 91, 163 XDB2 parameter 91 LU6.2 security CRTE 175, 177, 216, 228

Μ

MAC (message authentication code) 253 marking a certificate untrusted 269 MCICSPPT general resource class 102 MD5 encryption algorithm 257 members, group ADDMEM operand to add 68 DELMEM operand to remove 68 merging 151 message authentication code (MAC) 253 Message Digest encryption algorithm 257 messages authorization failures 84 class name and ICH408I message 335 destination of ICH408I message 84 DFHSNxxxx 70 ICH408I, RACF 84, 329 RLIST command 325 migration DFHSNMIG utility 399 example output from DFHSNMIG 400 sign-on table migration utility, DFHSNMIG 399 mirror transactions availability of 148 for DPL from CICS OS/2 180 for DPL on LU6.2 180 for DPL on MRO 231 function shipping 178, 207, 229 mixed case password 78 MIXIDPE parameter, ATTACHSEC operand 171 MRO (multiregion operation) security CRTE 175, 177, 216, 228 MRO logon and connect 221 multiple volumes 47 multiregion operation (MRO) 9 MVS library lookaside (LLA) facility 46 password and RACF authorization checking 35 program properties table (PPT) 35 router exit, ICHRTX00 313 MVS router, for security 375

Ν

National Language Support 19, 76 national languages 383 NATLANG and non-terminal transactions 79 NCICSPPT general resource class 102 NETNAME terminal definition 67 non-terminal security suppressing attach checks 321 transactions not associated with terminals 8

Ο

OIDCARD (operator identification card) 7 OPCLASS 15 operator, CICS terminal example of defining to RACF 78 obtaining data for 76 operator, terminal data at sign on 76 data for default user 76 OPERCMDS general resource class 25 OPIDENT 15 OPPRTY 15

Ρ

parameter authorizing access to CICS region 51 protecting CICS data sets 45 parameters security activating 369 checking 369 global 369 password mixed case 78 passwords 8 characters 193 in ESM user profile 196 information provided by APPC PEM 183 updating 183 PCICSPSB general resource class 108 PEM problem determination 337 PEM requester conversation type 192 definition 184 format of user data 194 sign-on completion status values returned by CICS 197 PEM server, CICS data exceeding maximum buffer size 193 EBCDIC for userids and passwords 193 error status returned 188 format of date and time subfields 197 PROFILE option 193 synclevel 0 193 permissions (system access privileges) 280 PERMIT command 28, 320 WHEN operand 69 PERSISTENT parameter, ATTACHSEC operand 171 persistent sessions XRFSOFF operand 16 persistent sessions restart remaining signed on 16 sign-off 16 persistent verification (PV) ATTACHSEC-PERSISTENT 188 CONNECTION 187 sign-on successful, example flow 188 sign-on unsuccessful, with PV 191 signed on 191 signed-on-from list 187 signed-on-to list 187 successful sign-on flow 190 unsuccessful sign-on 191 when implementing LU6.2 security 169

PIP (program initialization parameter) data 193 PKCS (public key cryptography standard) 254 post-initialization processing 113 PLT programs 85 PLTPI 85 PLTPISEC, system initialization parameter 57 PLTPIUSR system initialization parameter 57, 113 PLTSD 85 POSIT numbers installation-defined general resource classes 22, 31 post-initialization processing, surrogate security 113 PREFIX attribute definition 104 prefixing specify prefix on resource name in RLIST command 335 with SECPRFX 55 preset security sessions 74 preset terminal NATLANG 79 preset terminal security 8, 70, 114 autoinstall models 74 CEDA LOCK command 73 CEDA transaction 72 controlling definition and installation 72 other considerations 73 restricting batch access to CSD 73 starting tasks at terminals 100 SURROGAT transaction 73 terminal routing 177, 228 transactions not associated with a terminal 85 using MVS system console as CICS terminal 74 PRIMARY language parameter 19 problem determination 337 access is allowed incorrectly 331 access is denied incorrectly 325 ATTACH security fields 193 CICS security control points 315 class name and ICH408I message 335 data exceeds maximum buffer size 193 determining userid of CICS region 318 error messages for authorization failures 84 errors, common causes 337 FMH in error 337 GDS FREE command received 193 ICH408I, RACF message 84, 329 is CICS using RACF for resource? 326 new password ID 193 password not in EBCDIC 193 PIP data optional 193 PROFILE option 193 reasons for sign-on failure 188 response to incorrect data format 202 restriction on using EDF 339

problem determination (continued) revoked user attempting to sign on 334 RLIST command 325 RLIST command with AUTHUSER, example output 336 RLIST command with RESGROUP, example output 336 security-related CICS initialization failures 332 sign-on failure 188 sign-on request formatting errors 198 specify prefix on resource name in RLIST command 335 synclevel 193 transaction ID 193 user data in error 337 user has insufficient authority to a resource 335 userid and password of more than 8 characters 193 userid not in EBCDIC 193 which profile is RACF is using? 326 which profile is used to protect the resource? 327 which userid is supplied by CICS for authorization check? 326 PRODCFT1 237 profile 13 profile, data set 13 profile, discrete 13, 14 profile, general resource 13 profile, generic 13, 14 profile, resource group 13 profile, user 4, 13 profiles ACICSPCT general resource class 99 BCICSPCT general resource class 99 CCICSCMD general resource class 129, 140 data set 21 DCICSDCT general resource class 95 defining APPCLU general resource class 164 ECICSDCT general resource class 95 enhanced generic naming 21 FCICSFCT general resource class 97 GCICSTRN general resource class 56, 81, 100 generic 30 generic data set 21 HCICSFCT general resource class 97 JCICSJCT general resource class 98 JESSPOOL 54 KCICSJCT general resource class 98 MCICSPPT general resource class 102 NCICSPPT general resource class 102 not found 325 PCICSPSB general resource class 108 PROPCNTL 53 QCICSPSB general resource class 108 RALTER command to change 29 RCICSRES resource class 87 RDEFINE command to create 28

profiles (continued) RDELETE command to delete 29 refreshing in main storage 22 resource and WARNING option 94 resources, defining generic 110 SCICSTST general resource class 103 SETROPTS command 29, 67 SETROPTS EGN command 21 SURROGAT general resource class 53, 117 TCICSTRN general resource class 56, 81, 100 terminal (PoE), defining 67 transaction and conditional access lists 84 transaction, defining to RACF 83 UCICSTST general resource class 103 USER parameter on CICS JOB statement 39 VCICSCMD general resource class 128 VTAMAPPL 52 WCICSRES grouping class 87 profiles for transient data queues 95 profiles, group 13 PROGRAM general resource class 25 program initialization parameter (PIP) data 193 program properties table (PPT), MVS 35 program security XPPT parameter 58, 92, 103 propagation of userid, controlling 53 PROPCNTL general resource class 25, 53 defining profiles 53 protecting CICS resources 23 resources 23 system resources 24 PSB security access authorization levels 109 defining resource classes 108 PCICSPSB general resource class 108 QCICSPSB general resource class 108 XPSB parameter 58, 92, 109 PSBCHK parameter 109, 133 PSBCHK, system initialization parameter 57 pthreads 259 PTKTDATA general resource class 25 public key encryption 253, 254 PVDELAY system initialization parameter 172

Q

QCICSPSB general resource class 108 QUERY SECURITY command 8 and resource classes 134 and transaction routing 134 changing level of security checking 141 description 133 effect of SEC parameter 133 effect of SECPRFX parameter 134 field-level file security 141 how the command works 133 QUERY SECURITY command (continued) logging 140 RESCLASS 139 RESTYPE 134 RESTYPE, values returned 138 SPCOMMAND, RESID values 136 specifying user-defined resources 318 which transactions to offer a user 141

R

RACDCERT command 264, 268 RACF profile 13 RACF (resource access control facility) activating the CICS classes 22 administration 11 authorizing CICS users 77 CICS default user 18 CICS installation requirements 35 CICS segment 15 class descriptor table, ICHRRCDE 318 data set profiles 21 defining default CICS userid 41 defining port of entry profiles 67 defining your own resource class names 31 FIELD general resource class 18 general resource profiles 21 generic data set profiles 21 generic resource profiles 110 group profile 19 group profiles 19 language segment 19 overriding SETROPTS TERMINAL 68 RACF segment 14 refreshing resource profiles in main storage 22 router table, ICHRFR01 319 security labels 30 security levels 30 terminal profiles 67 undefined terminals 68 user profiles 14 with CICS XRF 35 with multiple MVS images 35 RACF (Resource Access Control Facility) controlling access to resources 349 defining transactions 346, 347 exempting items from security checking 368 RACF commands ADDGROUP, example 20 ADDUSER, example for default CICS userid 41 CONNECT, example 20 DELMEM operand 68 example of ALTUSER command 12 example of CONNECT command (group-SPECIAL) 13 PERMIT 28 RALTER 29, 68 RDEFINE 28 RDELETE 29

RACF commands (continued) REMOVE, example 20 RLIST 325 RLIST command with AUTHUSER, example output 336 RLIST command with RESGROUP, example output 336 SEARCH-warning 29 SETROPTS 21, 29 **RACF** definitions to configure CICS for security 286 RACF definitions for surrogate user checking 117 RACF PassTickets 10 **RACF** profiles refreshing 370 RACF security role generator utility, EJBROLE 293 RACF SPECIAL authority 268 RACFVARS profiles 118 RACLIST 319 RACROUTE macros 315 RACROUTE macros, for security 377 RALTER command 29 RC₂ encryption algoritm 257 RC4 encryption algoritm 257 RCICSRES 31 RCICSRES resource class 87 RDELETE command 29 RDO restricting use of transaction 72 refreshing RACF profiles 370 remote operators 169, 223 remote user sign-off 172, 215, 224 remote users 169, 223 RESID values for SPCOMMAND 136 Resource Access Control Facility (RACF) controlling access to resources 349 defining transactions 346, 347 exempting items from security checking 368 Resource and command check cross reference 385 resource class 13 APPCLU defining profiles 164 resource classes, CICSPlex SM controlling access to 349 resource definition LU6.2 (APPC) session security 165 resource security 176, 207, 227 SECURITYNAME option 165 transaction security 176, 206, 215, 226 user security in link definitions 170, 224 resource definition online (RDO) 154 resource definition parameters CMDSEC 129 RESSEC 92, 109 resource group DELMEM operand to remove 68 resource group classes GCPSMOBJ 23 GEJBROLE 24

resource group classes (continued) GTERMINL 25 resource group profile 13 resource grouping class 14 resource names, CICSPlex SM 349 resource profiles RALTER command to change 29 RDEFINE command to create 28 RDELETE command to delete 29 resource security 87, 176, 207, 227 access authorization levels, document templates 89 access authorization levels, files 97 access authorization levels, z/OS UNIX files 108 ACICSPCT general resource class 99 activating the CICS classes 22 application programs 102 auditing 94 authorization failures 94 BCICSPCT general resource class 99 CCICSCMD general resource class 140 CICS SIT parameters 57 DCICSDCT general resource class 95 defining generic profiles 110 defining profiles for TD queues 95 defining your own resource class names 31 document templates 87 ECICSDCT general resource class 95 FCICSFCT general resource class 97 FIELD general resource class 18 files 97 for IPIC connections 215 for ISC over TCP/IP connections 215 GCICSTRN general resource class 56, 81.100 general checking by CICS and RACF 91 general resource profiles 21 HCICSFCT general resource class 97 HFS files 106 JCICSJCT general resource class 98 journals and log streams 98 KCICSJCT general resource class 98 level of access required 111 logging RACF audit messages to SMF 94 MCICSPPT general resource class 102 NCICSPPT general resource class 102 PCICSPSB general resource class 108 profiles and WARNING option 94 program specification blocks 108 QCICSPSB general resource class 108 QUERY SECURITY command 8, 133 OUERY SECURITY RESCLASS 139 RCICSRES resource class 87 refreshing profiles in main storage 22 resource definition 176, 207, 227 **RESSEC** system initialization parameter 93 **RESSEC** transaction resource security parameter 92

resource security (continued) SCICSTST general resource class 103 SPCOMMAND, RESID values 136 TCICSTRN general resource class 56, 81, 100 temporary storage 103 transaction routing 176, 227 transient data destinations (queues) 95 UCICSTST general resource class 103 WCICSRES grouping class 87 XAPPC parameter 91 XCMD parameter 91 XDB2 parameter 91 XDCT parameter 91 XEJB parameter 91 XFCT parameter 91, 97 XHFS parameter 58, 91, 105, 106 XJCT parameter 91, 98 XPCT parameter 92, 99 XPPT parameter 92, 103 XPSB parameter 92, 109 XRES parameter 58, 87, 92 XTST parameter 92, 104 z/OS UNIX files 105 resources protecting 23 **RESSEC** operand of DEFINE TRANSACTION 176, 207, 216, 227 RESSEC resource security parameter 92 RESSEC, system initialization parameter 57 Rivest encryption algoritm 257 routing transaction, CRTE 175, 177, 216, 228

S

SAF (system authorization facility) and MVS router 313 CICS-RACF interface 313 installation exit 313 to route requests to RACF 3 Sample CLIST DFH\$CTA1 144 SCICSTST general resource class 103 scope in resource names 350 scoping sign-on definition 63 SEC, system initialization parameter 55 SECONDARY language parameter 19 SECPRFX, system initialization parameter 55 Secure Hash encryption algorithm 257 securing transactions and resources 161 security non-terminal 85 resource 87 security categories 30 security checking controlling CICS 367 ESM interface 375 evaluation sequence 371 exempting items 368 parameters 369 with another ESM 375

security checking (continued) with RACF 341 security classification of data and users 30 security labels 30 security levels 30 security manager applying a security policy 280 enabling a security policy 280 security profiles refreshing 370 security profiles, RACF creating 345 views protected by 351 security rebuild 20, 167 security role generator utility, EJBROLE 293 security tasks, example 379 security token of JES spool files 54 security, of enterprise beans access to data sets 286 deployed security roles 288 deriving distinguished names 286 file access permissions 285 introduction to 279 Java security policy 279 security manager applying a security policy 280 enabling a security policy 280 security roles 284 defining to RACF 295 implementing 293 **RACF EJBROLE** generator utility 293 specifying security policy files to apply to all JVMs 282 supplied enterprise beans policy file 283 SECURITYPREFIXID 237 segment CICS 15 data for terminal user 17 LANGUAGE 19 migrating from existing SNT 399 RACF 14 SERVAUTH general resource class 25 session key 163 session security 163 session segment 164 SETROPTS command 21, 29 CLASSACT option 319 generic data set profiles 21 GENERIC option 319 generic terminal profiles 67 generic user profiles 32 RACLIST option 319 REFRESH option 320 SETROPTS GENERICOWNER command 13 SHA encryption algorithm 257 shared data tables bind security 235 CONNECT security checks 234 file security 235 security checking 233

shared data tables (continued) server authorization security check 234 sign-off after persistent sessions restart 16 after XRF takeover 16 logging activity 70 process 65 sign-off process 65 sign-on after persistent sessions restart 16 after XRF takeover 16 logging activity 70 unsuccessful, example flow 189 user data for terminal user 76 sign-on table DFHSNMIG utility 399 migration utility 399 signon requester transaction ATTACH security fields 193 data exceeds maximum buffer size 193 EBCDIC for userids and passwords 193 input data required by CICS PEM server 195 new password ID 193 permitted userid and password length 193 PIP data optional 193 PROFILE option 193 SNA service transaction program name 195 synclevel 0 193 X'06F3F0F1', transaction ID 193 simulated CICS security 367 SIT parameters, CICS security-related 369 SMF (System Management Facility) 11, 70 SNA service transaction program name for sign-on transaction program 195 SNSCOPE sign-on operand 57 source libraries, protecting 36 SPCOMMAND, RESID values 136 spool files, security token 54 SPOOLOPEN commands 54 SSL client certificate authentication 249 SSL connection improvements 259 SSL pool 259 start transaction started transactions 114 STARTED general resource class 25 started jobs defining CICS region userid 38 started task and RACF userid 14 authorizing CICS procedures 37 started transaction security 99 SUBSYSNM general resource class 25 successful signon correct userid and password 199 new password 200 PEM client to CICS PEM server 188 response to correct sign-on data 200 response to incorrect data format 202 successful sign-on 188

successful signon (continued) successful sign-on with PV 190 unsuccessful sign-on 189 unsuccessful sign-on with PV 191 suppressing attach checks for non-terminal transactions 321 SURROGAT general resource class 25, 53.72.117 SURROGAT transaction 73 surrogate authority, querying a user's 140 surrogate job submission to JES internal reader 53 surrogate terminal 177, 228 surrogate user authorizing CICS region userid as 54 surrogate user security 113 checking 113 post-initialization processing 113 RACF definitions 117 RACF definitions examples 118 SURROGCHK parameter 116 symmetric encryption 254 system access privileges (permissions) 280 system data set authorizing access to 43 generic profiles needed 44 levels of access to 43 protecting 36 system initialization parameters, CICS CMDSEC 56, 129 DFLTUSER 56 EJBROLEPRFX 56 ESMEXITS 57, 315 PLTPISEC 57 PLTPIUSR 57 prefixing CICS resource names 55 PSBCHK 57, 109, 133 resource security 57 RESSEC 57 SEC 55 SEC with QUERY SECURITY 133 SECPRFX 55 SECPRFX with QUERY SECURITY 134 SNSCOPE 57 XAPPC 57, 60, 91, 163 XCMD 58, 91, 129 XDB2 58, 91 XDCT 58, 91, 95 XEJB 58, 60, 91 XFCT 58, 91, 97 XHFS 58, 60, 91, 105, 106 XJCT 58, 91, 98 Xname parameters 134, 331, 332 XPCT 58, 92, 99 XPPT 58, 92, 103 XPSB 58, 92, 109 XRES 58, 87, 92 XTRAN 83 XTST 58, 92, 104 XUSER 58, 60 System Management Facility (SMF) 11, 70 system resources protecting 24

system security CICS installation requirements 35 system-SPECIAL attribute 11 systems network architecture (SNA) session security 160

Т

tasks, example security 379 TCICSTRN general resource class 56, 81, 100TCP/IP connections bind-time security 211 temporary storage 92, 103 access authorization levels 105 authorizing access to named counter servers 49 authorizing access to the named counter pools 48 authorizing access to the TS pools 47 authorizing access to TS servers 47 defining resource classes 103 SCICSTST general resource class 103 UCICSTST general resource class 103 TERMINAL definition 67 TERMINAL general resource class 25 terminal security autoinstall models 74 CEDA LOCK command 73 controlling access 66 example of defining users to RACF 78 identifying users 63 obtaining CICS-related data for a user 76 overriding SETROPTS TERMINAL 68 preset 8,70 sign-on 63 terminal profiles 67 terminals in TCT 74 undefined terminals 68 universal access authority 68 user 7 using MVS system console as CICS terminal 74 XTRAN 58 terminal user security 7 terminals defined in TCT 74 Terminals, defining individual profiles 67 time subfields, format 197 TIMEOUT 15 trademarks 402 transaction attach security CICS parameters controlling 81 processing when SEC=YES and XTRAN=YES 83 transaction initiation 175, 206, 215, 226 transaction routing and QUERY SECURITY 134 transaction security 161 access authorization levels 102 categories of CICS-supplied transactions 143 category 1 transactions 144

transaction security (continued) category 2 transactions 148 category 3 transactions 154 CEBT transaction 84 conditional access lists 84 CRTE 175, 177, 216, 228 defining profiles to RACF 83 for IPIC connections 215 for ISC over TCP/IP connections 215 resource definition 176, 206, 215, 226 started transactions 81, 99 transaction-attach security 81 transactions started without terminals 100 XJCT parameter 99 XPCT parameter 58, 92 XPCT-checked transactions 99 XTRAN system initialization parameter 83 transactions 346, 347 in a CMAS 346 defining to RACF 346 in a MAS 347 defining to RACF 347 transient data access authorization levels 96 CICS-required transient data queue resource definitions 96 security considerations 95 transient data trigger-level transactions 115 trigger level transactions default security for 42, 115 specifying security for 85, 115 Triple DES encryption algorithm 257 TSO command refreshing using TSO command 22 TSO commands and security processing 320

U

UACC 83 UCICSTST general resource class 103 universal access 83 untrusted certificate, marking 269 URIMAP definitions surrogate security 117 user data attach FMH5 and data 194 format 194 GDS LL length 194 SFL1 and SFL2 lengths 194 TP LL length 194 user exits ICHRFX01 RACF user exit 321 ICHRTX00 MVS router exit 318 RACF parameter lists 314 XSNOFF global user exit 321 XSNON global user exit 321 user ID security checking with CRTE 175, 177, 216, 228 user ID in event bindings 117 USER parameter on CICS JOB statement 39

user profile 4, 13, 197 user profiles in RACF 14 refreshing 370 with ESM 196 user security 169, 223 CICS default user 18 for IPIC connections 213 transaction routing 176, 227 user profiles 14 user-defined classes 318 userid ADDUSER to add default CICS userid 41 controlling propagation of 53 default 56 defining CICS default user 41 defining for CICS 39 DFLTUSER parameter 56 EJBROLEPRFX parameter 56 non-terminal started transaction 100 of CICS region as security token 54 surrogate job submission 53 userid of non-terminal started transaction 100 userid on DB2 AUTHID and COMAUTHID parameters 116 userid on URIMAP resource definitions 117 userid passed as parameter on EXCI calls 116 userids used in CICS 4 users, CICS 4 USRDELAY, system initialization parameter 224

V

VCICSCMD general resource class 128 VERIFY parameter, ATTACHSEC operand 171 verifying remote users 172 views protected by security profiles 351 VSAM data sets, and BWO 46 VSAM data sets, and Dynamic Volume Count 47 VSAM ESDSs, access to 46 VTAM generic resource names 51 VTAM terminal VTAM ACB access 52 VTAMAPPL general resource class 26, 52 defining profiles 52

W

WARNING option 94 WCICSRES 31 WCICSRES grouping class 87 WHEN operand of PERMIT WHEN operand 69

Х

XAPPC, system initialization parameter 57, 60, 91, 163 XCMD, system initialization parameter 58, 91, 129 XDB2, system initialization parameter 58, 91 XDCT, system initialization parameter 58, 91, 95 considerations for triggered transactions 96 XEJB, system initialization parameter 58, 60,91 XFCT, system initialization parameter 58, 91, 97 XHFS, system initialization parameter 58, 60, 91, 105, 106 XJCT, system initialization parameter 58, 91, 98 Xname, system initialization parameters 331, 332 XPCT-checked transaction security 99 XPCT, system initialization parameter 58, 92, 99 XPPT, system initialization parameter 58, 92, 103 XPSB, system initialization parameter 58, 92, 109 XRES, system initialization parameter 58, 87, 92 XRF (extended recovery facility) FORCE operand 16 NOFORCE operand 16 remaining signed on after takeover 16 sign-off after takeover 16 XRFSOFF operand 16 XSNOFF global user exit 321 XSNON global user exit 321 XTRAN, system initialization parameter 58 XTST, system initialization parameter 58, 92, 104 XUSER, system initialization parameter 58, 60, 73 resource security XUSER parameter 92 system initialization parameters, CICS XUSER 92

Ζ

 z/OS Secure Authentication Service (z/SAS) 249
 z/OS UNIX file security access authorization levels 108
 XHFS parameter 105
 z/SAS 249

Readers' Comments — We'd Like to Hear from You

CICS Transaction Server for z/OS Version 4 Release 1 RACF Security Guide

Publication No. SC34-7003-03

We appreciate your comments about this publication. Please comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. The comments you send should pertain to only the information in this manual or product and the way in which the information is presented.

For technical questions and information about products and prices, please contact your IBM branch office, your IBM business partner, or your authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you. IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you state on this form.

Comments:

Thank you for your support.

Submit your comments using one of these channels:

• Send your comments to the address on the reverse side of this form.

- Send a fax to the following number: +44 1962 816151
- · Send your comments via email to: idrcf@uk.ibm.com

If you would like a response from IBM, please fill in the following information:

Name

Address


Company or Organization

Phone No.

Email address



Cut or Fold Along Line



IBM.®

SC34-7003-03

