



**Program Directory for
IBM Db2 13 for z/OS
QMF Classic Edition
National Language Version**

13.01.00

Program Number 5698-DB2

HSQDD10, HHPCC10, JYQDD10, JSQDD1C and NLVs

for Use with
z/OS

Document Date: May 2022

GI13-5536-00

Note

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 67.

© Copyright International Business Machines Corporation 1982, 2022.

©Rocket Software Incorporated 2022. All rights reserved

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

1.0 Introduction	1
1.1 QMF Classic Edition - NLV Description	2
1.2 QMF Classic Edition - NLV FMIDs	2
2.0 Program Materials	4
2.1 Basic Machine-Readable Material	4
2.2 Program Publications	14
2.2.1 Unlicensed publications for QMF Classic Edition - NLV	14
2.2.2 Optional Program Publications	14
2.3 Program Source Materials	14
2.4 Publications Useful During Installation	14
3.0 Program Support	16
3.1 Program Services	16
3.2 Preventive Service Planning	16
3.3 Statement of Support Procedures	17
4.0 Program and Service Level Information	19
4.1 Program Level Information	19
4.2 Service Level Information	19
5.0 Installation Requirements and Considerations	20
5.1 Driving System Requirements	20
5.1.1 Machine Requirements	20
5.1.2 Programming Requirements	20
5.2 Target System Requirements	21
5.2.1 Machine Requirements	21
5.2.2 Programming Requirements	21
5.2.2.1 Installation Requisites	21
5.2.2.2 Operational Requisites	22
5.2.2.3 Toleration/Coexistence Requisites	23
5.2.2.4 Incompatibility (Negative) Requisites	23
5.2.3 DASD Storage Requirements	23
5.3 FMIDs Deleted	39
5.4 Special Considerations	39
6.0 Installation Instructions	40
6.1 Installing QMF Classic Edition - NLV	40
6.1.1 SMP/E Considerations for Installing QMF Classic Edition - NLV	40
6.1.2 SMP/E Options Subentry Values	40
6.1.3 SMP/E CALLLIBS and SIDE DECK PROCESSING	41
6.1.4 Sample Jobs	41

6.1.4.1	Sample Jobs for National Language Version for QMF Korean	45
6.1.4.2	Sample Jobs for National Language Version for QMF Brazilian Portuguese	46
6.1.4.3	Sample Jobs for National Language Version for QMF Spanish	47
6.1.4.4	Sample Jobs for National Language Version for QMF Swedish	48
6.1.4.5	Sample Jobs for National Language Version for QMF Swiss French	49
6.1.4.6	Sample Jobs for National Language Version for QMF Swiss German	50
6.1.4.7	Sample Jobs for National Language Version for QMF Canadian French	51
6.1.4.8	Sample Jobs for National Language Version for QMF Uppercase English	52
6.1.4.9	Sample Jobs for National Language Version for QMF Danish	53
6.1.4.10	Sample Jobs for National Language Version for QMF French	54
6.1.4.11	Sample Jobs for National Language Version for QMF German	55
6.1.4.12	Sample Jobs for National Language Version for QMF Italian	56
6.1.4.13	Sample Jobs for National Language Version for QMF Japanese	57
6.1.5	Allocate SMP/E CSI (Optional)	58
6.1.6	Initialize CSI zones (Optional)	58
6.1.7	Perform SMP/E RECEIVE	58
6.1.8	Allocate SMP/E Target and Distribution Libraries	59
6.1.9	Create DDDEF Entries	59
6.1.10	Perform SMP/E APPLY	60
6.1.11	Perform SMP/E ACCEPT	63
6.1.12	Run REPORT CROSSZONE	64
6.2	Activating QMF Classic Edition - NLV	64
6.3	Product Customization	66
7.0	Notices	67
7.1	Trademarks	67
Reader's Comments		68

Figures

1.	Program File Content for QMF TSO/CICS Base	4
2.	Program File Content for QMF HPO	5
3.	Program File Content for QMF applications	5
4.	Program File Content for QMF Classic Edition Identifier	6
5.	Program File Content for QMF Korean	6
6.	Program File Content for QMF Brazilian Portuguese	7
7.	Program File Content for QMF Spanish	7
8.	Program File Content for QMF Swedish	8
9.	Program File Content for QMF Swiss French	8
10.	Program File Content for QMF Swiss German	9
11.	Program File Content for QMF Canadian French	10

12.	Program File Content for QMF Uppercase English	10
13.	Program File Content for QMF Danish	11
14.	Program File Content for QMF French	11
15.	Program File Content for QMF German	12
16.	Program File Content for QMF Italian	13
17.	Program File Content for QMF Japanese	13
18.	Publications Useful During Installation	14
19.	PSP Upgrade and Subset ID	16
20.	Component IDs	17
21.	Driving System Software Requirements	21
22.	Target System Mandatory Installation Requisites	21
23.	Target System Mandatory Operational Requisites	22
24.	Total DASD Space Required by QMF Classic Edition - NLV	24
25.	Total DASD Space Required by any National Language Version	24
26.	QMF National Language Identifiers	25
27.	Storage Requirements for QMF for TSO/CICS Target Libraries	26
28.	Storage Requirements for QMF HPO Target Libraries	27
29.	Storage Requirements for QMF applications Target Libraries	27
30.	Storage Requirements for QMF Classic Edition - NLV Target Libraries	27
31.	Storage Requirements for QMF for TSO/CICS Distribution Libraries	32
32.	Storage Requirements for QMF HPO Distribution Libraries	33
33.	Storage Requirements for QMF applications Distribution Libraries	33
34.	Storage Requirements for QMF Classic Edition - NLV Distribution Libraries	33
35.	Storage Requirements for QMF Classic Edition - NLV Non-SMP/E Data Sets	38
36.	SMP/E Options Subentry Values	40
37.	Sample Installation Jobs	41
38.	Sample Installation Jobs for QMF Korean	45
39.	Sample Installation Jobs for QMF Brazilian Portuguese	46
40.	Sample Installation Jobs for QMF Spanish	47
41.	Sample Installation Jobs for QMF Swedish	48
42.	Sample Installation Jobs for QMF Swiss French	49
43.	Sample Installation Jobs for QMF Swiss German	50
44.	Sample Installation Jobs for QMF Canadian French	51
45.	Sample Installation Jobs for QMF Uppercase English	52
46.	Sample Installation Jobs for QMF Danish	53
47.	Sample Installation Jobs for QMF French	54
48.	Sample Installation Jobs for QMF German	55
49.	Sample Installation Jobs for QMF Italian	56
50.	Sample Installation Jobs for QMF Japanese	57
51.	NLV Activating Jobs	65

1.0 Introduction

This program directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of IBM Db2 Query Management Facility Classic. This publication refers to IBM Db2 Query Management Facility Classic as QMF Classic Edition - NLV.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 4 identifies the basic program materials and documentation for QMF Classic Edition - NLV.
- 3.0, “Program Support” on page 16 describes the IBM support available for QMF Classic Edition - NLV.
- 4.0, “Program and Service Level Information” on page 19 lists the APARs (program level) and PTFs (service level) that have been incorporated into QMF Classic Edition - NLV.
- 5.0, “Installation Requirements and Considerations” on page 20 identifies the resources and considerations that are required for installing and using QMF Classic Edition - NLV.
- 6.0, “Installation Instructions” on page 40 provides detailed installation instructions for QMF Classic Edition - NLV. It also describes the procedures for activating the functions of QMF Classic Edition - NLV, or refers to appropriate publications.

Before installing QMF Classic Edition - NLV, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this program directory; after which, keep the documents for your reference. Section 3.2, “Preventive Service Planning” on page 16 tells you how to find any updates to the information and procedures in this program directory.

QMF Classic Edition - NLV is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The program directory that is provided in softcopy format on the CBPDO is identical to the hardcopy format if one was included with your order. All service and HOLDDATA for QMF Classic Edition - NLV are included on the CBPDO.

Do not use this program directory if you install QMF Classic Edition - NLV with a ServerPac. When you use one of those offerings, use the jobs and documentation supplied with the offering. The offering will point you to specific sections of this program directory as needed.

1.1 QMF Classic Edition - NLV Description

QMF Classic Edition feature of Db2 13 for z/OS supports user working entirely on traditional mainframe terminals and emulators, including IBM Host on Demand, to access Db2 databases.

QMF Classic Edition is a chargeable feature that consists of the following capabilities:

- QMF for TSO and CICS
- QMF Enhanced Editor
- QMF applications
- QMF for TSO and CICS Classic Edition
- QMF High Performance Option (HPO)

New **QMF for TSO and CICS** enhancements are:

- The CURRENT LOCK TIMEOUT special register can be set from within a QMF SQL query. This special register specifies the number of seconds to elapse before a resource timeout is detected.
- By using new keyword parameters options ALL or NONE on the folder keyword of the LIST command, users can view QMF objects needing to be organized by FOLDER that may help users organize QMF objects.
- The DESCRIBE Panel has been updated to show all folder names currently assigned to QMF objects.
- The DESCRIBE command is executed from an active list of QMF objects.

1.2 QMF Classic Edition - NLV FMIDs

QMF Classic Edition - NLV consists of the following FMIDs:

HSQDD10 (QMF TSO/CICS Base)
HHPCC10 (QMF HPO)
JYQDD10 (QMF applications)
JSQDD1C (QMF Classic Edition Identifier)

JSQDD5A (QMF Korean)
JSQDD5B (QMF Brazilian Portuguese)
JSQDD5C (QMF Spanish)
JSQDD5D (QMF Swedish)
JSQDD5E (QMF Swiss French)
JSQDD5F (QMF Swiss German)
JSQDD5G (QMF Canadian French)
JSQDD51 (QMF Uppercase English)
JSQDD55 (QMF Danish)
JSQDD56 (QMF French)
JSQDD57 (QMF German)
JSQDD58 (QMF Italian)
JSQDD59 (QMF Japanese)

Notes:

- To install the QMF for TSO and CICS product, install FMIDs HSQDD10 (QMF TSO/CICS Base) and JSQDD1C (QMF Classic Edition Identifier).
- To install the features QMF applications and the QMF Enhanced Editor for QMF for TSO and CICS, install FMID JYQDD10 (QMF applications). QMF for TSO and CICS FMID HSQDD10 is a prerequisite.
- To install QMF HPO, install the FMID HHPCC10 (QMF HPO). Please note that QMF HPO 12.1 FMID (HHPCC10) is provided with this QMF 13 feature.
- The installation of any QMF National Language FMID, requires the prerequisite QMF for TSO and CICS FMID HSQDD10.

2.0 Program Materials

An IBM program is identified by a program number. The program number for QMF Classic Edition - NLV is 5698-DB2.

Basic Machine-Readable Materials are materials that are supplied under the base license and are required for the use of the product.

The program announcement material describes the features supported by QMF Classic Edition - NLV. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is physical media or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 40 for more information about how to install the program.

You can find information about the physical media for the basic machine-readable materials for QMF Classic Edition - NLV in the *CBPDO Memo To Users Extension*.

Figure 1 (Page 1 of 2). Program File Content for QMF TSO/CICS Base

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.HSQDD10.F1	PDS	FB	80	8800
IBM.HSQDD10.F2	PDS	FB	80	8800
IBM.HSQDD10.F3	PDS	F	400	400
IBM.HSQDD10.F4	PDS	FB	80	8800
IBM.HSQDD10.F5	PDS	FB	80	8800
IBM.HSQDD10.F6	PDS	FB	80	8800
IBM.HSQDD10.F7	PDS	F	400	400
IBM.HSQDD10.F8	PDS	FB	80	8800
IBM.HSQDD10.F9	PDS	U	0	6144
IBM.HSQDD10.F10	PDS	FB	80	8800
IBM.HSQDD10.F11	PDS	VB	32622	32626
IBM.HSQDD10.F12	PDS	FB	80	8800

Figure 1 (Page 2 of 2). Program File Content for QMF TSO/CICS Base

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.HSQDD10.F13	PDS	FB	80	8800
IBM.HSQDD10.F14	PDS	FB	80	8800

Figure 2. Program File Content for QMF HPO

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.HHPCC10.F1	PDS	FB	80	8800
IBM.HHPCC10.F2	PDS	FB	80	8800
IBM.HHPCC10.F3	PDS	FB	80	8800
IBM.HHPCC10.F4	PDS	FB	80	8800
IBM.HHPCC10.F5	PDS	FB	80	8800
IBM.HHPCC10.F6	PDS	FB	80	8800
IBM.HHPCC10.F7	PDS	U	0	6144
IBM.HHPCC10.F8	PDS	FB	80	8800
IBM.HHPCC10.F9	PDS	FB	80	8800

Figure 3 (Page 1 of 2). Program File Content for QMF applications

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JYQDD10.F1	PDS	FB	80	8800
IBM.JYQDD10.F2	PDS	FB	80	8800
IBM.JYQDD10.F3	PDS	FB	80	8800
IBM.JYQDD10.F4	PDS	U	0	6144
IBM.JYQDD10.F5	PDS	FB	80	8800

Figure 3 (Page 2 of 2). Program File Content for QMF applications

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JYQDD10.F6	PDS	U	0	6144
IBM.JYQDD10.F7	PDS	FB	80	8800
IBM.JYQDD10.F8	PDS	FB	80	8800

Figure 4. Program File Content for QMF Classic Edition Identifier

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD1C.F1	PDS	U	0	6144

Figure 5. Program File Content for QMF Korean

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5A.F1	PDS	FB	80	8800
IBM.JSQDD5A.F2	PDS	FB	80	8800
IBM.JSQDD5A.F3	PDS	FB	80	8800
IBM.JSQDD5A.F4	PDS	FB	80	8800
IBM.JSQDD5A.F5	PDS	F	400	400
IBM.JSQDD5A.F6	PDS	FB	80	8800
IBM.JSQDD5A.F7	PDS	U	0	6144
IBM.JSQDD5A.F8	PDS	FB	80	8800
IBM.JSQDD5A.F9	PDS	V	32622	32626
IBM.JSQDD5A.F10	PDS	FB	80	8800
IBM.JSQDD5A.F11	PDS	FB	80	8800
IBM.JSQDD5A.F12	PDS	FB	80	8800

Figure 6. Program File Content for QMF Brazilian Portuguese

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5B.F1	PDS	FB	80	8800
IBM.JSQDD5B.F2	PDS	FB	80	8800
IBM.JSQDD5B.F3	PDS	FB	80	8800
IBM.JSQDD5B.F4	PDS	FB	80	8800
IBM.JSQDD5B.F5	PDS	F	400	400
IBM.JSQDD5B.F6	PDS	FB	80	8800
IBM.JSQDD5B.F7	PDS	U	0	6144
IBM.JSQDD5B.F8	PDS	FB	80	8800
IBM.JSQDD5B.F9	PDS	V	32622	32626
IBM.JSQDD5B.F10	PDS	FB	80	8800
IBM.JSQDD5B.F11	PDS	FB	80	8800
IBM.JSQDD5B.F12	PDS	FB	80	8800

Figure 7 (Page 1 of 2). Program File Content for QMF Spanish

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5C.F1	PDS	FB	80	8800
IBM.JSQDD5C.F2	PDS	FB	80	8800
IBM.JSQDD5C.F3	PDS	FB	80	8800
IBM.JSQDD5C.F4	PDS	FB	80	8800
IBM.JSQDD5C.F5	PDS	F	400	400
IBM.JSQDD5C.F6	PDS	FB	80	8800
IBM.JSQDD5C.F7	PDS	U	0	6144
IBM.JSQDD5C.F8	PDS	FB	80	8800
IBM.JSQDD5C.F9	PDS	V	32622	32626
IBM.JSQDD5C.F10	PDS	FB	80	8800

Figure 7 (Page 2 of 2). Program File Content for QMF Spanish

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD5C.F11	PDS	FB	80	8800
IBM.JSQDD5C.F12	PDS	FB	80	8800

Figure 8. Program File Content for QMF Swedish

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5D.F1	PDS	FB	80	8800
IBM.JSQDD5D.F2	PDS	FB	80	8800
IBM.JSQDD5D.F3	PDS	FB	80	8800
IBM.JSQDD5D.F4	PDS	FB	80	8800
IBM.JSQDD5D.F5	PDS	F	400	400
IBM.JSQDD5D.F6	PDS	FB	80	8800
IBM.JSQDD5D.F7	PDS	U	0	6144
IBM.JSQDD5D.F8	PDS	FB	80	8800
IBM.JSQDD5D.F9	PDS	V	32622	32626
IBM.JSQDD5D.F10	PDS	FB	80	8800
IBM.JSQDD5D.F11	PDS	FB	80	8800
IBM.JSQDD5D.F12	PDS	FB	80	8800

Figure 9 (Page 1 of 2). Program File Content for QMF Swiss French

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5E.F1	PDS	FB	80	8800
IBM.JSQDD5E.F2	PDS	FB	80	8800

Figure 9 (Page 2 of 2). Program File Content for QMF Swiss French

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD5E.F3	PDS	FB	80	8800
IBM.JSQDD5E.F4	PDS	FB	80	8800
IBM.JSQDD5E.F5	PDS	F	400	400
IBM.JSQDD5E.F6	PDS	FB	80	8800
IBM.JSQDD5E.F7	PDS	U	0	6144
IBM.JSQDD5E.F8	PDS	FB	80	8800
IBM.JSQDD5E.F9	PDS	V	32622	32626
IBM.JSQDD5E.F10	PDS	FB	80	8800
IBM.JSQDD5E.F11	PDS	FB	80	8800
IBM.JSQDD5E.F12	PDS	FB	80	8800

Figure 10. Program File Content for QMF Swiss German

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5F.F1	PDS	FB	80	8800
IBM.JSQDD5F.F2	PDS	FB	80	8800
IBM.JSQDD5F.F3	PDS	FB	80	8800
IBM.JSQDD5F.F4	PDS	FB	80	8800
IBM.JSQDD5F.F5	PDS	F	400	400
IBM.JSQDD5F.F6	PDS	FB	80	8800
IBM.JSQDD5F.F7	PDS	U	0	6144
IBM.JSQDD5F.F8	PDS	FB	80	8800
IBM.JSQDD5F.F9	PDS	V	32622	32626
IBM.JSQDD5F.F10	PDS	FB	80	8800
IBM.JSQDD5F.F11	PDS	FB	80	8800
IBM.JSQDD5F.F12	PDS	FB	80	8800

Figure 11. Program File Content for QMF Canadian French

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD5G.F1	PDS	FB	80	8800
IBM.JSQDD5G.F2	PDS	FB	80	8800
IBM.JSQDD5G.F3	PDS	FB	80	8800
IBM.JSQDD5G.F4	PDS	FB	80	8800
IBM.JSQDD5G.F5	PDS	F	400	400
IBM.JSQDD5G.F6	PDS	FB	80	8800
IBM.JSQDD5G.F7	PDS	U	0	6144
IBM.JSQDD5G.F8	PDS	FB	80	8800
IBM.JSQDD5G.F9	PDS	V	32622	32626
IBM.JSQDD5G.F10	PDS	FB	80	8800
IBM.JSQDD5G.F11	PDS	FB	80	8800
IBM.JSQDD5G.F12	PDS	FB	80	8800

Figure 12 (Page 1 of 2). Program File Content for QMF Uppercase English

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD51.F1	PDS	FB	80	8800
IBM.JSQDD51.F2	PDS	FB	80	8800
IBM.JSQDD51.F3	PDS	FB	80	8800
IBM.JSQDD51.F4	PDS	FB	80	8800
IBM.JSQDD51.F5	PDS	F	400	400
IBM.JSQDD51.F6	PDS	FB	80	8800
IBM.JSQDD51.F7	PDS	U	0	6144
IBM.JSQDD51.F8	PDS	FB	80	8800
IBM.JSQDD51.F9	PDS	V	32622	32626
IBM.JSQDD51.F10	PDS	FB	80	8800

Figure 12 (Page 2 of 2). Program File Content for QMF Uppercase English

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD51.F11	PDS	FB	80	8800
IBM.JSQDD51.F12	PDS	FB	80	8800

Figure 13. Program File Content for QMF Danish

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD55.F1	PDS	FB	80	8800
IBM.JSQDD55.F2	PDS	FB	80	8800
IBM.JSQDD55.F3	PDS	FB	80	8800
IBM.JSQDD55.F4	PDS	FB	80	8800
IBM.JSQDD55.F5	PDS	F	400	400
IBM.JSQDD55.F6	PDS	FB	80	8800
IBM.JSQDD55.F7	PDS	U	0	6144
IBM.JSQDD55.F8	PDS	FB	80	8800
IBM.JSQDD55.F9	PDS	V	32622	32626
IBM.JSQDD55.F10	PDS	FB	80	8800
IBM.JSQDD55.F11	PDS	FB	80	8800
IBM.JSQDD55.F12	PDS	FB	80	8800

Figure 14 (Page 1 of 2). Program File Content for QMF French

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD56.F1	PDS	FB	80	8800
IBM.JSQDD56.F2	PDS	FB	80	8800

Figure 14 (Page 2 of 2). Program File Content for QMF French

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD56.F3	PDS	FB	80	8800
IBM.JSQDD56.F4	PDS	FB	80	8800
IBM.JSQDD56.F5	PDS	F	400	400
IBM.JSQDD56.F6	PDS	FB	80	8800
IBM.JSQDD56.F7	PDS	U	0	6144
IBM.JSQDD56.F8	PDS	FB	80	8800
IBM.JSQDD56.F9	PDS	V	32622	32626
IBM.JSQDD56.F10	PDS	FB	80	8800
IBM.JSQDD56.F11	PDS	FB	80	8800
IBM.JSQDD56.F12	PDS	FB	80	8800

Figure 15. Program File Content for QMF German

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD57.F1	PDS	FB	80	8800
IBM.JSQDD57.F2	PDS	FB	80	8800
IBM.JSQDD57.F3	PDS	FB	80	8800
IBM.JSQDD57.F4	PDS	FB	80	8800
IBM.JSQDD57.F5	PDS	F	400	400
IBM.JSQDD57.F6	PDS	FB	80	8800
IBM.JSQDD57.F7	PDS	U	0	6144
IBM.JSQDD57.F8	PDS	FB	80	8800
IBM.JSQDD57.F9	PDS	V	32622	32626
IBM.JSQDD57.F10	PDS	FB	80	8800
IBM.JSQDD57.F11	PDS	FB	80	8800
IBM.JSQDD57.F12	PDS	FB	80	8800

Figure 16. Program File Content for QMF Italian

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD58.F1	PDS	FB	80	8800
IBM.JSQDD58.F2	PDS	FB	80	8800
IBM.JSQDD58.F3	PDS	FB	80	8800
IBM.JSQDD58.F4	PDS	FB	80	8800
IBM.JSQDD58.F5	PDS	F	400	400
IBM.JSQDD58.F6	PDS	FB	80	8800
IBM.JSQDD58.F7	PDS	U	0	6144
IBM.JSQDD58.F8	PDS	FB	80	8800
IBM.JSQDD58.F9	PDS	V	32622	32626
IBM.JSQDD58.F10	PDS	FB	80	8800
IBM.JSQDD58.F11	PDS	FB	80	8800
IBM.JSQDD58.F12	PDS	FB	80	8800

Figure 17 (Page 1 of 2). Program File Content for QMF Japanese

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.JSQDD59.F1	PDS	FB	80	8800
IBM.JSQDD59.F2	PDS	FB	80	8800
IBM.JSQDD59.F3	PDS	FB	80	8800
IBM.JSQDD59.F4	PDS	FB	80	8800
IBM.JSQDD59.F5	PDS	F	400	400
IBM.JSQDD59.F6	PDS	FB	80	8800
IBM.JSQDD59.F7	PDS	U	0	6144
IBM.JSQDD59.F8	PDS	FB	80	8800
IBM.JSQDD59.F9	PDS	V	32622	32626
IBM.JSQDD59.F10	PDS	FB	80	8800

Figure 17 (Page 2 of 2). Program File Content for QMF Japanese

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JSQDD59.F11	PDS	FB	80	8800
IBM.JSQDD59.F12	PDS	FB	80	8800

2.2 Program Publications

The basic publications for QMF Classic Edition - NLV are available in online IBM Documentation.

2.2.1 Unlicensed publications for QMF Classic Edition - NLV

The complete library of QMF publications may be found in the online product documentation at the following site;

<https://www.ibm.com/docs/en/qmf>

2.2.2 Optional Program Publications

No optional publications are provided for QMF Classic Edition - NLV. For product information see the online IBM Documentation.

2.3 Program Source Materials

No program source materials or viewable program listings are provided for QMF Classic Edition - NLV.

2.4 Publications Useful During Installation

You might want to use the publications listed in Figure 18 during the installation of QMF Classic Edition - NLV.

Figure 18 (Page 1 of 2). Publications Useful During Installation

Publication Title	Form Number
<i>IBM SMP/E for z/OS User's Guide</i>	SA23-2277
<i>IBM SMP/E for z/OS Commands</i>	SA23-2275

Figure 18 (Page 2 of 2). Publications Useful During Installation

Publication Title	Form Number
<i>IBM SMP/E for z/OS Reference</i>	SA23-2276
<i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i>	GA32-0883

Note: These publications can be found in IBM Documentation. Use a web browser with internet access to refer to: <https://www.ibm.com/docs/en/zos/2.5.0?topic=zos-smpe>

3.0 Program Support

This section describes the IBM support available for QMF Classic Edition - NLV.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before you install QMF Classic Edition - NLV, make sure that you have reviewed the current Preventive Service Planning (PSP) information. Review the PSP Bucket for General Information, Installation Documentation, and the Cross Product Dependencies sections. For the Recommended Service section, instead of reviewing the PSP Bucket, it is recommended you use the IBM.PRODUCTINSTALL-REQUIRESERVICE fix category in SMP/E to ensure you have all the recommended service installed. Use the **FIXCAT(IBM.PRODUCTINSTALL-REQUIRESERVICE)** operand on the **APPLY CHECK** command. See 6.1.10, "Perform SMP/E APPLY" on page 60 for a sample APPLY command

If you obtained QMF Classic Edition - NLV as part of a CBPDO, HOLDDATA is included.

If the CBPDO for QMF Classic Edition - NLV is older than two weeks by the time you install the product materials, you can obtain the latest PSP Bucket information by going to the following website:

<https://esupport.ibm.com/customercare/psearch/search?domain=psp>

You can also use S/390 SoftwareXcel or contact the IBM Support Center to obtain the latest PSP Bucket information.

For program support, access the Software Support Website at <https://www.ibm.com/mysupport/>.

PSP Buckets are identified by UPGRADEs, which specify product levels; and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for QMF Classic Edition - NLV are included in Figure 19.

Figure 19 (Page 1 of 2). PSP Upgrade and Subset ID

UPGRADE	SUBSET	Description
	HSQDD10	QMF TSO/CICS Base
	HHPCC10	QMF HPO
	JYQDD10	QMF applications

Figure 19 (Page 2 of 2). PSP Upgrade and Subset ID

UPGRADE	SUBSET	Description
	JSQDD1C	QMF Classic Edition Identifier
	JSQDD5A	QMF Korean
	JSQDD5B	QMF Brazilian Portuguese
	JSQDD5C	QMF Spanish
	JSQDD5D	QMF Swedish
	JSQDD5E	QMF Swiss French
	JSQDD5F	QMF Swiss German
	JSQDD5G	QMF Canadian French
	JSQDD51	QMF Uppercase English
	JSQDD55	QMF Danish
	JSQDD56	QMF French
	JSQDD57	QMF German
	JSQDD58	QMF Italian
	JSQDD59	QMF Japanese

3.3 Statement of Support Procedures

Report any problems which you feel might be an error in the product materials to your IBM Support Center. You may be asked to gather and submit additional diagnostics to assist the IBM Support Center in their analysis.

Figure 20 identifies the component IDs (COMPID) for QMF Classic Edition - NLV.

Figure 20 (Page 1 of 2). Component IDs

FMID	COMPID	Component Name	RETAIN Release
HSQDD10	566872101	QMF TSO/CICS Base	D10
HHPCC10	5668HPO00	QMF HPO	C10
JYQDD10	5668QCA00	QMF applications	D10
JSQDD1C	566872101	QMF Classic Edition Identifier	D1C
JSQDD5A	566872101	QMF Korean	D5A
JSQDD5B	566872101	QMF Brazilian Portuguese	D5B
JSQDD5C	566872101	QMF Spanish	D5C

Figure 20 (Page 2 of 2). Component IDs

FMID	COMPID	Component Name	RETAIN Release
JSQDD5D	566872101	QMF Swedish	D5D
JSQDD5E	566872101	QMF Swiss French	D5E
JSQDD5F	566872101	QMF Swiss German	D5F
JSQDD5G	566872101	QMF Canadian French	D5G
JSQDD51	566872101	QMF Uppercase English	D51
JSQDD55	566872101	QMF Danish	D55
JSQDD56	566872101	QMF French	D56
JSQDD57	566872101	QMF German	D57
JSQDD58	566872101	QMF Italian	D58
JSQDD59	566872101	QMF Japanese	D59

4.0 Program and Service Level Information

This section identifies the program and relevant service levels of QMF Classic Edition - NLV. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

4.1 Program Level Information

All PTFs for previous releases of QMF Classic Edition - NLV that were closed on or before February 16, 2022 are incorporated into QMF Version 13.

4.2 Service Level Information

No PTFs against this release of QMF Classic Edition - NLV have been incorporated into the product package.

Frequently check the QMF Classic Edition - NLV PSP Bucket for HIPER and SPECIAL attention PTFs against all FMIDs that you must install. You can also receive the latest HOLDDATA, then add the **FIXCAT(IBM.PRODUCTINSTALL-REQUIRESERVICE)** operand on your **APPLY CHECK** command. This will allow you to review the recommended and critical service that should be installed with your FMIDs.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating QMF Classic Edition - NLV. The following terminology is used:

- *Driving system*: the system on which SMP/E is executed to install the program.
The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.
- *Target system*: the system on which the program is configured and run.
The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

- When you install a new level of a product that is already installed, the new level of the product will replace the old one. By installing the new level onto a separate target system, you can test the new level and keep the old one in production at the same time.
- When you install a product that shares libraries or load modules with other products, the installation can disrupt the other products. By installing the product onto a separate target system, you can assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install QMF Classic Edition - NLV.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

Figure 21. Driving System Software Requirements

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	02.03.00	N/A	No

Note: SMP/E is a requirement for Installation and is an element of z/OS.

Note: Installation might require migration to new z/OS releases to be service supported. See <https://www.ibm.com/support/lifecycle/>

5.2 Target System Requirements

This section describes the environment of the target system required to install and use QMF Classic Edition - NLV.

QMF Classic Edition - NLV installs in the DBS (P115) SREL.

5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites

Installation requisites identify products that are required and *must* be present on the system or products that are not required but *should* be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product. These products are specified as PREs or REQs.

Figure 22 (Page 1 of 2). Target System Mandatory Installation Requisites

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	02.03.00 or higher	N/A	No
Any one of the following:				

Figure 22 (Page 2 of 2). Target System Mandatory Installation Requisites

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-DB2	IBM Db2 12 for z/OS	12.01.00 or higher	N/A	No
5770-AF3	IBM Db2 12 for z/OS Value Unit Edition	12.01.00 or higher	N/A	No
5698-DB2	IBM Db2 13 for z/OS	13.01.00	N/A	No
5698-DBV	IBM Db2 13 for z/OS Value Unit Edition	13.01.00	N/A	No

Note: Installation might require migration to new releases to obtain support. See <https://www.ibm.com/support/lifecycle/>

Conditional installation requisites identify products that are *not* required for successful installation of this product but can resolve such things as certain warning messages at installation time. These products are specified as IF REQs.

QMF Classic Edition - NLV has no conditional installation requisites.

5.2.2.2 Operational Requisites

Operational requisites are products that are required and *must* be present on the system or products that are not required but *should* be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions.

Figure 23 (Page 1 of 2). Target System Mandatory Operational Requisites

Program Number	Product Name and Minimum VRM/Service Level
Any one of the following:	
5650-DB2	IBM Db2 12 for z/OS
5770-AF3	IBM Db2 12 for z/OS Value Unit Edition
5698-DB2	IBM Db2 13 for z/OS

Figure 23 (Page 2 of 2). Target System Mandatory Operational Requisites

Program Number	Product Name and Minimum VRM/Service Level
5698-DBV	IBM Db2 13 for z/OS Value Unit Edition
Any one of the following (for QMF under CICS only)	
5655-Y04	IBM CICS Transaction Server for z/OS, 5.5
5655-Y04	IBM CICS Transaction Server for z/OS, 5.6

Note: Installation might require migration to new releases to obtain support. See <https://www.ibm.com/support/lifecycle/>

Conditional operational requisites identify products that are *not* required for this product to operate its basic functions but are required at run time for this product to operate specific functions. These products are specified as IF REQs.

QMF Classic Edition - NLV has no conditional operational requisites.

5.2.2.3 Toleration/Coexistence Requisites

Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

QMF Classic Edition - NLV has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites

Negative requisites identify products that must *not* be installed on the same system as this product.

QMF Classic Edition - NLV has no negative requisites.

5.2.3 DASD Storage Requirements

QMF Classic Edition - NLV libraries can reside on all supported DASD types.

Figure 24 lists the total space that is required for each type of library.

Figure 24. Total DASD Space Required by QMF Classic Edition - NLV

Library Type	Total Space Required in 3390 Trks	Description
Target	7336	
Distribution	6488	

Figure 25. Total DASD Space Required by any National Language Version

Library Type	Total Space Required in 3390 Trks
Target	281
Distribution	328

Notes:

1. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.
2. Abbreviations used for data set types are shown as follows.

- U** Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
- S** Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- E** Existing shared data set, used by this product and other products. This data set is *not* allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.8, "Allocate SMP/E Target and Distribution Libraries" on page 59.

3. Abbreviations used for the file system path type are as follows.

- N** New path, created by this product.
- X** Path created by this product, but might already exist from a previous release.
- P** Previously existing path, created by another product.

4. All target and distribution libraries listed have the following attributes:

- The default name of the data set can be changed.
- The default block size of the data set can be changed.
- The data set can be merged with another data set that has equivalent characteristics.
- The data set can be either a PDS or a PDSE, with some exceptions. If the value in the "ORG" column specifies "PDS", the data set must be a PDS. If the value in "DIR Blks" column specifies "N/A", the data set must be a PDSE.

5. All target libraries listed have the following attributes:

- These data sets can be SMS-managed, but they are not required to be SMS-managed.
- These data sets are not required to reside on the IPL volume.
- The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.

6. All target libraries that are listed and contain load modules have the following attributes:

- These data sets can not be in the LPA, with some exceptions. If the data set should be placed in the LPA, see the Special Considerations section below.
- These data sets can be in the LNKLIST. If so, see the Special Considerations section below.
- These data sets are not required to be APF-authorized, with some exceptions. If the data set must be APF-authorized, see the Special Considerations section below.

If you are installing a National Language in this document, please refer to the following table which associates a lettered language identifier to each National Language. The language identifier is the last character shown in the Storage Requirement figures for the Target, Distribution and Non-SMP/E data set names.

This language identifier does not apply to the QMF for TSO/CICS base.

Figure 26 (Page 1 of 2). QMF National Language Identifiers

Language	Language Identifier	F MID
QMF Korean	H	JSQDD5A
QMF Brazilian Portuguese	P	JSQDD5B
QMF Spanish	S	JSQDD5C
QMF Swedish	V	JSQDD5D
QMF Swiss French	Y	JSQDD5E
QMF Swiss German	Z	JSQDD5F
QMF Canadian French	C	JSQDD5G
QMF Uppercase English	U	JSQDD51

Figure 26 (Page 2 of 2). QMF National Language Identifiers

Language	Language Identifier	F MID
QMF Danish	Q	JSQDD55
QMF French	F	JSQDD56
QMF German	D	JSQDD57
QMF Italian	I	JSQDD58
QMF Japanese	K	JSQDD59

The following figures describe the target and distribution libraries required to install QMF Classic Edition - NLV. The storage requirements of QMF Classic Edition - NLV must be added to the storage required by other programs that have data in the same library or path.

Note: Use the data in these tables to determine which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

Figure 27. Storage Requirements for QMF for TSO/CICS Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C O R D S	L E N G T H	No. of 3390 Trks	No. of DIR Blks
SDSQBASE	SAMP	Any	U	PDS	FB	80	9	5
SDSQCHRT	DATA	Any	U	PDS	FB	400	2	5
SDSQCLTE	CLIST	Any	U	PDS	FB	80	34	5
SDSQDBRM	MAC	Any	U	PDS	FB	80	10	5
SDSQEXCE	EXEC	Any	U	PDS	FB	80	21	5
SDSQEXIT	LMOD	Any	U	PDS	U	0	4	5
SDSQLOAD	LMOD	Any	U	PDS	U	0	1626	30
SDSQMAPE	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBE	MSGENU	Any	U	PDS	FB	80	6	5
SDSQPLBE	PNLENU	Any	U	PDS	FB	80	22	10
SDSQPVRE	DATA	Any	U	PDS	V	32622	200	5
SDSQSAPE	MAC	Any	U	PDS	FB	80	51	15
SDSQSLBE	MAC	Any	U	PDS	FB	80	6	5
SDSQTLBE	TBL	Any	U	PDS	FB	80	17	5
SDSQUSRE	MAC	Any	U	PDS	FB	80	26	5

Figure 28. Storage Requirements for QMF HPO Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SRAACLST	CLIST	Any	U	PDS	FB	80	20	5
SRAADBRM	MAC	Any	U	PDS	FB	80	40	5
SRAAEXEC	EXEC	Any	U	PDS	FB	80	5	5
SRAAISPM	MSGENU	Any	U	PDS	FB	80	25	20
SRAAISPP	PNLENU	Any	U	PDS	FB	80	160	90
SRAALOAD	MOD	Any	U	PDS	U	0	400	25
SRAASAMP	SAMP	Any	U	PDS	FB	80	30	10
SRAASKEL	DATA	Any	U	PDS	FB	80	120	5

Figure 29. Storage Requirements for QMF applications Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDYQCFG	DATA	Any	U	PDS	FB	80	5	5

Figure 30 (Page 1 of 6). Storage Requirements for QMF Classic Edition - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQCLTH	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCH	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPH	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBH	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBH	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRH	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMH	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPH	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBH	TBL	Any	U	PDS	FB	80	11	5

Figure 30 (Page 2 of 6). Storage Requirements for QMF Classic Edition - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQUSRH	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTP	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCP	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPP	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBP	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBP	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRP	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMP	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPP	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBP	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRP	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTS	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCS	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPS	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBS	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBS	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRS	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMS	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPS	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBS	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRS	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTV	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCV	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPV	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBV	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBV	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRV	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMV	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPV	SAMPLE	Any	U	PDS	FB	80	56	15

Figure 30 (Page 3 of 6). Storage Requirements for QMF Classic Edition - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQTLBV	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRV	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTY	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCY	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPY	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBY	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBY	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRY	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMY	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPY	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBY	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRY	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTZ	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCZ	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPZ	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBZ	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBZ	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRZ	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMZ	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPZ	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBZ	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRZ	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTC	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCC	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPC	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBC	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBC	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRC	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMC	SAMPLE	Any	U	PDS	FB	80	16	5

Figure 30 (Page 4 of 6). Storage Requirements for QMF Classic Edition - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQSAPC	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBC	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRC	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTU	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCU	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPU	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBU	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBU	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRU	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMU	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPU	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBU	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRU	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTQ	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCQ	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPQ	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBQ	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBQ	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRQ	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMQ	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPQ	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBQ	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRQ	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTF	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCF	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPF	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBF	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBF	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRF	DATA	Any	U	PDS	V	32622	150	5

Figure 30 (Page 5 of 6). Storage Requirements for QMF Classic Edition - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQSAMF	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPF	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBF	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRF	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTD	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCD	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPD	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBD	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBD	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRD	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMD	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPD	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBD	TBL	Any	U	PDS	FB	80	5	10
SDSQUSRD	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTI	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCI	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPI	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBI	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBI	PANEL	Any	U	PDS	FB	80	22	5
SDSQPVRI	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMI	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPI	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBI	TBL	Any	U	PDS	FB	80	11	5
SDSQUSRI	SAMPLE	Any	U	PDS	FB	80	26	5
SDSQCLTK	CLIST	Any	U	PDS	FB	80	34	5
SDSQEXCK	EXEC	Any	U	PDS	FB	80	14	5
SDSQMAPK	DATA	Any	U	PDS	FB	400	5	5
SDSQMLBK	MSG	Any	U	PDS	FB	80	7	5
SDSQPLBK	PANEL	Any	U	PDS	FB	80	22	5

Figure 30 (Page 6 of 6). Storage Requirements for QMF Classic Edition - NLV Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SDSQPVRK	DATA	Any	U	PDS	V	32622	150	5
SDSQSAMK	SAMPLE	Any	U	PDS	FB	80	16	5
SDSQSAPK	SAMPLE	Any	U	PDS	FB	80	56	15
SDSQTLBK	TBL	Any	U	PDS	FB	80	5	10
SDSQUSRK	SAMPLE	Any	U	PDS	FB	80	26	5

Figure 31. Storage Requirements for QMF for TSO/CICS Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQBASE	U	PDS	FB	80	9	5
ADSQCHRT	U	PDS	FB	400	2	5
ADSQCLTE	U	PDS	FB	80	34	5
ADSQDBRM	U	PDS	FB	80	10	5
ADSQEXCE	U	PDS	FB	80	14	5
ADSQLOAD	U	PDS	U	0	7	5
ADSQMAPE	U	PDS	FB	400	5	5
ADSQMLBE	U	PDS	FB	80	6	5
ADSQOBJ	U	PDS	U	0	1005	200
ADSQPLBE	U	PDS	FB	80	19	10
ADSQPVRE	U	PDS	V	32622	150	5
ADSQSAPE	U	PDS	FB	80	51	15
ADSQSLBE	U	PDS	FB	80	6	5
ADSQTLBE	U	PDS	FB	80	17	5
ADSQUSRE	U	PDS	FB	80	26	5

Figure 32. Storage Requirements for QMF HPO Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ARAACLST	U	PDS	FB	80	20	5
ARAADBRM	U	PDS	FB	80	40	5
ARAAEXEC	U	PDS	FB	80	5	5
ARAAISPM	U	PDS	FB	80	25	20
ARAAISPP	U	PDS	FB	80	160	90
ARAALOAD	U	PDS	U	0	250	15
ARAASAMP	U	PDS	FB	80	20	10
ARAASKEL	U	PDS	FB	80	120	5

Figure 33. Storage Requirements for QMF applications Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADYQCFG	U	PDS	FB	80	5	5

Figure 34 (Page 1 of 6). Storage Requirements for QMF Classic Edition - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQCLTH	U	PDS	FB	80	16	5
ADSQEXCH	U	PDS	FB	80	16	5
ADSQMAPH	U	PDS	FB	400	5	5
ADSQMLBH	U	PDS	FB	80	16	5
ADSQPLBH	U	PDS	FB	80	26	5
ADSQPVRH	U	PDS	V	32622	150	5
ADSQSAMH	U	PDS	FB	80	16	5
ADSQSAPH	U	PDS	FB	80	51	15
ADSQTLBH	U	PDS	FB	80	16	5

Figure 34 (Page 2 of 6). Storage Requirements for QMF Classic Edition - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQUSRH	U	PDS	FB	80	16	5
ADSQCLTP	U	PDS	FB	80	16	5
ADSQEXCP	U	PDS	FB	80	16	5
ADSQMAPP	U	PDS	FB	400	5	5
ADSQMLBP	U	PDS	FB	80	16	5
ADSQPLBP	U	PDS	FB	80	26	5
ADSQPVRP	U	PDS	V	32622	150	5
ADSQSAMP	U	PDS	FB	80	16	5
ADSQSAPP	U	PDS	FB	80	51	15
ADSQTLBP	U	PDS	FB	80	16	5
ADSQUSRP	U	PDS	FB	80	16	5
ADSQCLTS	U	PDS	FB	80	16	5
ADSQEXCS	U	PDS	FB	80	16	5
ADSQMAPS	U	PDS	FB	400	5	5
ADSQMLBS	U	PDS	FB	80	16	5
ADSQPLBS	U	PDS	FB	80	26	5
ADSQPVRS	U	PDS	V	32622	150	5
ADSQSAMS	U	PDS	FB	80	16	5
ADSQSAPS	U	PDS	FB	80	51	15
ADSQTLBS	U	PDS	FB	80	16	5
ADSQUSRS	U	PDS	FB	80	16	5
ADSQCLTV	U	PDS	FB	80	16	5
ADSQEXCV	U	PDS	FB	80	16	5
ADSQMAPV	U	PDS	FB	400	5	5
ADSQMLBV	U	PDS	FB	80	16	5
ADSQPLBV	U	PDS	FB	80	26	5
ADSQPVRV	U	PDS	V	32622	150	5
ADSQSAMV	U	PDS	FB	80	16	5
ADSQSAPV	U	PDS	FB	80	51	15

Figure 34 (Page 3 of 6). Storage Requirements for QMF Classic Edition - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQTLBV	U	PDS	FB	80	16	5
ADSQUSRV	U	PDS	FB	80	16	5
ADSQCLTY	U	PDS	FB	80	16	5
ADSQEXCY	U	PDS	FB	80	16	5
ADSQMAPY	U	PDS	FB	400	5	5
ADSQMLBY	U	PDS	FB	80	16	5
ADSQPLBY	U	PDS	FB	80	26	5
ADSQPVRV	U	PDS	V	32622	150	5
ADSQSAMY	U	PDS	FB	80	16	5
ADSQSAPY	U	PDS	FB	80	51	15
ADSQTLBY	U	PDS	FB	80	16	5
ADSQUSRY	U	PDS	FB	80	16	5
ADSQCLTZ	U	PDS	FB	80	16	5
ADSQEXCZ	U	PDS	FB	80	16	5
ADSQMAPZ	U	PDS	FB	400	5	5
ADSQMLBZ	U	PDS	FB	80	16	5
ADSQPLBZ	U	PDS	FB	80	26	5
ADSQPVRZ	U	PDS	V	32622	150	5
ADSQSAMZ	U	PDS	FB	80	16	5
ADSQSAPZ	U	PDS	FB	80	51	15
ADSQTLBZ	U	PDS	FB	80	16	5
ADSQUSRZ	U	PDS	FB	80	26	5
ADSQCLTC	U	PDS	FB	80	16	5
ADSQEXCC	U	PDS	FB	80	16	5
ADSQMAPC	U	PDS	FB	400	5	5
ADSQMLBC	U	PDS	FB	80	16	5
ADSQPLBC	U	PDS	FB	80	26	5
ADSQPVRC	U	PDS	V	32622	150	5
ADSQSAMC	U	PDS	FB	80	16	5

Figure 34 (Page 4 of 6). Storage Requirements for QMF Classic Edition - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQSAPC	U	PDS	FB	80	51	15
ADSQTLBC	U	PDS	FB	80	16	5
ADSQUSRC	U	PDS	FB	80	26	5
ADSQCLTU	U	PDS	FB	80	16	5
ADSQEXCU	U	PDS	FB	80	16	5
ADSQMAPU	U	PDS	FB	400	5	5
ADSQMLBU	U	PDS	FB	80	16	5
ADSQPLBU	U	PDS	FB	80	26	5
ADSQPVRU	U	PDS	V	32622	150	5
ADSQSAMU	U	PDS	FB	80	16	5
ADSQSAPU	U	PDS	FB	80	51	15
ADSQTLBU	U	PDS	FB	80	16	5
ADSQUSRU	U	PDS	FB	80	26	5
ADSQCLTQ	U	PDS	FB	80	16	5
ADSQEXCQ	U	PDS	FB	80	16	5
ADSQMAPQ	U	PDS	FB	400	5	5
ADSQMLBQ	U	PDS	FB	80	16	5
ADSQPLBQ	U	PDS	FB	80	26	5
ADSQPVRQ	U	PDS	V	32622	150	5
ADSQSAMQ	U	PDS	FB	80	16	5
ADSQSAPQ	U	PDS	FB	80	51	15
ADSQTLBQ	U	PDS	FB	80	16	5
ADSQUSRQ	U	PDS	FB	80	26	5
ADSQCLTF	U	PDS	FB	80	16	5
ADSQEXCF	U	PDS	FB	80	16	5
ADSQMAPF	U	PDS	FB	400	5	5
ADSQMLBF	U	PDS	FB	80	16	5
ADSQPLBF	U	PDS	FB	80	26	5
ADSQPVRF	U	PDS	V	32622	150	5

Figure 34 (Page 5 of 6). Storage Requirements for QMF Classic Edition - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQSAMF	U	PDS	FB	80	16	5
ADSQSAPF	U	PDS	FB	80	51	15
ADSQTLBF	U	PDS	FB	80	16	5
ADSQUSRF	U	PDS	FB	80	26	5
ADSQCLTD	U	PDS	FB	80	16	5
ADSQEXCD	U	PDS	FB	80	16	5
ADSQMAPD	U	PDS	FB	400	5	5
ADSQMLBD	U	PDS	FB	80	16	5
ADSQPLBD	U	PDS	FB	80	26	5
ADSQPVRD	U	PDS	V	32622	150	5
ADSQSAMD	U	PDS	FB	80	16	5
ADSQSAPD	U	PDS	FB	80	51	15
ADSQTLBD	U	PDS	FB	80	16	5
ADSQUSRD	U	PDS	FB	80	26	5
ADSQCLTI	U	PDS	FB	80	16	5
ADSQEXCI	U	PDS	FB	80	16	5
ADSQMAPI	U	PDS	FB	400	5	5
ADSQMLBI	U	PDS	FB	80	16	5
ADSQPLBI	U	PDS	FB	80	26	5
ADSQPVRI	U	PDS	V	32622	150	5
ADSQSAMI	U	PDS	FB	80	16	5
ADSQSAPI	U	PDS	FB	80	51	15
ADSQTLBI	U	PDS	FB	80	16	5
ADSQUSRI	U	PDS	FB	80	26	5
ADSQCLTK	U	PDS	FB	80	16	5
ADSQEXCK	U	PDS	FB	80	16	5
ADSQMAPK	U	PDS	FB	400	5	5
ADSQMLBK	U	PDS	FB	80	16	5
ADSQPLBK	U	PDS	FB	80	26	5

Figure 34 (Page 6 of 6). Storage Requirements for QMF Classic Edition - NLV Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ADSQPVRK	U	PDS	V	32622	150	5
ADSQSAMK	U	PDS	FB	80	16	5
ADSQSAPK	U	PDS	FB	80	51	15
ADSQTLBK	U	PDS	FB	80	16	5
ADSQUSRK	U	PDS	FB	80	26	5

The following figures list data sets that are not used by SMP/E, but are required for QMF Classic Edition - NLV to run.

The following figures list data sets that are not used by SMP/E, but are required for QMF Classic Edition - NLV to run.

Figure 35. Storage Requirements for QMF Classic Edition - NLV Non-SMP/E Data Sets

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
DSQPNLE	U	VSAM	VS	32756	135	n/a
DSQPNLH	U	VSAM	VS	32756	135	n/a
DSQPNLP	U	VSAM	VS	32756	135	n/a
DSQPNLS	U	VSAM	VS	32756	135	n/a
DSQPNLV	U	VSAM	VS	32756	135	n/a
DSQPNLY	U	VSAM	VS	32756	135	n/a
DSQPNLZ	U	VSAM	VS	32756	135	n/a
DSQPNLC	U	VSAM	VS	32756	135	n/a
DSQPNLU	U	VSAM	VS	32756	135	n/a
DSQPNLQ	U	VSAM	VS	32756	135	n/a
DSQPNLF	U	VSAM	VS	32756	135	n/a
DSQPNLD	U	VSAM	VS	32756	135	n/a
DSQPNLI	U	VSAM	VS	32756	135	n/a
DSQPNLK	U	VSAM	VS	32756	135	n/a

5.3 FMIDs Deleted

Installing QMF Classic Edition - NLV might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install QMF Classic Edition - NLV into separate SMP/E target and distribution zones.

Note: These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, use the SMP/E REJECT NOFMID DELETEFMID command. See the SMP/E Commands book for details.

5.4 Special Considerations

- Db2 QMF TSO and CICS Clients' Special Requirements:
 - Operates on any z Systems hardware configuration that supports the required software.
 - Runs on any processor that is supported by the operating system. Some operations, however, will not work with columns that contain decimal floating point data if the processor on which QMF is running does not support decimal floating point instructions.
 - Accesses all of the DASD devices that are supported by z/OS and Db2 for z/OS, as well as all display devices supported by Graphical Data Display Manager (GDDM).
 - To implement a national language feature that uses a double-byte character set (DBCS), you need a workstation that supports DBCS. Ensure that this device is supported by GDDM.
 - When you plan your region size, consider the storage required to load modules during initialization and the virtual storage requirements for report operations.
 - Restriction: For TSO only, consider the amount of space required to run applications other than Db2 QMF.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of QMF Classic Edition - NLV.

Please note the following points:

- If you want to install QMF Classic Edition - NLV into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.
- You can use the SMP/E dialogs instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing QMF Classic Edition - NLV

6.1.1 SMP/E Considerations for Installing QMF Classic Edition - NLV

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of QMF Classic Edition - NLV.

6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 36. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

Figure 36. SMP/E Options Subentry Values

Subentry	Value	Comment
DSSPACE	(500,500,500)	3390 DASD tracks
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

6.1.3 SMP/E CALLIBS and SIDE DECK PROCESSING

QMF Classic Edition - NLV uses the CALLIBS function provided in SMP/E to resolve external references during installation. When QMF Classic Edition - NLV is installed, ensure that DDDEFs exist for the following libraries:

- SADMMOD
- SCEELKED
- SCEESPC
- SDFHLOAD
- SDSNLOAD
- SISPLoad

QMF Classic Edition - NLV also uses Side Deck processing during link-edits. When QMF Classic Edition - NLV is installed, ensure that the DDDEFs exist for the following libraries:

- SDSNLOAD

6.1.4 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install IBM Db2 QMF Enterprise Edition - NLV.

<i>Figure 37 (Page 1 of 2). Sample Installation Jobs</i>			
Job Name	Job Type	Description	SMPTLIB Data Set
DSQALA	SMP/E	Sample job to allocate and initialize a new SMP/E CSI data set (Optional)	IBM.HSQDD10.F2
DSQALB	SMP/E	Sample job to allocate SMP/E data sets (Optional)	IBM.HSQDD10.F2
DSQRECV1	RECEIVE	Sample RECEIVE job for QMF TSO/CICS Base	IBM.HSQDD10.F2
DSQRECV2	RECEIVE	Sample RECEIVE job for QMF HPO	IBM.HSQDD10.F2
DSQRECV3	RECEIVE	Sample RECEIVE job for QMF applications	IBM.HSQDD10.F2
DSQRECVE	RECEIVE	Sample RECEIVE job for QMF Classic Edition Identifier	IBM.HSQDD10.F2
DSQALLOC	ALLOCATE	Sample job to allocate target and distribution libraries for QMF (TSO/CICS, HPO and QMF applications)	IBM.HSQDD10.F2
DSQDDEF	DDDEF	Sample job to define SMP/E DDDEFs for QMF (TSO/CICS, HPO and QMF applications)	IBM.HSQDD10.F2
DSQAPPLY	APPLY	Sample APPLY job for QMF (TSO/CICS, HPO and QMF applications)	IBM.HSQDD10.F2

Figure 37 (Page 2 of 2). Sample Installation Jobs

Job Name	Job Type	Description	SMPTLIB Data Set
DSQAPLYE	APPLY	Sample APPLY job for QMF Enterprise Edition Identifier	IBM.HSQDD10.F2
DSQACCEP	ACCEPT	Sample ACCEPT job for QMF (TSO/CICS, HPO and QMF applications)	IBM.HSQDD10.F2
DSQACCEE	ACCEPT	Sample ACCEPT job for QMF Classic Edition Identifier	IBM.HSQDD10.F2

You can access the sample installation jobs by performing an SMP/E RECEIVE (refer to 6.1.7, “Perform SMP/E RECEIVE” on page 58) then copy the jobs from the SMPTLIB data sets to a work data set for editing and submission. See Figure 37 on page 41 to find the appropriate data set.

You can also copy the sample installation jobs from the product files by submitting the following job. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//IN DD DSN=IBM.HSQDD10.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,
// SPACE=(TRK,(primary,secondary,dir))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=IN,OUTDD=OUT
/*
```

See the following information to update the statements in the previous sample:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT:

jcl-library-name is the name of the output data set where the sample jobs are stored.

dasdvol is the volume serial of the DASD device where the output data set resides.


```

//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//*****
/* Make the //TAPEIN DD statement below active if you install*
/* from a CBPDO tape by uncommenting the DD statement below. *
//*****
/*TAPEIN DD DSN=IBM.HSQDD10.F2,UNIT=tunit,
/* VOL=SER=volser,LABEL=(x,SL),
/* DISP=(OLD,KEEP)
/*TAPEIN2 DD DSN=IBM.&FMID5..F2,UNIT=tunit,
/* VOL=SER=volser,LABEL=(x,SL),
/* DISP=(OLD,KEEP)
//*****
/* Make the //TAPEIN DD statement below active if you install*
/* from a product tape received outside the CBPDO process *
/* (using the optional SMP/E RECEIVE job) by uncommenting *
/* the DD statement below. *
//*****
/*TAPEIN DD DSN=IBM.HSQDD10.F2,UNIT=tunit,
/* VOL=SER=SQDD10,LABEL=(3,SL),
/* DISP=(OLD,KEEP)
/*TAPEIN2 DD DSN=IBM.&FMID5..F2.,UNIT=tunit,
/* VOL=SER=QDCC10,LABEL=(3,SL),
/* DISP=(OLD,KEEP)
//*****
/* Make the //FILEIN DD statement below active for *
/* downloaded DASD files. *
//*****
/*FILEIN DD DSN=IBM.HSQDD10.F2,UNIT=SYSALLDA,DISP=SHR,
/* VOL=SER=filevol
/*FILEIN2 DD DSN=IBM.&FMID5..F2.,UNIT=SYSALLDA,DISP=SHR,
/* VOL=SER=filevol
//OUT DD DSNAME=jc1-library-name,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,
// SPACE=(TRK,(20,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
COPY INDD=yyyyIN,OUTDD=OUT
/*

```

See the following information to update the statements in the previous sample:

TAPEIN/TAPEIN2:

- tunit** is the unit value that matches the product package.
- volser** is the volume serial that matches the product package.
- x** is the tape file number that indicates the location of the data set name on the tape.

See the documentation that is provided by CBPDO for the location of IBM.HSQDD10.F2 and IBM.&FMID5..F2 on the tape.

FILEIN/FILEIN2:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT:

jcl-library-name is the name of the output data set where the sample jobs are stored.

dasdvol is the volume serial of the DASD device where the output data set resides.

SYSIN:

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

yyyyIN is either TAPEIN2 or FILEIN2 depending on your input DD statement.

6.1.4.1 Sample Jobs for National Language Version for QMF Korean

<i>Figure 38. Sample Installation Jobs for QMF Korean</i>			
Job Name	Job Type	Description	RELFILE
DSQHRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5A.F2
DSQHALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5A.F2
DSQHDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5A.F2
DSQHAPLY	APPLY	Sample APPLY job	IBM.JSQDD5A.F2
DSQHACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5A.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 38 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD5A.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD5A.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD5A.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.2 Sample Jobs for National Language Version for QMF Brazilian Portuguese

Figure 39. Sample Installation Jobs for QMF Brazilian Portuguese

Job Name	Job Type	Description	RELFILE
DSQPRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5B.F2
DSQPALLOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5B.F2
DSQPDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5B.F2
DSQPAPPLY	APPLY	Sample APPLY job	IBM.JSQDD5B.F2
DSQPACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5B.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 39 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD5B.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD5B.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSN=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD5B.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.3 Sample Jobs for National Language Version for QMF Spanish

<i>Figure 40. Sample Installation Jobs for QMF Spanish</i>			
Job Name	Job Type	Description	RELFILE
DSQSRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5C.F2
DSQSALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5C.F2
DSQSDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5C.F2
DSQSAPLY	APPLY	Sample APPLY job	IBM.JSQDD5C.F2
DSQSACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5C.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 40 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD5C.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD5C.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD5C.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.4 Sample Jobs for National Language Version for QMF Swedish

Figure 41. Sample Installation Jobs for QMF Swedish

Job Name	Job Type	Description	RELFILE
DSQVRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5D.F2
DSQVALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5D.F2
DSQVDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5D.F2
DSQVAPLY	APPLY	Sample APPLY job	IBM.JSQDD5D.F2
DSQVACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5D.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 41 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD5D.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD5D.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD5D.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.5 Sample Jobs for National Language Version for QMF Swiss French

<i>Figure 42. Sample Installation Jobs for QMF Swiss French</i>			
Job Name	Job Type	Description	RELFILE
DSQYRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5E.F2
DSQYALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5E.F2
DSQYDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5E.F2
DSQYAPLY	APPLY	Sample APPLY job	IBM.JSQDD5E.F2
DSQYACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5E.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 42 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD5E.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD5E.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSN=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD5E.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.6 Sample Jobs for National Language Version for QMF Swiss German

Figure 43. Sample Installation Jobs for QMF Swiss German

Job Name	Job Type	Description	RELFIL
DSQZRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5F.F2
DSQZALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5F.F2
DSQZDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5F.F2
DSQZAPLY	APPLY	Sample APPLY job	IBM.JSQDD5F.F2
DSQZACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5F.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 43 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD5F.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD5F.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSN=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD5F.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.7 Sample Jobs for National Language Version for QMF Canadian French

Figure 44. Sample Installation Jobs for QMF Canadian French

Job Name	Job Type	Description	RELFILE
DSQCRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD5G.F2
DSQCALLOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD5G.F2
DSQCDDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD5G.F2
DSQCAPLY	APPLY	Sample APPLY job	IBM.JSQDD5G.F2
DSQACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD5G.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 44 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD5G.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD5G.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD5G.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.8 Sample Jobs for National Language Version for QMF Uppercase English

Figure 45. Sample Installation Jobs for QMF Uppercase English

Job Name	Job Type	Description	RELFILE
DSQURECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD51.F2
DSQUALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD51.F2
DSQUDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD51.F2
DSQUAPLY	APPLY	Sample APPLY job	IBM.JSQDD51.F2
DSQUACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD51.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 45 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD51.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD51.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD51.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.9 Sample Jobs for National Language Version for QMF Danish

<i>Figure 46. Sample Installation Jobs for QMF Danish</i>			
Job Name	Job Type	Description	RELFILE
DSQQRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD55.F2
DSQQALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD55.F2
DSQQDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD55.F2
DSQQAPLY	APPLY	Sample APPLY job	IBM.JSQDD55.F2
DSQQACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD55.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 46 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD55.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD55.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD55.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.10 Sample Jobs for National Language Version for QMF French

Figure 47. Sample Installation Jobs for QMF French

Job Name	Job Type	Description	RELFILE
DSQFRCV	RECEIVE	Sample RECEIVE job	IBM.JSQDD56.F2
DSQFALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD56.F2
DSQFDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD56.F2
DSQFAPLY	APPLY	Sample APPLY job	IBM.JSQDD56.F2
DSQFACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD56.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 47 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD56.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD56.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD56.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.11 Sample Jobs for National Language Version for QMF German

<i>Figure 48. Sample Installation Jobs for QMF German</i>			
Job Name	Job Type	Description	RELFILE
DSQDRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD57.F2
DSQDALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD57.F2
DSQDDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD57.F2
DSQDAPLY	APPLY	Sample APPLY job	IBM.JSQDD57.F2
DSQDACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD57.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 48 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD57.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD57.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD57.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.12 Sample Jobs for National Language Version for QMF Italian

Figure 49. Sample Installation Jobs for QMF Italian

Job Name	Job Type	Description	RELFIL
DSQIRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD58.F2
DSQIALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD58.F2
DSQIDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD58.F2
DSQIAPLY	APPLY	Sample APPLY job	IBM.JSQDD58.F2
DSQIACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD58.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 49 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD58.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD58.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSN=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD58.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4.13 Sample Jobs for National Language Version for QMF Japanese

<i>Figure 50. Sample Installation Jobs for QMF Japanese</i>			
Job Name	Job Type	Description	RELFILE
DSQKRECV	RECEIVE	Sample RECEIVE job	IBM.JSQDD59.F2
DSQKALOC	ALLOCATE	Sample job to allocate target/distribution libraries	IBM.JSQDD59.F2
DSQKDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.JSQDD59.F2
DSQKAPLY	APPLY	Sample APPLY job	IBM.JSQDD59.F2
DSQKACEP	ACCEPT	Sample ACCEPT job	IBM.JSQDD59.F2

You can access the sample installation jobs by performing a SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 50 for the relfile data set.

You may also choose to copy the jobs from the tape or product files by submitting the job below. Use either the //TAPEIN or the //FILEIN DD statement, depending on your distribution medium, and comment out or delete the other statement. Add a job card and change the lowercase parameters to uppercase values to meet your site's requirements before submitting.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.JSQDD59.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(3,SL),DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.JSQDD59.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,SPACE=(TRK,(15,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

In the sample above, update the statements as noted below:

If using TAPEIN:

tunit is the unit value matching the product tape.

volser is the volume serial matching the product tape.

x is the tape file number where the data set name is on the tape.

Refer to the documentation provided by CBPDO to see where IBM.JSQDD59.F2 is on the tape.

If using FILEIN

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT

jcl-library-name is the name of the output data set where the sample jobs will be stored.

dasdvol is the volume serial of the DASD device where the output data set will reside.

SYSIN

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.5 Allocate SMP/E CSI (Optional)

If you are using an existing CSI, do not execute this job.

If you are allocating a new SMP/E data set for this install, edit and submit sample job DSQALA to allocate the SMP/E data set for QMF Classic Edition - NLV. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.6 Initialize CSI zones (Optional)

If you are using an existing CSI, do not execute this job.

Edit and submit sample job DSQALB to initialize SMP/E zones for QMF Classic Edition - NLV. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.7 Perform SMP/E RECEIVE

If you have obtained QMF Classic Edition - NLV as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the QMF Classic Edition - NLV FMIDs, service, and HOLDDATA that are included on the CBPDO package. For more information, see the documentation that is included in the CBPDO.

1. You can also choose to edit and submit sample job DSQRECV1 to perform the SMP/E RECEIVE for QMF TSO/CICS Base. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

2. You can also choose to edit and submit sample job DSQRECV2 to perform the SMP/E RECEIVE for QMF HPO. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

3. You can also choose to edit and submit sample job DSQRECV3 to perform the SMP/E RECEIVE for QMF applications. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

4. You can also choose to edit and submit sample job DSQRECV4 to perform the SMP/E RECEIVE for QMF Classic Edition Identifier. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

5. You may also edit and submit a sample job below to perform the SMP/E RECEIVE for the National Language Version you have selected.

- DSQHRECV - National Language Version for QMF Korean
- DSQPRECV - National Language Version for QMF Brazilian Portuguese

- DSQSRECV - National Language Version for QMF Spanish
- DSQVRECV - National Language Version for QMF Swedish
- DSQYRECV - National Language Version for QMF Swiss French
- DSQZRECV - National Language Version for QMF Swiss German
- DSQCRECV - National Language Version for QMF Canadian French
- DSQURECV - National Language Version for QMF Uppercase English
- DSQQRECV - National Language Version for QMF Danish
- DSQFRECV - National Language Version for QMF French
- DSQDRECV - National Language Version for QMF German
- DSQIRECV - National Language Version for QMF Italian
- DSQKRECV - National Language Version for QMF Japanese

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.8 Allocate SMP/E Target and Distribution Libraries

1. Edit and submit sample job DSQALLOC to allocate the SMP/E target and distribution libraries for QMF Classic Edition - NLV. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

2. You may also edit and submit a sample job below to allocate the SMP/E target and distribution libraries of the National Language Version you have selected.

- DSQHALOC - National Language Version for QMF Korean
- DSQPALOC - National Language Version for QMF Brazilian Portuguese
- DSQSALOC - National Language Version for QMF Spanish
- DSQVALOC - National Language Version for QMF Swedish
- DSQYALOC - National Language Version for QMF Swiss French
- DSQZALOC - National Language Version for QMF Swiss German
- DSQCALOC - National Language Version for QMF Canadian French
- DSQUALOC - National Language Version for QMF Uppercase English
- DSQQALOC - National Language Version for QMF Danish
- DSQFALOC - National Language Version for QMF French
- DSQDALOC - National Language Version for QMF German
- DSQIALOC - National Language Version for QMF Italian
- DSQKALOC - National Language Version for QMF Japanese

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.9 Create DDDEF Entries

1. Edit and submit sample job DSQDDEF to create DDDEF entries for the SMP/E target and distribution libraries for QMF Classic Edition - NLV. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

2. You may also edit and submit a sample job below to create DDDEF entries for the SMP/E target and distribution libraries of the National Language Version you have selected.

- DSQHDDEF - National Language Version for QMF Korean
- DSQPDDEF - National Language Version for QMF Brazilian Portuguese
- DSQSDDEF - National Language Version for QMF Spanish
- DSQVDDEF - National Language Version for QMF Swedish
- DSQYDDEF - National Language Version for QMF Swiss French
- DSQZDDEF - National Language Version for QMF Swiss German
- DSQCDDEF - National Language Version for QMF Canadian French
- DSQUDEF - National Language Version for QMF Uppercase English
- DSQQDDEF - National Language Version for QMF Danish
- DSQFDDEF - National Language Version for QMF French
- DSQDDDEF - National Language Version for QMF German
- DSQIDDEF - National Language Version for QMF Italian
- DSQKDDEF - National Language Version for QMF Japanese

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.10 Perform SMP/E APPLY

1. Ensure that you have the latest HOLDDATA; then edit and submit sample job DSQAPPLY to perform an SMP/E APPLY CHECK for QMF TSO/CICS Base, HPO and QMF applications. Consult the instructions in the sample job for more information.

The latest HOLDDATA is available through several different portals, including <http://service.software.ibm.com/holddata/390holddata.html>. The latest HOLDDATA may identify HIPER and FIXCAT APARs for the FMIDs you will be installing. An APPLY CHECK will help you determine if any HIPER or FIXCAT APARs are applicable to the FMIDs you are installing. If there are any applicable HIPER or FIXCAT APARs, the APPLY CHECK will also identify fixing PTFs that will resolve the APARs, if a fixing PTF is available.

You should install the FMIDs regardless of the status of unresolved HIPER or FIXCAT APARs. However, do not deploy the software until the unresolved HIPER and FIXCAT APARs have been analyzed to determine their applicability. That is, before deploying the software either ensure fixing PTFs are applied to resolve all HIPER or FIXCAT APARs, or ensure the problems reported by all HIPER or FIXCAT APARs are not applicable to your environment.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. The SMP/E root cause analysis identifies the cause only of *errors* and not of *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here are sample APPLY commands:

- a. To ensure that all recommended and critical service is installed with the FMIDs, receive the latest HOLDDATA and use the APPLY CHECK command as follows

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND .
```

Some HIPER APARs might not have fixing PTFs available yet. You should analyze the symptom flags for the unresolved HIPER APARs to determine if the reported problem is applicable to your environment and if you should bypass the specific ERROR HOLDS in order to continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixing PTFs available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

- b. To install the FMIDs without regard for unresolved HIPER APARs, you can add the BYPASS(HOLDCLASS(HIPER)) operand to the APPLY CHECK command. This will allow you to install FMIDs even though one or more unresolved HIPER APARs exist. After the FMIDs are installed, use the SMP/E REPORT ERRSYSMODS command to identify unresolved HIPER APARs and any fixing PTFs.

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER)) .
..any other parameters documented in the program directory
```

This method is quicker, but requires subsequent review of the Exception SYSMOD report produced by the REPORT ERRSYSMODS command to investigate any unresolved HIPERs. If you have received the latest HOLDDATA, you can also choose to use the REPORT MISSINGFIX command and specify Fix Category IBM.PRODUCTINSTALL-REQUIREDSERVICE to investigate missing recommended service.

If you bypass HOLDS during the installation of the FMIDs because fixing PTFs are not yet available, you can be notified when the fixing PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 or 4 if these jobs run correctly.

You may receive any of the following messages which do not affect product installation: GIM23903I, GIM23903W, GIM23913W, IEW2454W.

2. After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 or 4 if these jobs run correctly.

You may receive any of the following messages which do not affect product installation: GIM23903I, GIM23903W, GIM23913W, IEW2454W. You may receive the following message for DFHEI1 in the CQDHLI module which does not affect product installation: IEW2456E. This means CICS is not setup for this installation.

After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Expected Return Codes and Messages: You will receive a return code of 0 or 4 if this job runs correctly. You may also receive the following message for DFHEI1 in the CQDHLI module which does not affect product installation: IEW2456E. This means CICS is not setup for this installation.

3. You can also choose to edit and submit sample job DSQAPLYE to perform the SMP/E APPLY CHECK for QMF Classic Edition Identifier. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

4. You may also edit and submit a sample job below to perform the SMP/E APPLY CHECK of the National Language Version you have selected.

- DSQHAPLY - National Language Version for QMF Korean
- DSQPAPLY - National Language Version for QMF Brazilian Portuguese
- DSQSAPLY - National Language Version for QMF Spanish
- DSQVAPLY - National Language Version for QMF Swedish
- DSQYAPLY - National Language Version for QMF Swiss French
- DSQZAPLY - National Language Version for QMF Swiss German
- DSQCAPLY - National Language Version for QMF Canadian French
- DSQUAPLY - National Language Version for QMF Uppercase English
- DSQQAPLY - National Language Version for QMF Danish
- DSQFAPLY - National Language Version for QMF French
- DSQDAPLY - National Language Version for QMF German
- DSQIAPLY - National Language Version for QMF Italian
- DSQKAPLY - National Language Version for QMF Japanese

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 if this job runs correctly.

After the APPLY CHECK completes successfully remove the CHECK and run the job again to perform the APPLY.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 if this job runs correctly.

6.1.11 Perform SMP/E ACCEPT

Edit and submit sample job DSQACCEP to perform an SMP/E ACCEPT CHECK QMF TSO/CICS Base, HPO and QMF applications. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. The SMP/E root cause analysis identifies the cause of *errors* but not *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E Commands book for details.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 if this job runs correctly.

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 if this job runs correctly. You may receive the following message for DFHEI1 in the CQDHLI module which does not affect product installation: IEW2456E. This means CICS is not setup for this installation.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Expected Return Codes and Messages: You will receive a return code of 0 or 4 if this job runs correctly. You may receive the following message for DFHEI1 in the CQDHLI module which does not affect product installation: IEW2456E. This means CICS is not setup for this installation.

1. You can also choose to edit and submit sample job DSQACCEE to perform the SMP/E ACCEPT CHECK for QMF Classic Edition Identifier. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

2. You may also edit and submit a sample job below to perform the SMP/E ACCEPT CHECK of the National Language Version you have selected.

- DSQHACEP - National Language Version for QMF Korean
- DSQPACEP - National Language Version for QMF Brazilian Portuguese
- DSQSACEP - National Language Version for QMF Spanish
- DSQVACEP - National Language Version for QMF Swedish
- DSQYACEP - National Language Version for QMF Swiss French
- DSQZACEP - National Language Version for QMF Swiss German
- DSQCACEP - National Language Version for QMF Canadian French
- DSQUACEP - National Language Version for QMF Uppercase English
- DSQQACEP - National Language Version for QMF Danish
- DSQFACEP - National Language Version for QMF French
- DSQDACEP - National Language Version for QMF German
- DSQIACEP - National Language Version for QMF Italian
- DSQKACEP - National Language Version for QMF Japanese

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 if this job runs correctly.

After the ACCEPT CHECK completes successfully remove the CHECK and run the job again to perform the ACCEPT.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 if this job runs correctly.

6.1.12 Run REPORT CROSSZONE

The SMP/E REPORT CROSSZONE command identifies requisites for products that are installed in separate zones. This command also creates APPLY and ACCEPT commands in the SMPPUNCH data set. You can use the APPLY and ACCEPT commands to install those cross-zone requisites that the SMP/E REPORT CROSSZONE command identifies.

After you install QMF Classic Edition - NLV, it is recommended that you run REPORT CROSSZONE against the new or updated target and distribution zones. REPORT CROSSZONE requires a global zone with ZONEINDEX entries that describe all the target and distribution libraries to be reported on.

For more information about REPORT CROSSZONE, see the SMP/E manuals.

6.2 Activating QMF Classic Edition - NLV

Once the SMP/E installation is completed for QMF Classic Edition - NLV, the QMF VSAM panel library, DSQPNLE, must be populated. The VSAM data set DSQPNLE was created when QMF SMP/E job, DSQALLOC (allocate QMF target and distribution libraries), was run in section 6.1.8 "Allocate SMP/E Target and Distribution Libraries" of this Program Directory.

Edit the job SDSQSAPE(DSQ1EPNL). Modify the job card and the variable QMFTPRES to the QMF target library prefix. Submit the job and verify that it runs successfully. This job will copy member DSQPNLE from the SDSQPVRE target library to the VSAM panel data set.

Run the corresponding job for each QMF National Language Version being accessed.

<i>Figure 51. NLV Activating Jobs</i>		
Language	Job	Description
QMF Korean	SDSQSAPH(DSQ1HPNL)	Copy SDSQPVRH(DSQPNLH) to the VSAM panel data set DSQPNLH
QMF Brazilian Portuguese	SDSQSAPP(DSQ1PPNL)	Copy SDSQPVRP(DSQPNLP) to the VSAM panel data set DSQPNLP
QMF Spanish	SDSQSAPS(DSQ1SPNL)	Copy SDSQPVRS(DSQPNLS) to the VSAM panel data set DSQPNLS
QMF Swedish	SDSQSAPV(DSQ1VPNL)	Copy SDSQPVRV(DSQPNLV) to the VSAM panel data set DSQPNLV
QMF Swiss French	SDSQSAPY(DSQ1YPNL)	Copy SDSQPVRV(DSQPNLY) to the VSAM panel data set DSQPNLY
QMF Swiss German	SDSQSAPZ(DSQ1ZPNL)	Copy SDSQPVRZ(DSQPNLZ) to the VSAM panel data set DSQPNLZ
QMF Canadian French	SDSQSAPC(DSQ1CPNL)	Copy SDSQPVRC(DSQPNLC) to the VSAM panel data set DSQPNLC
QMF Uppercase English	SDSQSAPU(DSQ1UPNL)	Copy SDSQPVRU(DSQPNLU) to the VSAM panel data set DSQPNLU
QMF Danish	SDSQSAPQ(DSQ1QPNL)	Copy SDSQPVRQ(DSQPNLQ) to the VSAM panel data set DSQPNLQ
QMF French	SDSQSAPF(DSQ1FPNL)	Copy SDSQPVRF(DSQPNLF) to the VSAM panel data set DSQPNLF
QMF German	SDSQSAPD(DSQ1DPNL)	Copy SDSQPVRD(DSQPNLD) to the VSAM panel data set DSQPNLD
QMF Italian	SDSQSAPI(DSQ1IPNL)	Copy SDSQPVRF(DSQPNLI) to the VSAM panel data set DSQPNLI
QMF Japanese	SDSQSAPK(DSQ1KPNL)	Copy SDSQPVRD(DSQPNLK) to the VSAM panel data set DSQPNLI

6.3 Product Customization

The publication *Installing and Managing QMF for TSO and CICS* (SC28-2788) contains the step-by-step procedures to customize and use QMF for TSO/CICS and QMF applications.

The publication *Db2 High Performance Option User's Guide for TSO and CICS*, (SC28-3269) contains the necessary information to customize and use QMF HPO.

The complete library of QMF publications may be found in the online product documentation at the following site;

<https://www.ibm.com/docs/en/qmf>

7.0 Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan, Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan

7.1 Trademarks

IBM, the IBM logo, and other IBM trademark listed on the IBM Trademarks List are trademarks or registered trademarks of International Business Machines Corporation, in the United States and/or other countries. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on ibm.com/trademark.

Reader's Comments

Program Directory for IBM Db2 Query Management Facility Classic, May 2022 We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Send your comments by emailing us at ibmdocs@us.ibm.com, and include the following information:

Your name and address
Your email address
Your telephone or fax number
The publication title and order number
The topic and page number related to your comment
The text of your comment

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit.

Thank you for your participation. °



Printed in USA

G113-5536-00

