

Operating **S**ystem **E**nvironment **M**anager

For z/OS

User's Guide

Version 6.0

SC31-6901-00

Limits of Liability and Disclaimer of Warranty

Trident Services and E.S.A. Software makes no warranty of any kind, expressed or implied, with regard to the programs or documentation. Trident Services and E.S.A. Software shall not be liable in any event for incidental or consequent damages in connection with or arising out of the furnishing, performance, or use of these programs.

Information in this manual is subject to change without notice and does not represent a commitment on the part of the vendor. The software described in this manual is furnished under a license agreement, and may be used or copied only in accordance with the terms of that agreement.

Copyright Notice

IBM Operating System Environment Manager (OSEM) for z/OS. Licensed materials - Property of IBM.
5799-HAX

(c) Copyright IBM Corp 2005. All rights reserved.

(c) Copyright E.S.A. Software 1990-2005. All rights reserved.

No parts of this publication may be copied or distributed, transmitted, transcribed, stored in a retrieval system, translated into any human or computer language, or disclosed to third parties without the express written permission of IBM Corp or E.S.A. Software.

The following are trademarks of IBM Corp:

DFHSM
DFSMS
IBM
OS/390
RACF
z/OS

The following are trademarks of Computer Associates International:

CA-ACF2
CA-TOPSECRET
CA-1
EZ-Proclib

First Edition (April 2005)

This edition applies to Operating System Environment Manager for z/OS (OSEM for z/OS) Version 6 Release 0 Modification 0 (Program Number 5799-HAX).

Table of Contents

What's New	New-1
Version 6.0	New-1
Version 5.6	New-2
Version 5.5	New-3
Introduction to OS/EM	1-1
What is OS/EM?	1-1
Extended OS/EM Functions	1-1
OS/EM The Operating System/Environment Manager	1-1
System availability	1-2
Isolated production testing	1-2
Operating system standardization	1-2
Ease of maintenance	1-2
How OS/EM works	1-2
Supported exits	1-3
System components	1-3
OS/EM Messages Under TSO	1-3
ISPF Interface	2-1
ISPF Interface Description	2-1
Entering data	2-1
Specifying options and parameters	2-2
Internal documentation	2-3
Generated commands	2-3
Help Screens	2-5
Starting the ISPF Interface	2-5
Primary Options Menu	2-5
System Controls, Maintenance & Installation Functions	3-1
System Level Controls	3-2
Authorization Codes	3-2
Expire Warning Messages	3-3
Abend Notification	3-3
Define Notify Groups	3-4
Define Users for Abend Notification	3-5
SMF Recording	3-6
Performance Counts and Timings	3-7
Execute Online Warning Message	3-7
Maintenance	3-8
Pending Changes Table Maintenance	3-8
Rebuild OS/EM Tables	3-8
Installation	3-10
Create OS/EM Tables	3-10
Upgrade to OS/EM 6.0	3-11
Basic Exit Functions	4-1
Description	4-1

OS/EM Exit Functions	4-1
List of Exits Supported	4-2
Autoinstall Feature	4-2
Basic Exit Functions Menu	4-3
JES2 Exits	4-4
JES2 Exit Point Options	4-5
JES2 User Exit Modules	4-6
JES2 User Exit Module Definition	4-9
Limit Masking	4-10
JES3 Exits	4-11
JES3 User Exit Options	4-12
JES3 User Exit Modules	4-14
JES3 User Exit Module Definition	4-16
Limit Masking	4-17
MVS Exits	4-18
MVS User Exit Options	4-19
MVS User Exit Modules	4-20
MVS User Exit Module Definition	4-23
Limit Masking	4-24
Extended OS/EM Functions	5-1
Define Dataset Name Groups	5-3
Add a DSN Group	5-5
Change a DSN Group	5-6
Delete a DSN Group	5-7
Temporarily Disable a DSN Group	5-9
Dataset Name Masks	5-10
Examples of dataset name masks	5-10
Define Volume Groups	5-12
Add a Volume Group	5-14
Change a Volume Group	5-15
Delete a Volume Group	5-16
Temporarily Disable a Volume Group	5-16
Volume Masks	5-17
Examples of volume serial number masks	5-17
HSM Optimizer	5-18
Description	5-18
Summary of Features	5-18
HSM Optimizer Menu	5-19
Backup Control	5-21
Defragmentation	5-23
Delete-by-Age Control	5-28
Delete-if-Backed-Up Control	5-31
Direct-to-Level-2 Control	5-34
Early Batch Recall	5-36
Force DSORG to PS	5-38
Migration Control (ML0-ML1)	5-39
Migration Level-2 Control (ML1-ML2)	5-42
Prioritize Recall/Recover Requests	5-46
Quick Delete Control	5-54
Reblocking Control	5-55
Recall/Recover Volume Selection	5-58
HSM Optimizer Report System	5-59
Description	5-59
Summary of Features	5-59
HSM Optimizer Report XREF	5-61
DFHSM Report Descriptions	5-62
Report-01 MIGRATION DETAIL (Primary - ML1)	5-62
Report-02 MIGRATION DELAY SUMMARY (Primary - ML1)	5-64

Report-03 MIGRATION AGE SUMMARY (Primary - ML1)	5-65
Report-04 MIGRATION DETAIL (ML1 - ML2)	5-66
Report-05 MIGRATION DELAY SUMMARY (ML1 - ML2)	5-67
Report-06 MIGRATION AGE SUMMARY (ML1 - ML2)	5-68
Report-07 MIGRATION DETAIL (PRIMARY - ML2)	5-70
Report-08 MIGRATION DELAY SUMMARY (PRIMARY - ML2)	5-71
Report-09 MIGRATION AGE SUMMARY (PRIMARY - ML2)	5-72
Report-10 RECALL DETAIL (ML1 - PRIMARY)	5-73
Report-11 RECALL DELAY SUMMARY (ML1 - PRIMARY)	5-74
Report-12 RECALL AGE SUMMARY (ML1 - PRIMARY)	5-75
Report-13 RECALL DETAIL (ML2 - PRIMARY)	5-76
Report-14 RECALL DELAY SUMMARY (ML2 - PRIMARY)	5-77
Report-15 RECALL AGE SUMMARY (ML2 - PRIMARY)	5-78
Report-16 DFHSM DASD VOLUME SUMMARY	5-79
Report-17 PRIMARY DATASET ACTIVITY REPORT	5-80
Report-18 DFHSM ERROR DETAIL REPORT	5-82
Report-19 DFHSM ERROR SUMMARY REPORT	5-83
Report-20 ACTIVITY SUMMARY	5-84
Report-21 MIGRATED DATASET SUMMARY	5-85
Report-22 DATASET BACKUP SUMMARY	5-86
Report-23 PRIMARY VOLUMES	5-87
Report-24 PRIMARY VOLUME DETAIL	5-89
Report-25 PRIMARY VOLUME DATE REFERENCE DETAIL	5-90
Report-26 MIGRATED DATASET DETAIL (MCDS Sorted by DSN)	5-92
Report-27 BACKED UP DATASET DETAIL (BCDS Sorted by DSN With XREF)	5-93
Report-28 MIGRATED DATASET DETAIL (MCDS Sorted by Date)	5-95
Report-29 BACKED UP DATASET DETAIL (BCDS Sorted by Date With XREF)	5-96
Report-30 BACKED UP DATASET DETAIL (BCDS Sorted by DSN No XREF)	5-98
Report-31 BACKED UP DATASET DETAIL BY DATE	5-99
HSM Optimizer Report Menu	5-100
Produce HSM Reports	5-102
Collect SMF Data for HSM database	5-104
Define/Allocate HSM Optimizer Files	5-106
ISPF File Prefix Controls	5-108
Description	5-108
System Requirements	5-109
JCL Controls	5-110
Description	5-110
Summary of Features	5-110
JCL Control Menu	5-111
Account Number Controls	5-112
Convert EZ-Proclib(R) to JCLLIB	5-115
Jobclass/Jobname Controls	5-116
Other JCL Controls	5-122
STEPLIB Controls	5-127
Sysout Class/Parameters	5-131
Tape Usage Controls	5-135
Virtual Storage Controls	5-136
Job Controls	5-139
Description	5-139
Summary of Features	5-139
Job Controls Menu	5-140
Add Notify Statement	5-141
Control JES2 Commands	5-142
Control Operating System Commands	5-143
Dataset Name Conflict Resolution	5-144
Job Step Notify	5-145
Job/Program Limits	5-146
Job Limits By User	5-147

Program Limits	5-150
Job Start Message	5-152
Job/Step Statistics	5-153
Not Cataloged 2 Correction	5-156
Reformat Jobcard Account Field	5-158
Surrogate Password Control	5-159
Job Name Masks	5-160
Surrogate Password Use	5-160
Sysout Extensions	5-162
TSO Logoff Statistics	5-167
Verify User Defined to RACF	5-168
Verify User ID with Jobname	5-169
Job Routing Controls	5-170
Description	5-170
Job Routing/Classing Controls Menu	5-170
System Level Controls	5-172
JECL Defaults	5-174
Message Number Substitution	5-176
Job Routing Resource Groups	5-177
Change Jobclass/Priority Groups	5-181
Change Scheduling Environment Groups	5-183
Change SRVCLASS Groups	5-185
Change XEQ Node Groups	5-187
Miscellaneous Controls	5-189
Description	5-189
Miscellaneous Controls Menu	5-189
ACF2 Non-cancel Override Control	5-189
Catalog Account Control	5-190
Estimated Costs Controls	5-193
TSO Program Intercept	5-197
WTO Controls	5-198
QuickPool	5-201
Description	5-201
Summary of Features	5-201
QuickPool Menu	5-202
DASD Allocation Control	5-203
QuickPool Rules	5-206
RACF Controls	5-210
Description	5-210
RACF Controls Menu	5-210
RACF Discrete Profiles	5-210
External Tape Control	5-211
Restrict Devices	5-213
Description	5-213
Summary of Features	5-213
Restrict Devices	5-213
Specify Jobname	5-214
Jobname / Jobname Mask	5-214
SVC Controls	5-215
Description	5-215
Tape Share Controls	5-218
Description	5-218
Tape Share Controls Menu	5-218
System Level Controls	5-219
Device Level Controls	5-222
Time Controls	5-224
Description	5-224
Summary of Features	5-224
Time Controls Menu	5-224

Job Time Controls	5-224
Time Extensions System Level Controls	5-226
Selection Lists Processing	5-228
Query OS/EM Status	6-1
Reload Exits	7-1
Selection Menu	7-1
JES2 Exits User Modules	7-2
JES3 Exits User Modules	7-3
MVS Exits User Modules	7-4
OS/EM System Modules	7-5
RACF Tables	7-6
Set JES2 Name	8-1
Execute Pending Changes	9-1
Build Initialization Member	10-1
Appendix A. Supported Exits	A-1
Allocation Exits	A-1
Data Facility Product (DFP) Exits	A-2
Data Facility Hierarchical Storage Manager (DFHSM) Exits	A-3
ISPF Exits	A-4
Job Entry System Two (JES2) Exits	A-5
IBM supported Exit points 0-49	A-5
User Defined Exit points 50-255	A-6
Job Entry System Three (JES3) Exits	A-7
IBM supported Exit points	A-7
JES3 Exits IATUX73 - IATUX99	A-8
Resource Access Control Facility (RACF)	A-9
System Authorization Facility (SAF) Exits	A-10
System Management Facility (SMF) Exits	A-11
Time Sharing Option Extended (TSO/E) Exits	A-12
Appendix B. General Masking	B-1
Example Volume Serial Number Masks	B-1
Example of Jobname Mask	B-1
Example of Terminal Mask	B-1
Example of Program Name Mask	B-2
Appendix C. Define Dataset Name Groups	C-1
Dataset name masks	C-1
Examples of dataset name masks	C-1
Appendix D. Define Volume Groups	D-1
Volume/Jobname Masks	D-1
Example Volume Serial Number Masks	D-1
Example of Jobname Mask	D-2
Appendix E. SMF Record Format	E-1
Appendix F. JES2 Commands for Job Routing	F-1
RACF Resources and Authority Table	F-6
Appendix G. JCL Statements for Job Routing	G-1
Resource Routing Control Cards	G-1
/*CNTL and /*THREAD Cards	G-2

After, Before, Exclude, PRED and With Control Cards	G-2
Appendix H. \$HASP Messages for Job Routing	H-1
Appendix I. MVS Commands for Tape Share	I-1
Index	Index-1
Readers's Comment Form	I-1

List of Illustrations

Figure 1.	Primary Option Menu	2-5
Figure 2.	Setup and Maintenance	3-1
Figure 3.	Authorization Codes	3-2
Figure 4.	Expiration Warning Message Control	3-3
Figure 5.	Notify Menu	3-3
Figure 6.	Define User Groups Menu	3-4
Figure 7.	Define User IDs for a Group	3-5
Figure 8.	Define IDs or Groups	3-6
Figure 9.	SMF Recording	3-6
Figure 10.	OS/EM Performance Stats	3-7
Figure 11.	OS/EM Execution Warn Mode Panel	3-7
Figure 12.	Pending Changes Maintenance	3-8
Figure 13.	Verify Rebuild	3-9
Figure 14.	ISPF Table Rebuild Utility	3-10
Figure 15.	Create OS/EM ISPF Tables	3-10
Figure 16.	Verify Upgrade	3-11
Figure 17.	Basic Exit Functions	4-3
Figure 18.	JES2 Exit Selection List	4-4
Figure 19.	JES2 Exit Point Options	4-5
Figure 20.	JES2 User Exit Modules	4-7
Figure 21.	JES2 User Exit Module Definition Panel	4-9
Figure 22.	Basic JES3 Exit Selection	4-11
Figure 23.	JES3 User Exit Options	4-12
Figure 24.	JES3 User Exit Modules	4-14
Figure 25.	JES3 User Exit Module Definition Panel	4-16
Figure 26.	Basic MVS Exit Selection	4-18
Figure 27.	MVS User Exit Options	4-19
Figure 28.	MVS User Exit Modules	4-21
Figure 29.	MVS User Exit Module Definition Panel	4-23
Figure 30.	Extended OS/EM Support	5-1
Figure 31.	Dataset Name Group List	5-3
Figure 32.	DSN Name Groups - Add Group Name	5-5
Figure 33.	DSN Name Groups - Change	5-6
Figure 34.	DSN Name Groups - Wait	5-7
Figure 35.	DSN Name Groups - Delete	5-7
Figure 36.	DSN Name Groups - References	5-8
Figure 37.	DSN Name Groups - No References	5-8
Figure 38.	Volume Name Groups	5-12
Figure 39.	Volume Name Groups - Add Group Name	5-14
Figure 40.	Volume Name Groups - Change	5-15
Figure 41.	HSM Optimizer Menu	5-20
Figure 42.	HSM Optimizer Backup Control	5-21
Figure 43.	Select DSN Groups for Backup Exclusion Pop-up	5-22
Figure 44.	Defragmentation Control/Procedure	5-23
Figure 45.	Defragmentation VOL Group Controls with "POPUP" screen	5-26
Figure 46.	Delete-By-Age Hold Options	5-28
Figure 47.	Delete-By-Age Hold Options with DSN Groups "POP-UP" screen	5-29

Figure 48.	Delete-If-Backed-UP Hold Options	5-31
Figure 49.	Delete-If-Backed-Up Hold Options with DSN Group "POP-UP" screen	5-32
Figure 50.	Migration Control: Direct to ML2	5-34
Figure 51.	Early Batch Recall Control	5-36
Figure 52.	Entry panel for Force DSORG to PS	5-38
Figure 53.	Migration Controls	5-39
Figure 54.	Migration Hold Options with "POPUP" screen	5-40
Figure 55.	MIG Level-2 Hold Options with "POPUP" screen	5-44
Figure 56.	Prioritize Recall/Recover Requests Menu	5-46
Figure 57.	Priority System Level Controls	5-47
Figure 58.	Recall Selection Lists	5-48
Figure 59.	Selection Group Entry Panel	5-50
Figure 60.	Recover Selection Lists	5-51
Figure 61.	Selection Group Entry Panel	5-53
Figure 62.	Entry panel for Quick Delete Control	5-54
Figure 63.	Reblock Control Menu	5-55
Figure 64.	Reblock Control - Add or Delete	5-56
Figure 65.	Recall/Recover Selection Control	5-58
Figure 66.	REPORT-01 MIGRATION DETAIL (Primary - ML1)	5-62
Figure 67.	REPORT-02 MIGRATION DELAY SUMMARY (Primary - ML1)	5-64
Figure 68.	REPORT-03 MIGRATION AGE SUMMARY (Primary - ML1)	5-65
Figure 69.	REPORT-04 MIGRATION DETAIL (ML1 - ML2)	5-66
Figure 70.	REPORT-05 MIGRATION DELAY SUMMARY (ML1 - ML2)	5-67
Figure 71.	REPORT-06 MIGRATION AGE SUMMARY (ML1 - ML2)	5-68
Figure 72.	REPORT-07 MIGRATION DETAIL (PRIMARY - ML2)	5-70
Figure 73.	REPORT-08 MIGRATION DELAY SUMMARY (PRIMARY - ML2)	5-71
Figure 74.	REPORT-09 MIGRATION AGE SUMMARY (PRIMARY - ML2)	5-72
Figure 75.	REPORT-10 RECALL DETAIL (ML1 - PRIMARY)	5-73
Figure 76.	REPORT-11 RECALL DELAY SUMMARY (ML1 - PRIMARY)	5-74
Figure 77.	REPORT-12 RECALL AGE SUMMARY (ML1 - PRIMARY)	5-75
Figure 78.	REPORT-13 RECALL DETAIL (ML2 - PRIMARY)	5-76
Figure 79.	REPORT-14 RECALL DELAY SUMMARY (ML2 - PRIMARY)	5-77
Figure 80.	REPORT-15 RECALL AGE SUMMARY (ML2 - PRIMARY)	5-78
Figure 81.	REPORT-16 DFHSM DASD VOLUME SUMMARY	5-79
Figure 82.	REPORT-17 PRIMARY DATASET ACTIVITY REPORT	5-80
Figure 83.	REPORT-18 DFHSM ERROR DETAIL REPORT	5-82
Figure 84.	REPORT-19 DFHSM ERROR SUMMARY REPORT	5-83
Figure 85.	REPORT-20 ACTIVITY SUMMARY	5-84
Figure 86.	REPORT-21 MIGRATED DATASET SUMMARY	5-85
Figure 87.	REPORT-22 DATASET BACKUP SUMMARY	5-86
Figure 88.	REPORT-23 PRIMARY VOLUMES	5-87
Figure 89.	REPORT-24 PRIMARY VOLUME DETAIL	5-89
Figure 90.	REPORT-25 PRIMARY VOLUME DATE REFERENCE DETAIL	5-90
Figure 91.	REPORT-26 MIGRATED DATASET DETAIL (MCDS Sorted by DSN)	5-92
Figure 92.	REPORT-27 BACKED UP DATASET DETAIL (BCDS Sorted by DSN With XREF)	5-93
Figure 93.	REPORT-28 MIGRATED DATASET DETAIL (MCDS Sorted by Date)	5-95
Figure 94.	REPORT-29 BACKED UP DATASET DETAIL (BCDS Sorted by Date With XREF)	5-96
Figure 95.	REPORT-30 BACKED UP DATASET DETAIL (BCDS Sorted by DSN No XREF)	5-98
Figure 96.	REPORT-31 Backed Up Dataset Detail By Date	5-99
Figure 97.	HSM Optimizer Reports Menu	5-100
Figure 98.	HSM Optimizer Reports - JCL	5-101
Figure 99.	HSM Optimizer Reports - Select Reports	5-102
Figure 100.	HSM Optimizer Reports Collect SMF Data	5-104
Figure 101.	HSM Optimizer Reports - Define/Allocate Files	5-106
Figure 102.	ISPF File Prefix Controls	5-108
Figure 103.	JCL Controls for JES2	5-111
Figure 104.	Account Number Controls	5-112
Figure 105.	JCL Controls: ACCT1	5-112
Figure 106.	Convert EZ-Proclib(R) to JCLLIB	5-115

Figure 107. Jobclass/Jobname Controls	5-117
Figure 108. Job Class Check	5-118
Figure 109. Job Name Checking Controls	5-119
Figure 110. Job Name Checking Controls with "POPUP" screen	5-120
Figure 111. Other JCL Controls	5-122
Figure 112. JCL Controls: DDNAME	5-124
Figure 113. STEPLIB Controls Menu	5-127
Figure 114. System Level Controls Panel	5-127
Figure 115. Selection Lists Panel	5-128
Figure 116. Selector Entry Panel	5-129
Figure 117. SYSOUT Parameter Controls	5-131
Figure 118. JCL Controls: SYSOUT	5-133
Figure 119. Tape Usage Controls	5-135
Figure 120. Virtual Storage Controls	5-136
Figure 121. Selector Entry Panel	5-138
Figure 122. Job Controls	5-140
Figure 123. Add Notify Statement	5-141
Figure 124. Control JES2 Commands	5-142
Figure 125. Control Operating System Commands	5-143
Figure 126. Dataset Name Conflict Resolution	5-144
Figure 127. Job Step Notify	5-145
Figure 128. Job/Program Limits Menu	5-146
Figure 129. Job Limits	5-147
Figure 130. Selector Entry Panel	5-148
Figure 131. Program Limits Entry Panel	5-150
Figure 132. Job Start Message	5-152
Figure 133. Job/Step Statistics	5-153
Figure 134. Not Cataloged 2 Controls	5-156
Figure 135. Popup Window for Job Class Entry	5-157
Figure 136. Reformat Jobcard Account Field	5-158
Figure 137. Surrogate Password Control	5-159
Figure 138. Job Name List - STC	5-160
Figure 139. Sysout Extension Controls Menu	5-162
Figure 140. JES2 Sysout Extension Controls	5-162
Figure 141. JES2 Sysout Extension Selectors	5-164
Figure 142. Sysout Extension Controls	5-165
Figure 143. Sysout Extension Lists	5-166
Figure 144. Logoff Statistics	5-167
Figure 145. Verify User Defined to RACF	5-168
Figure 146. Verify UserID with Jobname	5-169
Figure 147. Job Routing/Classing Controls Menu	5-170
Figure 148. System Level Controls	5-172
Figure 149. JECL Defaults	5-174
Figure 150. Mellon Message Substitution	5-176
Figure 151. Job Routing Resource Groups Entry Panel	5-177
Figure 152. Selector Entry Panel.	5-178
Figure 153. Delete Warning Panel.	5-180
Figure 154. Jobclass/Priority Change Groups Entry Panel	5-181
Figure 155. Scheduling Environment Change Groups Entry Panel	5-183
Figure 156. SRVCLASS Change Groups Entry Panel	5-185
Figure 157. XEQ Node Change Groups Entry Panel	5-187
Figure 158. Miscellaneous Controls Menu	5-189
Figure 159. ACF2 Non-cancel Override Entry Panel	5-189
Figure 160. Catalog Account Control Entry Panel	5-191
Figure 161. Catalog Account Lists	5-192
Figure 162. Estimated Cost Groups Panel	5-194
Figure 163. Estimated Cost Controls Panel	5-195
Figure 164. TSO Program Intercept Entry Panel	5-197
Figure 165. WTO Controls Entry Panel	5-198

Figure 166. Selector Entry Panel	5-199
Figure 167. QuickPool Menu	5-202
Figure 168. Control DASD Allocation	5-203
Figure 169. QuickPool Functions	5-206
Figure 170. QuickPool Add/Delete "POPUP" screen	5-208
Figure 171. RACF Controls Menu	5-210
Figure 172. RACF Discrete Profiles Entry Panel	5-211
Figure 173. RACF External Tape Entry Panel	5-212
Figure 174. Restrict Devices	5-213
Figure 175. Restrict Device With Jobname "POPUP" Screen	5-214
Figure 176. SVC Delete/Replace Controls	5-215
Figure 177. SVC Delete/Reload Entry panel	5-216
Figure 178. Tape Share Controls Menu	5-218
Figure 179. System Level Controls Panel	5-219
Figure 180. Device Level Controls Panel	5-222
Figure 181. Time Controls Menu	5-224
Figure 182. Job Time Controls	5-225
Figure 183. Job Time Controls Pop-up window.	5-226
Figure 184. System Level Controls	5-227
Figure 185. Selection Lists	5-228
Figure 186. Selector Entry Panel	5-229
Figure 187. OS\$CNTL Query Command	6-1
Figure 188. Sample Query Output	6-2
Figure 189. Module Type Reload Selection	7-1
Figure 190. JES2 Reload Selection	7-2
Figure 191. JES3 Reload Selection	7-3
Figure 192. MVS Exit Reload Selection	7-4
Figure 193. System Reload Selection	7-5
Figure 194. RACF Table Reload Selection	7-6
Figure 195. JES2 Subsystem Names	8-1
Figure 196. Add JES2 Subsystem	8-2
Figure 197. Execute Pending Changes - Review/Execute	9-1
Figure 198. Pending Changes - Detail	9-3
Figure 199. Execute Pending Changes In Batch	9-3
Figure 200. Pending Changes Job Card	9-4
Figure 201. Build Initialization Members	10-1
Figure 202. Build Initialization Members - Status	10-2

What's New

Version 6.0

The following enhancements have been made to OS/EM version 6.0:

- OS/EM now supports z/OS 1.6
- The **OS/EM Autoinstall Feature** (new for version 6.0) significantly simplifies the OS/EM product installation process. See “Basic Exit Functions” on page 4-1 for more information about this feature.
- Job Routing now supports up to 127 route statements.
- Job Routing now supports up to 127 dependent job control statements.
- Job Routing now supports up to 127 CNTL statements.
- The Job Routing communications dataset's record size has been increased to a maximum of 32719 from 4504 to allow additional resource entries.
- Job Routing has been enhanced to allow routing by:
 - PDS member name
 - Source name
 - Source program name
 - Source type
 - WLM Scheduling Environment
- OS/EM internals have been modified to enhance performance.
- Notification of User and OS/EM abends has been enhanced.

You may now specify up to three IDs to be notified in the case of a user exit abend. You may also create notification groups where each ID within the group will receive a TSO send message.

You may optionally specify a user ID or notify group name for each major section of OS/EM, i.e. ALLOCATION, SMF, HSM, etc.

- Performance Counts and Timings have been added to the Query Report.
- All load modules referenced in a Query Report now includes the name of the load library where the module was located.
- OS/EM now supports up to 255 user exits per supported exit point.
- OS/EM can optionally prevent a job from starting until all required datasets are available.
- OS/EM can optionally limit the concurrent execution of selected programs.

- OS/EM can issue DFSMSHSM Recall commands at conversion time and optionally prevent execution until needed files have been recalled.
- The TMSACCT option has been removed from version 6.0.
- The ENHANCED \$HASP165 message option has been removed from version 6.0.

Version 5.6

The following enhancements have been made to OS/EM version 5.6:

- OS/EM now supports z/OS 1.6
- A **PRIMARY JES** indicator has been added to the **Set JES Name** function in the ISPF interface as well as the Query Report.
- OS/EM can now convert EZ-Proclib(R) statements to JCLLIB statements.
See Exit 4 in the Reference Manual, and Miscellaneous Controls in the User Guide.
- Sysout Extension Support for JES2 Parameters
 - You may now control sysout extensions based on the JES2 Initialization parameters ESTLNCT, ESTPAGE and ESTBYTE. See Exit 9 in the Reference Manual, and Job Controls in the User Guide.

- Job/Step Statistics

The STEPENDWTO message has been enhanced to show the CPU time and I/O counts. This is an optional feature and the original message is still available for customers using an automation package to trap the message.

- Job Routing Changes

See Exit 5 in the Reference Manual, or option 1 on the Job Routing Controls Menu.

- OS/EM now supports 999 selection groups.
- SMF Records are now cut for jobs having resources attached to them.

A record number must be assigned to OS/EM for this function to become active. See “SMF Recording” on page 3-6 for instructions on assigning a record number.

- Jobs may now be routed based on the account number field.
- Jobs may be routed by the time parameter on the job card.
- A Default Resource option has been added.

Any job which does not have a resource attached to it will receive this new default resource.

- Convert SCHENV JOBCARD parameter to OS/EM Route

OS/EM can scan for the keyword SCHENV= on the JOBCARD statement and remove it. It then inserts an OS/EM Job routing JECL statement using the scheduling environment name just removed as the resource name.

- Convert SYSAFF=name to SYSAFF=ANY if OS/EM Route present

OS/EM can set a job's system affinity (SYSAFF) to ANY, if, and only if, the job has been assigned one or more OS/EM Job Route resources. The job route resources may be from either JECL control cards (*ROUTE resource) or automatically generated.

- OS/EM will now route a job or range of jobs to another node if the job has the named resource attached to it. See Appendix F for the command format.
- The \$DC (display conflicts) command has been enhanced to show jobs coming from a system without OS/EM job routing active, and to flag jobs which have a multi-system resource conflict.
- Region Controls now supports the MEMLIMIT keyword.
OS/EM can now control the amount of storage given to a job above the 2 gigabyte bar. You may specify anything between zero for nothing above the bar to a maximum of 16 exabytes.
See SMF exit OS\$USI in the Reference Manual or option 7 on the JCL Controls Menu.
- The HSM Optimizer Priority Controls now supports failing requests based on the source of the request, location of data or dataset name/masks.
See HSM exit ARCRPEXT in the Reference Manual, or option 8 on the HSM Optimizer Menu.
- The OS/EM RACF area now controls access to external tapes.
OS/EM will allow a user to read any tape dataset with the following criteria is met, thus bypassing the RACF PROTECALL(FAIL) option:
 - A RACF profile does not exist for the dataset.
 - The user has READ access authority or higher to the FACILITY class profile EXTERNAL.TAPE.

Version 5.5

The following enhancements have been made to OS/EM version 5.5:

- ISPF Exit 16
 - Static System Symbolics may be used to generate file names for the ISPF Log dataset, List dataset and work datasets.
- JES2 Exit 5
 - Job Resource Routing (formally the Mellon Modifications) has been enhanced to allow automatic routing of jobs based on:
 1. DDNAME
 2. Dataset Name
 3. Job Class
 4. Job Name
 5. Program Name
 6. RACF Group
 7. Unit Name
 8. TSO User ID
 9. Workload Manager Service Class
 10. Execution Parm value
 - Set JOBCLASS based on:

1. DDNAME
 2. Dataset Name
 3. Job Class
 4. Job Name
 5. Program Name
 6. RACF Group
 7. Unit Name
 8. TSO User ID
 9. Workload Manager Service Class
 10. Execution Parm value
- Set JES2 Job Priority based on:
 1. DDNAME
 2. Dataset Name
 3. Job Class
 4. Job Name
 5. Program Name
 6. RACF Group
 7. Unit Name
 8. TSO User ID
 9. Workload Manager Service Class
 10. Execution Parm value
 - Set Service Class based on:
 1. DDNAME
 2. Dataset Name
 3. Job Class
 4. Job Name
 5. Program Name
 6. RACF Group
 7. Unit Name
 8. TSO User ID
 9. Workload Manager Service Class
 10. Execution Parm value
 - Set Job Scheduling Environment (SCHENV=) based on:
 1. DDNAME

2. Dataset Name
 3. Job Class
 4. Job Name
 5. Program Name
 6. RACF Group
 7. Unit Name
 8. TSO User ID
 9. Workload Manager Service Class
 10. Execution Parm value
- JES2 Exit 6
 - Account Number Controls now support up to six (6) accounting fields.
 - Account Number Controls may be limited to batch jobs, or both batch jobs and TSO users.
 - The Time Control function now allows jobs to be cancelled instead of having their time parameter adjusted.
 - SMF IEFACTRT
 - A new function **Estimated Costs** has been added.

The Estimated Cost function of OS/EM can be used to calculate an approximate charge for running each step of a job and an approximate total cost of running the job. The costs are presented in the "flower box" produced by requesting OS/EM's STEP/JOB-end statistics.
 - SMF IEFUSI
 - Region Control values for region size below the line and limit value below the line may be specified as a negative value. This means that the job will be given all available space minus the value specified.
 - A new function **Quick Delete** has been added.

This function specifies that any files coded with a retention setting of DELETE and the program name is IEFBR14 will be deleted by OS/EM. No DFSMSHSM RECALL will be performed. Instead a HDELETE will be generated.
 - SMF IEFU83
 - A new function **Catalog Account Controls** has been added.

This function can be used to place up to 32 bytes of JOB or STEP accounting information into the catalog record for a newly created VSAM dataset or SMS-managed non-VSAM dataset. Additionally, the JOB's User ID is placed into the Owner field of the catalog record. Neither of these fields is overridden if the information has already been provided.
 - MISC Controls ACF2 Non-cancel Override
 - It is now possible to override the ACF2 non-cancel user attribute to allow OS/EM to enforce its controls.

Introduction to OS/EM

What is OS/EM?

OS/EM (Operating System/Environment Manager) is a dynamic exit manager and a set of optional, standard control exits for the OS/390 and z/OS environments. As a dynamic exit manager, it provides a consistent, easy-to-use interface to most exit points provided by IBM to enhance the OS/390 and z/OS environment.

The Extended OS/EM Functions provide most options commonly included in exits written by Systems Programmers, without the overhead associated with developing, maintaining, testing and implementing those exits. The ISPF interface also allows the changing of Extended OS/EM Functions without an IPL.

Extended OS/EM Functions

OS/EM can supply functions that incorporate many of the features which user exits are commonly intended. In many cases, the Extended Functions will provide all of the services required by your installation without any coding.

Where applicable, the exits have a WARN mode for the gradual introduction of the new functions.

These parameter-driven exits enable your installation to achieve:

- Optimization
- Maintainability
- Standardization
- Control

The benefits to this approach apply to installations new and old.

OS/EM The Operating System/Environment Manager

OS/EM provides your OS/390 or z/OS installation with:

- Greater system availability
- Isolated production testing
- Operating System standardization
- Ease of maintenance

System availability

With the ever-increasing size of host networks and seven-day, 24-hour service requirements, availability has become the keyword as far as both users and the operating system support staff is concerned. Your installation needs the system to function to carry on the business of the business, and your support staff needs the system to install program products, "tune" resource control functions, apply maintenance, etc.

OS/EM allows your system staff to install any product or user-written control function that uses an OS/390 or z/OS SMF, TSO, JES2, JES3, RACF, HSM, DADSM or allocation exit without requiring an IPL.

- This can be extremely useful when doing recovery on another processor since no IPL is needed to start your version of the environment.

Isolated production testing

OS/EM enhances system reliability by allowing your systems staff to thoroughly test new exits in the same production environment in which they will be running. A standard OS/EM function is to remove any exit which abends, thereby allowing normal production work to proceed. This allows the systems staff to do more thorough testing because the testing process will not have a negative impact on your system's integrity.

Another standard OS/EM function is to limit, by jobname, the scope of SMF, TSO, RACF, DADSM, and some JES2/JES3 exits. This facility will allow the testing of new exits without impacting the function of existing exits.

Operating system standardization

OS/EM allows your installation to have a standard operating environment, whether on a single processor or multiple processors, by allowing all exit modules to exist outside of the operating system. Trying to stay vanilla is the very reason OS/EM was developed; you can now have the controls/products you need while still keeping a vanilla operating system without reliability exposure, availability interruptions, or system modification problems. Variations from the standard IBM supplied OS/390 or z/OS environments, such as those supplied by program products or user-written control functions, no longer require an IPL or system modification (SMP/E). Loading or reloading any of these exits can now be done via a TSO command (or ISPF dialogue).

- Combining OS/EM and its associated Extended functions with an IBM OS/390 or z/OS IPO results in an operating system environment that many installations take many months to obtain. The sample exits supplied with the IPO can easily be specified as user exits to OS/EM, or the Extended OS/EM Functions can provide all the functions that the sample exits from the IPO provide plus much more.

Ease of maintenance

Since OS/EM manages the loading of exits, SMP/E is not needed to install exits into the operating system. While useful for any exit, this standard OS/EM function greatly simplifies the installation and maintenance of program products or user-written functions that need to share exits. OS/EM allows multiple exits sharing an exit point to exist independently; therefore SMP/E user modifications are not needed.

How OS/EM works

OS/EM replaces all IBM supplied SMF, TSO, JES2, JES3, RACF, ISPF, SAF, Allocation and HSM exits with its own control processor. This processor is installed at IPL time. OS/EM then dynamically loads and processes your installation's exits whether they are user-written, program products (job schedulers, report distribution systems, etc.), or OS/EM's optional control functions.

At any time after the IPL you may:

- Alter the parameters by which OS/EM's optional control functions operate
- Reload an existing exit (presumably because it has been modified)
- Disable an exit
- Load an exit not previously installed

OS/EM has the ability to manage up to 255 modules per exit point. Using the Extended Functions does not restrict this number. However, stringing together multiple modules at a given exit point assumes that each module can work together. The functioning of an exit point may require that only one module can be "active", the other modules being "passive".

For example, TSO exit IKJEFF10 (the TSO SUBMIT exit) is normally used to alter or produce additional job statements. Multiple modules doing such would not seem prudent.

Supported exits

A list of currently supported exits is documented in "Appendix A. Supported Exits" on page A-1.

System components

The OS/EM system is comprised of the following five main components:

- OS\$IPL** This program obtains storage for the OS/EM CVT (Communications Vector Table), which is required by the OS/EM control process. This program is run as part of the IPL process and uses the OS/390 or z/OS sub-system interface to establish the OS/EM environment.
- OS\$INIT** This program is started at IPL time by the OS\$IPL program. It attaches the TSO control program IKJEFT01 to process the initial OS\$CNTL commands before JES2 starts.
- OS\$CNTL** This program is the main program of process. It is a TSO command processor that checks the command function (the first operand on the command) and calls the appropriate modules to process the request. Before the OS\$CNTL command can be used, the OS\$IPL program must have been run to create the OS/EM environment.

Interface modules

These serve as the control facility to invoke the dynamically loaded exits that perform the actual exit functions.

Dynamic exits

These are the exits for your program products, in house coded exits, and OS/EM Extended Functions which are loaded by the OS\$CNTL command processor.

OS/EM Messages Under TSO

In order to receive OS/EM message numbers under ISPF or TSO, the MSGID parameter in your TSO profile must be set on.

The following command may be issued to set OS/EM message numbers on, under ISPF or TSO.

```
TSO PROFILE MSGID
```


ISPF Interface

The ISPF interface provides for the creation of the necessary OS/EM initialization parameters, and provides for the execution of OS/EM commands online. The interface has a function orientation. That is, the Extended OS/EM Functions are presented without regard to the OS/EM commands or exits that implement the function. The intent is to make OS/EM as accessible as possible.

ISPF Interface Description

The OS/EM Primary Option Menu provides for two major processing options. The 'Basic Exit Function' provides for the specification and management of all the OS/EM supported exit points. The Extended OS/EM Functions provides the support for DASD controls, QuickPool, JCL Controls, Job Controls, HSM Optimizer, HSM Reports, RACF Controls Device Restriction, ISPF File Prefix, Job Routing, Tape Share, SVC Delete/Replace Controls and Time Controls. Although initialization member generation and command generation bring the two processes together, the actual specification of basic and extended functions are independent of one another. The only requirement is that an exit point's OPTIONS be specified. The interface will ensure that this is true. This means that if your installation has no exits of its own, but you wish to use OS/EM Extended Functions, you will not have to be concerned with specifying basic functions.

The entries you make are saved from one use of the interface to the next. Each time you use the interface for a particular command, your last entries will be presented for any changes you wish to make.

- It is important to scan the presented information since you might build a new initialization member that contains parameters that you wished to be only temporary.

The interface saves all information in ISPF tables. This enables multiple users of the interface, each of who have access to the same information. However, only one user at a time may use the interface.

The required tables are not shipped with the OS/EM install package. They are generated the first time you invoke any of the interface functions. The amount of time required for this generation varies depending on your hardware and the work being done at the time of generation. Each time a particular function's tables are generated, a panel is presented indicating that tables are being generated. Some tables, such as volume and dataset name group tables, are generated only as required.

You may elect to generate the ISPF tables all at one time. To accomplish this, select option 1 from the OS/EM primary options menu.

Entering data

All OS/EM ISPF panels conform to standard display and data input conventions. Each panel has an ISPF command line at the top of the display (indicated by **COMMAND ===>**) and accepts the applicable ISPF commands.

The most commonly used ISPF commands are:

- Parameter entry can be terminated at any time by entering the ISPF **END** (or **RETURN**) command. This is the normal method for signaling that you have finished your specifications. You will be returned to the next higher screen level.
- **CAN** or **CANCEL** in the command line will completely negate any entries you have made up to that point. The **CANCEL** command can only negate the last series of entries you have made. For example:

You have specified GLOBAL ALLOW entries in the QuickPool function. Then you start specifying GLOBAL DISALLOW entries, change your mind and CANCEL. You have only canceled the DISALLOW entries, not the ALLOW entries you have already completed. If you have any doubts about what has been canceled, you should review your entries and make adjustments as necessary.

- The ENTER key will redisplay the current panel, along with any error messages that your entries may have generated.

Where necessary, panels contain "scrollable" areas that allow you to specify as many entries (such as volume and dataset name groups) as required by your installation. Panels with scrollable viewing are indicated by the presence of the **SCROLL** field in the top right hand corner of the panel. These panels support ISPF scrolling and location commands. The commands typically used are:

- The **MAX** (or **M**) command, when used in conjunction with PF7 / PF8 will position the display to the top / bottom of the entry list.
- The **L** command is used to position the display at a specific entry in the list based in the entry value. For example:

L PROD will position the list to the entry with the value PROD. If there is no entry that exactly matches the value specified in the L command, the display will be positioned at the first entry that is alphabetically & numerically higher.

First use of the interface will present you with empty fields (of the appropriate type) which you modify. Additional entries are made by inserting new, blank fields; or by using an ADD command and overtyping existing information. Provision is made to allow you to delete entries that are no longer needed, while ensuring that information necessary to the successful operation of OS/EM is not deleted.

PF Key Usage

The Program Function (PF) keys supported by the OS/EM ISPF panels are:

- PF1** Display HELP information
- PF2** Split display screen at cursor
- PF3** Return to previous menu (updates saved)
- PF7** Scroll up
- PF8** Scroll down
- PF9** Swap display panels
- PF12** Return to previous menu (updates discarded)

Specifying options and parameters

The bulk of a function's parameters/options are specified by entering either a YES or NO value, or leaving the option blank. Entering a YES will enable the option. Entering a NO will disable the option, etc. Once entered, each parameter and option will display with your last entry until you change it.

Internal documentation

Where appropriate, you may enter descriptions that can serve as documentation. For example, each volume and dataset name group may have an optional description associated with it. You may use this description to describe the function of the group, document who created the group, etc. The description fields are provided strictly for your use and are included in the generated initialization commands for documentation.

Generated commands

All OS/EM commands are generated via ISPF skeleton processing. If an initialization member is requested, the final output is placed in the dataset pointed to by DD name OS\$FILE which is automatically allocated when you enter the ISPF interface. If the command is issued online, the final output is executed via a TSO EXEC command.

- Specifying parameters via the ISPF Interface has no effect on OS/EM processing until you either build an initialization member or execute OS/EM's online function. Further, initialization members are only processed during OS/EM startup, they have no effect on current processing.
- Remember to ensure that procedure OSV6 contains a SYSTSIN DD statement pointing to the correct dataset and that each initialization member is properly specified (for a detailed explanation, see OS/EM Reference manual under Installation).

The following initialization members are currently generated:

CODEINIT Contains the statements required to authorize the use of OS/EM, for the CPU ID, time period and options that your company has licensed.

Contains the SMF Recording Record Type number.

Contains Notification Group information.

Created when you select SYSTEM from the Build Initialization Members menu.

Note: The CODEINIT member must be the first member processed in the procedure OSV6 SYSTSIN concatenation. No other OS/EM commands will be processed until this command is processed.

DASDINIT Contains the statements required to generate the DASD allocation controls.

Created when you select DASD from the Build Initialization Members menu.

DSNINIT Contains the statements required to generate your specified dataset name groups. If you have entered a description for a group, the description will appear as a comment before the group.

Created when you select Dataset from the Build Initialization Members menu.

HSMINIT Contains the statements required to generate the HSM Optimizer controls.

Created when you select HSM from the Build Initialization Members menu.

JCLINIT Contains the statements required to generate the JES2 JCL controls.

Created when you select JCL from the Build Initialization Members menu.

JES2INIT Contains the statements required to generate basic support for the various JES2 exits that you wish to load your routines.

Created when you select JES2 from the Build Initialization Members menu.

- JES3INIT** Contains the statements required to generate basic support for the various JES3 exits that you wish to load your routines.
- JOBINIT** Contains the statements required to generate various Job related JCL controls.
Created when you select JOB from the Build Initialization Members menu.
- JOBRINIT** Contains the statements required to generate the Job Routing JES2 controls.
Created when you select JOBR from the Build Initialization Members menu.
- MISCINIT** Contains the statements required to generate the ACF2 Non-cancel Override Controls, Catalog Account Controls, Estimated Cost Controls, TSO Program Intercept Controls and the WTO Controls.
Created when you select MISC from the Build Initialization Members menu.
- MVSINIT** Contains the statements required to generate basic support for the various MVS exits that you wish to load your routines.
Created when you select MVS from the Build Initialization Members menu.
- POOLINIT** Contains the statements required to generate your specified global ALLOW and DISALLOW list; and the associations between volume pools and datasets explicitly ALLOWed or DISALLOWed on volumes within the pool.
Created when you select QuickPool from the Build Initialization Members menu.
- PREFINIT** Contains the statements required to generate the ISPF LOG/LIST/TEMP file prefix controls.
Created when you select PREFIX from the Build Initialization Members menu.
- RACFINIT** Contains the statements required to generate the RACF Discrete Profile controls.
Created when you select RACF from the Build Initialization Members menu.
- RSTRINIT** Contains the statements required to generate the Restrict Device controls.
Created when you select RSTR from the Build Initialization Members menu.
- SVCINIT** Contains the statements required to generate the SVC Delete/Replace controls.
Created when you select SVC from the Build Initialization Members menu.
- TPSHINIT** Contains the statements required to generate the TAPESHR controls.
Created when you select TPSHR from the Build Initialization Members menu.
- TIMEINIT** Contains the statements required to generate the Time Controls.
Created when you select TIME from the Build Initialization Members menu.
- VOLINIT** Contains the statements required to generate your specified volume groups. If you have entered a description for a group.
Created when you select Volume from the Build Initialization Members menu.

If you browse any of the initialization members, you will note that each exit point is generated as a separate OS/EM command. This is not an OS/EM requirement but it makes the commands easier to "read". Comments are included to help document what the command is for, and to document the user who last generated the command (along with date and time). If you use the description fields, they will be included as comments in the generated commands.

Do not EDIT the initialization commands. All maintenance of the initialization members should be done through the interface. Any changes you make by editing the member will not be included the next time

you use the interface unless you have executed OSV6 and used the REBUILD command to resync the interface.

Help Screens

An extensive set of HELP screens is supplied for the ISPF interface. These screens will guide you through the various fields on their "owning" panels and explain the use/contents of the fields.

Starting the ISPF Interface

The OS/EM ISPF Interface is reached either by selecting the OS/EM option from an existing ISPF Menu screen (assuming you created an OS/EM option on some existing ISPF Menu screen during the installation process), or by entering the command **OS\$START** from the TSO READY prompt or ISPF Option 6 (TSO Command Processor).

Primary Options Menu

The Primary Option Menu (refer to Figure 1) presents several selections. Each option presents another selection menu, taking you down the path you have chosen.

```
OS/EM ----- Primary Option Menu ----- Version 6.0
Option ===>

          1  System Level Controls
             Maintenance Functions
             Installation Functions

          2  Basic Exit Functions
          3  Extended OS/EM Functions
          4  Query OS/EM Status
          5  Reload Exits
          6  Set JES name / currently: JES2
          7  Execute Pending Changes
          8  Build Initialization Member

          T  Tutorial
          X  Exit from OS/EM

          UserID  -SPJRT
          System ID-BLUE
          Time    -15:29
          Terminal -3278
          PF Keys -24
```

Figure 1. Primary Option Menu

Each of these paths is presented in the following sections:

- 1 System Level Controls (see “System Controls, Maintenance & Installation Functions” on page 3-1)
- 2 Basic Exit Functions (see “Basic Exit Functions” on page 4-1)
- 3 Extended OS/EM Functions (see “Extended OS/EM Functions” on page 5-1)
- 4 Query OS/EM Status (see “Query OS/EM Status” on page 6-1)
- 5 Reload Exits (see “Reload Exits” on page 7-1)
- 6 Set JES2 name (see “Set JES2 Name” on page 8-1)
- 7 Execute Pending Changes (see “Execute Pending Changes” on page 9-1)

- 8** Build Initialization Member (see “Build Initialization Member” on page 10-1)
- T** ISPF Tutorial
- X** Exit OS/EM

System Controls, Maintenance & Installation Functions

This menu is divided into three sections:

1. System Level Controls - defines general OS/EM system parameters
2. Maintenance - OS/EM "housekeeping" functions
3. Installation - OS/EM installation & upgrade functions

```
OS/EM ----- MAINTENANCE AND INSTALLATION ----- Version 6.0
SELECTION ====>

                SYSTEM LEVEL CONTROLS
1 - Authorization Codes
2 - Enable/Disable Expiration Warning Message
3 - Abend Notify TSO IDs
4 - Recording Record Type Number
5 - Performance Counts and Timings
6 - Turn On/Off Execute Online Warning Message

                MAINTENANCE
7 - Pending Changes Table Clean-up
8 - Rebuild OS/EM Tables from Query Function

                INSTALLATION
9 - Create Tables for Version 6.0 (New Install Only)
10 - Upgrade to OS/EM Version 6.0
```

Figure 2. Setup and Maintenance

Enter the **number** for the function that needs to be performed. The appropriate panel will then be displayed.

Each of these paths is presented in the following sections:

System Level Controls

See "System Level Controls" on page 3-2

Maintenance

See "Maintenance" on page 3-8

Installation

See "Installation" on page 3-10

System Level Controls

Authorization Codes

The Authorization Codes function is used to authorize OS/EM to execute on your installation's CPU(s).

```
OS/EM ----- AUTHORIZATION CODES ----- Version 6.0
COMMAND ==>> SCROLL ==>> CSR

Line Cmds: (A)dd new code, (D)elete existing code, (S)elect for update

      Authorization
Sel   Code           Description
-    3CF8BB8233      Blue System_____
-    2F83A6F119      Disaster Recovery Site_____
-    3D66C1E203      Green System_____

***** Bottom of data *****
```

Figure 3. Authorization Codes

Enter the **Authorization Code** supplied with your installation materials.

When your order for OS/EM was placed, you were asked for the four low-order digits of the CPUID you will be running on. Therefore you need supply only one CPUID if your CPU contains more than one processor.

Each CPU that you intend running OS/EM on must have an authorization code. Multiple authorization codes are allowed in the initialization member so that a single initialization member can be used for all the CPUs at your site.

Note: You may also want to add authorization codes for your disaster recovery site so that there will be no problems if you have to execute offsite.

There are 3 line commands available:

A Add a new code.

Enter 'A' in the SEL column and overtype any existing information and press enter.

D Delete an existing code.

Enter 'D' in the SEL column to delete an entry no longer needed.

S Select an existing code to update the description.

Enter 'S' in the SEL column to update the description field. The authorization code itself may not be updated. If an incorrect code is entered, you will need to re-add it as a new code, then delete the incorrect code.

Expire Warning Messages

Warning messages will be issued starting 30 days before expiration of the authorization code. You will need to obtain a new code within that time.

By default OS/EM will produce the message **OS\$DCN031 *WARNING* OS/EM WILL EXPIRE IN xx DAYS** every hour for the entire month before expiration.

```
----- OS/EM EXPIRATION WARNING MESSAGE -----  
Cmd ==>>  
  
Display Expiration Warning Message? ==> YES      (YES/NO)  
  
By default, OS/EM will display the message:  
OS$DCN031 *WARNING* OS/EM WILL EXPIRE IN xx DAYS  
approximately every hour for the last 30 days before the authorization  
code expires.  
  
If you do not want this warning message displayed, you may turn it off  
here.
```

Figure 4. Expiration Warning Message Control

Some customers have found this to be distracting and have requested a way to turn off the warning message. This function will allow you to suppress the message.

Note: Suppressing this message may be unwise as OS/EM will fail to operate once your current authorization code has expired.

Abend Notification

This function defines the TSO users who are to be notified in the event of an ABEND.

```
OS/EM ----- NOTIFY MENU ----- Version 6.0  
SELECTION ==>>  
  
1 Define Notify Groups  
   Specify IDs or Groups  
2 ALLOC Exits  
3 DASD Exits  
4 HSM Exits  
5 ISPF Exits  
6 JES2 Exits  
7 JES3 Exits  
8 MISC Exits  
9 RACF Exits  
10 SAF Exits  
11 SMF Exits  
12 TSO Exits  
13 Any OS/EM Exit  
14 Any User Exit
```

Figure 5. Notify Menu

TSO user IDs can be defined explicitly to one or more exit functions and/or to one or more user groups which are subsequently defined to the desired exit functions.

Each exit function can have a maximum of three user definitions. Therefore, it is often recommended that user groups be used.

Selection Options:

- 1 Define & maintain notification user groups.
- 2-12 Define users/groups to receive ABEND notification for specific user exit functional areas.
- 13 Define users/groups to receive ABEND notification for **any** OS/EM exit.
- 14 Defines users/groups to receive ABEND notification for **any** user exit.

Options 2 through 14 have the same selection panel and so will not be described individually.

Define Notify Groups

This function provides the ability to group multiple users into a single logical entity that can be used for ABEND notification. Up to 32 user groups can be defined.

When this function is entered, the list of group names is displayed. **PF7 / PF8** scrolls backwards/forwards through the group list.




Figure 6. Define User Groups Menu

The **S** line command selects the entry to be defined or altered. The group name and description fields can be entered or modified (Caution: altering the group name may have adverse effects on existing abend notification lists).

When **Enter** is pressed, the following entry box will be displayed:




Figure 7. Define User IDs for a Group

Enter the user name(s) in the available fields (1 through 8). **PF3** completes the user name definition and returns to the user group list panel.

User Notes:

- OS/EM supports up to 32 TSO user ID groups
- Each user group can have up to 8 TSO ID definitions.

Define Users for Abend Notification

Options 2 through 12 of the Notify Menu panel maintains the notification lists for user exit abends. When any of these options is selected, the following panel is displayed:

```

OS/EM ----- NOTIFY MENU ----- Version 6.0
S +----- SPECIFY IDS FOR ALLOCATION EXITS -----+
  | COMMAND ==>                                     |
  | Enter TSO IDs below:                             |
  | 1) SYSPROG   2) HERCB   3)                       |
  |-----+-----+-----+-----+-----+-----+
                                     4 HSM Exits
                                     5 ISPF Exits
                                     6 JES2 Exits
                                     7 JES3 Exits
                                     8 MISC Exits
                                     9 RACF Exits
                                    10 SAF Exits
                                    11 SMF Exits
                                    12 TSO Exits
                                    13 Any OS/EM Exit
                                    14 Any User Exit

```

Figure 8. Define IDs or Groups

Enter the TSO user IDs and/or user groups to be notified of an abend. **PF3** completes the update process and the user is returned to the Notify Menu.

SMF Recording

OS/EM can create SMF records to track each execution of the **OS\$CNTL** command and its output. Job Routing changes also create SMF records.

```

OS/EM ----- SMF RECORDING RECORD NUMBER ----- Version 6.0
COMMAND ==>

SMF Recording Active ==> YES (Yes/No)

Enter Record Number for SMF Recording ==> 222

```

Figure 9. SMF Recording

Field entry is as follows:

1. SMF Recording Active

Enter **Yes** or **No** to control the creation of the OS/EM SMF records.
2. Enter Record Number for SMF Recording

Enter the number of the record type you want OS/EM to use.

Note: This number may also be specified on the OSV6 subsystem PROCLIB member. Be sure that it is the same number if it is specified in both places. See Step 7: Define subsystem name OSV6 in the OS/EM Reference manual.

Performance Counts and Timings

OS/EM can track the number of times an exit is called and the CPU time each exit took to execute. These values are displayed on the OS/EM Query Report. Because tracking these values adds overhead to your system, it is suggested that you normally leave this tracking function disabled.

```
----- OS/EM PERFORMANCE STATS -----
Command ==>

Display Performance Stats? ==> YES      (YES/NO)

Performance counts and timings are displayed on the OS/EM Query Report.
```

Figure 10. OS/EM Performance Stats

Enter **YES** to enable performance tracking, enter **NO** to disable tracking.

Execute Online Warning Message

The OS/EM ISPF interface allows you to execute online (or via batch) the changes you have made to the different options. To make the changes effective across IPLs, the INIT members have to be updated.

To remind you of this needed function, a warning pop-up window is displayed each time you execute the changes.

You may disable this message with the **WARN** System Level Control.

```
OS/EM ----- OS/EM Execution Warn Mode ----- Version 6.0
COMMAND ==>

DISPLAY EXECUTE PENDING WARNING MESSAGE? ==> NO      (YES/NO)

By default, OS/EM will display a pop-up window reminding you to use 'Option 8
Build Initialization Member' each time you execute your pending changes
online. Specifying NO here will disable this pop-up.

This option is stored in your ISPF profile. This means that each OS/EM user
may set this option.
```

Figure 11. OS/EM Execution Warn Mode Panel

Enter **NO** to turn off the warning pop-up. Enter **YES** to keep the pop-up reminder.

Note: This setting is stored in the individual users ISPF profile dataset. As such this setting applies to the individual OS/EM user.

Maintenance

This section allows you to remove old entries from the Pending Changes table and synchronize the tables used by the ISPF interface with the currently active options on the system running OS/EM.

Pending Changes Table Maintenance

The Pending Changes Maintenance function is used to clean up the Pending Changes table by deleting changes that have been permanently implemented by having the initialization members built (see “Build Initialization Member” on page 10-1).

This function is particularly useful when frequent changes are being made to OS/EM (e.g. initial setup and tuning) because it reduces the amount of data in the table (all changes to the OS/EM system are recorded in the Pending Changes table).

Note:

1. If the Pending Changes table library is a standard PDS, periodic compression of the dataset will be necessary.
2. The Rebuild Function will automatically delete all Pending Changes entries (See "Rebuild OS/EM Tables" in this topic)




Figure 12. Pending Changes Maintenance

Field entry is as follows:

1. Enter the **date** in YY/MM/DD format, of the latest changes to delete.
2. Press **Enter** to begin the deletion process, or **PF3** (end) to exit.

Rebuild OS/EM Tables

The Rebuild Function reconstructs the ISPF tables from the current OS/EM system environment.

The function first executes the Query command to obtain the OS/EM information currently in storage then deletes the old tables and recreates them from the information obtained from the query command. Any descriptions which have been previously entered will be copied from the original ISPF tables before they are deleted.

The Rebuild Function can be of great use when changes have been made to the OS/EM system environment without going through the ISPF interface.

```
OS/EM ----- VERIFY REBUILD ----- Version 6.0  
COMMAND ===>
```

Selecting the REBUILD option will destroy all of the current OS/EM ISPF tables and rebuild them from either an existing FULL Query Report or by issuing the QUERY command directly.

If you specify an existing Query Report, be sure that the previous table library specified is from the same system as the Query Report. The previous table library will be used to obtain any descriptive information that may have been entered.

Existing Query Report file (may be blank)

====>

Previous Table Library (used only if Query Report specified)

====>

Current Table Library (may not be changed, information only)

====> 'SPJRT.OSEM.VER60.ISPTLIB'

Figure 13. Verify Rebuild

Field entry is as follows:

1. Enter an existing **Query Report** which will be used in place of executing the query command directly (optional).

If used, be sure to enclose the DSN in apostrophes (single quotes), otherwise your TSO ID will be appended to the front of the dataset name.

2. If you entered a Query Report DSN, you must also enter the name of the matching table library. If this library is not on shared DASD, make a temporary copy available on the system which will execute the rebuild function.

Again, use apostrophes to qualify the dataset name.

3. Press **ENTER** to destroy all existing OS/EM ISPF tables and rebuild them based on current storage.
4. Press **PF3** (END) to cancel.

Note: If you have valid changes pending, they should be executed prior to using this function, or those changes will be lost. See "Execute Pending Changes" on page 9-1 for more information on this process.

```

OS/EM ----- ISPF TABLE REBUILD UTILITY ----- Version 6.0
COMMAND ==>

PLEASE WAIT. . . . .

The OS/EM tables are being rebuilt.

Generating function: BASIC

Depending on the options you have chosen, this process may take some
time.

Currently processing member: OS$TBUJY

```

Figure 14. ISPF Table Rebuild Utility

Since this process takes several minutes to complete, the above panel is displayed to let you know what processing is currently being done.

Installation

Create OS/EM Tables

The create process is used when OS/EM is first installed. The function creates all of the ISPF tables which the ISPF interface uses to store the information needed to build the initialization parameter members used at IPL time.

```

OS/EM ----- INSTALLATION PROCESS ----- Version 6.0
COMMAND ==>

PLEASE WAIT. . . . .

Various tables are being created to support OS/EM basic and option
functions. This is a one-time process and will take a few moments to
complete.

OS$EXTB

```

Figure 15. Create OS/EM ISPF Tables

If the tables create process fails for any reason, you cannot simply reselect it from the menu. You need to delete any tables that may have been added to the new table library first.

Use ISPF option 3.1 (Library Utility) to delete any members which may have been added.

Note: The OS/EM supplied table library (TLIB) contains three members, OSEMCMDS, OSEMKEYS and OSEMVER. Be sure these members are not deleted, or are recopied into the table library if the **CREATE** process needs to be restarted.

After the table library has been cleaned-up, re-select the CREATE process from the maintenance menu.

Upgrade to OS/EM 6.0

The upgrade function parses a Query Report of your current OS/EM environment to determine which exits and/or optional features you are using and stores that information in ISPF tables. This function will also rebuild the initialization members.

Note: Since the upgrade function rebuilds the initialization members, it is advisable to execute this function before you IPL. Otherwise the initialization members which the install procedure places into parmlib will be empty, and no OS/EM features or user exits will be activated.

```
OS/EM ----- VERIFY UPGRADE ----- Version 6.0
COMMAND ===>

Selecting this option will attempt to upgrade your existing OS/EM
options into the format required by the current release of OS/EM.
This is done by parsing a Query Report showing your existing options.

If you are installing OS/EM on a system where OS/EM does not exist you
may specify a file name which contains a Full Query Report from the system
where OS/EM is currently running.

Execute Query Function? ===>                (Yes/No)

    or

Use this Query Report    ===>                (Query Report DSN)

Previous Table Library ===> 'SYS1.OSEM.VER56.ISPTLIB'
Current Table Library ===> 'SYS1.OSEM.VER60.ISPTLIB'
Current Parm Library ===> 'SYS1.OSEM.VER60.PARMLIB'
Current Command Library => 'SYS1.OSEM.VER60.ISREXEC'
```

Figure 16. Verify Upgrade

1. Specify whether you want to have the Upgrade function execute the Query Function, or specify a Query Report dataset name which will be parsed.

If you are going to run this function prior to your first IPL with the new OS/EM release, you may allow the Upgrade to execute the query directly. However, if you will be doing an IPL before the upgrade, you should create a Query Report using the **ALL** parameter and save the report so that the upgrade function will have access to it.

Note: To successfully run the upgrade function on a different machine from where OS/EM is currently running, create a query report and point the upgrade function to it.

2. The four libraries needed for the upgrade are listed at the bottom of the panel. If any of these names are incorrect, you will need to edit the OS\$START CLIST and correct any incorrectly entered **site variables**.
3. Press the **Enter** key to begin the upgrade.
4. Press **END** to cancel.

Basic Exit Functions

Description

The basic OS/EM Function provides for the dynamic loading, and reloading of all supported OS/390 and z/OS Exits. Exit points may be enabled and disabled dynamically; and, where appropriate, exit points may be limited to specific jobnames giving an installation a Quality Assurance or testing environment not previously available.

OS/EM Exit Functions

- Automatic Management of Exits with predefined names for Allocation, DFP, HSM, JES2, JES3, RACF, SAF, SMF and TSO.
- Eliminates the need to IPL to refresh LPA modules that are managed by OS/EM Allocation, DFP, HSM, ISPF, JES2, JES3, RACF, SAF, SMF and TSO.
- Error Recovery for Exit abends (ESTAE and FRR as appropriate)
- Backup Exit programs specified to automatically switch to, if an Exit program abends
- Security Interface to an External Security Manager (e.g. RACF, CA-TOPSECRET, CA-ACF2) to allow access to OS/EM functions
- ISPF interface for Exit Management
- Query Interface to display Exit Status
- 255 Independent Exit programs per exit point
- Jobname limiting for each Exit program (where available)
- Valid Return code checking
- Good Return code checking
- Disabling Return code checking (To remove an Exit program from execution)
- Default Return code
- TSO Notify support for Exit programs that abend
- Loading of Exits from LINKLIBs, JOBLIB, STEPLIB, LLIB or private authorized load library
- SVC dumps for Exit program abends
- Loading of Exit programs in either CSA or ECSA depending on RMODE/AMODE addressability
- Dynamically Reload individual Exit programs
- Dynamically Reload OS/EM Controller Programs without an IPL

- Dynamically Disable individual Exit programs

List of Exits Supported

For a complete list, see “Appendix A. Supported Exits” on page A-1.

- Allocation Exits
- DFSMS DFP Exits
- DFSMS HSM Exits
- ISPF Installation Wide Exits
- JES2 Exits
- JES3 Exits
- RACF Exits
- SAF Exits
- System Management Facilities (SMF) Exits
- TSO/E Exits

Autoinstall Feature

New to version 6.0, the OS/EM Autoinstall Feature greatly simplifies the installation and migration process by dynamically defining exit points and automatically loading both OS/EM and user exit modules.

Autoinstall provides the following functions:

- **Dynamic Enabling of Exits** -Autoinstall will automatically define and enable MVS user exits during system initialization. This eliminates the need to define these exits in the PROGxx or EXITxx system PARMLIB members.
- **Automatic Loading of LPA Modules** - Autoinstall will automatically load OS/EM control modules that are required to be resident in the FLPA / PLPA. This eliminates the need to define these modules in the IEAFIXxx and IEALPaxx system PARMLIB members.
- **Automatic Loading of Standard User Exit Modules** - OS/EM will automatically load and enable user exit modules when all the following criteria is met:
 1. There are no user exits defined in OS/EM for that user exit point
 2. The load module name matches the user exit point name
 3. The load module is located in the system LINKLST or LPA
 4. The load module is not a dummy user exit (OS/EM will examine the load module to ensure it does more than simply return to the caller).
- **Automatic Implementation of JES2 Exits** -Autoinstall will perform the following functions during JES2 initialization:
 1. Dynamically defines the OS/EM JES2 user exit interface modules.
 2. Places all user exits under OS/EM control.
 3. Processes all EXIT(XXX) and LOADMOD(yyyyyyyy) statements in the JES2 initialization parameters and dynamically defines these exits to OS/EM. The EXIT and LOADMOD statements are not processed by JES2.

Prior releases of OS/EM required the user to modify the JES2 initialization parameters to remove existing exit & module definitions and add the OS/EM exits and load modules. Additionally, the user exits had to be manually defined to OS/EM.

Autoinstall provides a much simpler and automated implementation process requiring no initial changes to the JES2 & OS/EM parameters in order to initialize OS/EM. For more information about migrating JES2 exits into an OS/EM environment, refer to the OS/EM Installation Guide.

Basic Exit Functions Menu

Basic Exit Functions allow you to specify:

- Whether a particular exitpoint is enabled or disabled
- Whether or not there are active user exits, and what those exits are
- Up to three jobname masks per exit to limit the effect of the associated user exit, if LIMIT checking is applicable to the exitpoint
- An optional description for each of the specified user exits
 - Use the description field to document the author of the user exit, the date the user exit was installed or modified, etc.

If you wish to enable OS/EM Extended Functions for an exitpoint, such as HSM Optimizer functions, but you do not have any user exits, you do not need to "visit" Basic Function Support. The OS/EM Extended Function interface ensures that the proper specifications are made in order to generate support, and you do not need to concern yourself with which exit point(s) supports the OS/EM Extended Function you are invoking.




Figure 17. Basic Exit Functions

Each of these paths is presented in the following sections:

1. JES2 Exits (see "JES2 Exits" on page 4-4)
2. JES3 Exits (see "JES3 Exits" on page 4-11)
3. MVS Exits (see "MVS Exits" on page 4-18)

JES2 Exits

This panel displays all of the JES2 exits in alphabetical order by exit name and tells you which JES2 user exits are being used. You may page up and down with PFK7 and PFK8.

```
OS/EM ----- JES2 EXIT SELECTION ----- Version 6.0
COMMAND ==>>                                     SCROLL ==>> CSR

(CMD = Exit Point (O)ptions, (U)ser Exits

      Exit      User
CMD Active Point Exits  Description
'  ACTIVE EXIT000
'  ACTIVE EXIT001      Print/Punch Separators
'  ACTIVE EXIT002      YES Job Statement Scan
'  ACTIVE EXIT003      Job Statement Accounting Field Scan
'  ACTIVE EXIT004      JCL and Job Statement Accoun
'  ACTIVE EXIT005      JES2 Command Preprocessor
'  ACTIVE EXIT006      Converter/Interpreter Text Scan
'  ACTIVE EXIT007      JCT Read/Write
'  ACTIVE EXIT008      Control Block Read/Write
'  ACTIVE EXIT009      Job Output Overflow
'  ACTIVE EXIT010      $WTO Screen
'  ACTIVE EXIT011      Spool Partitioning Allocation ($TRACK)
'  ACTIVE EXIT012      Spool Partitioning Allocation ($STRAK)
'  ACTIVE EXIT013      TSO/E Transmit Facility Screen/Notification
'  ACTIVE EXIT014      Job Queue Work Select ($QGET)
'  ACTIVE EXIT015      Output Dataset/Copy Select
```

Figure 18. JES2 Exit Selection List

Line commands are:

O Define exit point options

This function controls the execution options for the exit point.

“JES2 Exit Point Options” on page 4-5 documents the resulting panel(s) and actions for this selection.

U Define user exit modules

This function defines the user exit modules to be executed for the exit point and their execution sequence.

“JES2 User Exit Modules” on page 4-6 documents the resulting panel(s) and actions for this selection.

JES2 Exit Point Options

The following panel is displayed when the when the **O** line command is entered for a JES2 exit point.

```
OS/EM ----- EXIT POINT EXIT002 OPTIONS ----- Version 6.0
COMMAND ==>

Exit Point EXIT002    ==> ACTIVE                (Active/Inactive/Disable)

OS/EM Exit Called    ==> FIRST                    (First/Last)
Notify For OS/EM ABEND ==>      ,      ,          (Up to 3 TSO IDs)

Exit Re-entrant Key  ==> 0                        (0 or 1)

Default Return Code ==> ___ or Reset ==> Y      (0-999 or Y to reset)

Valid Return Codes:  or Reset ==> Y            (Enter Y to reset)
_____

Good Return Codes    or Reset ==> Y            (Enter Y to reset)
_____

Disabling Return Codes or Reset ==> Y        (Enter Y to reset)
_____

Enter any combination of the following separated by commas or spaces:
0,4,8,12,16,20,24,28,32,36,40,44,ANY,GE255,LT255,NONZERO or the literal NONE
```

Figure 19. JES2 Exit Point Options

This field entry panel allows you to set the general execution options for the selected JES2 user exit.

1. Exit Point xxxxxxxx

ACTIVE - the defined JES2 exit(s) will be loaded at IPL time and executed when the exit is driven.

INACTIVE - the defined JES2 exit(s) will be loaded at IPL time but will not be executed when the exit is driven.

DISABLE - the defined JES2 exit(s) will not be loaded or executed.

2. OS/EM Exit Called

FIRST - specifies that the OS/EM Extended Functions will be applied before any JES2 user exit modules are invoked for this exit point.

LAST - specifies that the OS/EM Extended Functions will be applied after the JES2 user exits are invoked for this exit point.

Note: If the exit being displayed does not have associated OS/EM Extended Functions, the OS/EM fields will be locked.

3. Notify for OS/EM ABEND

Enter up to three **TSO User IDs** or **Notify Group Names** to be notified if an ABEND occurs in any of the OS/EM extended functions for this JES2 exit point.

4. Exit Re-entrant Key

0 - the JES2 exit modules must be MVS re-entrant.

1 - the JES2 exit modules need not be MVS re-entrant.

Note: Key 0 programs may be loaded to LPA, key 1 programs will be loaded to CSA.

5. Default Return Code

The return code (register 15) passed by the OS/EM exit interface if no User exit modules are present, if the exit module controller module is not loaded, or some other internal error has occurred. There is a default return code provided by the exit interface module for each JES2 exit point that is managed. Use this option with extreme caution.

6. Valid Return Codes

OS/EM checks for valid return codes (register 15) being issued by user exit modules as defined by the IBM JES2 exit programming documentation for each exit point. The valid return codes for each IBM JES2 exit point are built into OS/EM. If anything is specified it completely replaces the IBM list. Use this option with extreme caution.

7. Good Return Codes

OS/EM checks for good return codes (register 15) being issued by user exit modules. A good return code allows subsequent user exit modules to be called. OS/EM provides a default list. For example, if a user exit for IEFUTL set the return code to zero (indicating the job processing is to be cancelled), then no other user exit modules would be called, including the optional features if they were to be called last. Check the IBM JES2 exit programming documentation to determine which return codes are valid for good return codes. If anything is specified it completely replaces the IBM list. Use this option with extreme caution.

8. Disabling Return Codes

OS/EM checks for a return code (register 15) being issued by a user exit module then disables that user exit module from being executed again. This option is primarily provided for JES3 support, but could be used for one time loading of tables, etc.

Note: When specifying return codes, enter any combination of the following values separated by blanks or commas:

- 0,4,8,12,16,20,24,28,32,36,40,44
- ANY
- GE255
- LT255
- NONZERO
- NONE

JES2 User Exit Modules

The following panel is displayed when the U line command is entered for a JES2 user exit point.

```

OS/EM ----- USER EXIT SELECTION - EXIT001 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

(S)elect, (C)opy, (M)ove, (B)efore, (A)fter, (I)nsert, (D)elete), (R)peat
      Primary/Backup
SEL Active   Names           Description
'   YES   RDJESX01 : USER01__ Xerox Separators_____
'   ___   _____ : _____
'   ___   _____ : _____
'   ___   _____ : _____
'   ___   _____ : _____
'   ___   _____ : _____
'   ___   _____ : _____
'   ___   _____ : _____
***** Bottom of data *****

```

Figure 20. JES2 User Exit Modules

This panel displays the modules defined for the selected JES2 exit point. The user can add & delete modules entries, update entries and change the execution sequence of the user exit modules.

Line commands are:

S Select a user exit module entry

This function displays the user exit module field entry panel and allows the user to modify the definition parameters for that module.

“JES2 User Exit Module Definition” on page 4-9 documents the resulting panel(s) and actions for this selection.

I Insert entry

This function adds an empty module entry immediately following the specified entry. This blank entry can then be defined by using the **S** line command to edit the module details.

D Delete entry

This function deletes the specified module entry.

C Copy entry

This function makes a copy of the specified entry. This line command is used in conjunction with the **A** and **B** line commands to control the location of the copied entry.

M Move entry

This function relocates the specified entry within the module selection list. This line command is used in conjunction with the **A** and **B** line commands to control the new location of the moved entry.

R Repeat entry

This function duplicates the specified entry and inserts it immediately following the specified entry.

A Locate AFTER

This function locates a copied/moved entry immediately after the selected entry.

B Locate BEFORE

This function locates a copied/moved entry immediately before the selected entry.

JES2 User Exit Module Definition

The following panel is displayed when the **S** line command is entered in the JES2 User Exit Module display panel.

```
OS/EM ----- USER EXIT 1 FOR EXIT POINT EXIT001 ----- Version 6.0
COMMAND ==>                                         SCROLL ==> CSR

User Exit Active      ==> YES                               (Yes/No)

Notify for User ABEND ==> 1) SYSPROG_ 2) _____ 3) _____

Primary Exit Module Name ==> RDJESX01
      Entry Point ==> USER01__
      Library ==> _____

Backup Exit Module Name ==> _____
      Entry Point ==> _____
      Library ==> _____

Limits ==> _____
      Location ==> _____

Description: Xerox Separators_____
            _____
```

Figure 21. JES2 User Exit Module Definition Panel

This field entry panel defines the characteristics of the user exit module to be executed.

1. User Exit Active

YES - the defined JES2 exit module will be loaded at IPL time and executed when the exit is driven.

NO - the defined JES2 exit(s) will not be loaded or executed.

2. Notify for User Exit ABEND

Enter up to three **TSO User IDs** or **Notify Group Names** to be notified if an ABEND occurs in the defined user exit module for this JES2 exit point.

3. Primary User Exit - this is the user exit module to be executed when the JES2 exit is driven.

- Module Name - the name of the load module (or alias) to be executed.
- Entry Point - the name of the load module entry point to be used.
- Library - if the load module does not reside in a library defined in the system's LINKLIST, you may specify the name of the load library dataset. The dataset name with single quotes (!) and the library must be APF authorized.

Note: If a library is specified and the load module is not found in that library, OS/EM will not continue to search for the module and it will not be loaded.

4. Backup User Exit - this user exit module (if specified) will be used in the event that an ABEND occurs in the primary module.

- Module Name - the name of the load module (or alias) to be executed.
- Entry Point - the name of the load module entry point to be used.

- c. Library - if the load module does not reside in a library defined in the system's LINKLIST, you may specify the name of the load library dataset. The dataset name with single quotes (') and the library must be APF authorized.

Note: If a library is specified and the load module is not found in that library, OS/EM will not continue to search for the module and it will not be loaded.

5. Limits

This field allows the execution of the user exit module to be restricted to specific jobnames and/or jobname masks. Multiple names or masks should be separated by spaces.

This is particularly useful for limiting the scope of an exit module while it is being tested by restricting its execution to specific test jobs. When the module is to be put into production, the execution of the exit can be made global by removing the jobname limits.

Note: If the exit point does not support limits this field will be locked and no entry will be allowed.

6. Location

This specifies the address of the jobname field in the parameters being passed to this user exit. Refer to the TSO TEST command for a discussion of addressing conventions for this parameter. The value contained at the specified address will be compared to the jobname specified by the **limits** entry above and if a match is found the exit is allowed to execute.

7. Description

This field provides an area to document the function of the user exit module.

Limit Masking

Job Name Masks: The following table shows the allowable mask characters:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

JES3 Exits

```
OS/EM ----- EXIT SELECTION ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

(CMD = Exit Point (O)ptions, (U)ser Exits)

      Exit      User
CMD Active Point Exits Description
'  ACTIVE IATUX00      Reserved Name
'  ACTIVE IATUX01      Reserved Name
'  ACTIVE IATUX02      Reserved Name
'  ACTIVE IATUX03      Examine Converter/Interpreter Text
'  ACTIVE IATUX04      Examine Job Information from JCL
'  ACTIVE IATUX05      Examine Step Information from JCL
'  ACTIVE IATUX06      Examine DD Statement Information from JCL
'  ACTIVE IATUX07      Examine/Substitute Unit, Type and VOLSER Info
'  ACTIVE IATUX08      Examine Setup Information
'  ACTIVE IATUX09      Examine Final Job Status, JST and JVT
'  ACTIVE IATUX10      Generate a Message
'  ACTIVE IATUX11      Inhibit Printing of LOCATE Request/Response
'  ACTIVE IATUX12      Reserved Name
'  ACTIVE IATUX13      Reserved Name
'  ACTIVE IATUX14      Job Validation/Restart LOCATE Req/Response
'  ACTIVE IATUX15      Scan an Initialization Statement
```

Figure 22. Basic JES3 Exit Selection

Line commands are:

O Define exit point options

This function controls the execution options for the exit point.

“JES3 User Exit Options” on page 4-12 documents the resulting panel(s) and actions for this selection.

U Define user exit modules

This function defines the user exit modules to be executed for the exit point and their execution sequence.

“JES3 User Exit Modules” on page 4-14 documents the resulting panel(s) and actions for this selection.

This panel displays all of the JES3 exits in alphabetical order by exit name and tells you which JES3 user exits are being used. You may page up and down with PFK7 and PFK8.

JES3 User Exit Options

The following panel is displayed when the when the **O** line command is entered for a JES3 user exit point.

```
OS/EM ----- EXIT POINT IATUX14 OPTIONS ----- Version 6.0
COMMAND ==>

Exit Point IATUX14      ==> ACTIVE                (Active/Inactive/Disable)

OS/EM Exit Called      ==> FIRST                  (First/Last)
Notify For OS/EM ABEND ==> _____ , _____ , _____ (Up to 3 TSO IDs)

Linkage Edit Style     ==> _____            (BAKR/BALR/ARET/ARETRC)

Default Return Code ==> ____ or Reset ==> Y      (0-999 or Y to reset)
Default R15 Value     ==> _____

Valid Return Codes:   or Reset ==> Y            (Enter Y to reset)
Valid R15 Values:
_____

Good Return Codes     or Reset ==> Y            (Enter Y to reset)
Good R15 Values:
_____

Disabling Return Codes or Reset ==> Y            (Enter Y to reset)
Disabling R15 Values
_____

Enter any combination of the following separated by commas or spaces:
0,4,8,12,16,20,24,28,32,36,40,44,ANY,GE255,LT255,NONZERO or the literal NONE
```

Figure 23. JES3 User Exit Options

This field entry panel allows you to set the general execution options for the selected JES3 user exit.

1. Exit Point xxxxxxxx

ACTIVE - the defined JES3 exit(s) will be loaded at IPL time and executed when the exit is driven.

INACTIVE - the defined JES3 exit(s) will be loaded at IPL time but will not be executed when the exit is driven.

DISABLE - the defined JES3 exit(s) will not be loaded or executed.

2. OS/EM Exit Called

FIRST - specifies that the OS/EM Extended Functions will be applied before any JES3 user exit modules are invoked for this exit point.

LAST - specifies that the OS/EM Extended Functions will be applied after the JES3 user exits are invoked for this exit point.

Note: If the exit being displayed does not have associated OS/EM Extended Functions, the OS/EM fields will be locked.

3. Notify for OS/EM ABEND

Enter up to three **TSO User IDs** or **Notify Group Names** to be notified if an ABEND occurs in any of the OS/EM extended functions for this JES3 exit point.

4. Exit Linkage Style

BAKR - The exit is called using the BAKR (Branch and Stack) instruction.

BALR - The exit is called using the BALR (Branch and Link Register) instruction.

ARET - The exit is called using the ACALL macro and control is returned with the ARETURN macro **without** the RC= parameter.

ARETRC - The exit is called using the ACALL macro and control is returned with the ARETURN macro **with** the RC= parameter.

Note: For more information about these program linkage options, refer to the IBM JES3 Customization manual.

5. Default Return Code

The return code (register 15) passed by the OS/EM exit interface if no User exit modules are present, if the exit module controller module is not loaded, or some other internal error has occurred. There is a default return code provided by the exit interface module for each JES3 exit point that is managed. Use this option with extreme caution.

6. Valid Return Codes

OS/EM checks for valid return codes (register 15) being issued by user exit modules as defined by the IBM JES3 exit programming documentation for each exit point. The valid return codes for each IBM JES3 exit point are built into OS/EM. If anything is specified it completely replaces the IBM list. Use this option with extreme caution.

7. Good Return Codes

OS/EM checks for good return codes (register 15) being issued by user exit modules. A good return code allows subsequent user exit modules to be called. OS/EM provides a default list. For example, if a user exit for IEFUTL set the return code to zero (indicating the job processing is to be cancelled), then no other user exit modules would be called, including the optional features if they were to be called last. Check the IBM JES3 exit programming documentation to determine which return codes are valid for good return codes. If anything is specified it completely replaces the IBM list. Use this option with extreme caution.

8. Disabling Return Codes

OS/EM checks for a return code (register 15) being issued by a user exit module then disables that user exit module from being executed again. This option is primarily provided for JES3 support, but could be used for one time loading of tables, etc.

Note: When specifying return codes, enter any combination of the following values separated by blanks or commas:

- 0,4,8,12,16,20,24,28,32,36,40,44
- ANY
- GE255
- LT255
- NONZERO
- NONE

For JES3, there is a second set of return code values - Default / Valid / Good / Disabling R15 Values. These settings are applicable when the user exit uses ARETURN RC= (ARETC) program linkage conventions.

JES3 User Exit Modules

The following panel is displayed when the when the U line command is entered for a JES3 user exit point.

```

OS/EM ----- USER EXIT SELECTION - IATUX20 ----- Version 6.0
COMMAND ===>                                     SCROLL ===> CSR

(S)elect, (C)opy, (M)ove, (B)efore, (A)fter, (I)nsert, (D)elete), (R)peat
      Primary/Backup
SEL  Active   Names      Description
'    _____ J3USRX9_  _____
'    _____  _____  _____
'    _____  _____  _____
'    _____  _____  _____
'    _____  _____  _____
'    _____  _____  _____
'    _____  _____  _____
***** Bottom of data *****

```

Figure 24. JES3 User Exit Modules

This panel displays the modules defined for the selected JES3 exit point. The user can add & delete modules entries, update entries and change the execution sequence of the user exit modules.

Line commands are:

S Select a user exit module entry

This function displays the user exit module field entry panel and allows the user to modify the definition parameters for that module.

“JES3 User Exit Module Definition” on page 4-16 documents the resulting panel(s) and actions for this selection.

I Insert entry

This function adds an empty module entry immediately following the specified entry. This blank entry can then be defined by using the **S** line command to edit the module details.

D Delete entry

This function deletes the specified module entry.

C Copy entry

This function makes a copy of the specified entry. This line command is used in conjunction with the **A** and **B** line commands to control the location of the copied entry.

M Move entry

This function relocates the specified entry within the module selection list. This line command is used in conjunction with the **A** and **B** line commands to control the new location of the moved entry.

R Repeat entry

This function duplicates the specified entry and inserts it immediately following the specified entry.

A Locate **AFTER**

This function locates a copied/moved entry immediately after the selected entry.

B Locate **BEFORE**

This function locates a copied/moved entry immediately before the selected entry.

JES3 User Exit Module Definition

The following panel is displayed when the **S** line command is entered in the JES3 User Exit Module display panel.

```
OS/EM ----- USER EXIT 1 FOR EXIT POINT IATUX03 ----- Version 6.0
COMMAND ==>

User Exit Active      ==> YES                                (Yes/No)

Notify for User ABEND ==> 1) SYSPROG_ 2) _____ 3) _____

Primary Exit Module Name ==> J3USRX9
Library ==> _____

Backup Exit Module Name ==> _____
Library ==> _____

Limits ==> _____
Location ==> _____

Description: _____
              _____
```

Figure 25. JES3 User Exit Module Definition Panel

This field entry panel defines the characteristics of the user exit module to be executed.

1. User Exit Active

YES - the defined JES3 exit module will be loaded at IPL time and executed when the exit is driven.

NO - the defined JES3 exit(s) will not be loaded or executed.

2. Notify for User Exit ABEND

Enter up to three **TSO User IDs** or **Notify Group Names** to be notified if an ABEND occurs in the defined user exit module for this JES3 exit point.

3. Primary User Exit - this is the user exit module to be executed when the JES3 exit is driven.

- a. Module Name - the name of the load module (or alias) to be executed.
- b. Entry Point - the name of the load module entry point to be used.
- c. Library - if the load module does not reside in a library defined in the system's LINKLIST, you may specify the name of the load library dataset. The dataset name with single quotes (') and the library must be APF authorized.

Note: If a library is specified and the load module is not found in that library, OS/EM will not continue to search for the module and it will not be loaded.

4. Backup User Exit - this user exit module (if specified) will be used in the event that an ABEND occurs in the primary module.

- a. Module Name - the name of the load module (or alias) to be executed.
- b. Entry Point - the name of the load module entry point to be used.
- c. Library - if the load module does not reside in a library defined in the system's LINKLIST, you may specify the name of the load library dataset. The dataset name with single quotes (') and the library must be APF authorized.

Note: If a library is specified and the load module is not found in that library, OS/EM will not continue to search for the module and it will not be loaded.

5. Limits

This field allows the execution of the user exit module to be restricted to specific jobnames and/or jobname masks. Multiple names or masks should be separated by spaces.

This is particularly useful for limiting the scope of an exit module while it is being tested by restricting its execution to specific test jobs. When the module is to be put into production, the execution of the exit can be made global by removing the jobname limits.

Note: If the exit point does not support limits this field will be locked and no entry will be allowed.

6. Location

This specifies the address of the jobname field in the parameters being passed to this user exit. Refer to the TSO TEST command for a discussion of addressing conventions for this parameter. The value contained at the specified address will be compared to the jobname specified by the **limits** entry above and if a match is found the exit is allowed to execute.

7. Description

This field provides an area to document the function of the user exit module.

Limit Masking

Job Name Masks: The following table shows the allowable mask characters:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

MVS Exits

This panel displays all of the MVS exits in alphabetical order by exit name and tells you which MVS user exits are being used. You may page up and down with PFK7 and PFK8.

```
OS/EM ----- BASIC EXIT SELECTION ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

(CMD = Exit Point (O)ptions, (U)ser Exits)
  Exit      Exit      User
  Type      Active    Point  Exits  Description
' SMF       ACTIVE    IEFACRTRT  YES   SMF Job/Step Termination
' ALLOC     ACTIVE    IEFALLOD      Allocated/Offline Device
' ALLOC     ACTIVE    IEFALLSW      Specific Waits
' ALLOC     ACTIVE    IEFALLVE      Volume Enqueue
' ALLOC     ACTIVE    IEFALLVM      Volume Mount
' ALLOC     ACTIVE    IEFDB401      Allocation Input Validation (SVC99)
' SMF       ACTIVE    IEFUAV        User Account Validation
' SMF       ACTIVE    IEFUJI        Job Initiation
' SMF       ACTIVE    IEFUJP        Job Purge
' SMF       ACTIVE    IEFUJV        Job Validation
' SMF       ACTIVE    IEFUSI        Step Initiation
' SMF       ACTIVE    IEFUSO        SYSOUT OUTLIM
' SMF       ACTIVE    IEFUTL        Time Limits
' SMF       ACTIVE    IEFU29        SMF Dump
' SMF       ACTIVE    IEFU83        SMF Record
```

Figure 26. Basic MVS Exit Selection

Line commands are:

O Define exit point options

This function controls the execution options for the exit point.

“MVS User Exit Options” on page 4-19 documents the resulting panel(s) and actions for this selection.

U Define user exit modules

This function defines the user exit modules to be executed for the exit point and their execution sequence.

“MVS User Exit Modules” on page 4-20 documents the resulting panel(s) and actions for this selection.

MVS User Exit Options

The following panel is displayed when the when the **O** line command is entered for a MVS exit point.

```
OS/EM ----- EXIT POINT IEFACTRT OPTIONS ----- Version 6.0
COMMAND ===>

Exit Point IEFACTRT    ===> ACTIVE                (Active/Inactive/Disable)
More:                  +
OS/EM Exit Called     ===> FIRST                (First/Last)
Notify For OS/EM ABEND ===>      ,      ,      (Up to 3 TSO IDs)
Default Return Code   ===>  ___    or Reset ===> Y    (0-999 or Y to reset)
Valid Return Codes:   or Reset ===> Y                (Enter Y to reset)
_____
Good Return Codes     or Reset ===> Y                (Enter Y to reset)
_____
Disabling Return Codes or Reset ===> Y                (Enter Y to reset)
_____

Enter any combination of the following separated by commas or spaces:
0,4,8,12,16,20,24,28,32,36,40,44,ANY,GE255,LT255,NONZERO or the literal NONE
```

Figure 27. MVS User Exit Options

This field entry panel allows you to set the general execution options for the selected MVS user exit.

1. Exit Point xxxxxxxx

ACTIVE - the defined MVS exit(s) will be loaded at IPL time and executed when the exit is driven.

INACTIVE - the defined MVS exit(s) will be loaded at IPL time but will not be executed when the exit is driven.

DISABLE - the defined MVS exit(s) will not be loaded or executed.

2. OS/EM Exit Called

FIRST - specifies that the OS/EM Extended Functions will be applied before any MVS user exit modules are invoked for this exit point.

LAST - specifies that the OS/EM Extended Functions will be applied after the MVS user exits are invoked for this exit point.

Note: If the exit being displayed does not have associated OS/EM Extended Functions, the OS/EM fields will be locked.

3. Notify for OS/EM ABEND

Enter up to three **TSO User IDs** or **Notify Group Names** to be notified if an ABEND occurs in any of the OS/EM extended functions for this MVS exit point.

4. Default Return Code

The return code (register 15) passed by the OS/EM exit interface if no User exit modules are present, if the exit module controller module is not loaded, or some other internal error has occurred. There

is a default return code provided by the exit interface module for each MVS exit point that is managed. Use this option with extreme caution.

5. Valid Return Codes

OS/EM checks for valid return codes (register 15) being issued by user exit modules as defined by the IBM MVS exit programming documentation for each exit point. The valid return codes for each IBM MVS exit point are built into OS/EM. If anything is specified it completely replaces the IBM list. Use this option with extreme caution.

6. Good Return Codes

OS/EM checks for good return codes (register 15) being issued by user exit modules. A good return code allows subsequent user exit modules to be called. OS/EM provides a default list. For example, if a user exit for IEFUTL set the return code to zero (indicating the job processing is to be cancelled), then no other user exit modules would be called, including the optional features if they were to be called last. Check the IBM MVS exit programming documentation to determine which return codes are valid for good return codes. If anything is specified it completely replaces the IBM list. Use this option with extreme caution.

7. Disabling Return Codes

OS/EM checks for a return code (register 15) being issued by a user exit module then disables that user exit module from being executed again. This option is primarily provided for JES3 support, but could be used for one time loading of tables, etc.

Note: When specifying return codes, enter any combination of the following values separated by blanks or commas:

- 0,4,8,12,16,20,24,28,32,36,40,44
- ANY
- GE255
- LT255
- NONZERO
- NONE

MVS User Exit Modules

The following panel is displayed when the U line command is entered for an MVS user exit point.

```

OS/EM ----- USER EXIT SELECTION - IEFACTRT ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

(S)elect, (C)opy, (M)ove, (B)efore, (A)fter, (I)nsert, (D)elete, (R)epeat
      Primary/Backup
SEL  Active      Names      Description
'    YES        USRXIT1_  _____
'    _____  _____  _____
'    _____  _____  _____
'    _____  _____  _____
'    _____  _____  _____
'    _____  _____  _____
'    _____  _____  _____
***** Bottom of data *****

```

Figure 28. MVS User Exit Modules

This panel displays the modules defined for the selected MVS exit point. The user can add & delete modules entries, update entries and change the execution sequence of the user exit modules.

Line commands are:

S Select a user exit module entry

This function displays the user exit module field entry panel and allows the user to modify the definition parameters for that module.

“MVS User Exit Module Definition” on page 4-23 documents the resulting panel(s) and actions for this selection.

I Insert entry

This function adds an empty module entry immediately following the specified entry. This blank entry can then be defined by using the **S** line command to edit the module details.

D Delete entry

This function deletes the specified module entry.

C Copy entry

This function makes a copy of the specified entry. This line command is used in conjunction with the **A** and **B** line commands to control the location of the copied entry.

M Move entry

This function relocates the specified entry within the module selection list. This line command is used in conjunction with the **A** and **B** line commands to control the new location of the moved entry.

R Repeat entry

This function duplicates the specified entry and inserts it immediately following the specified entry.

A Locate **AFTER**

This function locates a copied/moved entry immediately after the selected entry.

B Locate **BEFORE**

This function locates a copied/moved entry immediately before the selected entry.

MVS User Exit Module Definition

The following panel is displayed when the **S** line command is entered in the MVS User Exit Module display panel.

```
OS/EM ----- USER EXIT FOR EXIT POINT IEFACTRT ----- Version 6.0
COMMAND ==>

User Exit Active      ==> YES                               (Yes/No)

Notify for User ABEND ==> 1) MVSPROG_ 2) _____ 3) _____

Primary Exit Module Name ==> USRXIT1_
Library ==> _____

Backup Exit Module Name ==> _____
Library ==> _____

Limits ==> _____

Description: _____
              _____
```

Figure 29. MVS User Exit Module Definition Panel

This field entry panel defines the characteristics of the user exit module to be executed.

1. User Exit Active

YES - the defined MVS exit module will be loaded at IPL time and executed when the exit is driven.

NO - the defined MVS exit(s) will not be loaded or executed.

2. Notify for User Exit ABEND

Enter up to three **TSO User IDs** or **Notify Group Names** to be notified if an ABEND occurs in the defined user exit module for this MVS exit point.

3. Primary User Exit - this is the user exit module to be executed when the MVS exit is driven.

- a. Module Name - the name of the load module (or alias) to be executed.
- b. Entry Point - the name of the load module entry point to be used.
- c. Library - if the load module does not reside in a library defined in the system's LINKLIST, you may specify the name of the load library dataset. The dataset name with single quotes (') and the library must be APF authorized.

Note: If a library is specified and the load module is not found in that library, OS/EM will not continue to search for the module and it will not be loaded.

4. Backup User Exit - this user exit module (if specified) will be used in the event that an ABEND occurs in the primary module.

- a. Module Name - the name of the load module (or alias) to be executed.
- b. Entry Point - the name of the load module entry point to be used.
- c. Library - if the load module does not reside in a library defined in the system's LINKLIST, you may specify the name of the load library dataset. The dataset name with single quotes (') and the library must be APF authorized.

Note: If a library is specified and the load module is not found in that library, OS/EM will not continue to search for the module and it will not be loaded.

5. Limits

This field allows the execution of the user exit module to be restricted to specific jobnames and/or jobname masks. Multiple names or masks should be separated by spaces.

This is particularly useful for limiting the scope of an exit module while it is being tested by restricting its execution to specific test jobs. When the module is to be put into production, the execution of the exit can be made global by removing the jobname limits.

Note: If the exit point does not support limits this field will be locked and no entry will be allowed.

6. Description

This field provides an area to document the function of the user exit module.

Limit Masking

Job Name Masks: The following table shows the allowable mask characters:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

Extended OS/EM Functions

```
OS/EM ----- EXTENDED OS/EM SUPPORT ----- Version 6.0
SELECTION ==>

          1 Define Dataset name groups
          2 Define Volume groups
          3 HSM Optimizer
          4 HSM Reports
          5 ISPF File Prefix Controls
          6 JCL Controls
          7 Job Controls
          8 Job Routing/Classing
          9 Miscellaneous Controls
         10 Quickpool/DASD Allocation Controls
         11 RACF Controls
         12 Restrict Devices
         13 SVC Delete/Replace
         14 Tape Share Controls
         15 Time Controls
```

Figure 30. Extended OS/EM Support

Each of these paths is presented in the following sections:

1. Define Dataset Name Groups (see “Define Dataset Name Groups” on page 5-3)
2. Define Volume Groups (see “Define Volume Groups” on page 5-12)
3. HSM Optimizer (see “HSM Optimizer” on page 5-18)
4. HSM Reports (see “HSM Optimizer Report System” on page 5-59)
5. ISPF File Prefix Controls (see “ISPF File Prefix Controls” on page 5-108)
6. JCL Controls (see “JCL Controls” on page 5-110)
7. Job Controls (see “Job Controls” on page 5-139)
8. Job Routing/Classing (see “Job Routing Controls” on page 5-170)
9. Miscellaneous Controls (see “Miscellaneous Controls” on page 5-189)
10. QuickPool (see “QuickPool” on page 5-201)
11. RACF Controls (see “RACF Controls” on page 5-210)
12. Restrict Devices (see “Restrict Devices” on page 5-213)
13. SVC Delete/Replace (see “SVC Controls” on page 5-215)
14. Tape Share Controls (see “Tape Share Controls” on page 5-218)

15. Time Controls (see “Time Controls” on page 5-224)

Define Dataset Name Groups

Dataset Name Groups are used to establish a list of dataset name mask(s) and/or dataset name(s). The group names are then used in various OS/EM functions instead of specifying the same dataset name or masks(s) in every function.

Build groups as needed. A dataset name or mask(s) may appear in more than one group since each OS/EM function will use Dataset Name Groups in a different way.

This dialog displays the list of Dataset Name Groups and provides the functions to create new groups as well as maintain and delete existing groups.

```
OS/EM ----- DSN NAME GROUPS ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

  Enable groups      ==> YES      (Enter YES to enable; NO to disable)

  (CMD = (A)dd (D)elete (C)hange (T)emporarily disable toggle)

Cmd  Group Name  Description
-    ANY         : PATTERN TO MATCH ANY MULTI-LEVEL DSN_____
      : _____
-    BATCH       : MIGRATABLE BATCH FILES_____
      : _____
-    BKPEXC      : datasets excluded from hsm backup_____
      : _____
-    CATLG       : CATALOGS_____
      : _____
-    CLMSBAT     : Claims for Portland flat files_____
      : _____
```

Figure 31. Dataset Name Group List

This panel displays the Dataset Groups that are currently defined to the OS/EM system. The PF7 & PF8 keys can be used to scroll up & down the list of groups.

Creating Group Names

Group Names are a maximum of eight characters in length, and may not start with the letters **NO**.

Each Group Name represents a group of one or more dataset names and/or mask(s). Dataset group names are used wherever OS/EM Extended Functions (such as the HSM Optimizer Direct to ML2 function) can use dataset name groups for its INCLUDE option.

There is no practical limit to the number of dataset name groups that may be created; especially since the groups may consist of dataset name(s)/mask(s) that represent a subset of your installation's total number of datasets.

It is suggested that you develop a naming scheme which will give some indication as to the dataset name group's use.

Note: Groups are stored internally in alphabetical order. Keep this in mind when creating group names. The OS/EM initialization member will also be built in alphabetic order. This determines OS/EM's search order when going through the dataset name(s) and mask(s) in each group to find a match. Dataset name(s)

and mask(s) are searched in the order entered within the Dataset Name Group list. The first match that OS/EM finds will be the one used.

Panel Input Fields

1. **Panel Command Line** - see “Entering data” on page 2-1 for more information regarding ISPF commands.
2. **Enable Groups**
 - YES** The Dataset Groups function is enabled and the defined groups are available to the OS/EM extended functions.
 - NO** The Dataset Groups function is disabled.
3. **Line Commands**
 - A** - Add a Dataset Group (see “Add a DSN Group” on page 5-5)
 - C** - Change the Dataset Group (see “Change a DSN Group” on page 5-6)
 - D** - Deletes the Dataset Group (see “Delete a DSN Group” on page 5-7)
 - T** - Toggles the Dataset Group to/from being temporarily disabled (see “Temporarily Disable a DSN Group” on page 5-9)

Add a DSN Group

The following screen is displayed when the line command **A** (Add a group) is entered:

```
OS/EM ----- DSN NAME GROUPS ----- Version 6.0
COMMAND ==>

Enter DSN Group Name and optional Description

Group Name ==>          (Enter DSN Group Name)

Description ==> _____
                   _____
```

Figure 32. DSN Name Groups - Add Group Name

1. Group Name

This is the name of the group to be defined. The group name can be up to 8 characters in length and must not start with **NO**. See **Creating Group Names** earlier in this section for more details about selecting a Dataset Group name.

2. Description

This optional field provides an area for the user to provide comments relating to the group.

When the **ENTER** key is pressed, the Change Group panel is displayed (see Figure 33 on page 5-6). This allows the user to define the dataset name(s) and mask(s) which will constitute the group.

Change a DSN Group

The following panel is displayed in response to the Change and Add (after Dataset group is defined) line commands. This panel which will allow you to change the group description and to change, add and delete dataset name(s) and mask(s) for the group.

```
OS/EM ----- DSN NAME GROUPS ----- Version 6.0
COMMAND ===>                                     SCROLL ===> CSR

Group Name ===> BATCH

Description ===> MIGRATABLE BATCH FILES_____
                _____

Enter DSN names for group:
(CMD = (I)nsert line (D)elete line (S)elect for update)

  CMD      DSN names or masks
  --      -
  --      GSA%..-.FIL.+
  --      GSA%..-.OBS.PRC
  --      GSA%..-.OBS.SRC
  --      GSA%..-.OBS.JCL
  --      GSA%..-.OBS.CPY
  --      GSA%..-.BKP.+
  --      GSA%..-.LOG.+
  --      GSA%..-.IMC.+
  --      GSA%..-.COM.+
  --      GSA%..-.SAV.+
***** Bottom of Data *****
```

Figure 33. DSN Name Groups - Change

The change panel contains a scrollable area where the dataset name(s) or mask(s) are maintained. Each row consists of a single dataset name or mask.

The following line commands can be used:

D - Delete the entry

I - Insert a new dataset name / mask immediately following the selected line.

S - Select the entry for update. The dataset name / mask can be modified prior to pressing ENTER.

You may NOT change the group name. If you wish to change the name, you must create a new group with the desired name and enter all the dataset name(s) and mask(s) that will constitute the group. Delete the old group once the new group is active.

Delete a DSN Group

A dataset group is deleted by entering a **D** line command next to the desired group.

The group, and all the dataset name(s) and mask(s) comprising the group, will be deleted. OS/EM will check that the group is not referenced in any function and will not delete the group if it is, however no checks are made to determine whether the group is still referenced within an OS/EM initialization member. Initialization will produce undesired results if undefined Dataset Name Groups are referenced.

A series of panels will display after a group has been selected for deletion. These panels will be as follows:

```
OS/EM ----- DSN NAME GROUPS ----- Version 6.0
COMMAND ==>

PLEASE WAIT. . . .

A search is being made of all functions that use DSN name groups
to ensure that you are not attempting to delete a group that is
still in use. This process will take a few moments.
```

Figure 34. DSN Name Groups - Wait

```
OS/EM ----- DSN NAME GROUPS ----- Version 6.0
COMMAND ==>

The search has found that Group BATCH is referenced
1 times in various functions. You must delete all references
before you can delete the group.

Deleting the group and building a new Group initialization
member will NOT remove the group until the next IPL.

If you wish to immediately remove the group, temporarily disable the
group, then EXECUTE the DSN Group function. Finally, build the
initialization member so that the group will not reappear with the
next IPL.

Use ENTER to see the list of references for Group BATCH
```

Figure 35. DSN Name Groups - Delete

```
OS/EM ----- DSN NAME GROUPS ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR
```

Group BATCH is referenced in the following functions:

```
QUICKPOOL: POOL NAME IS VOLG15, POOL TYPE IS ALLOW
***** BOTTOM OF DATA *****
```

Figure 36. DSN Name Groups - References

```
OS/EM ----- DSN NAME GROUPS ----- Version 6.0
COMMAND ==>
```

The search has found no references to Group BATCH2.

Deleting the group and building a new Group initialization member will NOT remove the group until the next IPL.

If you wish to immediately remove the group, temporarily disable the the group, then EXECUTE the Group function. Finally, build the initialization member so that the group will not reappear with the next IPL.

Use ENTER to continue, or use CANCEL to quit.

Figure 37. DSN Name Groups - No References

Temporarily Disable a DSN Group

A dataset group may be temporarily disabled by entering a **T** in line command field before the desired group entry. The group definition will be retained but none of the dataset name(s) within the group will be available for OS/EM processing.

Disabled groups are indicated by a **T** immediately to the left of the group name. These groups may be enabled by entering a **T** in the line command field. The **T** line command acts as a disable/enable toggle.

While the definition is retained, the same considerations apply as if the group were being deleted (see “Delete a DSN Group” on page 5-7).

As with all changes in the interface, you must remember to execute this change online for it to take effect.

Dataset Name Masks

Dataset name masks are created by using qualifiers within a dataset name. Valid qualifiers are:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The minus sign is used to unconditionally match a single node of the dataset name. Multiples are allowed.
+	The plus sign is used to unconditionally match all characters/nodes of the dataset name beyond where it is entered in the specification. A single plus sign may be specified.

Examples of dataset name masks

<i>Example</i>	<i>Explanation</i>
AA	Specifies single-level dataset AA
AA?AA	Specifies a single-level dataset name of five characters. The first and last two characters are AA. The third character can be anything: AA5AA,AABAA, etc.
AA+	Specifies any dataset name beginning with the two characters AA: AA55.TEST
AA-	Specifies a single-level dataset name beginning with the characters AA: AA5PROD
AA.+	Specifies a two or more level dataset name. The first node is AA: AA.PROD.COMP
AA.-	Specifies a two level dataset name. The first node is AA: AA.CICS
-.AA	Specifies a two level dataset name. The last node is AA: PROD.AA
SYS1.-.HRP1000	Specifies a three-level dataset name. The first node is SYS1 and the last node is HRP1000
-.-.-	Specifies any three-level dataset name. This type of specification will match every three-level dataset name within your installation.
GSAX.-.PRM	Specifies a three-level dataset name. The first node is GSAX and the last node is PRM.
SYS?-.	Specifies a two-level dataset name. The first node starts with SYS and any other character. The second node can be anything: SYS1.LINKLIB
SYS&.-	Specifies a two-level dataset name. The first node starts with SYS and any other alphabetic character. The second node can be anything: SYSX.LINKLIB
SYS%-.	Specifies a two-level dataset name. The first node starts with SYS and any other numeric character. The second node can be anything: SYS5.LINKLIB

- SYSX.-EZT???** Specifies a three-level dataset name. The first node is SYSX. The second node can be anything. The third node begins with EZT and any three characters:
SYSX.CICS.EZT030
- ??SYSUT?.+** Specifies a two or more level dataset name. The first node begins with any two characters, followed by SYSUT and any other single character.
- AA.+BB** Specifies a three or more level dataset name. The first node is AA and the last node is BB.
- AA+AA** Specifies a single-level dataset name. The first two characters are AA and the last two characters are AA. The up to four middle characters can be anything. There has to be at least one middle character - AAAA will not match.
- SYSX.PROCLIB**
A fully qualified dataset name.

Define Volume Groups

Volume name groups are used to establish a list of DASD volumes. These group names are then used in various OS/EM Extended Functions instead of specifying the same volume serial numbers in every function.

Build groups as needed. A volume serial number may appear in more than one group since each OS/EM Extended Function will use volume serial numbers in a different way.

This dialog displays the list of Volume Groups and provides the functions to create new groups as well as maintain and delete existing groups.

```
OS/EM ----- VOL NAME GROUPS ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

  Enable groups      ==> YES      (Enter YES to enable; NO to disable)

(CMD = (A)dd (D)elete (C)hange (T)emporarily disable toggle)

Cmd  Group Name  Description
-   MVSAUX      : MVS Auxiliary volumes (SMP/E SMF ISPF Etc..)
   : _____
-   SMSSTD      : volumes in sms standard pool
   : _____
-   VOLG1       : _____
   : _____
-   VOLG10      : dispatch online viewing
   : _____
-   VOLG16      : HSM ML1 VOLUMES
   : _____
```

Figure 38. Volume Name Groups

This panel displays the Volume Groups that are currently defined to the OS/EM system. The PF7 & PF8 keys can be used to scroll up & down the list of groups.

Creating Group Names

Group Names are a maximum of eight characters in length, and may not start with the letters **NO**.

Each Group Name represents a group of one or more DASD volumes. Masking characters may be used to define a generic range of volumes (see “Volume Masks” on page 5-17 for more information on volume name masking). Volume group names are used wherever OS/EM Extended Functions (such as the HSM Optimizer defragmentation function) may require volume names on which to operate.

There is no practical limit to the number of volume groups that may be created; especially since groups may consist of volume serial mask(s) that represent a subset of your installation's total number of volumes.

It is suggested that you develop a naming scheme which will give some indication as to the volume group's use.

Note: Groups are stored internally in alphabetical order. Keep this in mind when creating group names. The OS/EM initialization member will also be built in alphabetic order. This determines OS/EM's search order when going through the volume name(s) and mask(s) in each group to find a match. Volume name(s) and mask(s) are searched in the order entered within the Volume Group list. The first match that OS/EM finds will be the one used.

Panel Input Fields

1. **Panel Command Line** - see “Entering data” on page 2-1 for more information regarding ISPF commands.
2. **Enable Groups**
 - YES** The Volume Groups function is enabled and the defined groups are available to the OS/EM extended functions.
 - NO** The Volume Groups function is disabled.
3. **Line Commands**
 - A** - Add a Volume Group (see “Add a Volume Group” on page 5-14)
 - C** - Change the Volume Group (see “Change a Volume Group” on page 5-15)
 - D** - Deletes the Volume Group (see “Delete a Volume Group” on page 5-16)
 - T** - Toggles the Volume Group to/from being temporarily disabled (see “Temporarily Disable a Volume Group” on page 5-16)

Add a Volume Group

The following screen is displayed when the line command **A** (Add a group) is entered:

```
OS/EM ----- VOL NAME GROUPS ----- Version 6.0
COMMAND ==>

Enter VOL Group Name and optional Description

Group Name ==>          (Enter VOL Group Name)

Description ==> _____
                  _____
```

Figure 39. Volume Name Groups - Add Group Name

1. Group Name

This is the name of the group to be defined. The group name can be up to 8 characters in length and must not start with **NO**. See **Creating Group Names** earlier in this section for more details about selecting a Volume Group name.

2. Description

This optional field provides an area for the user to provide comments relating to the group.

When the **ENTER** key is pressed, the Change Group panel is displayed (see Figure 40 on page 5-15). This allows the user to define the volume name(s) and/or mask(s) which will constitute the group.

Change a Volume Group

The following panel is displayed in response to the **Change** and **Add** (after Volume group is defined) line commands. This panel which will allow you to change the group description and to change, add and delete volume name(s) and mask(s) for the group.

```
OS/EM ----- VOL NAME GROUPS ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Group Name ==> MVSAUX

Description ==> MVS Auxiliary volumes (SMP/E SMF ISPF Etc..)
_____

Enter VOL names for group:
(CMD = (I)nsert line (D)elete line (S)elect for update)

CMD      VOL names or masks
-        MVSCTA
-        MVSCTB
-        PAGE01
-        PAGE02
-        SYS000
-        SYS001
***** Bottom of data *****

Figure 40. Volume Name Groups - Change
```

The change panel contains a scrollable area where the volume name(s) or mask(s) are maintained. Each row consists of a single volume name or mask.

The following line commands can be used:

D - Delete the entry

I - Insert a new volume name / mask immediately following the selected line.

S - Select the entry for update. The volume name / mask can be modified prior to pressing ENTER.

You may NOT change the group name. If you wish to change the name, you must create a new group with the desired name and enter all the volume name(s) and mask(s) that will constitute the group. Delete the old group once the new group is active.

Delete a Volume Group

A Volume Group is deleted by entering a **D** line command next to the desired group.

The group, and all the volume name(s) and mask(s) comprising the group, will be deleted. OS/EM will check that the group is not referenced in any function and will not delete the group if it is, however no checks are made to determine whether the group is still referenced within an OS/EM initialization member. Initialization will produce undesired results if undefined Volume Name Groups are referenced.

A series of panels will display after a group has been selected for deletion. These panels will be as follows:

Delete a complete volume group by entering a **D** in the CMD field before the group.

The group, and all the dataset names and masks comprising the group, will be deleted. OS/EM will check that the group is not referenced in any other panel and will not delete the group if it is, however no checks are made to determine whether the group is still referenced within OS/EM initialization member. Initialization will produce undesired results if undefined Volume Groups are referenced.

Temporarily Disable a Volume Group

A volume group may be temporarily disabled by entering a **T** in line command field before the desired group entry. The group definition will be retained but none of the volume name(s) within the group will be available for OS/EM processing.

Disabled groups are indicated by a **T** immediately to the left of the group name. These groups may be enabled by entering a **T** in the line command field. The **T** line command acts as a disable/enable toggle.

While the definition is retained, the same considerations apply as if the group were being deleted (see “Delete a Volume Group”).

As with all changes via the interface, you must remember to execute the change online to have it take effect.

Volume Masks

Volume masks are created by using qualifiers within a volume serial number. Valid qualifiers are:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

Examples of volume serial number masks

Example

Explanation

VOL0%%

Matches any serial number that begins with VOL0 and any two numeric characters: VOL010

&%%%%

Matches any serial number that begins with any alpha character and five numbers

HSM Optimizer

Description

The HSM Optimizer allows you to more precisely control DFHSM migration and backup. DFHSM as supplied by IBM in both SMS and Non-SMS environments provides a limited set of specifications in determining which datasets will, or will not, be migrated or backed up. Complete volumes may be excluded, datasets may be excluded from migration, and a residency factor (the number of days since last reference) may be specified. The HSM Optimizer, in contrast allows multiple residency specifications, the dataset size as a factor at migration time versus allocation time in DFSMS, and a relationship between a dataset's size and specification in a dataset name list.

Summary of Features

- Provide a default DSORG for all datasets allocation so that DFHSM can manage all datasets
- Global rules for Migration from Primary volumes to Migration Level 1 for DFSMS environments based on dataset size at migration time
- Global rules for Migration from Migration Level 1 to Migration Level 2 for DFSMS environments based on dataset size at migration time
- Global rules for Direct Migration from Primary volumes to Migration Level 2 for DFSMS environments based on dataset size at migration time
- Eliminates DFHSM Error messages by allowing simple lists of dataset name(s) or dataset name mask(s) to be entered for exception processing. i.e. Exclude dataset name(s) or dataset name mask(s) for datasets that are always open during DFHSM daily migration or backup processing
- Automatic defragmentation of Primary volumes based on fragmentation index, time of day, day of week, and volume serial for Non-SMS and DFSMS environments
- Direct Migration from Primary volumes to Migration Level 2 based on dataset size and/or dataset name at migration time versus DFSMS at allocation time
- Migration from Primary volumes to Migration Level 1 refused for datasets based on dataset size and/or dataset name at migration time versus DFSMS at allocation time
- Migration from Migration Level 1 to Migration Level 2 refused for datasets based on dataset size and/or dataset name at migration time versus DFSMS at allocation time
- Exclude datasets from DFHSM back up in a Non-SMS or DFSMS environment
- Optimum Re-blocking of recalled datasets, and exclusion of datasets to be Re-blocked based on dataset size and/or dataset names
- Residency specified at the dataset level for Non-SMS environments
- Ability to prioritize batch and online recall and recover requests.
- Ability to initiate batch recalls when the job goes through conversion and to optionally hold the job in the input queue until recalls have completed.

HSM Optimizer Menu

DFHSM, as currently supplied by IBM, offers only coarse control over which datasets get migrated and backed up. Only one aging factor may be supplied, and this factor applies to all datasets, except those explicitly excluded from processing. If your installation has a very aggressive aging factor, say only one or two days, and a high percentage factor for migration 'kick-in', datasets will be continually migrated and recalled, with no regard to their usage or size. Further, the same sort of factors apply to DFHSM's Level-1 storage. If your Level-1 storage is on the small side and a large dataset migrates, you might find that many of your recalls will be coming from Level-2 storage. If this level is tape, there will be delays while the tape is found and mounted.

The HSM Optimizer has been designed to give you much finer control over the migration and backup process. It also gives you the option to reblock datasets when they are recalled, and to automatically defragment DASD volumes based on supplied criteria. The following details the HSM Optimizer's functions (it is assumed that you have some familiarity with DFHSM processing and the setting of options in the ARCCMDxx parm member):

- The HSM Optimizer's basic control mechanism is the HOLD day, the amount of time a dataset must remain unreferenced before it is eligible for processing. Multiple HOLD days are supplied for every DFHSM process that ages datasets before processing. You are given choices of 1-10 days, 15-50 days by 5 day increments, and 60-90 days in 10 day increments. You may also choose 9999 as an aging factor which, effectively, holds a dataset indefinitely.
- Dataset size may be specified. Depending on the function, this is either a maximum dataset size which datasets have to be less than or equal to, or it is a minimum size that datasets must exceed or be equal to before being selected for processing.
- A list of datasets that are always to be included, or excluded, from processing may be specified. These lists are formed by specifying the appropriate data set name groups.
- A connection between dataset size and a dataset being in an included or excluded list may be established, further refining the selection process.
- Datasets may be reblocked during the recall process. Full through eighth track blocking is supported, along with system reblocking if your installation has the correct level of DFP installed.
- Automatic defragmentation of your DASD volumes may be done by setting fragmentation levels and assigning volumes to one of eight different pools.
- A reporting system is furnished which should help you in determining the proper HSM Optimizer controls for your installation.

We recommend that you run the report system before attempting to specify any of the HSM Optimizer's controls. Once you have determined a strategy, implement it in phases. Also, to get the most effect from the HSM Optimizer, set DFHSM's aging factors to one day and specify a low THRESHOLD for the volumes, see Programmer's Guide. The HSM Optimizer only "sees" those datasets that DFHSM considers eligible for processing. By setting aggressive factors in your DFHSM ARCCMDxx parm member, you let the HSM Optimizer determine whether a dataset should be processed. Consider, too, removing all specifications for datasets that you currently set as NOMIG or COMMANDMIGRATION via the SETMIG statement. Handle such datasets via the HSM Optimizer. This will place all DFHSM control in one place.

Directed Recall requires that the following DFHSM SETSYS option be present in DFHSM ARCCMDxx member.

```
SETSYS RECALL (PRIVATE (UNLIKE) )
```

Note: If the dataset is a DFSMS dataset this option will not be invoked. If QUICKPOOL allocation is in effect, you must specify DIRECTRECALL. DFHSM RECALL/RECOVERY will most likely fail if this option is not enabled.

```

OS/EM ----- HSM OPTIMIZER ----- Version 6.0
COMMAND ==>

      1 - Backup Control
      2 - Defragmentation Control
      3 - Delete-By-Age Control
      4 - Delete-If-Backed-Up Control
      5 - Direct to Level-2 Control (ML0 -> ML2)
      6 - Early Batch Recall (JES2)
      7 - Force DSORG to PS
      8 - Migration Control (ML0 -> ML1)
      9 - Migration Level-2 Control (ML1 -> ML2)
     10 - Prioritize Recall/Recover Requests
     11 - Quick Delete Control
     12 - Reblocking Control
     13 - Recall/Recover Volume Selection Control

```

Figure 41. HSM Optimizer Menu

Each of the Optimizer's functions is detailed in the following sections. Many of the panels are repetitious. For example, any function that is driven by a dataset group list has a panel on which you specify the dataset name groups. The interface presents this panel, with an appropriate title, for each function; but the panel will be detailed only once.

Each of these paths is presented in the following sections:

1. Backup Control (see "Backup Control" on page 5-21)
2. Defragmentation Control (see "Defragmentation" on page 5-23)
3. Delete-By-Age Control (see "Delete-by-Age Control" on page 5-28)
4. Delete-If-Backed-Up Control (see "Delete-if-Backed-Up Control" on page 5-31)
5. Direct to Level-2 Control (see "Direct-to-Level-2 Control" on page 5-34)
6. Early Batch Recall (see "Early Batch Recall" on page 5-36)
7. Force DSORG to PS (see "Force DSORG to PS" on page 5-38)
8. Migration Control (see "Migration Control (ML0-ML1)" on page 5-39)
9. Migration Level-2 Control (see "Migration Level-2 Control (ML1-ML2)" on page 5-42)
10. Prioritize Recall/Recover Requests (see "Prioritize Recall/Recover Requests" on page 5-46)
11. Quick Delete Control (see "Quick Delete Control" on page 5-54)
12. Reblocking Control (see "Reblocking Control" on page 5-55)
13. Recall/Recover Volume Selection Control (see "Recall/Recover Volume Selection" on page 5-58)

Backup Control

Backup control allows you to specify datasets which should not be backed up. DFHSM processing will back up every dataset that has changed or is new. Many installations have datasets that are created, used, and overwritten the next time they are used. There really is no need to back up such datasets.

The first panel presented (Figure 42) allows you to ENABLE or DISABLE backup control. You also specify whether any EXCLUDE dataset name group list(s) will be a part of backup processing.

The EXCLUDE list consists of previously defined dataset name groups. Any dataset that can be resolved to a group on the list will NOT be backed up. Be careful that datasets you are excluding should not be backed up. Note that the displayed description is the description you entered, if any, when you created the dataset name group. It is displayed here for documentation purposes.

```
OS/EM ----- BACKUP CONTROL ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enable Backup Control ==> YES (Enter YES to enable; NO to disable)

Enter Dataset Name Groups that are to be excluded; leave groups blank for
normal DFHSM processing.

(CMD = (A)dd group; (D)elete group)
Cmd  Dataset Name Group(s)
_    BKPEXC : datasets excluded from hsm backup_____
      : _____
_    ZBD1   : _____
      : _____
_    ZBD2   : _____
      : _____
***** Bottom of data *****
```

Figure 42. HSM Optimizer Backup Control

Field entry is as follows:

1. Enable Backup Control

Entering **YES** in this field will enable OS/EM's extended processing.

Entering **NO** will disable this function.

2. Exclude Dataset Name Groups

The area in which the group names are entered is a scrollable area. Normal ISPF commands for scrolling are in effect.

Group names are up to eight characters in length. They are created by using the Define Dataset Name Groups function (see "Define Dataset Name Groups" on page 5-3). Each group represents a set of dataset name masks or fully qualified dataset names.

Note: The dataset group names that you enter must have been properly defined by using the Define Dataset Name Groups option before they can be accepted on this panel.

To add a dataset name group, enter an **A** in the CMD field and **overtyp**e the name of the **dataset name group** in the group field (overtyping will not alter the old entry).

If you enter a group name which does not exist, a popup window (see Figure 43 on page 5-22) will be displayed which lists all available groups. Use the 'S' line command to select as many groups as needed.

Note: The initial display of the Group Selection List will be positioned to the closest match for the name you tried to enter. Use the Up and Down scroll PF keys to reposition the display.

To delete an existing entry, enter a **D** in the CMD field.

```

OS/EM ----- BACKUP CONTROL ----- Row 1 from 37
COMMAND ==>                                SCROLL ==> CSR
----- SELECT DSN GROUPS FOR BACKUP EXCLUSION -----
                                           Row 16 from 29
  S Group      Description
  _ ONLINE    cics online files_____
  _ SYSTEM    SYSTEM DATASETS_____
  _ SYS1      sys1 for rename_____
  _ USERS     tso userid datasets_____
COMMAND ==>
* -----
                                           )
                                           nk for
                                           *****

```

Figure 43. Select DSN Groups for Backup Exclusion Pop-up

Defragmentation

OS/EM's Defragmentation control automates the "compaction" of DASD volumes.

DASD volumes become fragmented over time. This can eventually lead to allocation failure because, while the total free space on the volume may be adequate, too many secondary allocations would be required to satisfy an allocation request.

DFHSM returns a "fragmentation index" every time it does space management on a volume. OS/EM uses this index, based on your specification, to determine when to issue a DFDSS defrag procedure.

Invoking the Optimizer's Defragmentation Control presents the following panel:

```
OS/EM ----- DEFRAGMENTATION CONTROL ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enable DEFRAG Control   ==> YES           (Enter YES to enable DEFRAG control;
Defragmentation procedure ==> OS$DFRAG    (Default OS$DFRAG)

Default:                -- Time --          ----- DAYS -----
                        Start  End          Mon Tue Wed Thu Fri Sat Sun
                        0800 : 1200         _  Y  Y  Y  Y  _  _

(CMD = (S)elect for update (G)roup update)
Fragmentation          -- Time --          ----- DAYS -----          VOL
CMD Lvl Enable Index   Start  End          Mon Tue Wed Thu Fri Sat Sun          Groups
'   1   Y   52__       1600 : 2300         _  _  _  _  _  Y  Y           Y
'   2   Y   15__       0200 : 0400         Y  _  _  _  _  _  _
'   3   _   ___       ___ : ___          _  _  _  _  _  _  _
'   4   _   ___       ___ : ___          _  _  _  _  _  _  _
'   5   _   ___       ___ : ___          _  _  _  _  _  _  _
'   6   _   ___       ___ : ___          _  _  _  _  _  _  _
'   7   _   ___       ___ : ___          _  _  _  _  _  _  _
'   8   _   ___       ___ : ___          _  _  _  _  _  _  _
***** Bottom of data *****
```

Figure 44. Defragmentation Control/Procedure

Field entry is as follows:

1. Enable DEFRAG Control

Entering **YES** in this field will enable OS/EM's extended processing.

Entering **NO** in this field will disable OS/EM's extended processing.

2. Defragmentation Procedure

You may also specify the procedure name which will be used to start the DFDSS procedure which will actually defragment the DASD volume. The default name is OS\$DFRAG. Any other procedure name can be specified. The procedure must exist in your installation's procedure library. Processing will not be affected if the procedure does not exist; however, the defragmentation process will not be done.

The procedure should be a regular DFDSS defragmentation procedure. It must be created with a single symbolic parameter - V - which becomes the serial number of the volume to be defragmented (this may be passed in the PARM of the DFDSS EXECUTE statement). Each execution of the procedure will defragment a single volume. It is suggested that the executed procedure not actually be the DFDSS procedure, but a procedure which submits a batch job, with the appropriate parameter, that is the DFDSS defragment job. This will prevent your system from being flooded with many started tasks when a large number of volumes are being defragmented.

3. Default

Setting Global Time values

```
Default:          -- Time --
                  Start  End
                  0900  : 1400
```

Specifies the time of day during which OS/EM will issue the start for the defrag procedure. This time will apply to every defrag level which does not have its own time specification.

The time is based on a 24 hour clock. The first time parameter specifies the earliest start time that the defrag procedure will be submitted; the second time parameter, the latest time that the defrag procedure will be submitted.

For example, if you enter 0900 as the first time and 1400 as the second time, the defrag procedure will be submitted anywhere from 9AM to 2PM. The day of submission will depend on the DAYS that you specify.

Setting Global Days values

```
Default:          ----- DAYS -----
                  Mon Tue Wed Thu Fri Sat Sun
                  Y  _  _  Y  _  Y  _
```

Specifies the day(s) of the week on which OS/EM will issue the start for the defrag procedure. The day(s) will apply to any defrag level which does not specifically set its own days.

Enter Y beneath the appropriate column for the desired day. Each day must be specifically entered. If you do not wish a particular day to be active, do not enter it.

If you enter MON, THU, SAT, for example, the defrag procedure will be submitted on these days.

4. Defrag Levels

Specify the defrag level you wish to customize by placing an S in the CMD column. Eight levels are available, each with its own fragmentation index, times, days, and list of volume groups. There is no inherent meaning to the level numbers.

The defrag level parameter may be used in a couple of different ways. You may code all 8 levels with the same fragmentation index, but supply a different volume list for each level. This creates a series of volume pools that may be defrag'd on different days of the week by specifying the proper TIME and DAY parameters. Using this technique enables you to defrag your volumes on a weekly basis, spreading the process throughout the week.

The second method would be to code different fragmentation indexes for each level, specifying appropriate volumes and TIME and DAY parameters. This method allows you to defrag volumes based on their content and usage (i.e., some volumes may have large files allocated to them; therefore, you might want to defrag such volumes more frequently to minimize secondary allocation).

```
(CMD = (S)elect for update (G)roup update)
  Fragmentation  -- Time --          ----- DAYS -----          VOL
CMD Lvl Enable Index      Start  End      Mon Tue Wed Thu Fri Sat Sun      Groups
'   1   Y   350_         2300  : 0300      _  Y  _  Y  _  Y  _          Y
'   2   _   _____         _____ : _____      _  _  _  _  _  _  _
```

- Enable

Enter a Y in the Enable column to turn on that level.

- Index

Specify the fragmentation index that is to be used to determine whether a list of volumes should be defragmented. The number ranges from 0 (the default) to 999. A 0 implies that no defragmentation is to be done. 999 indicates that the volume is very fragmented: equivalent to half a volume's worth of one-track datasets placed on every other track.

An appropriate initial value would be between 350 and 500. However, the value most appropriate to your installation must be determined by the type of datasets--large or small--on the volume, and the frequency of dataset allocation on the volume.

- Setting level time values

Specifies the time of day during which OS/EM will issue the start for the defrag procedure. This time applies to the specific defrag level being configured.

The time is based on a 24 hour clock. The first time parameter specifies the earliest start time that the defrag procedure will be submitted; the second time parameter, the latest time that the defrag procedure will be submitted.

For example, if you enter 0400 as the first time and 1400 as the second time, the defrag procedure will be submitted anywhere from 4AM to 2PM. The day of submission will depend on the DAYS that you specify.

- Setting level days values

Specifies the day(s) of the week on which OS/EM will issue the start for the defrag procedure. The day(s) will apply to the specific defrag level which is being configured.

Enter **Y** beneath the appropriate column for the desired day. Each day must be specifically entered. If you do not wish a particular day to be active, do not enter it.

If you enter MON, THU, SAT, for example, the defrag procedure will be submitted on these days.

- Include Volume Groups

If you wish to INCLUDE a list of volume groups to limit the effect of the defrag level, enter **G** in the CMD field. The **Y** in the VOL Groups column will either appear or disappear based on whether you have an INCLUDE group.

If no volume list is present for a defrag level, it is assumed that the level applies to ALL volumes.

When you press the enter key after using the G line command, a pop-up window (see Figure 45 on page 5-26) will appear where you may specify the volume groups to be used for this defrag level.

To add a volume group, enter an **A** in the CMD field and the name of the volume group in the group field. Type a description of the group in the description field. Overtyping any existing entry - the old entry will not be altered.

To delete an existing entry, enter a **D** in the CMD field.

Delete-by-Age Control

DFHSM Delete-by-Age processing is rather draconian in its approach: a single aging factor may be specified after which ALL datasets exceeding this age are deleted.

OS/EM provides finer control by allowing the size of the dataset to be a determining factor, along with various aging factors OS/EM also allows specified datasets to not be deleted, even if they exceed the aging factor.

In order to use this extended function, you must activate DFHSM's Delete-By-Age processing in the appropriate ARCCMDxx parm member. The value must be set low since HSM Optimizer processing actually determines whether a dataset should be deleted. For example, if you wish to start aging datasets after 1 day, the Delete-By-Age parameter in ARCCMDxx must specify 1 day.

```

OS/EM ----- HOLD OPTIONS ----- Version 6.0
Command ==>                               Scroll ==> CSR

Controls Active for DELETE-BY-AGE          ==> YES (YES to enable, NO to disable)

(CMD = (S)elect for update, (G)roup display)

  En-  Num-  Max   AND  DSN
CMD able days size  /OR  Groups Description
'   Y   01  3000  ___  ___  _____
'   Y   02  _____  ___  3  _____
'   Y   03  4520  OR   1  _____
'   Y   04  6000  AND  2  _____
'   _   05  _____  ___  ___  _____
'   _   06  _____  ___  ___  _____
'   _   07  _____  ___  ___  _____

```

Figure 46. Delete-By-Age Hold Options

Field entry is as follows:

1. Controls Active

Enter **YES** to enable extended processing; **NO** to disable extended processing.

2. CMD

There are two line commands available, **S** and **G**. You must enter a **S** on any line you make changes to for the changes to be saved.

Enter a **S** in the CMD field of the line that contains the number of days specified datasets are to be held on Level-0 storage before being eligible for deletion.

OS/EM allows the specification of 22 different aging factors.

3. Enable Days

Enter **Y** in the ENABLE area for the specified number of days.

Enter **N** in the area to deactivate processing for this number of days.

To update the DSN groups, use the **G** line command. This will cause a POPUP window (see Figure 47 on page 5-29) to appear where you may update the groups.

Use these values, along with MAXSIZE, OR/AND connective and INCLUDED datasets, to determine how long unreferenced datasets will be held before they are deleted.

4. Maxsize

Enter **maximum dataset size** to hold in K bytes, **blank to suppress** MAXSIZE criteria.

Only datasets that are larger than this value will be deleted once they exceed the aging factor.

This value is in K bytes. Thus, a value of 1000 means that datasets less than or equal to 1,024,000 bytes will not be deleted even if they are older than the specified number of days.

If you do not wish to hold datasets based on their size, leave this value blank, or blank it if you have already entered a value.

5. OR/AND

Enter logical connection between MAXSIZE and INCLUDED datasets: OR = MAXSIZE datasets or specified datasets; AND = MAXSIZE datasets and specified datasets; blank = suppress OR/AND criteria.

A logical connection between the MAXSIZE specification and INCLUDED datasets is established by entering **OR** or **AND**.

If you enter **OR**, datasets will be held if they do not exceed the MAXSIZE value, OR if the dataset is in any of the dataset name groups that are in the INCLUDE list.

If you enter **AND**, datasets will be held if they do not exceed the MAXSIZE value, AND the dataset is in any of the dataset name groups that are in the INCLUDE list.

6. Add or Delete DSN Groups




Figure 47. Delete-By-Age Hold Options with DSN Groups "POP-UP" screen

Use the "POP-UP" panel to add or delete the DSN Groups.

The area in which the group names are entered is a scrollable area. Normal ISPF commands for scrolling are in effect.

Group names are up to eight characters in length. Create them by using the Define Dataset Name Groups function (see “Define Dataset Name Groups” on page 5-3). Each group represents a set of dataset name masks or fully qualified dataset names.

- To add a dataset name group, enter an **A** in the CMD field and the name of the dataset name group in the group field. Type a description of the group in the description field. Overtyping any existing entry - the old entry will not be altered.
- To delete an existing entry, enter a **D** in the CMD field.

Note: The dataset group names that you enter must have been properly defined by using the Define Dataset Name Groups option before they can be accepted on this panel.

Delete-if-Backed-Up Control

DFHSM can be directed to delete datasets that it has backed up, but as with Delete-By-Age processing, it is an all or nothing approach.

OS/EM provides finer control by allowing the size of the dataset to be a determining factor, along with various aging factors OS/EM also allows specified datasets to not be deleted, even if they exceed the aging factor.

In order to use this extended function, you must activate DFHSM's Delete-If-Backed-Up processing in the appropriate ARCCMDxx parm member.

```

OS/EM ----- HOLD OPTIONS ----- Version 6.0
Command ==>                               Scroll ==> CSR

Controls Active for DELETE-IF-BACKED-UP ==> YES (YES to enable, NO to disable)

(CMD = (S)elect for update, (G)roup display)

  En-  Num-  Max   AND  DSN
CMD able days size /OR Groups Description
'   Y   01   _____  ___   2   _____
'   Y   02   3000   OR   3   _____
'   Y   03   4000   AND  1   _____
'   Y   04   5200   ___   _____
'   _   05   _____  ___   _____
'   _   06   _____  ___   _____
'   _   07   _____  ___   _____

```

Figure 48. Delete-If-Backed-UP Hold Options

Field entry is as follows:

1. Controls Active

Enter **YES** to enable extended processing; **NO** to disable extended processing.

Enter an **S** to select the days specified datasets are to be held on Level-0 storage before being eligible for deletion.

Enter a **Y** in the ENABLE area to activate hold processing for the specified number of days.

OS/EM allows the specification of 22 different aging factors.

Use these values, along with MAXSIZE, OR/AND connective and INCLUDED datasets, to determine how long unreferenced datasets will be held before they are deleted.

2. Maxsize

Enter maximum dataset size to hold in K bytes, blank to suppress MAXSIZE criteria.

Only datasets that are larger than this value will be deleted once they exceed the aging factor.

This value is in K bytes. Thus, a value of 1000 means that datasets less than or equal to 1,024,000 bytes will not be deleted even if they are older than the specified number of days.

If you do not wish to hold datasets based on their size, leave this value blank, or blank it if you have already entered a value.

3. OR/AND

Enter logical connection between MAXSIZE and INCLUDED datasets: OR = MAXSIZE datasets or specified datasets; AND = MAXSIZE datasets and specified datasets; blank = suppress OR/AND criteria.

A logical connection between the MAXSIZE specification and INCLUDED datasets is established by entering **OR** or **AND**.

If you enter **OR**, datasets will be held if they do not exceed the MAXSIZE value, OR if the dataset is in any of the dataset name groups that are in the INCLUDE list.

If you enter **AND**, datasets will be held if they do not exceed the MAXSIZE value, AND if the dataset is in any of the dataset name groups that are in the INCLUDE list.

4. DSN Groups

If you wish to INCLUDE a list of datasets which will not be deleted, enter **G** in the CMD field. When the enter key is pressed, a pop-up window will be displayed where you can specify the group names.

5. Add or Delete DSN Groups




Figure 49. Delete-If-Backed-Up Hold Options with DSN Group "POP-UP" screen

Use the "POP-UP" panel to add or delete the DSN Groups.

The area in which the group names are entered is a scrollable area. Normal ISPF commands for scrolling are in effect.

Group names are up to eight characters in length. They are created by using the Define Dataset Name Groups function (see "Define Dataset Name Groups" on page 5-3). Each group represents a set of dataset name masks or fully qualified dataset names.

To add a dataset name group, enter an **A** in the CMD field and the name of the dataset name group in the group field. Type a description of the group in the description field. Overtyping any existing entry - the old entry will not be altered.

To delete an existing entry, enter a **D** in the CMD field.

Note: The dataset group names that you enter must have been properly defined by using the Define Dataset Name Groups option before they can be accepted on this panel.

Direct-to-Level-2 Control

Datasets that are not used on a regular basis, say daily or weekly, should probably be migrated. However, you do not want to exhaust ML1 storage with such datasets. ML2 storage (tape) is provided by DFHSM for this purpose. But DFHSM only migrates from ML0-ML1-ML2, unless you manually issue a DFHSM command to migrate a particular dataset directly to ML2 storage. The Optimizer can automate this process.

Selecting DIRML2 presents you with the MIGRATION CONTROL:DIR TO ML2 panel (Figure 50). This panel is similar to those already shown except that there are no HOLD days to specify. You ENABLE or DISABLE DIRML2 processing on this panel; specify a MINIMUM dataset size (datasets equal to or greater than this size will be eligible for DIRML2 processing); specify the logical connective between size and the dataset name group list, and whether the dataset name group list is an INCLUDE list or an EXCLUDE list (only one type of list may be created).

Direct migration to Level-2 storage may be controlled by use of this option. A minimum size for such datasets may be established; and, via an OR/AND connective, either include or exclude datasets from such processing.

The intent of this option is to move large, infrequently used datasets directly to Level-2 storage (usually tape) freeing Level-1 storage for smaller frequently used datasets.

```
OS/EM ----- MIGRATION CONTROL: DIR TO ML2 ----- Version 6.0
COMMAND ==>                                         SCROLL ==> CSR

Enable DIRML2 Control ==> YES ( Enter YES to enable; NO to disable )

Minimum dataset size to migrate directly to ML2:
==> 20000      ( in K bytes, blank to suppress MINSIZE criteria)

Logical connection between MINSIZE and datasets:
==> AND        ( AND/OR/blank )

Include or Exclude Dataset Name Groups:
==> EXCLUDE    ( INCLUDE/EXCLUDE/blank )

CMD  Dataset Name Group(s) (CMD = (A)dd group; (D)elete group)
"    HSM      : HSM DATASETS AND DATASETS DURING RECALL/RE
      : _____

"    ZMD1     : _____
      : _____

"    ZMD2     : _____
      : _____
```

Figure 50. Migration Control: Direct to ML2

Field entry is as follows:

1. DIRML2 Control

Enter **YES** to enable Migration control.

Enter **NO** to disable Migration Control.

2. MINSIZE

Enter **minimum dataset size** (in K bytes) to migrate directly to ML2; **blank to suppress** MINSIZE criteria.

Only datasets that are equal to or larger than this specified size will be eligible for direct migration to Level-2 storage.

If you do not wish to direct datasets to Level-2 storage based on their size, leave this field blank or blank it out if you have already entered a value.

3. OR/AND

Enter logical connection between MINSIZE and INCLUDED/EXCLUDED datasets.

A logical connection between the MINSIZE specification and the INCLUDED or EXCLUDED datasets is established by entering **OR/AND**.

If you enter **OR**, datasets will be selected if they are MINSIZE OR in the INCLUDE or EXCLUDE lists.

If you enter **AND**, datasets will be selected if they are either MINSIZE AND also in the INCLUDE or EXCLUDE lists.

4. INCLUDE/EXCLUDE

Enter **INCLUDE** to include Dataset Name Groups, or **EXCLUDE** to exclude Dataset Name Groups.

Note: You may have either an INCLUDE list or an EXCLUDE list, but NOT both.

5. Add or Delete a Dataset Name Group

The area in which the group names are entered is a scrollable area. Normal ISPF commands for scrolling are in effect.

Group names are up to eight characters in length. Create them by using the Define Dataset Name Groups function (see "Define Dataset Name Groups" on page 5-3). Each group represents a set of dataset name masks or fully qualified dataset names.

Note: The dataset group names that you enter must have been properly defined by using the Define Dataset Name Groups option before they can be accepted on this panel.

- To add a dataset name group, enter an **A** in the CMD field and the name of the dataset name group in the group field. Type a description of the group in the description field. Overtyping any existing entry - the old entry will not be altered.
- To delete an existing entry, enter a **D** in the CMD field.

Early Batch Recall

OS/EM's early batch recall function will cause DFSMSHSM to recall needed datasets while the job waits in the input queue, thus keeping initiators available for jobs which can begin execution immediately.

Note: This control is unique to each JES2 subsystem you have defined. Use Primary Option 6 - Set JES name to control which JES2 subsystem you are updating (see "Set JES2 Name" on page 8-1.)

```
OS/EM ----- EARLY BATCH RECALL CONTROL - JES2 ----- Version 6.0
COMMAND ==>

    Early Batch Recall Active  ==> YES                (Yes/No)

    Disallow Local Recalls?    ==> NO                (Yes/No)
    Ignore Failed Recalls?     ==> YES                (Yes/No)
    Only Recall First Dataset? ==> NO                (Yes/No)
    Recall COND=ONLY Steps?    ==> NO                (Yes/No)
    Recheck All Datasets?      ==> YES                (Yes/No)
    Send Message to Job Owner? ==> YES                (Yes/No)
    Send Message to Joblog?    ==> YES                (Yes/No)
    WTO to Console?           ==> YES                (Yes/No)

    Wait for:
        Only Tape Datasets      ==> YES                (Yes/No)
        Only First Recall       ==> YES                (Yes/No)
        Condition Only          ==> NO                (Yes/No)

    Recheck Interval for:
        Generationdatagroups    ==> 90                (Seconds)
        Normal datasets         ==> 300                (Seconds)
```

Figure 51. Early Batch Recall Control

The options and their meanings follow:

Disallow Local Recalls? OS/EM will not issue the recall request on the local system.

Ignore Failed Recalls? OS/EM will allow the job to be selected for execution even if an early recall has failed.

Only Recall First Dataset? OS/EM will only issue a recall request for the first dataset of the job.

Send Message to Job Owner? OS/EM will send a TSO message to the owner of a job that is being held because of pending recalls.

Send Message to Joblog? OS/EM will write a message to the joblog showing the datasets recalled.

Send Message to Console? OS/EM will write message OS\$2HM251 to the console.

OS\$2HM251 OS/EM INITIATING HRECALL OF dataset.

Wait for: Only Tape Datasets? OS/EM will only block execution of the job if the job had datasets migrated to tape.

Wait for: Only First Recall? OS/EM will only block execution of the job until the first migrated dataset has been recalled.

Wait for: Condition Only? OS/EM will block execution of the job until all migrated datasets in COND=ONLY steps have been recalled.

Recheck Interval for Generationdatagroups Specify the time in seconds that OS/EM will wait before rechecking the status of a HRECALL request. Default time is 30 seconds.

REcheck Interval for Normal Datasets Specify the time in seconds that OS/EM will wait before re-checking the status of a HRECALL request. Default time is 300 seconds.

Force DSORG to PS

This control is applied to datasets which have been allocated but never opened, which leaves an unknown DSORG causing DFSMSHSM to bypass the dataset during migration and backup processing.

Forcing the DSORG to PS allows DFSMSHSM to process the dataset.

```
OS/EM ----- FORCE DSORG TO PS ----- Version 6.0
COMMAND ==>

      Force DSORG to PS? ==> YES          (Yes/No)

This control applies to datasets allocated but never opened so that DFSMSHSM
may migrate and backup these datasets.
```

Figure 52. Entry panel for Force DSORG to PS

Enter **YES** to force the DSORG, or enter **NO** to leave unopened new datasets alone.

Migration Control (ML0-ML1)

OS/EM's migration control extends standard DFHSM migration control by considering the size of datasets and the number of days a dataset has been resident on Level-0 storage.

In order to use this extended function, you must activate DFHSM's migration processing in the appropriate ARCCMDxx parm member.

```

OS/EM ----- HOLD OPTIONS ----- Version 6.0
Command ==>                               Scroll ==> CSR

Controls Active for MIGRATION           ==> YES (YES to enable, NO to disable)

(CMD = (S)elect for update, (G)roup display)

  En-  Num-  Max   AND   DSN
CMD able days size  /OR  Groups Description
'  _   01   _____  ___  _____
'  Y   02   _____  ___  3
'  _   03   _____  ___  _____
'  _   04   _____  ___  _____
'  Y   05   752   OR   3
'  _   06   _____  ___  _____
'  _   07   _____  ___  _____

```

Figure 53. Migration Controls

Migration from primary storage (referred to as Level-0 or ML0 storage) to secondary storage (referred to as Level-1 or ML1 storage) moves datasets from primary to secondary storage when they exceed the aging criterion. Such datasets are commonly compressed to maximize secondary storage utilization. DFHSM also supports Small-Dataset-Packing (SDSP), which allows small datasets to become records within a single VSAM file which you establish.

Field entry is as follows:

1. Controls Active

Enter **YES** to enable extended processing; **NO** to disable extended processing.

OS/EM allows the specification of 22 different aging factors.

Use these values, along with MAXSIZE, OR/AND connective and INCLUDED datasets, to determine how long unreferenced datasets will be held before they are migrated.

2. Enable

Enter **Y** in the ENABLE area to activate hold processing for the specified number of days.

Note: You must use either the **S** or **G** line command for any updates to take place.

3. Maxsize

Enter **maximum dataset size** to hold in K bytes, **blank to suppress** MAXSIZE criteria.

Only datasets that are larger than this value will be migrated once they exceed the aging factor.

This value is in K bytes. Thus, a value of 1000 means that datasets less than or equal to 1,024,000 bytes will not be migrated even if they are older than the specified number of days.

If you do not wish to hold datasets based on their size, leave this value blank, or blank it if you have already entered a value.

4. OR/AND

Enter logical connection between MAXSIZE and INCLUDED DSN Groups; OR = MAXSIZE datasets or specified DSN Groups; AND = MAXSIZE datasets and specified DSN Groups; blank = suppress OR/AND criteria.

A logical connection between the MAXSIZE specification and INCLUDED DSN Groups is established by entering **OR** or **AND**.

If you enter **OR**, datasets will be held if they do not exceed the MAXSIZE value, OR if the dataset is in any of the dataset name groups that are in the INCLUDE list. The default is OR.

If you enter **AND**, datasets will be held if they do not exceed the MAXSIZE value, AND if the dataset is in any of the dataset name groups that are in the INCLUDE list.

5. INCLUDE/EXCLUDE

Enter **INC** to include Dataset Name Groups, **EXC** to exclude Dataset Name Groups.

Note: You may have either an INCLUDE list or an EXCLUDE list, but NOT both.

6. DSN Groups

If you wish to INCLUDE a list of datasets which will not be migrated, enter **Y** in this field.

Enter **N** to not have an INCLUDE list.

7. Add or Delete DSN Groups




Figure 54. Migration Hold Options with "POPUP" screen

The area in which the group names are entered is a scrollable area. Normal ISPF commands for scrolling are in effect.

Group names are up to eight characters in length. Create them by using the Define Dataset Name Groups function (see “Define Dataset Name Groups” on page 5-3). Each group represents a set of dataset name masks or fully qualified dataset names.

Note: The dataset group names that you enter must have been properly defined by using the Define Dataset Name Groups option before they can be accepted on this panel.

- To add a dataset name group, enter an **A** in the CMD field and the name of the dataset name group in the group field. Type a description of the group in the description field. Overtyping any existing entry - the old entry will not be altered.
- To delete an existing entry, enter a **D** in the CMD field.

Migration Level-2 Control (ML1-ML2)

Migration from secondary storage to the final level (referred to as Level-2 or ML2 storage, and most commonly tape) moves datasets when ML1 storage exceeds its defined threshold and room must be made to hold the datasets migrated to ML1 storage from ML0 storage (Primary).

Each of these functions presents a first panel such as illustrated by the Delete-by-Age Control panel (Figure 46 on page 5-28). The function (DBA, DBU, MIG, ML2) is ENABLED by specific HOLD day. Each specific HOLD day may be ENABLED--enter a **Y** on the ENABLE area of the HOLD day you desire (use Y to also change a HOLD day specification)--or DISABLED by entering a **N** in the ENABLE area of the HOLD day selection. You may change the description connected with a particular HOLD day at any time. You might consider using the description to briefly annotate the criteria being used for HOLD day. The illustration shows HOLD day 3 with such a description.

Note: Hold day 9999 represents a special case. A dataset placed in this HOLD day will never age. The effect is identical to specifying NOMIG for the dataset in your ARCCMDxx member.

Figure 47 on page 5-29 shows the panel presented when you enable a particular HOLD day. The title area of the panel will indicate the HOLD day you are currently specifying. If you find that you have chosen the wrong day, CANCEL the panel and you will be returned to the HOLD day selection list.

The action of a particular HOLD day may be qualified by a maximum dataset size to hold, and a list of datasets which should be included with the HOLD day. If you specify none of these options, ALL datasets, not otherwise qualified, will be aged for possible processing. This still extends DFHSM processing by giving you multiple aging factors. However, the best use of a HOLD day is to specify a maximum dataset size and specify a dataset name list.

The maximum dataset size you specify indicates that if a particular dataset is less than or equal to the maximum size, it will not be processed (the size is expressed in K).

Note: To be effective, this number should decrease as the number of days a dataset is held (not deleted or migrated) increases. That is, large datasets should be held for a few days; small datasets can be effectively held for a longer period of time. While there is no requirement that this policy be implemented, holding large datasets beyond when DFHSM processing would normally remove eligible datasets from a volume defeats the purpose of removing such datasets--maximizing available DASD space.

If a particular dataset resolves to the include list, it will not be processed. You can connect the two criteria with the AND/OR connective.

If you specify that a dataset name group INCLUDE list should be part of the HOLD day's processing, you will be presented with the standard DATASET NAME GROUPS panel already presented (Figure 31 on page 5-3).

The relationship between these various elements is best demonstrated with an example. Assume the following has been established for the indicated HOLD days:

DAY	Maxsize	Connective	Include
9999	50	AND	SYSXGRP P3RDINS
2	130	OR	TESTGRP
10			DEVTEMP
15	30	AND	TESTT

Assume, also, that the following dataset name groups have been previously defined:

GROUP	Datasets, dataset name masks
SYSXBRP	SYSX.+ All datasets that begin with SYSX.
P3RDINS	P3RD.INSTALL.+ All datasets that begin with P3RD.INSTALL
TESTGRP	TEST.+ All datasets that begin with TEST
DEVTMP	\$DEV%%%.TEMP.+ Datasets that begin with \$DEV
TESTT	TEST.T?????.- Datasets which begin with TEST.T plus any five characters and one other node name.
PRODW	PROD.WORKS%% sys%%%. - Datasets which begin with PROD as the first node


Although the above examples show only one dataset name mask in each group, dataset name groups may contain multiple fully qualified dataset names and/or multiple dataset name masks.

Determining whether a particular dataset should be processed is as follows:

- Datasets which do not exceed 50K AND match dataset names or masks contained within dataset name groups SYSXGRP or P3RDINS will never be migrated or deleted.
- Datasets which do not exceed 130K OR match dataset names or masks contained within dataset name group TESTGRP will not be migrated or deleted for two days. After this time, they will be eligible for migration or deletion.
- Datasets which match dataset names or masks contained within dataset name group DEVTMP will be retained for ten days. After this time, they will be eligible for migration or deletion.
- Datasets which do not exceed 30K AND match dataset names or masks contained within dataset name group TESTT will be held for fifteen days. After this time, they will become eligible for migration or deletion.

While limited, this example shows the definitions you need to effectively manage DFHSM. Remember, the goal is to ensure that active datasets are always available in a timely manner and to maximize your primary storage utilization.

ML2 usage note: Remember that datasets will not be held if Level-2 storage is not tape. The purpose for keeping datasets from migrating to tape Level-2 storage is to hasten their recall. If Level-2 storage is another DASD device, such a consideration does not apply. Issuing the FREEVOL AGE(0) command will also bypass ML2 hold processing. It is assumed that if you issue this command, the Level-1 volume is to be cleared.



Field entry is as follows:

1. Controls Active

Enter **YES** to enable extended processing; **NO** to disable extended processing.

This field must be completed before you will be allowed to leave the panel.

Enter a **S** in the CMD field to select the hold days for datasets to be held on Level-1 storage before being eligible for migration.

Enter a **Y** in the ENABLE area to activate hold processing for the specified number of days.

OS/EM allows the specification of 22 different aging factors.

Use these values, along with MAXSIZE, OR/AND connective and INCLUDED datasets, to determine how long unreferenced datasets will be held before they are migrated.

2. Maxsize

Enter **maximum dataset** size to hold in K bytes; blank to suppress MAXSIZE criteria.

Only datasets that are larger than this value will be deleted once they exceed the aging factor.

This value is in K bytes. Thus, a value of 1000 means that datasets less than or equal to 1,024,000 bytes will not be migrated even if they are older than the specified number of days.

Leave this value blank if you do not wish to hold datasets based on their size, or blank it out if you have already entered a value.

3. OR/AND

Enter logical connection between MAXSIZE and INCLUDED DSN Groups; OR = MAXSIZE datasets or specified DSN Groups; AND = MAXSIZE datasets and specified DSN Groups; blank = suppress OR/AND criteria.

A logical connection between the MAXSIZE specification and INCLUDED DSN Groups is established by entering **OR** or **AND**.

If you enter **OR**, datasets will be held if they do not exceed the MAXSIZE value, OR if the dataset is in any of the dataset name groups that are in the INCLUDE list. The default is OR.

If you enter **AND**, datasets will be held if they do not exceed the MAXSIZE value, AND if the dataset is in any of the dataset name groups that are in the INCLUDE list.

4. INCLUDE/EXCLUDE

Enter **INC** to include Dataset Name Groups, **EXC** to exclude Dataset Name Groups.

Note: You may have either an INCLUDE list or an EXCLUDE list, but NOT both.

5. DSN Groups

If you wish to INCLUDE a list of datasets which will not be deleted, enter **G** in the CMD field; a pop-up window will open to allow entry of the DSN Groups.

Use the "POPUP" panel to add or delete the DSN Groups.

The area in which the group names are entered is a scrollable area. Normal ISPF commands for scrolling are in effect.

Group names are up to eight characters in length. They are created by using the Define Dataset Name Groups function (see "Define Dataset Name Groups" on page 5-3). Each group represents a set of dataset name masks or fully qualified dataset names.

Note: The dataset group names that you enter must have been properly defined by using the Define Dataset Name Groups option before they can be accepted on this panel.

- To add a dataset name group, enter an **A** in the CMD field and the name of the dataset name group in the group field. Type a description of the group in the description field. Overtyping any existing entry - the old entry will not be altered.
- To delete an existing entry, enter a **D** in the CMD field.

Prioritize Recall/Recover Requests

This function allows you to prioritize DFHSM recall and recover requests based on where the request was generated: Batch or Online; where the data resides: DASD or Tape. You may limit the requests that are prioritized by time of day/day of week, job name/mask, dataset name/mask or user ID/mask. A request which does not meet any of these selection criteria will receive the specified default priority.

In order to use this extended function, you must activate DFHSM's ARCRPEXT exit processing in the appropriate ARCCMDxx parmlib member.

```
OS/EM ----- PRIORITIZE RECALL/RECOVER REQUESTS ----- Version 6.0
COMMAND ==>

          1 - Prioritize System Level Controls
          2 - Recall Requests Priority
          3 - Recover Requests Priority
```

Figure 56. Prioritize Recall/Recover Requests Menu

The primary menu for this function contains three options. Option 1: 'Prioritize System Level Controls' must always be filled out, as this is where the function is turned on or off. Options 2 and 3 are filled in as needed.

Each of these paths is presented in the following sections:

1. Prioritize System Level Controls (see “Prioritize System Level Controls” on page 5-47)
2. Recall Requests Priority (see “Recall Requests Priority” on page 5-48)
3. Recover Requests Priority (see “Recover Requests Priority” on page 5-51)

Prioritize System Level Controls

```
OS/EM ----- PRIORITIZE SYSTEM LEVEL CONTROL----- Version 6.0  
COMMAND ==>
```

```
Priority Controls Active:      YES      (Yes/No)  
Operator/HSM Generated Requests: 50      (1 to 100)
```

Figure 57. Priority System Level Controls

To turn priority controls on or off enter **YES** or **NO** in the 'Priority Controls Active' field.

To specify a priority setting for **operator** or HSM internally generated requests, enter the value in the second field.

Recall Requests Priority

```

OS/EM ----- HSM RECALL PRIORITY ----- Version 6.0
COMMAND ===>                                SCROLL ==> CSR

    Controls Active:  NO          (Yes/No)
    Default Priority:  ___        (1 to 100)

                                Job DS   User
                                (1234) Days Name Name ID
    Weight:  _   _   _   _

(S)elect Group, (D)elete Group
    Priority      Request from
Sel Number  Active  Batch / Online  | Data coming from
-----|-----
_   1       N      ___   ___   | ___   ___
_   2       N      ___   ___   | ___   ___
_   3       N      ___   ___   | ___   ___
_   4       N      ___   ___   | ___   ___
_   5       N      ___   ___   | ___   ___
_   6       N      ___   ___   | ___   ___
_   7       N      ___   ___   | ___   ___
_   8       N      ___   ___   | ___   ___
_   9       N      ___   ___   | ___   ___
_  10       N      ___   ___   | ___   ___
_  11       N      ___   ___   | ___   ___
_  12       N      ___   ___   | ___   ___

```

Figure 58. Recall Selection Lists

There are 22 selection lists or groups available. For each list you may specify time of day by day of week, job names/masks, dataset names/masks or user ids/masks. Each list has its own priority setting.

Field entry is as follows:

1. Controls Active

Enter **YES** to enable **RECALL** priority processing; **NO** to disable **RECALL** processing.

2. Default Priority

Enter a value from 1 to 100 to specify the priority that requests which do not match one of the 22 selection lists will receive.

3. Weight

For the four selection types, enter the weight which is to be given to each type.

Each active selection list is checked for a matching entry. The **weight** parameters are added to each matching entry and the list with the highest value will be used to determine the priority given to the request.

The scrollable portion of the panel contains the 22 selection lists. Four line commands are used to access the selection types.

Field entry is as follows:

1. Sel

Two line commands are available: **S** to update the selection entries or **D** to delete the selection entries.

No line command is needed to update any other field, simply overtype the field and press enter for the selection list to be updated.

2. Active

Enter a **Y** to activate this selection list, or a **N** to deactivate it. Deactivating the list allows the selection type entries to remain even though they are not used. This allows you to turn on the selection list at a later time without having to respecify the different type entries.

3. Request from Batch

Enter a value here from 1 to 99.

The **batch, online, DASD and tape** parameters control the actual priority value assigned to a request. OS/EM determines if the request is from a batch job or an online user, and whether the dataset to be recalled/recovered is currently stored on tape or DASD. It then calculates the priority to be assigned by adding the stated values together.

As an example, if the following values have been specified to OS/EM:

BATCH:	30	TAPE:	40
ONLINE:	40	DASD:	45

If a request is received from a batch job, and HSM has the dataset stored on DASD, the priority assigned to the request would be:

$$30 + 45 = 75\%$$

While a request from an online user for a dataset which is stored on tape would be:

$$40 + 40 = 80\%$$

4. Request from Online

Enter a value from 1 to 99.

5. Data coming from DASD

Enter a value from 1 to 99.

6. Data coming from Tape

Enter a value from 1 to 99.

The final four fields on this panel will display either **INC** or **EXC** depending if you have entered any selection type items.

The selection group panel is a scrollable list of all the selectors needed to determine the jobs/users which should have the appropriate priority.

```

OS/EM ----- SELECTOR ENTRY - 1 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enter Selector Types, either Include or Exclude
          Jobname ==> INCLUDE          DSName  ==> INCLUDE
          UserID  ==> INCLUDE

Line Cmds: (D)delete line, (I)nsert line

  Selector
    Type      Selector Names/Mask List
- DSNAME      TRP.+ SAP.+ USP.+
- JOBNAME     TRPD- SAPD- USPD-
- USERID      CA7
- TUESDAY     0800:1600
- FRIDAY      0500:0900
***** Bottom of data *****

```

Figure 59. Selection Group Entry Panel

The selector types for this function are:

MONDAY - SUNDAY Days of the week are used to allow entry of time values. In the above example the selection group is only applicable on Tuesday between 8AM and 4PM or Friday between 5AM and 9AM. Only one time range per day is permitted. Be sure to enter the time in 24 hour format separating the beginning and ending times with a colon (:).

JOBNAME Enter complete jobnames or jobname masks. You may enter as many names or masks as will fit on the line (separated by spaces). If more names/masks are needed, insert another line and use the same selector type (JOBNAME).

DSNAME Enter full dataset names or dataset name masks. You may enter as many names or masks as will fit on the line (separated by spaces). If more names/masks are needed, insert another line and use the same selector type (DSNAME).

USERID Enter user IDs or user ID masks separated by spaces. You may enter as many IDs/masks as will fit on the line. If more IDs/masks are needed simply insert another blank line and use the same selector type (USERID).

Recover Requests Priority

```

OS/EM ----- HSM RECALL PRIORITY ----- Version 6.0
COMMAND ===>                                SCROLL ==> CSR

    Controls Active:  NO          (Yes/No)
    Default Priority:  ___        (1 to 100)

                                Job DS   User
                                (1234) Days Name Name ID
    Weight:  _   _   _   _

(S)elect Group, (D)elete Group
    Priority      Request from
Sel Number  Active  Batch / Online  | Data coming from
-----|-----
_   1         N     ___   ___   | ___   ___
_   2         N     ___   ___   | ___   ___
_   3         N     ___   ___   | ___   ___
_   4         N     ___   ___   | ___   ___
_   5         N     ___   ___   | ___   ___
_   6         N     ___   ___   | ___   ___
_   7         N     ___   ___   | ___   ___
_   8         N     ___   ___   | ___   ___
_   9         N     ___   ___   | ___   ___
_  10         N     ___   ___   | ___   ___
_  11         N     ___   ___   | ___   ___
_  12         N     ___   ___   | ___   ___

```

Figure 60. Recover Selection Lists

There are 22 selection lists or groups available. For each list you may specify time of day by day of week, job names/masks, dataset names/masks or user ids/masks. Each list has its own priority setting.

Field entry is as follows:

1. Controls Active

Enter **YES** to enable **RECOVER** priority processing; **NO** to disable RECOVER processing.

2. Default Priority

Enter a value from 1 to 100 to specify the priority that requests which do not match one of the 22 selection lists will receive.

3. Weight

For the four selection types, enter the weight which is to be given to each type.

Each active selection list is checked for a matching entry. The **weight** parameters are added to each matching entry and the list with the highest value will be used to determine the priority given to the request.

The scrollable portion of the panel contains the 22 selection lists. Four line commands are used to access the selection types.

Field entry is as follows:

1. Sel

Two line commands are available: **S** to update the selection entries or **D** to delete the selection entries.

No line command is needed to update any other field, simply overtype the field and press enter for the selection list to be updated.

2. Active

Enter a **Y** to activate this selection list, or a **N** to deactivate it. Deactivating the list allows the selection type entries to remain even though they are not used. This allows you to turn on the selection list at a later time without having to respecify the different type entries.

3. Request from Batch

Enter a value here from 1 to 99.

The **batch, online, DASD and tape** parameters control the actual priority value assigned to a request. OS/EM determines if the request is from a batch job or an online user, and whether the dataset to be recalled/recovered is currently stored on tape or DASD. It then calculates the priority to be assigned by adding the stated values together.

As an example, if the following values have been specified to OS/EM:

BATCH:	30	TAPE:	40
ONLINE:	40	DASD:	45

If a request is received from a batch job, and HSM has the dataset stored on DASD, the priority assigned to the request would be:

$$30 + 45 = 75\%$$

While a request from an online user for a dataset which is stored on tape would be:

$$40 + 40 = 80\%$$

4. Request from Online

Enter a value from 1 to 99.

5. Data coming from DASD

Enter a value from 1 to 99.

6. Data coming from Tape

Enter a value from 1 to 99.

The final four fields on this panel will display either **INC** or **EXC** depending if you have entered any selection type items.

The selection group panel is a scrollable list of all the selectors needed to determine the jobs/users which should have the appropriate priority.

```

OS/EM ----- SELECTOR ENTRY - 1 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enter Selector Types, either Include or Exclude
          Jobname ==> INCLUDE          DSName  ==> INCLUDE
          UserID  ==> INCLUDE

Line Cmds: (D)delete line, (I)nsert line

  Selector
    Type      Selector Names/Mask List
- DSNAME      TRP.+ SAP.+ USP.+
- JOBNAME     TRPD- SAPD- USPD-
- USERID     CA7
- TUESDAY     0800:1600
- FRIDAY     0500:0900
***** Bottom of data *****

```

Figure 61. Selection Group Entry Panel

The selector types for this function are:

MONDAY - SUNDAY Days of the week are used to allow entry of time values. In the above example the selection group is only applicable on Tuesday between 8AM and 4PM or Friday between 5AM and 9AM. Only one time range per day is permitted. Be sure to enter the time in 24 hour format separating the beginning and ending times with a colon (:).

JOBNAME Enter complete jobnames or jobname masks. You may enter as many names or masks as will fit on the line (separated by spaces). If more names/masks are needed, insert another line and use the same selector type (JOBNAME).

DSNAME Enter full dataset names or dataset name masks. You may enter as many names or masks as will fit on the line (separated by spaces). If more names/masks are needed, insert another line and use the same selector type (DSNAME).

USERID Enter user IDs or user ID masks separated by spaces. You may enter as many IDs/masks as will fit on the line. If more IDs/masks are needed simply insert another blank line and use the same selector type (USERID).

Quick Delete Control

The Quick Delete function allows OS/EM to delete files which are migrated by issuing an **HDEL** command instead of first recalling the files.

The requirements for this option are that the program name is IEFBR14 and the retention status of any files coded is **DELETE**.

```
OS/EM ----- QUICK DELETE CONTROL ----- Version 6.0
COMMAND ==>

Quick Delete Active ==> YES      (Yes/No)
```

Figure 62. Entry panel for Quick Delete Control

Enter **YES** to enable the Quick Delete function or enter **NO** to disable it.

Reblocking Control

While everyone acknowledges that files should be blocked for the optimum DASD efficiency, the task is rarely done. Sequential files can be automatically reblocked whenever they are recalled or recovered to DASD by DFHSM. The HSM Optimizer supports FULL through EIGHTH track reblocking, plus SYSTEM reblocking if your installation has level 3.+ of DFP installed.

As usual, the first field on the reblock panel (Figure 63) allows you to ENABLE or DISABLE this function. Select the reblocking factor of choice by entering an **S** in the CMD field and typing **YES** in the ENABLED field. Figure 63.

Reblocking is advantageous when migrating to new, higher capacity DASD devices; and to ensure that DASD utilization is optimal.

Note: If either your programs or JCL contain explicit block sizes, this function will cause job failure since the internal description of the file and your external description of it will not match. You should specify block sizes in the JCL, ONLY when first creating the file.

Reblock Control requires that the following DFHSM SETSYS option be present in DFHSM ARCCMDxx member.

```
SETSYS CONVERSION(REBLOCKTOANY)
```

Note: Refer to the DFHSM Systems Programmer's Guide for further information and discussion.

```
OS/EM ----- REBLOCK CONTROL ----- Version 6.0
COMMAND ==>                                     Scroll ==> CSR

  Enable Reblock Control ==> YES (Enter YES to enable; NO to disable)

(CMD = (S)elect for update; (G)roup display)

  CMD      REBLOCKING      ENABLED      MINIMUM      EXCLUDED DSN
          FACTOR          ENABLED      SIZE         GROUPS
  "        SYSTEM
  "        FULL           YES
  "        HALF           YES           1           2
  "        THIRD
  "        FOURTH
  "        FIFTH
  "        SIXTH
  "        SEVENTH
  "        EIGHTH
***** Bottom of data *****
```

Figure 63. Reblock Control Menu

Field entry is as follows:

1. Enable Reblocking Control

Each reblocking factor may be Enabled or Disabled. Each reblocking factor may specify a minimum dataset size which a dataset must equal or exceed before it is eligible for reblocking. Finally, you may create an EXCLUDE list of dataset name groups. Datasets resolved to this list will not be reblocked.

Entering **YES** in this field will enable the OS/EM's extended processing.

Entering **NO** will disable this function.

2. Select Reblocking Factor

SYSTEM

System reblocking is available only on systems that have DFP 3.0 or higher.

FULL

Full track blocking depends on the target device. For those devices with a track size larger than 32760, such as the 3380, the resulting blocksize used will actually be HALF-track blocking. For devices with a track size smaller than 32760, the actual track size will be used.

The actual block size used is determined by the device track size, whether the file contains fixed or variable length records, and DFHSM. The block size will not be adjusted by DFHSM if the file contains variable length records. The block size will become the maximum blocksize for the file.

If the file contains fixed length records, DFHSM will adjust the block size downward until an even number of logical records will fit.

3. Enable

Entering **YES** in this field will enable OS/EM's extended processing.

Entering **NO** will disable this function.

4. Minimum Dataset Size

If you wish to prevent small datasets from being reblocked, enter a **minimum dataset size** (in K bytes) to be reblocked. Blank this field to allow datasets of any size to be reblocked.

5. Excluded DSN Groups

If you wish to exclude particular datasets from being reblocked by DFHSM, enter **G** in the CMD field. You will be presented with a pop-up window where you may enter the Dataset Name Groups which will be exempt from reblocking.

6. Add or Delete DSN Groups

```
OS/EM ----- REBLOCK CONTROL ----- Row 1 to 9 of 9

----- DSN GROUPS FOR FACTOR HALF -----  (sable)
                                         Row 36 from 37
Enter Dataset Name Groups to be used:
(CMD = (A)dd group (D)elete group)
CMD Group   Description
_ ZCD1      Z Control Datasets group 1_____
_ ZCD2      Z Control Datasets group 2_____
***** Bottom of data *****

*  CMD =>                                     *****
```

Figure 64. Reblock Control - Add or Delete

Use the "POPUP" panel to add or delete the DSN Groups.

The area in which the group names are entered is a scrollable area. Normal ISPF commands for scrolling are in effect.

Group names are up to eight characters in length. They are created by using the Define Dataset Name Groups function (see “Define Dataset Name Groups” on page 5-3). Each group represents a set of dataset name masks or fully qualified dataset names.

Note: The dataset group names that you enter must have been properly defined by using the Define Dataset Name Groups option before they can be accepted on this panel.

- To add a dataset name group, enter an **A** in the CMD field and the name of the dataset name group in the group field. Overtyping any existing entry - the old entry will not be altered.
- To delete an existing entry, enter a **D** in the CMD field.

Recall/Recover Volume Selection

This option determines whether DFHSM RECALL/RECOVER will proceed according to the DASD allocation rules established with OS/EM's QuickPool option.

If the QuickPool option is in effect, you must enable this option. DFHSM RECALL/RECOVERY might fail if this option is not in effect; especially if you change the allocation rules after DFHSM has migrated or backed up the dataset.

Directed Recall requires that the following DFHSM SETSYS option be present in DFHSM ARCCMDxx member.

```
SETSYS RECALL(PRIVATE(UNLIKE))
```

Note: If the dataset is a DFSMS dataset this option will not be invoked. If QUICKPOOL allocation is in effect, you must specify DIRECTRECALL. DFHSM RECALL/RECOVERY will most likely fail if this option is not enabled.

```
OS/EM ----- RECALL/RECOVER VOLUME SELECTION CONTROL ----- Version 6.0
COMMAND ==>

Specify if RECALL/RECOVERY will proceed according to the QuickPool
allocation rules:

====> YES      (Enter YES to use rules; NO to not use rules)

* Specifying NO for this option when QuickPool allocation rules are
  enabled may result in failed RECALL/RECOVERY.
```

Figure 65. Recall/Recover Selection Control

Field entry is as follows:

1. Enable Recall/Recover Control

Entering **YES** in this field will enable the OS/EM's extended processing.

Entering **NO** will disable this function.

HSM Optimizer Report System

Description

HSM Report System provides reports detailing the performance of the DFHSM component in both a Non-SMS and DFSMS environment utilizing the DFHSM SMF Function Statistic Records (FSR), Volume Statistic Records (VSR), and the Daily Statistic Records (DSR). A database of the DFHSM SMF records is maintained to provide both daily and historical reporting.

Summary of Features

- Dynamic Date Selection for Report Selection
- Summary DFHSM Error Report by Function, Return and Reason code
- Detail DFHSM Error Report by Function, Return and Reason code
- Dataset Activity Report details excessive Migration and Recall for datasets
- Primary Volume Summary Report
 - Available space
 - Space releasable
 - Last Backup date/time
 - Last Migration date/time
 - Last Dump date/time
 - Summary of volume utilization by DSORG
 - Type of Volume DFSMS or DFHSM
- Primary Volume Detail Report
 - Dataset Name
 - DSORG
 - Type of allocation (CYL, TRK, Megabytes, Kilobytes)
 - Space allocated
 - Space used
 - Space releasable
 - Number of extents
 - DFSMS managed
- Activity Summary Report utilizing the DSR records for the Reporting Period
 - Number of datasets migrated to ML1 and ML2
 - Number and percent datasets that failed migration to ML1 and ML2
 - Number of datasets recalled from ML1 and ML2
 - Number and percent datasets that failed recall from ML1 and ML2
 - Number of datasets backed up
 - Number and percent of datasets that failed backup
- Volume Summary Report utilizing the VSR records for the Reporting Period
 - Volume Utilization including minimum, maximum, and average
 - Number of datasets migrated
 - Number of datasets recalled
 - Number of datasets backed up
 - Number of datasets recovered
 - Date/time of last volume dump
- Detail Dataset movement reports

- Primary to ML1
- ML1 to ML2
- Primary to ML2
- ML1 to Primary
- ML2 to Primary

- Summaries of Dataset movement by Size and Age of dataset
 - Primary to ML1
 - ML1 to ML2
 - Primary to ML2
 - ML1 to Primary
 - ML2 to Primary

- Summary Reports on Migration Control Dataset (MCDS) by Age
- Summary Reports on Migration Control Dataset (BCDS) by Age
- Detail Reports on Migration Control Dataset (MCDS) by Age
- Detail Reports on Migration Control Dataset (BCDS) by Age

- Extensive ISPF interface

HSM Optimizer Report XREF

Report Number	Report Name
REPORT-01	MIGRATION DETAIL (PRIMARY - ML1)
REPORT-02	MIGRATION DELAY SUMMARY (PRIMARY - ML1)
REPORT-03	MIGRATION AGE SUMMARY (PRIMARY - ML1)
REPORT-04	MIGRATION DETAIL (ML1 - ML2)
REPORT-05	MIGRATION DELAY SUMMARY (ML1 - ML2)
REPORT-06	MIGRATION AGE SUMMARY (ML1 - ML2)
REPORT-07	MIGRATION DETAIL (PRIMARY - ML2)
REPORT-08	MIGRATION DELAY SUMMARY (PRIMARY - ML2)
REPORT-09	MIGRATION AGE SUMMARY (PRIMARY - ML2)
REPORT-10	RECALL DETAIL (ML1 - PRIMARY)
REPORT-11	RECALL DELAY SUMMARY (ML1 - PRIMARY)
REPORT-12	RECALL AGE SUMMARY (ML1 - PRIMARY)
REPORT-13	RECALL DETAIL (ML2 - PRIMARY)
REPORT-14	RECALL DELAY SUMMARY (ML2 - PRIMARY)
REPORT-15	RECALL AGE SUMMARY (ML2 - PRIMARY)
REPORT-16	DFHSM DASD VOLUME SUMMARY
REPORT-17	PRIMARY DATASET ACTIVITY REPORT
REPORT-18	DFHSM ERROR DETAIL REPORT
REPORT-19	DFHSM ERROR SUMMARY REPORT
REPORT-20	ACTIVITY SUMMARY
REPORT-21	MIGRATED DATASET SUMMARY
REPORT-22	DATASET BACKUP SUMMARY
REPORT-23	PRIMARY VOLUMES
REPORT-24	PRIMARY VOLUME DETAIL
REPORT-25	PRIMARY VOLUME DATE REFERENCE DETAIL
REPORT-26	MIGRATED DATASET DETAIL (MCDS Sorted by DSN)
REPORT-27	BACKED UP DATASET DETAIL (BCDS Sorted by DSN With XREF)
REPORT-28	MIGRATED DATASET DETAIL (MCDS Sorted by Date)
REPORT-29	BACKED UP DATASET DETAIL (BCDS Sorted by Date with XREF)
REPORT-30	BACKED UP DATASET DETAIL (BCDS Sorted by DSN No XREF)
REPORT-31	BACKED UP DATASET DETAIL (BCDS Sorted by Date No XREF)

DFHSM Report Descriptions

Report-01 MIGRATION DETAIL (Primary - ML1)

This report presents a list of all datasets migrated from primary storage to ML1 storage for the requested reporting period.

If you find very large datasets going to ML1, especially if they have low compression ratios, you might want to consider moving these datasets directly to ML2 storage (assuming this is tape in your installation). Such datasets impact ML1 utilization and might result in a ML1 to ML2 migration which will impact recall times for all datasets migrated.

HSM OPTIMIZER 5.6		MIGRATION DETAIL (PRIMARY - ML1)					REPORT TIME: 12:14		DATE: 2/13/02		PAGE 3	
REPORT: 01 FORMAT: 01		02/10/02 - 02/12/02										
DATASET NAME	FROM VOLUME	TO VOLUME	USER ID	DATE	TIME	LAST ACCESS DATE	DATA					
							AGE	READ BYTES	WRITE BYTES	CMP PCT	MGEMENT CLASS	
OSEM560.COMPAT56.BIN	SMS528	HSM000	**HSM***	02/10/02	5:09:53	02/04/02	6	642K	644K	0	SMP	
GSA3.OP.RMMBK.BKP.RMMDB.G2452V00	SMS502	HSM000	**HSM***	02/10/02	16:06:33	02/10/02	0	18.1M	18.1M	0	STD10YR	
GSA4.AW.B8050.FIL.AW0BEEM	SMS506	HSM000	**HSM***	02/10/02	16:07:06	02/10/02	0	1.93M	1.93M	0	STD10YR	
GSA4.LG.B8050.FIL.LG0BMBR	SMS506	HSM000	**HSM***	02/10/02	16:07:10	02/10/02	0	1.66M	1.66M	0	STD10YR	
GSA4.SE.B8050.FIL.SE0BMBR	SMS502	HSM000	**HSM***	02/10/02	16:11:02	02/10/02	0	13.5M	13.5M	0	STD10YR	
GSA3.OP.RMMBK.BKP.RMMDB.G2453V00	SMS507	HSM000	**HSM***	02/11/02	2:08:13	02/11/02	0	18.1M	18.1M	0	STD10YR	
GSA2.PD.D2001.FIL.FLAT	SMS505	HSM000	SPJRM	02/11/02	11:09:25	02/11/02	0	574K	94.0K	84	STD10YR	
GSA7.LB.V0900.FIL.TESTFILE	SMS508	HSM000	**HSM***	02/11/02	16:07:47	02/11/02	0	3.96M	3.96M	0	STD10YR	
GSA2.SE.D2001.FIL.DOWNIRS	SMS508	HSM000	**HSM***	02/11/02	16:08:06	02/11/02	0	767K	124K	84	STD10YR	
GSA4.AI.B0902.FIL.LASTWRK	SMS506	HSM000	**HSM***	02/12/02	17:06:04	02/12/02	0	1.34M	1.34M	0	STD10YR	
GSA3.OP.SMPDM.BKP.SMP.G0003V00	SMS507	HSM000	**HSM***	02/12/02	21:01:50	02/12/02	0	16.2M	16.2M	0	STD10YR	
GSA7.IW.K0210.BKP.IWEEMST.G0069V00	SMS507	HSM000	**HSM***	02/12/02	21:01:56	02/12/02	0	16.2M	16.2M	0	STD10YR	
GSA7.LM.K0170.BKP.LMEEMST	SMS507	HSM000	**HSM***	02/12/02	21:02:00	02/12/02	0	11.8M	11.8M	0	STD10YR	
GSA7.FN.K0170.BKP.FNEEMST	SMS518	HSM000	**HSM***	02/12/02	21:02:43	02/12/02	0	5.08M	5.08M	0	STD10YR	
GSA7.LB.V0900.FIL.PRINTFIL	SMS518	HSM000	**HSM***	02/12/02	21:02:46	02/12/02	0	4.87M	4.87M	0	STD10YR	
GSA4.AI.B0941.FIL.ENRLBEN	SMS518	HSM000	**HSM***	02/12/02	21:02:50	02/12/02	0	3.74M	3.75M	0	STD10YR	
GSA2.ZZ.C1002.FIL.LTRTRANS.G3376V00	SMS518	HSM000	**HSM***	02/12/02	21:02:54	02/12/02	0	2.53M	952K	63	STD10YR	
GSA2.ZZ.C0000.BKP.QLMPSTG.G2657V00	SMS507	HSM000	**HSM***	02/12/02	21:03:51	02/12/02	0	3.76M	3.05M	19	STD10YR	
GSA4.OL.B0940.FIL.MBRINFO	SMS507	HSM000	**HSM***	02/12/02	21:04:02	02/12/02	0	5.78M	5.78M	0	STD10YR	

Figure 66. REPORT-01 MIGRATION DETAIL (Primary - ML1)

The report contains the following data:

- Dataset Name
- The primary DASD volume the dataset was migrated from
- The DFHSM ML1 DASD volume the dataset was migrated to
- The userid requesting the migration. This will usually be ****HSM****, indicating that the dataset was migrated because it met your current automatic migration criteria. If some other ID is listed, it is the ID of the user who specifically requested the dataset to be migrated.
- The date the migration request was completed.
- The time the migration request was completed.
- The date the dataset was last referenced. Remember, this date is not necessarily the date the dataset was last updated.
- The dataset age in days. It is the difference between the migration completed date and the last referenced date.
- The number of bytes read.
- The number of bytes written by DFHSM.
- The compression percentage achieved by DFHSM, assuming that you've activated DFHSM data compression. Files smaller than 2K will always result in DFHSM writing a 2K file. If you are not already using DFHSM's Small Dataset Packing feature, you should seriously consider doing so if you have many such small files.

DFSMS Management Class

Report-02 MIGRATION DELAY SUMMARY (Primary - ML1)

This report presents a summary, by dataset size, of delays in migrating datasets. Delays usually occur when all defined DFHSM migration tasks are currently busy. Unless the average delay seems overly long, do not be too concerned with the values reported. If the average delays do seem overly long, you might want to consider allowing more concurrent DFHSM migration tasks.

HSM OPTIMIZER 5.6		MIGRATION DELAY SUMMARY (PRIMARY - ML1)						REPORT TIME: 8:36		DATE: 3/18/02	PAGE 2
REPORT: 02 FORMAT: 02		02/01/02 - 03/31/02									
DATASET SIZE	NUMBER OF REQUESTS	PERCENT OF TOTAL REQUESTS	TOTAL WAIT TIME	PERCENT OF TOTAL WAIT TIME	AVERAGE WAIT TIME	TOTAL BYTES READ	TOTAL BYTES WRITTEN	AVERAGE PERCENT COMPRESSION	TOTAL CPU TIME		
25.0K	45	4	0:03:52	2	0:00:05	49.9K	92.0K	0	0:00:21.89		
50.0K	31	2	0:02:16	1	0:00:04	1.25M	132K	90	0:00:14.83		
75.0K	14	1	0:01:22	1	0:00:06	840K	524K	38	0:00:07.04		
100K	16	1	0:01:20	1	0:00:05	1.39M	414K	71	0:00:07.97		
250K	52	4	0:04:22	3	0:00:05	8.16M	2.56M	69	0:00:26.50		
500K	43	3	0:03:51	2	0:00:05	15.3M	2.81M	82	0:00:24.27		
750K	43	3	0:09:09	6	0:00:13	25.9M	9.17M	65	0:00:26.88		
1024K	52	4	0:05:07	3	0:00:06	46.0M	17.3M	62	0:00:34.60		
1.50M	116	9	0:11:17	7	0:00:06	140M	97.0M	31	0:01:17.24		
2.00M	83	6	0:08:13	5	0:00:06	147M	98.8M	33	0:00:56.27		
3.00M	91	7	0:09:29	6	0:00:06	226M	175M	23	0:01:00.55		
4.00M	76	6	0:07:51	5	0:00:06	270M	195M	28	0:00:51.28		
5.00M	70	5	0:07:40	5	0:00:07	311M	229M	26	0:00:46.82		
7.50M	115	9	0:12:22	8	0:00:06	685M	616M	10	0:01:15.52		
10.0M	99	8	0:13:58	9	0:00:08	885M	794M	10	0:01:05.33		
20.0M	285	22	0:40:50	26	0:00:09	4.25G	4.08G	4	0:03:10.89		
30.0M	42	3	0:08:10	5	0:00:12	917M	862M	6	0:00:30.05		
40.0M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00		
50.0M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00		
75.0M	1	0	0:00:26	0	0:00:26	74.1M	74.1M	0	0:00:00.66		
100M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00		
OVER	4	0	0:05:48	4	0:01:27	1.45G	1.45G	0	0:00:03.52		
TOTAL	1,278		2:37:23			9.37G	8.63G		0:13:42.11		

Figure 67. REPORT-02 MIGRATION DELAY SUMMARY (Primary - ML1)

The migration delay summary report contains the following data:

- Dataset size.
- The number of migration requests for the dataset size.
- The percentage of the total migration requests this dataset size represents.
- The total wait time for these datasets.
- The percent of the total wait time datasets of this size represent.
- The average wait time for each individual request of this dataset size.
- The total bytes read.
- The total bytes written to ML1 storage.
- The average compression achieved.
- The total CPU time used for datasets of this size.

Report-03 MIGRATION AGE SUMMARY (Primary - ML1)

This report presents a summary, by dataset age, of all datasets migrated during the reporting period.

This report will help you pinpoint problems with your current aging strategy, if any. For example, a report may show 45 requests for datasets that have not been referenced within 50 days. It may also show 2,487 requests for a dataset age of 2. If the total bytes read for the age 50 datasets is fairly large, when compared to the total bytes read for the age 2 datasets, you may be holding such datasets on primary storage for too long a period.

HSM OPTIMIZER 5.6		MIGRATION AGE SUMMARY (PRIMARY - ML1)				REPORT TIME: 8:36		DATE: 3/18/02	PAGE 3
REPORT: 03 FORMAT: 03		02/01/02 - 03/31/02							
DATASET AGE	NUMBER OF REQUESTS	PERCENT OF REQUESTS	CUMULATIVE REQUESTS	CUMULATIVE PERCENT	TOTAL BYTES READ	TOTAL BYTES WRITTEN	TOTAL CPU TIME		
1	1,251	98	1,251	98	9.33G	8.61G	0:13:24.36		
2	0	0	1,251	98	0.00K	0.00K	0:00:00.00		
3	8	1	1,259	99	944K	144K	0:00:03.95		
4	1	0	1,260	99	5.83M	5.83M	0:00:00.68		
5	0	0	1,260	99	0.00K	0.00K	0:00:00.00		
6	5	0	1,265	99	2.57M	2.58M	0:00:02.06		
7	0	0	1,265	99	0.00K	0.00K	0:00:00.00		
8	1	0	1,266	99	110K	112K	0:00:00.45		
9	0	0	1,266	99	0.00K	0.00K	0:00:00.00		
10	6	0	1,272	100	17.0M	7.11M	0:00:06.35		
15	3	0	1,275	100	4.26M	620K	0:00:02.09		
20	1	0	1,276	100	97.2K	74.0K	0:00:00.48		
25	0	0	1,276	100	0.00K	0.00K	0:00:00.00		
30	2	0	1,278	100	8.47M	446K	0:00:01.69		
40	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
50	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
60	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
70	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
80	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
90	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
100	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
125	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
150	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
175	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
200	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
250	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
300	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
350	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
400	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
450	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
500	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
600	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
700	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
800	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
900	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
1000	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
1250	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
1500	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
1750	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
2000	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
OVER	0	0	1,278	100	0.00K	0.00K	0:00:00.00		
TOTAL	1,278		1,278		9.37G	8.63G	0:13:42.11		

Figure 68. REPORT-03 MIGRATION AGE SUMMARY (Primary - ML1)

The Migration Age Summary Report contains the following data:

- The dataset age in days.
- The number of migration requests for the dataset age.
- The percentage of the total requests this age represents.
- Cumulative requests.
- A cumulative percentage.
- Total bytes read.
- Total bytes written.
- Total CPU time used for these requests.

Report-04 MIGRATION DETAIL (ML1 - ML2)

This report presents a listing of all datasets migrated from DFHSM ML1 storage to ML2 storage (this is usually tape in most installations).

HSM OPTIMIZER 5.6		MIGRATION DETAIL (ML1 - ML2)						REPORT TIME: 13:00		PAGE 4	
REPORT: 04 FORMAT: 01		01/16/02 - 02/13/02						DATE: 2/14/02			
DATASET NAME	FROM VOLUME	TO VOLUME	USER ID	DATE COMPLETE	TIME COMPLETE	LAST ACCESS DATE	SET	READ	WRITE	CMP	MGEMENT
							AGE	BYTES	BYTES	PCT	CLASS
GSA5.LB.P0301.FIL.LB1PSSN	HSM000	031230	**HSM**	01/30/02	4:55:40	01/29/02	1	4.01M	4.01M	0	STD10YR
GSA5.LB.P0301.FIL.PPSORT	HSM000	031230	**HSM**	01/30/02	4:55:49	01/29/02	1	10.8M	10.8M	0	STD10YR
GSA5.LB.P0302.BKP.FICHE.G0004V00	HSM000	031230	**HSM**	01/30/02	4:55:51	01/07/02	23	1.02M	1.02M	0	STD10YR
GSA5.LB.P0302.BKP.FICHE.G0005V00	HSM000	031230	**HSM**	01/30/02	4:55:53	01/29/02	1	1.02M	1.02M	0	STD10YR
GSA5.LB.P0360.FIL.CKAFP	HSM000	031230	**HSM**	01/30/02	4:56:02	01/29/02	1	10.8M	10.8M	0	STD10YR
GSA5.LC.P0101.BKP.LC1PPEN.G0031V00	HSM000	031230	**HSM**	01/30/02	4:56:05	01/14/02	16	1.93M	1.93M	0	STD10YR
GSA5.LC.P5030.BKP.LC1PPTR.G0796V00	HSM000	031230	**HSM**	01/30/02	4:56:34	01/29/02	1	14.7M	14.7M	0	STD10YR
GSA5.OI.A5150.FIL.OI1ADET	HSM000	031230	**HSM**	01/30/02	4:56:37	01/07/02	23	1.61M	1.61M	0	STD10YR
GSA5.OI.P0201.BKP.OI1PPEN	HSM000	031230	**HSM**	01/30/02	4:56:39	01/22/02	8	1.29M	1.29M	0	STD10YR
GSA5.OI.P5000.BKP.OI1PPTR.G0034V00	HSM000	031230	**HSM**	01/30/02	4:56:51	01/24/02	6	13.7M	13.7M	0	STD10YR
GSA5.OI.P5030.BKP.OI1PPTR.G0972V00	HSM000	031232	**HSM**	01/30/02	4:59:35	01/29/02	1	13.7M	13.7M	0	STD10YR
GSA5.OT.P0301.FIL.OT1PSSN	HSM000	031232	**HSM**	01/30/02	4:59:39	01/23/02	7	4.82M	4.82M	0	STD10YR
GSA5.OT.P0375.FIL.VHAFP	HSM000	031232	**HSM**	01/30/02	4:59:51	01/23/02	7	11.9M	11.9M	0	STD10YR
GSA5.OT.P5092.FIL.FED1099.G0002V00	HSM000	031232	**HSM**	01/30/02	4:59:54	01/28/02	2	1.80M	1.80M	0	STD10YR
GSA5.OU.P2260.BKP.OU1PPTR	HSM000	031232	**HSM**	01/30/02	4:59:58	01/11/02	19	3.69M	3.69M	0	STD10YR
GSA5.PH.P0360.FIL.CKAFP	HSM000	031232	**HSM**	01/30/02	5:00:04	01/23/02	7	4.39M	4.39M	0	STD10YR
GSA5.SW.P5030.BKP.SW1PPTR.G0689V00	HSM000	031233	**HSM**	01/30/02	5:06:39	01/29/02	1	13.1M	13.1M	0	STD10YR
GSA5.SY.P2260.BKP.SY1PPTR	HSM000	031233	**HSM**	01/30/02	5:06:45	01/22/02	8	5.08M	5.08M	0	STD10YR
GSA5.SY.P2260.BKP.SY1P0201	HSM000	031233	**HSM**	01/30/02	5:06:50	01/28/02	2	5.03M	5.03M	0	STD10YR
GSA5.UA.P5030.BKP.UA1PPTR.G0838V00	HSM000	031233	**HSM**	01/30/02	5:07:03	01/25/02	5	14.7M	14.7M	0	STD10YR
GSA5.UA.P5030.BKP.UA1PPTR.G0841V00	HSM000	031233	**HSM**	01/30/02	5:07:14	01/29/02	1	14.7M	14.7M	0	STD10YR
GSA5.WS.P0304.FIL.WSALPHA	HSM000	031233	**HSM**	01/30/02	5:07:29	01/24/02	6	1.66M	1.66M	0	STD10YR
GSA5.WS.P2260.FIL.SORTED	HSM000	031233	**HSM**	01/30/02	5:07:44	01/11/02	19	18.7M	18.7M	0	STD10YR
GSA5.WS.P5030.BKP.WS1PPTR.G0934V00	HSM000	031233	**HSM**	01/30/02	5:07:58	01/22/02	8	19.0M	19.0M	0	STD10YR
GSA5.WS.P5092.FIL.FED1099.G0003V00	HSM000	031233	**HSM**	01/30/02	5:08:14	01/23/02	7	184K	184K	0	STD10YR

Figure 69. REPORT-04 MIGRATION DETAIL (ML1 - ML2)

The report contains the following data:

- Dataset Name
- The primary DASD volume the dataset was migrated from
- The DFHSM ML1 DASD volume the dataset was migrated to
- The userid requesting the migration. This will usually be ****HSM****, indicating that the dataset was migrated because it met your current automatic migration criteria. If some other ID is listed, it is the ID of the user who specifically requested the dataset to be migrated.
- The date the migration request was completed.
- The time the migration request was completed.
- The date the dataset was last referenced. Remember, this date is not necessarily the date the dataset was last updated.
- The dataset age in days. It is the difference between the migration completed date and the last referenced date.
- The number of bytes read.
- The number of bytes written by DFHSM.
- The compression percentage achieved by DFHSM, assuming that you've activated DFHSM data compression. Files smaller than 2K will always result in DFHSM writing a 2K file. If you are not already using DFHSM's Small Dataset Packing feature, you should seriously consider doing so if you have many such small files.
- DFSMS Management Class for this dataset.

Report-05 MIGRATION DELAY SUMMARY (ML1 - ML2)

This report presents a summary, by dataset size, of all datasets migrated from DFHSM ML1 storage to ML2 storage and the wait time associated with the migration requests.

If most of your migration activity seems to be concentrated in datasets of small to medium size, you might want to investigate the Migration Detail report, paying particular attention to datasets of small size. Migrating small datasets really doesn't buy that much especially if they must be recalled in a short period of time.

HSM OPTIMIZER 5.6		MIGRATION DELAY SUMMARY (ML1 - ML2)							PAGE 4	
REPORT: 05 FORMAT: 02		02/01/02 - 03/31/02							REPORT TIME: 8:36 DATE: 3/18/02	
DATASET SIZE	NUMBER OF REQUESTS	PERCENT OF TOTAL REQUESTS	TOTAL WAIT TIME	PERCENT OF TOTAL WAIT TIME	AVERAGE WAIT TIME	TOTAL BYTES READ	TOTAL BYTES WRITTEN	AVERAGE PERCENT COMPRESSION	TOTAL CPU TIME	
25.0K	58	6	0:01:01	0	0:00:01	560K	560K	0	0:00:02.38	
50.0K	29	3	0:02:27	1	0:00:05	1002K	1002K	0	0:00:01.50	
75.0K	30	3	0:00:35	0	0:00:01	1.82M	1.82M	0	0:00:02.09	
100K	15	2	0:00:17	0	0:00:01	1.36M	1.36M	0	0:00:01.26	
250K	38	4	0:43:30	11	0:01:09	6.09M	6.09M	0	0:00:03.34	
500K	28	3	0:02:60	1	0:00:06	10.4M	10.4M	0	0:00:02.78	
750K	14	2	0:00:26	0	0:00:02	8.52M	8.52M	0	0:00:01.42	
1024K	26	3	0:00:47	0	0:00:02	22.8M	22.8M	0	0:00:02.86	
1.50M	77	9	0:10:36	3	0:00:08	91.1M	91.1M	0	0:00:09.22	
2.00M	44	5	0:01:56	0	0:00:03	76.4M	76.4M	0	0:00:06.06	
3.00M	65	7	0:13:44	3	0:00:13	159M	159M	0	0:00:10.83	
4.00M	41	5	0:05:17	1	0:00:08	140M	140M	0	0:00:07.92	
5.00M	34	4	0:05:31	1	0:00:10	150M	150M	0	0:00:08.35	
7.50M	87	10	0:33:01	8	0:00:23	520M	520M	0	0:00:24.74	
10.0M	66	7	0:24:10	6	0:00:22	592M	592M	0	0:00:25.99	
20.0M	204	23	1:55:35	29	0:00:34	3.02G	3.02G	0	0:02:01.95	
30.0M	34	4	0:29:45	7	0:00:53	742M	742M	0	0:00:28.30	
40.0M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00	
50.0M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00	
75.0M	1	0	0:05:57	1	0:05:57	74.1M	74.1M	0	0:00:02.78	
100M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00	
OVER	4	0	1:41:08	25	0:25:17	1.45G	1.45G	0	0:00:50.27	
TOTAL	895		6:38:41			7.01G	7.01G		0:05:14.04	

Figure 70. REPORT-05 MIGRATION DELAY SUMMARY (ML1 - ML2)

The Migration Delay Summary Report contains the following data:

- The dataset size.
- Number of requests.
- Percent of total requests.
- Total wait time.
- Percent of total wait time.
- Average wait time.
- Total bytes read.
- Total bytes written.
- Average percent compression.
- Total CPU time.

Report-06 MIGRATION AGE SUMMARY (ML1 - ML2)

This report presents a summary, by dataset age, of all datasets migrated from DFHSM ML1 storage to ML2 storage.

This report will help you pinpoint problems with your current aging strategy, if any. For example, a report may show 45 requests for datasets that have not been referenced within 50 days. It may also show 2,487 requests for a dataset age of 2. If the total bytes read for the age 50 datasets is fairly large, when compared to the total bytes read for the age 2 datasets, you may be holding such datasets on primary storage for too long a period.

If the bulk of your requests are concentrated at low aging factors, either your current DFHSM aging is very aggressive or your DASD is limited and you must continually migrate. You should also take a close look at your ARCCMDxx member or your ACS parameters and determine whether an excessive number of datasets are being excluded from the migration process. Such datasets limit the amount of primary storage under DFHSM management, and probably cause excessive migration for the remaining datasets.

HSM OPTIMIZER 5.6		MIGRATION AGE SUMMARY (ML1 - ML2)				REPORT TIME: 8:36		DATE: 3/18/02
REPORT: 06 FORMAT: 03		02/01/02 - 03/31/02				TOTAL	TOTAL	TOTAL
DATASET	NUMBER	PERCENT	CUMULATIVE	CUMULATIVE	BYTES	BYTES	CPU	
AGE	OF	OF	REQUESTS	PERCENT	READ	WRITTEN	TIME	
1	315	35	315	35	3.47G	3.47G	0:02:26.53	
2	121	14	436	49	778M	778M	0:00:35.13	
3	104	12	540	60	631M	631M	0:00:29.68	
4	39	4	579	65	353M	353M	0:00:16.20	
5	65	7	644	72	494M	494M	0:00:21.92	
6	21	2	665	74	59.4M	59.4M	0:00:03.21	
7	20	2	685	77	47.5M	47.5M	0:00:02.68	
8	24	3	709	79	80.6M	80.6M	0:00:04.32	
9	27	3	736	82	151M	151M	0:00:07.17	
10	0	0	736	82	0.00K	0.00K	0:00:00.00	
15	125	14	861	96	887M	887M	0:00:39.44	
20	26	3	887	99	132M	132M	0:00:06.84	
25	0	0	887	99	0.00K	0.00K	0:00:00.00	
30	0	0	887	99	0.00K	0.00K	0:00:00.00	
40	8	1	895	100	7.01M	7.01M	0:00:00.92	
50	0	0	895	100	0.00K	0.00K	0:00:00.00	
60	0	0	895	100	0.00K	0.00K	0:00:00.00	
70	0	0	895	100	0.00K	0.00K	0:00:00.00	
80	0	0	895	100	0.00K	0.00K	0:00:00.00	
90	0	0	895	100	0.00K	0.00K	0:00:00.00	
100	0	0	895	100	0.00K	0.00K	0:00:00.00	
---	0	---	0	---	0	---	0	
450	0	0	895	100	0.00K	0.00K	0:00:00.00	
500	0	0	895	100	0.00K	0.00K	0:00:00.00	
600	0	0	895	100	0.00K	0.00K	0:00:00.00	
700	0	0	895	100	0.00K	0.00K	0:00:00.00	
800	0	0	895	100	0.00K	0.00K	0:00:00.00	
900	0	0	895	100	0.00K	0.00K	0:00:00.00	
1000	0	0	895	100	0.00K	0.00K	0:00:00.00	
1250	0	0	895	100	0.00K	0.00K	0:00:00.00	
1500	0	0	895	100	0.00K	0.00K	0:00:00.00	
1750	0	0	895	100	0.00K	0.00K	0:00:00.00	
2000	0	0	895	100	0.00K	0.00K	0:00:00.00	
OVER	0	0	895	100	0.00K	0.00K	0:00:00.00	
TOTAL	895		895		7.01G	7.01G	0:05:14.04	

Figure 71. REPORT-06 MIGRATION AGE SUMMARY (ML1 - ML2)

The Migration Age Summary Report contains the following data:

- The dataset age in days.
- The number of migration requests for the dataset age.
- The percentage of the total requests this represents.
- Cumulative requests.
- A cumulative percentage.
- Total bytes read.
- Total bytes written.

- Total CPU Time.

Report-07 MIGRATION DETAIL (PRIMARY - ML2)

This report presents a listing of all datasets migrated from DFHSM storage directly to ML2 storage (this is usually tape in most installations). It presents the same information shown for migration from primary to ML1 storage. Such migration is usually explicitly requested since the normal migration path is from primary to ML1 to ML2. Datasets on this report would be likely candidates for the Optimizer's Direct-to-ML2 support.

HSM OPTIMIZER 5.6		MIGRATION DETAIL (PRIMARY - ML2)					REPORT TIME: 12:14		DATE: 2/13/02		PAGE 30
REPORT: 07 FORMAT: 01		02/10/02 - 02/12/02									
		FROM	TO	DATE	TIME	LAST ACCESS	SET	READ	WRITE	CMP	MGEMENT
DATASET NAME		VOLUME	VOLUME	COMPLETE	COMPLETE	DATE	AGE	BYTES	BYTES	PCT	CLASS
GSA2.ZZ.D8509.FIL.VCHRS.G3245V00	SMS507	029656	**HSM***	02/12/02	21:13:40	02/01/02	11	0.84K	0.84K	0	STD10YR
GSA2.ZZ.D8406.FIL.FIYRECON.G2963V00	SMS507	029656	**HSM***	02/12/02	21:13:43	02/01/02	11	0.84K	0.84K	0	STD10YR
GSA4.XI.B1014.FIL.LOSELIG	SMS507	029656	**HSM***	02/12/02	21:13:46	02/01/02	11	55.5K	55.5K	0	STD10YR
GSA2.ZZ.D8406.FIL.SNWRECON.G1570V00	SMS507	029656	**HSM***	02/12/02	21:13:50	02/01/02	11	16.5K	16.5K	0	STD10YR
GSA2.ZZ.M0406.FIL.FIBRECON.G3308V00	SMS507	029656	**HSM***	02/12/02	21:13:53	02/05/02	7	0.84K	0.84K	0	STD10YR
GSA2.ZZ.D8406.FIL.USBRECON.G1014V00	SMS507	029656	**HSM***	02/12/02	21:13:56	02/02/02	10	7.44K	7.44K	0	STD10YR
GSA2.PI.X3002.FIL.PIXWLF.G1225V00	SMS507	029656	**HSM***	02/12/02	21:13:59	02/02/02	10	0.84K	0.84K	0	STD10YR
GSA2.ZZ.M0406.FIL.CITRECON.G3304V00	SMS507	029656	**HSM***	02/12/02	21:14:02	02/01/02	11	0.84K	0.84K	0	STD10YR
GSA2.ZZ.M0406.FIL.WLFCTL.G2010V00	SMS507	029656	**HSM***	02/12/02	21:14:05	02/01/02	11	2.52K	2.52K	0	STD10YR
GSA2.ZZ.C3502.FIL.LOUISVL.G1326V00	SMS507	029656	**HSM***	02/12/02	21:14:08	02/03/02	9	43.7K	43.7K	0	STD10YR
GSA2.ZZ.M0406.FIL.FBRECON.G0202V00	SMS507	029656	**HSM***	02/12/02	21:14:11	02/05/02	7	14.8K	14.8K	0	STD10YR
GSA5.BK.P0315.FIL.BKRECON	SMS507	029656	**HSM***	02/12/02	21:14:14	01/28/02	15	55.5K	55.5K	0	STD10YR
GSA2.ZZ.D8406.FIL.BOARECON.G2182V00	SMS507	029656	**HSM***	02/12/02	21:14:17	02/02/02	10	0.84K	0.84K	0	STD10YR
GSA2.ZZ.D8406.FIL.FINRECON.G2186V00	SMS507	029656	**HSM***	02/12/02	21:14:20	02/02/02	10	0.84K	0.84K	0	STD10YR
GSA2.ZZ.D8406.FIL.WLFRECON.G1976V00	SMS507	029656	**HSM***	02/12/02	21:14:23	02/02/02	10	2.52K	2.52K	0	STD10YR
GSA2.ZZ.M0406.FIL.SBRECON.G2954V00	SMS507	029656	**HSM***	02/12/02	21:14:26	02/02/02	10	0.84K	0.84K	0	STD10YR
GSAC.Z0.I1010.FIL.SELJRN.L.G2153V00	SMS507	029656	**HSM***	02/12/02	21:14:29	02/02/02	10	55.5K	55.5K	0	TEST
GSA7.MA.K8520.FIL.MTDMAINT.G0460V00	SMS507	029656	**HSM***	02/12/02	21:14:32	02/04/02	8	0.84K	0.84K	0	STD10YR
GSA2.TD.R2001.FIL.FLAT	SMS507	029656	**HSM***	02/12/02	21:14:58	01/28/02	15	15.5K	15.5K	0	STD10YR
GSA2.ZZ.M0406.FIL.LSBRECON.G2350V00	SMS518	029656	**HSM***	02/12/02	22:03:38	01/29/02	14	0.84K	0.84K	0	STD10YR
GSA7.PP.K1790.FIL.UPKMSTR	SMS563	031611	**HSM***	02/12/02	22:06:39	02/12/02	0	95.1M	95.1M	0	STD10YR
GSA4.AI.B8050.FIL.A10BMBR	SMS563	031611	**HSM***	02/12/02	22:07:19	02/10/02	2	79.6M	79.6M	0	STD10YR
ATP3.LB.BABPA.FIL.ER.HISTORY.L18	SMS560	029593*	**HSM***	02/12/02	22:08:32	02/12/02	0	399M	399M	0	STD10YR
	SMS559	031208	**HSM***	02/12/02	23:03:19	02/11/02	1	1.55M	1.55M	0	STD10YR
	SMS559	031276	**HSM***	02/12/02	23:03:45	02/11/02	1	16.0M	16.0M	0	STD10YR
GSA5.UA.A0890.BKP.UA1APEN	SMS503	031612	**HSM***	02/12/02	23:09:11	02/09/02	3	20.2M	20.2M	0	STD10YR
GSA4.PL.B8050.FIL.PLOMBR	SMS503	031612	**HSM***	02/12/02	23:09:29	02/10/02	2	32.8M	32.8M	0	STD10YR
GSA5.PP.A0890.BKP.PP1APEN	SMS503	031612	**HSM***	02/12/02	23:09:40	02/09/02	3	18.4M	18.4M	0	STD10YR
GSA1.Z0.I9991.FIL.CNTLM	SMS503	031612	**HSM***	02/12/02	23:09:45	02/09/02	3	23.4M	23.4M	0	STD10YR
GSA5.AI.P5035.BKP.AI1PPTR.G0160V00	SMS559	014583	**HSM***	02/12/02	23:13:07	02/11/02	1	119M	119M	0	STD10YR
GSA5.PJ.A0890.BKP.PU1APEN	SMS559	014583	**HSM***	02/12/02	23:13:29	02/09/02	3	37.6M	37.6M	0	STD10YR
TOTAL RECORDS:		1,059									

* DATASET EXISTS ON MULTIPLE TAPE VOLUMES

Figure 72. REPORT-07 MIGRATION DETAIL (PRIMARY - ML2)

The report contains the following data:

- Dataset Name
- The primary DASD volume the data was migrated from.
- The tape volume the dataset was migrated to.
- The user ID requesting the migration. This will usually be ****HSM*****, indicating that the dataset was migrated because it met your current automatic migration criteria. If some other ID is listed, it is the ID of the user who specifically requested the dataset to be migrated.
- The date the migration request was completed.
- The time the migration request was completed.
- The date the dataset was last referenced. Remember, this date is not necessarily the date the dataset was last updated.
- The dataset age in days. It is the difference between the migration completed date and the last referenced date.
- The number of bytes read.
- The number of bytes written by DFHSM.
- The DFSMS Management Class of the dataset.

Report-08 MIGRATION DELAY SUMMARY (PRIMARY - ML2)

This report presents a summary, by dataset size, of all datasets migrated from DFHSM primary storage to ML2 storage.

HSM OPTIMIZER 5.6		MIGRATION DELAY SUMMARY (PRIMARY - ML2)						REPORT TIME: 8:36		DATE: 3/18/02	PAGE 6
REPORT: 08 FORMAT: 02		02/01/02 - 03/31/02									
DATASET SIZE	NUMBER OF REQUESTS	PERCENT OF TOTAL REQUESTS	TOTAL WAIT TIME	PERCENT OF TOTAL WAIT TIME	AVERAGE WAIT TIME	TOTAL BYTES READ	TOTAL BYTES WRITTEN	AVERAGE PERCENT COMPRESSION	TOTAL CPU TIME		
25.0K	3,381	24	5:16:35	5	0:00:06	13.7M	13.7M	0	0:27:30.16		
50.0K	801	6	1:16:30	1	0:00:06	31.8M	31.8M	0	0:06:27.06		
75.0K	1,430	10	2:22:49	2	0:00:06	77.6M	77.6M	0	0:11:40.36		
100K	138	1	0:14:28	0	0:00:06	11.8M	11.8M	0	0:01:05.26		
250K	1,408	10	2:04:09	2	0:00:05	203M	203M	0	0:10:55.18		
500K	1,117	8	1:30:13	1	0:00:05	399M	399M	0	0:08:46.86		
750K	478	3	1:09:60	1	0:00:09	294M	294M	0	0:03:45.88		
1024K	363	3	0:35:33	1	0:00:06	311M	311M	0	0:02:52.92		
1.50M	625	4	1:03:40	1	0:00:06	775M	775M	0	0:04:43.13		
2.00M	324	2	0:44:02	1	0:00:08	568M	568M	0	0:02:26.64		
3.00M	506	4	1:09:48	1	0:00:08	1.23G	1.23G	0	0:04:13.98		
4.00M	312	2	0:56:30	1	0:00:11	1.07G	1.07G	0	0:02:46.30		
5.00M	327	2	1:07:44	1	0:00:12	1.44G	1.44G	0	0:02:38.94		
7.50M	476	3	2:13:34	2	0:00:17	2.79G	2.79G	0	0:04:11.24		
10.0M	327	2	2:06:50	2	0:00:23	2.80G	2.80G	0	0:02:54.47		
20.0M	835	6	9:07:21	9	0:00:39	11.9G	11.9G	0	0:08:41.34		
30.0M	245	2	4:55:47	5	0:01:12	5.96G	5.96G	0	0:03:03.84		
40.0M	165	1	3:31:30	3	0:01:17	5.36G	5.36G	0	0:02:24.93		
50.0M	192	1	5:14:53	5	0:01:38	8.16G	8.16G	0	0:04:42.27		
75.0M	238	2	9:16:57	9	0:02:20	14.3G	14.3G	0	0:04:43.34		
100M	173	1	12:42:59	12	0:04:25	15.1G	15.1G	0	0:03:55.10		
OVER	273	2	34:35:39	33	0:07:36	58.1G	58.1G	0	0:21:36.71		
TOTAL	14,134		103:17:31			130G	130G		2:26:05.91		

Figure 73. REPORT-08 MIGRATION DELAY SUMMARY (PRIMARY - ML2)

The migration delay summary report contains the following data:

- Dataset size.
- The number of migration requests for the dataset size.
- The percentage of the total migration requests this dataset size represents.
- The total wait time for these files.
- The percent of the total wait time datasets of this size represent.
- The average wait time for each individual request of this dataset size.
- The total bytes read.
- The total bytes written to ML2 storage.
- The average compression achieved.
- The total CPU time required to migrate the datasets.

Report-09 MIGRATION AGE SUMMARY (PRIMARY - ML2)

This report presents a summary, by dataset age, of all datasets migrated from DFHSM primary storage to ML2 storage.

This report will help you pinpoint problems with your current aging strategy, if any. For example, a report may show 45 requests for datasets that have not been referenced within 50 days. It may also show 2,487 requests for a dataset age of 2. If the total bytes read for the age 50 datasets is fairly large, when compared to the total bytes read for the age 2 datasets, you may be holding such datasets on primary storage for too long a period.

If the bulk of your requests are concentrated at low aging factors, either your current DFHSM aging is very aggressive or your DASD is limited and you must continually migrate. You should also take a close look at your ARCCMDxx member or your ACS parameters and determine whether an excessive number of datasets are being excluded from the migration process. Such datasets limit the amount of primary storage under DFHSM management, and probably cause excessive migration for the remaining datasets.

HSM OPTIMIZER 5.6		MIGRATION AGE SUMMARY (PRIMARY - ML2)				REPORT TIME: 8:36		DATE: 3/18/02
REPORT: 09 FORMAT: 03		02/01/02 - 03/31/02						PAGE 7
DATASET AGE	NUMBER OF REQUESTS	PERCENT OF REQUESTS	CUMULATIVE REQUESTS	CUMULATIVE PERCENT	TOTAL BYTES READ	TOTAL BYTES WRITTEN	TOTAL CPU TIME	
1	918	6	918	6	44.8G	44.8G	0:09:35.59	
2	462	3	1,380	10	12.4G	12.4G	0:04:09.38	
3	447	3	1,827	13	15.5G	15.5G	0:07:48.29	
4	451	3	2,278	16	10.6G	10.6G	0:05:01.25	
5	316	2	2,594	18	5.78G	5.78G	0:03:15.63	
6	2,813	20	5,407	38	12.0G	12.0G	0:34:54.97	
7	1,280	9	6,687	47	5.20G	5.20G	0:12:18.53	
8	794	6	7,481	53	4.64G	4.64G	0:07:04.55	
9	573	4	8,054	57	2.44G	2.44G	0:05:17.48	
10	617	4	8,671	61	1.97G	1.97G	0:05:21.72	
15	2,395	17	11,066	78	9.02G	9.02G	0:20:26.27	
20	1,274	9	12,340	87	1.61G	1.61G	0:11:15.68	
25	404	3	12,744	90	455M	455M	0:03:37.99	
30	274	2	13,018	92	14.6M	14.6M	0:02:09.04	
40	278	2	13,296	94	2.17G	2.17G	0:02:33.53	
50	243	2	13,539	96	96.9M	96.9M	0:01:54.70	
60	105	1	13,644	97	349M	349M	0:00:49.40	
70	95	1	13,739	97	2.89M	2.89M	0:00:46.48	
80	116	1	13,855	98	3.13M	3.13M	0:00:57.36	
90	68	0	13,923	99	1.22M	1.22M	0:00:35.17	
100	48	0	13,971	99	1.53M	1.53M	0:00:25.04	
125	43	0	14,014	99	14.5M	14.5M	0:00:22.48	
150	21	0	14,035	99	54.5M	54.5M	0:00:25.68	
175	12	0	14,047	99	43.3M	43.3M	0:00:24.15	
200	17	0	14,064	100	771K	771K	0:00:09.68	
250	8	0	14,072	100	63.6M	63.6M	0:00:32.21	
300	1	0	14,073	100	309K	309K	0:00:00.37	
350	12	0	14,085	100	109M	109M	0:00:32.86	
---	0	---	---	0	---	---	---	
1750	0	0	14,134	100	0.00K	0.00K	0:00:00.00	
2000	0	0	14,134	100	0.00K	0.00K	0:00:00.00	
OVER	0	0	14,134	100	0.00K	0.00K	0:00:00.00	
TOTAL	14,134		14,134		130G	130G	2:26:05.91	

Figure 74. REPORT-09 MIGRATION AGE SUMMARY (PRIMARY - ML2)

The Migration Age Summary Report contains the following data:

- The dataset age in days.
- The number of migration requests for the dataset age.
- The percentage of the total requests this represents.
- Cumulative requests.
- A cumulative percentage.
- Total bytes read.
- Total bytes written.
- Total CPU Time.

Report-10 RECALL DETAIL (ML1 - PRIMARY)

This report is a listing of all datasets recalled from DFHSM ML1 storage to primary storage for the requested period. It presents the same information shown for migration from primary to ML1 storage.

Again, look for an excessive number of recalls for datasets that were migrated for a short period of time. Datasets that remained migrated for a relatively long period of time might be likely candidates for migration directly to ML2 storage. This will free space on ML1 storage, allowing more frequently referenced datasets to remain on ML1 storage and give better service times for dataset recall.

HSM OPTIMIZER 5.6	RECALL DETAIL (ML1 - PRIMARY)	PAGE 33	
REPORT: 10 FORMAT: 01	02/10/02 - 02/12/02	REPORT TIME: 12:14 DATE: 2/13/02	
		LAST DATA	
DATASET NAME	FROM TO	DATE TIME ACCESS	SET READ WRITE CMP MGMT
	VOLUME VOLUME	COMPLETE COMPLETE DATE	AGE BYTES BYTES PCT CLASS
OSEM560.COMPAT56.BIN	HSM000 SMS528	*H*S*M* 02/10/02 5:09:56	02/04/02 0 644K 642K 0 SMP
GSA7.LB.V0900.FIL.TESTFILE	HSM000 SMS563	AEDMF 02/12/02 13:50:28	02/12/02 0 3.91M 3.90M 0 STD10YR
GSA5.PH.P5092.FIL.FED1099.G0001V00	HSM000 SMS563	PCALX 02/12/02 15:00:46	01/31/02 12 454K 2.49M 82 STD10YR
GSA3.OP.SMFDM.BKP.SMF.G0003V00	HSM000 SMS505	GNLPROD 02/12/02 22:00:53	02/12/02 0 16.2M 16.2M 0 STD10YR
GSA5.ZZ.P0403.FIL.MTDCHG.G0631V00	HSM000 SMS566	GNLPROD 02/12/02 23:37:12	02/12/02 0 2.89M 2.89M 0 STD10YR
TOTAL RECORDS:	5		

Figure 75. REPORT-10 RECALL DETAIL (ML1 - PRIMARY)

The Recall Detail Report contains the following data:

- Dataset Name
- The DFHSM ML1 DASD volume the dataset was recalled from
- The primary DASD volume the dataset was recalled to
- The userid requesting the recall.
- The date the recall request was completed.
- The time the recall request was completed.
- The last access date of the dataset.
- The dataset age.
- The number of bytes read.
- The number of bytes written.
- The compression percentage.
- The DFSMS Management class of the dataset.

Report-11 RECALL DELAY SUMMARY (ML1 - PRIMARY)

This report presents a summary by dataset size, of delays in recalling datasets. Delays usually occur when all defined DFHSM recall tasks are currently busy. Unless the average delay seems overly long, do not be too concerned with the values reported. If the average delays do seem overly long, you might want to consider allowing more concurrent DFHSM recall tasks.

HSM OPTIMIZER 5.6		RECALL DELAY SUMMARY (ML1 - PRIMARY)						REPORT TIME: 8:36		DATE: 3/18/02		PAGE 8
REPORT: 11 FORMAT: 04		02/01/02 - 03/31/02										
DATASET SIZE	NUMBER OF REQUESTS	PERCENT OF TOTAL REQUESTS	TOTAL WAIT TIME	PERCENT OF TOTAL WAIT TIME	AVERAGE WAIT TIME	TOTAL BYTES READ	TOTAL BYTES WRITTEN	AVERAGE PERCENT COMPRESSION	TOTAL CPU TIME			
25.0K	22	12	0:12:48	20	0:00:35	44.0K	18.5K	0	0:00:16.85			
50.0K	2	1	0:00:11	0	0:00:06	14.0K	92.2K	85	0:00:01.35			
75.0K	4	2	0:00:40	1	0:00:10	96.0K	234K	59	0:00:02.31			
100K	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00			
250K	2	1	0:00:09	0	0:00:05	118K	285K	59	0:00:01.19			
500K	1	1	0:00:05	0	0:00:05	146K	277K	47	0:00:00.77			
750K	10	5	0:01:56	3	0:00:12	4.47M	5.60M	20	0:00:05.56			
1024K	9	5	0:01:13	2	0:00:08	4.99M	7.90M	37	0:00:07.22			
1.50M	16	8	0:02:15	3	0:00:08	15.4M	18.4M	16	0:00:11.94			
2.00M	13	7	0:02:26	4	0:00:11	15.4M	23.1M	33	0:00:09.41			
3.00M	19	10	0:02:55	4	0:00:09	38.7M	48.7M	21	0:00:14.82			
4.00M	9	5	0:01:49	3	0:00:12	25.1M	31.8M	21	0:00:06.49			
5.00M	8	4	0:01:24	2	0:00:10	32.6M	36.3M	10	0:00:06.53			
7.50M	12	6	0:07:05	11	0:00:35	64.6M	75.0M	14	0:00:09.84			
10.0M	13	7	0:16:57	26	0:01:18	107M	112M	4	0:00:10.90			
20.0M	45	24	0:12:00	18	0:00:16	644M	685M	6	0:00:37.38			
30.0M	6	3	0:01:43	3	0:00:17	128M	128M	0	0:00:05.27			
40.0M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00			
50.0M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00			
75.0M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00			
100M	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00			
OVER	0	0	0:00:00	0	0:00:00	0.00K	0.00K	0	0:00:00.00			
TOTAL	191		1:05:36			1.06G	1.15G		0:02:27.83			

Figure 76. REPORT-11 RECALL DELAY SUMMARY (ML1 - PRIMARY)

The recall Delay Summary Report contains the following data:

- Dataset size.
- The number of recall requests for the dataset size.
- The percentage of the total recall requests this dataset size represents.
- The total wait time for this size datasets.
- The percent of total wait time for these datasets.
- The average unit time for each individual request of this dataset size.
- The total bytes read.
- The total bytes written to ML1 storage.
- The average compression achieved.
- The total CPU time to recall these datasets.

Report-12 RECALL AGE SUMMARY (ML1 - PRIMARY)

This report presents a summary, by dataset age, of all datasets recalled from DFHSM ML1 storage to primary storage.

HSM OPTIMIZER 5.6		RECALL AGE SUMMARY (ML1 - PRIMARY)				REPORT TIME: 8:36 DATE: 3/18/02		
REPORT: 12 FORMAT: 03		02/01/02 - 03/31/02				PAGE 9		
DATASET	NUMBER	PERCENT	CUMULATIVE	CUMULATIVE	TOTAL	TOTAL	TOTAL	
AGE	OF	OF	REQUESTS	PERCENT	BYTES	BYTES	CPU	
	REQUESTS	REQUESTS			READ	WRITTEN	TIME	
1	157	82	157	82	964M	1.01G	0:02:01.33	
2	12	6	169	88	52.0M	52.9M	0:00:09.77	
3	7	4	176	92	11.9M	12.6M	0:00:05.35	
4	3	2	179	94	19.2M	28.7M	0:00:02.47	
5	0	0	179	94	0.00K	0.00K	0:00:00.00	
6	3	2	182	95	4.35M	4.38M	0:00:02.05	
7	5	3	187	98	3.14M	4.83M	0:00:03.69	
8	1	1	188	98	22.7M	22.7M	0:00:00.78	
9	1	1	189	99	1.07M	1.07M	0:00:00.81	
10	0	0	189	99	0.00K	0.00K	0:00:00.00	
15	2	1	191	100	3.88M	9.00M	0:00:01.58	
20	0	0	191	100	0.00K	0.00K	0:00:00.00	
25	0	0	191	100	0.00K	0.00K	0:00:00.00	
30	0	0	191	100	0.00K	0.00K	0:00:00.00	
40	0	0	191	100	0.00K	0.00K	0:00:00.00	
50	0	0	191	100	0.00K	0.00K	0:00:00.00	
60	0	0	191	100	0.00K	0.00K	0:00:00.00	
70	0	0	191	100	0.00K	0.00K	0:00:00.00	
80	0	0	191	100	0.00K	0.00K	0:00:00.00	
90	0	0	191	100	0.00K	0.00K	0:00:00.00	
100	0	0	191	100	0.00K	0.00K	0:00:00.00	
125	0	0	191	100	0.00K	0.00K	0:00:00.00	
150	0	0	191	100	0.00K	0.00K	0:00:00.00	
175	0	0	191	100	0.00K	0.00K	0:00:00.00	
200	0	0	191	100	0.00K	0.00K	0:00:00.00	
250	0	0	191	100	0.00K	0.00K	0:00:00.00	
300	0	0	191	100	0.00K	0.00K	0:00:00.00	
350	0	0	191	100	0.00K	0.00K	0:00:00.00	
400	0	0	191	100	0.00K	0.00K	0:00:00.00	
450	0	0	191	100	0.00K	0.00K	0:00:00.00	
500	0	0	191	100	0.00K	0.00K	0:00:00.00	
600	0	0	191	100	0.00K	0.00K	0:00:00.00	
700	0	0	191	100	0.00K	0.00K	0:00:00.00	
800	0	0	191	100	0.00K	0.00K	0:00:00.00	
900	0	0	191	100	0.00K	0.00K	0:00:00.00	
1000	0	0	191	100	0.00K	0.00K	0:00:00.00	
1250	0	0	191	100	0.00K	0.00K	0:00:00.00	
1500	0	0	191	100	0.00K	0.00K	0:00:00.00	
1750	0	0	191	100	0.00K	0.00K	0:00:00.00	
2000	0	0	191	100	0.00K	0.00K	0:00:00.00	
OVER	0	0	191	100	0.00K	0.00K	0:00:00.00	
TOTAL	191		191		1.06G	1.15G	0:02:27.83	

Figure 77. REPORT-12 RECALL AGE SUMMARY (ML1 - PRIMARY)

The following data is presented:

- The dataset age in days.
- The number of recall requests for the dataset age.
- The percentage of the total requests this age represents.
- Cumulative requests.
- A cumulative percentage.
- Total bytes read.
- Total bytes written.
- Total CPU time needed to recall these datasets.

Report-13 RECALL DETAIL (ML2 - PRIMARY)

This report is a listing of all datasets recalled from DFHSM ML2 storage to primary storage for the requested period.

Again, look for an excessive number of recalls for datasets that were migrated for a short period of time. Datasets that remained migrated for a relatively long period of time might be likely candidates for migration directly to ML2 storage. This will free space on ML1 storage, allowing more frequently referenced datasets to remain on ML1 storage and give better service times for dataset recall.

HSM OPTIMIZER 5.6		RECALL DETAIL (ML2 - PRIMARY)						PAGE 37				
REPORT: 13 FORMAT: 01		02/10/02 - 02/12/02						REPORT TIME: 12:14 DATE: 2/13/02				
DATASET NAME		FROM	TO	DATE	TIME	LAST ACCESS	DATA	SET	READ	WRITE	CMP	MGEMENT
		VOLUME	VOLUME	COMPLETE	COMPLETE	DATE	AGE	BYTES	BYTES	PCT	CLASS	
GSA5.SP.P5035.BKP.SP1PPTR.G0150V00	026044	SMS572	AEKEW	02/11/02	17:45:17	01/17/02	11	0.00K	31.9M	0	STD10YR	
GSA1.Z0.I6102.FIL.TIMEDATA.G0153V00	031494	SMS558	GNLPROD	02/11/02	23:25:40	02/04/02	1	0.00K	275K	0	STD10YR	
GSA1.Z0.I0403.FIL.MTDCHEG.G1676V00	022454	SMS501	GNLPROD	02/12/02	0:22:18	02/09/02	1	0.00K	11.9M	0	STD10YR	
GSA4.LB.B0307.FIL.MTDCHEG.G0028V00	025498	SMS501	GNLPROD	02/12/02	0:43:12	02/09/02	1	0.00K	519K	0	STD10YR	
GSA5.CT.P5090.BKP.CT1PPTR	024649	SMS504	AEKEW	02/12/02	9:44:25	01/19/99	1105	0.00K	1.44M	0	STD10YR	
GSA5.AI.P5090.BKP.AI1PPTR	029451	SMS504	AEKEW	02/12/02	9:45:41	02/11/02	0	0.00K	119M	0	STD10YR	
GSA5.IC.P5090.BKP.IC1PPTR	023239	SMS563	AEKEW	02/12/02	9:46:44	01/26/99	1095	0.00K	329K	0	STD10YR	
GSA2.ZZ.M0406.FIL.UBCRECON.G1450V00	025498	SMS563	SPJRM	02/12/02	9:47:21	02/06/02	0	0.00K	40.1K	0	STD10YR	
GSA5.KC.P5090.BKP.KC1PPTR	028837	SMS563	AEKEW	02/12/02	9:48:22	12/30/99	644	0.00K	0.82K	0	STD10YR	
GSA5.OI.P5090.BKP.OI1PPTR	023114	SMS563	AEKEW	02/12/02	9:49:28	01/27/99	1104	0.00K	3.69M	0	STD10YR	
GSA5.PU.P5090.BKP.PU1PPTR	028008	SMS504	AEKEW	02/12/02	10:00:30	12/30/99	676	0.00K	0.82K	0	STD10YR	
GSA5.XL.P5090.BKP.XL1PPTR	028837	SMS563	AEKEW	02/12/02	10:13:11	12/30/99	644	0.00K	0.82K	0	STD10YR	
GSA4.AI.B0941.FIL.ENRLBEN	023313	SMS504	AEJHT	02/12/02	10:16:19	02/08/02	0	0.00K	2.73M	0	STD10YR	
GSA5.FN.L2001.FIL.FED1099.G0017V00	019068	SMS563	SPJRM	02/12/02	11:08:34	01/24/02	12	0.00K	55.5K	0	STD10YR	
GSAE.LB.F0000.DBS.LB2FNTR	031567	SMS563	AEVSB	02/12/02	12:05:38	01/30/02	0	0.00K	627K	0	TEST	
GSAE.LB.F0000.DBS.LB2FATR	031607	SMS563	TESTUSR	02/12/02	12:07:02	01/30/02	4	0.00K	1.71K	0	TEST	
GSAE.LB.F0000.DBS.LB2FGTR	012567	SMS504	AEVSB	02/12/02	12:07:40	01/30/02	7	0.00K	783K	0	TEST	
GSA4.AI.B0902.FIL.AI0BHST.G0049V00	026744*	SMS512	AEOLP	02/12/02	12:27:27	01/01/02	41	0.00K	214M	0	STD10YR	
ATP3.LB.D0400.FIL.TOOTH	031464	SMS504	APJBW	02/12/02	12:28:44	02/06/02	3	0.00K	119M	0	STDMPLY	
GSA4.AI.B0902.FIL.AI0BHST.G0050V00	023170*	SMS510	AEOLP	02/12/02	12:29:56	01/31/02	6	0.00K	217M	0	STD10YR	
GSA4.AI.B080B.FIL.GENACTG.G0056V00	022057	SMS563	AEOLP	02/12/02	12:41:49	01/31/02	1	0.00K	7.06M	0	STD10YR	
GSA5.TC.P0301.FIL.TCALPHA	025821	SMS563	AEKEW	02/12/02	12:53:19	01/23/02	10	0.00K	165K	0	STD10YR	
GSA4.AI.B0943.FIL.AI0BTRN	019255	SMS503	AEJHT	02/12/02	14:19:09	11/09/01	92	0.00K	119M	0	STD10YR	
GSA7.PP.K1790.FIL.UPKMSTR	026482	SMS563	AECBS	02/12/02	15:09:01	02/09/02	2	0.00K	95.1M	0	STD10YR	
GSA4.PP.B1006.FIL.PP0BELG.G0041V00	031566	SMS502	AEJHT	02/12/02	16:15:05	02/08/02	0	0.00K	9.09M	0	STD10YR	
GSA5.BK.P5035.BKP.BK1PPTR.G0114V00	019508	SMS566	AEKEW	02/12/02	16:34:06	02/11/02	0	0.00K	8.45M	0	STD10YR	
GSA5.CY.P5035.BKP.CY1PPTR.G0132V00	019242	SMS503	AEKEW	02/12/02	16:43:05	01/23/02	18	0.00K	16.7M	0	STD10YR	
GSA5.IC.P5035.BKP.IC1PPTR.G0163V00	025512	SMS505	AEKEW	02/12/02	17:20:20	01/10/02	12	0.00K	1.44M	0	STD10YR	
ATP3.LB.BABPA.FIL.ER.HISTORY.G06	030824	SMS505	AEOLP	02/12/02	21:27:04	01/29/02	13	0.00K	7.14M	0	STDMPLY	

* DATASET EXISTS ON MULTIPLE TAPE VOLUMES

Figure 78. REPORT-13 RECALL DETAIL (ML2 - PRIMARY)

The Recall Detail Report contains the following data:

- Dataset Name
- The DFHSM ML2 tape volume the dataset was recalled from.
- The primary DASD volume the dataset was recalled to.
- The userid requesting the recall.
- The date the recall request was completed.
- The time the recall request was completed.
- The last access date of the dataset.
- The dataset age.
- The number of bytes read.
- The number of bytes written.
- The compression percentage.
- The DFSMS Management class of the dataset.

Report-14 RECALL DELAY SUMMARY (ML2 - PRIMARY)

This report presents a summary by dataset size, of delays in recalling datasets. Delays usually occur when waiting for a tape mount to occur.

HSM OPTIMIZER 5.6		RECALL DELAY SUMMARY (ML2 - PRIMARY)						REPORT TIME: 8:36		DATE: 3/18/02	PAGE 10
REPORT: 14 FORMAT: 04		02/01/02 - 03/31/02									
DATASET SIZE	NUMBER OF REQUESTS	PERCENT OF TOTAL REQUESTS	TOTAL WAIT TIME	PERCENT OF TOTAL WAIT TIME	AVERAGE WAIT TIME	TOTAL BYTES READ	TOTAL BYTES WRITTEN	AVERAGE PERCENT COMPRESSION	TOTAL CPU TIME		
25.0K	91	6	6:14:14	7	0:04:07	0.00K	311K	0	0:01:08.72		
50.0K	106	7	5:20:25	6	0:03:01	0.00K	3.90M	0	0:01:19.42		
75.0K	81	5	3:18:48	4	0:02:27	0.00K	4.46M	0	0:01:04.40		
100K	21	1	1:00:19	1	0:02:52	0.00K	1.83M	0	0:00:16.02		
250K	180	12	8:39:25	9	0:02:53	0.00K	26.5M	0	0:02:22.77		
500K	160	10	6:58:30	7	0:02:37	0.00K	57.4M	0	0:02:03.15		
750K	88	6	4:19:59	5	0:02:57	0.00K	53.9M	0	0:01:10.22		
1024K	74	5	3:56:51	4	0:03:12	0.00K	63.7M	0	0:01:02.90		
1.50M	128	8	5:59:10	6	0:02:48	0.00K	156M	0	0:01:45.80		
2.00M	56	4	3:34:14	4	0:03:50	0.00K	97.9M	0	0:00:46.84		
3.00M	62	4	2:43:34	3	0:02:38	0.00K	154M	0	0:00:54.48		
4.00M	49	3	2:42:34	3	0:03:19	0.00K	168M	0	0:00:46.59		
5.00M	52	3	3:07:03	3	0:03:36	0.00K	229M	0	0:00:55.23		
7.50M	54	4	3:06:45	3	0:03:28	0.00K	339M	0	0:00:50.56		
10.0M	40	3	2:24:60	3	0:03:37	0.00K	344M	0	0:00:38.62		
20.0M	111	7	10:48:09	12	0:05:50	0.00K	1.58G	0	0:02:24.46		
30.0M	33	2	2:04:19	2	0:03:46	0.00K	753M	0	0:00:40.55		
40.0M	15	1	1:05:19	1	0:04:21	0.00K	496M	0	0:00:19.71		
50.0M	15	1	0:42:46	1	0:02:51	0.00K	669M	0	0:00:39.62		
75.0M	27	2	1:56:44	2	0:04:19	0.00K	1.72G	0	0:01:19.72		
100M	25	2	2:27:28	3	0:05:54	0.00K	2.14G	0	0:04:05.84		
OVER	70	5	10:35:41	11	0:09:05	0.00K	15.2G	0	0:07:52.83		
TOTAL	1,538		93:07:17			0.00K	24.2G		0:34:28.45		

Figure 79. REPORT-14 RECALL DELAY SUMMARY (ML2 - PRIMARY)

The Recall Delay Summary Report contains the following data:

- Dataset size.
- The number of recall requests for the dataset size.
- The percentage of the total recall requests this dataset size represents.
- The total wait time for this size datasets.
- The percent of total wait time for these datasets.
- The average unit time for each individual request of this dataset size.
- The total bytes read.
- The total bytes written to ML1 storage.
- The average compression achieved.
- The total CPU time to recall these datasets.

Report-15 RECALL AGE SUMMARY (ML2 - PRIMARY)

This report presents a summary, by dataset age, of all datasets recalled from DFHSM ML2 storage to primary storage.

HSM OPTIMIZER 5.6		RECALL AGE SUMMARY (ML2 - PRIMARY)				REPORT TIME:		8:36	DATE:	PAGE 11
REPORT: 15 FORMAT: 03		02/01/02 - 03/31/02								3/18/02
DATASET	NUMBER	PERCENT	CUMULATIVE	CUMULATIVE	TOTAL	TOTAL	TOTAL			
AGE	OF	OF	REQUESTS	PERCENT	BYTES	BYTES	CPU			
	REQUESTS	REQUESTS			READ	WRITTEN	TIME			
1	206	13	206	13	0.00K	6.22G	0:07:55.16			
2	75	5	281	18	0.00K	1.94G	0:01:53.30			
3	65	4	346	22	0.00K	1.13G	0:00:55.52			
4	65	4	411	27	0.00K	566M	0:01:23.31			
5	55	4	466	30	0.00K	1.26G	0:01:45.98			
6	50	3	516	34	0.00K	670M	0:00:41.75			
7	48	3	564	37	0.00K	583M	0:01:15.96			
8	33	2	597	39	0.00K	574M	0:00:27.31			
9	39	3	636	41	0.00K	1.03G	0:00:31.90			
10	38	2	674	44	0.00K	317M	0:00:31.35			
15	206	13	880	57	0.00K	2.99G	0:05:01.35			
20	155	10	1,035	67	0.00K	1.50G	0:03:36.50			
25	118	8	1,153	75	0.00K	1.14G	0:01:34.06			
30	75	5	1,228	80	0.00K	710M	0:01:03.19			
40	63	4	1,291	84	0.00K	149M	0:01:02.31			
50	44	3	1,335	87	0.00K	2.81G	0:00:41.23			
60	18	1	1,353	88	0.00K	105M	0:00:21.08			
70	15	1	1,368	89	0.00K	61.3M	0:00:18.11			
80	5	0	1,373	89	0.00K	76.3M	0:00:09.44			
90	7	0	1,380	90	0.00K	87.6M	0:00:09.28			
100	9	1	1,389	90	0.00K	189M	0:00:07.36			
125	16	1	1,405	91	0.00K	47.7M	0:00:19.77			
150	10	1	1,415	92	0.00K	95.2M	0:00:21.50			
175	16	1	1,431	93	0.00K	261M	0:00:18.08			
200	12	1	1,443	94	0.00K	92.1M	0:00:13.42			
250	10	1	1,453	94	0.00K	288M	0:00:09.25			
300	15	1	1,468	95	0.00K	111M	0:00:12.75			
350	7	0	1,475	96	0.00K	38.6M	0:00:05.84			
400	13	1	1,488	97	0.00K	69.3M	0:00:10.45			
450	6	0	1,494	97	0.00K	10.9M	0:00:06.49			
500	3	0	1,497	97	0.00K	8.54M	0:00:04.75			
600	3	0	1,500	98	0.00K	2.57M	0:00:03.84			
700	11	1	1,511	98	0.00K	16.3M	0:00:12.60			
800	12	1	1,523	99	0.00K	4.26M	0:00:11.62			
900	1	0	1,524	99	0.00K	2.29M	0:00:02.52			
1000	3	0	1,527	99	0.00K	7.37M	0:00:02.29			
1250	5	0	1,532	100	0.00K	6.25M	0:00:03.75			
1500	0	0	1,532	100	0.00K	0.00K	0:00:00.00			
1750	2	0	1,534	100	0.00K	5.69M	0:00:01.49			
2000	0	0	1,534	100	0.00K	0.00K	0:00:00.00			
OVER	4	0	1,538	100	0.00K	98.1M	0:00:22.59			
TOTAL	1,538		1,538		0.00K	25.1G	0:34:28.45			

Figure 80. REPORT-15 RECALL AGE SUMMARY (ML2 - PRIMARY)

The following data is presented:

- The dataset age in days.
- The number of recall requests for the dataset age.
- The percentage of the total requests this age represents.
- Cumulative requests.
- A cumulative percentage.
- Total bytes read.
- Total bytes written.
- Total CPU time needed to recall these datasets.

Report-16 DFHSM DASD VOLUME SUMMARY

The DFHSM Volume Report shows the activity of all the volumes under DFHSM control.

HSM OPTIMIZER 5.6		DFHSM DASD VOLUME SUMMARY												REPORT TIME: 16:08 DATE: 3/18/02				PAGE 2	
REPORT: 16 FORMAT: 08		02/01/02 - 03/31/02																	
		PERCENT USED			FRAGMENT INDEX			MIGRATION		RECALL		BACKUP		RECOVER		VOLUME DUMP			
VOLSER	TYPE	AVG	MIN	MAX	AVG	MIN	MAX	DATASET	ELPSD	DATASET	ELPSD	DATASET	ELPSD	DATASET	ELPSD	DUMP	ELPSD	LAST	DUMP
		COUNT	TIME	COUNT	TIME	COUNT	TIME	COUNT	TIME	COUNT	TIME	COUNT	TIME	COUNT	TIME	COUNT	TIME	DATE	TIME
HSM000	M	40	4	91	166	39	392	2,179	8:07	183	0:50	864	5:02	0	0:00	0	0:00		
MVSRSF	P	99	99	99	207	207	207	0	0:00	0	0:00	541	3:17	0	0:00	3	1:41	03/10/02	10:58:43
MVRSO	P	97	97	97	9	9	9	0	0:00	0	0:00	544	3:24	0	0:00	5	2:55	03/10/02	10:13:22
MVRSR2	P	96	96	96	26	26	26	0	0:00	0	0:00	0	0:00	0	0:00	0	0:00		
MVRSR3	P	99	99	99	6	6	6	0	0:00	0	0:00	544	2:59	0	0:00	5	2:49	03/10/02	10:46:08
MVRSR5	P	99	99	99	16	16	16	0	0:00	0	0:00	544	2:43	0	0:00	2	1:07	03/10/02	10:25:58
MVRSR6	P	97	96	99	122	16	168	0	0:00	0	0:00	547	2:42	0	0:00	4	2:08	03/10/02	11:16:48
PAGE00	P	0	0	0	0	0	0	0	0:00	0	0:00	0	0:00	0	0:00	1	0:24	03/03/02	11:03:06
PAGE03	P	79	79	79	0	0	0	0	0:00	0	0:00	10	0:50	0	0:00	2	0:34	03/10/02	11:16:10
SMS402	P	91	91	91	534	533	535	0	0:00	0	0:00	279	2:45	0	0:00	3	1:43	03/10/02	9:33:13
SMS403	P	1	1	1	114	114	114	0	0:00	0	0:00	0	0:00	0	0:00	0	0:00		
SMS501	P	69	44	85	275	135	458	1,262	9:10	188	1:15	1,811	28:51	3	0:03				
SMS502	P	69	49	86	378	234	564	1,235	9:37	151	1:15	3,749	47:27	0	0:00				
SMS503	P	70	58	84	352	144	518	1,266	9:18	135	0:38	3,478	35:08	4	0:11				
SMS504	P	69	52	85	290	118	463	1,156	7:50	234	1:18	3,178	27:44	2	0:04				
SMS505	P	70	55	90	324	143	541	1,492	8:54	255	0:57	3,443	34:52	1	0:02				
SMS506	P	75	60	85	272	164	390	956	5:26	60	0:16	2,240	27:32	0	0:00				
SMS507	P	72	61	81	349	187	509	1,008	6:19	46	0:28	2,474	25:06	0	0:00				
SMS508	P	74	53	87	247	131	431	1,069	6:58	79	0:15	1,875	30:10	0	0:00				
SMS510	P	62	24	98	91	43	297	8	0:49	4	0:26	68	6:16	0	0:00				
SMS511	P	60	47	97	130	103	285	5	0:19	0	0:00	75	9:27	0	0:00				
SMS513	P	56	3	96	103	0	203	8	1:03	6	1:08	22	2:29	0	0:00				
SMS517	P	63	57	96	99	77	146	1	0:02	0	0:00	70	11:02	0	0:00				
SMS518	P	72	55	89	576	487	713	963	6:29	107	0:31	2,288	29:08	0	0:00				
SMS520	P	78	74	80	326	274	347	5	0:02	1	0:00	130	3:01	0	0:00				
SMS521	P	80	77	82	343	333	366	18	0:02	0	0:00	119	2:59	0	0:00				
SMS522	P	78	76	83	238	232	251	7	0:04	0	0:00	245	2:40	0	0:00				
SMS524	P	78	75	79	272	266	281	1	0:01	0	0:00	102	1:22	0	0:00				
SMS525	P	80	79	80	340	325	360	10	0:04	0	0:00	146	2:33	1	0:05				
SMS527	P	56	50	61	137	120	163	4	0:04	1	0:01	229	3:14	0	0:00				
SMS532	P	95	95	95	212	211	214	0	0:00	0	0:00	136	1:22	0	0:00	4	2:43	03/10/02	9:52:03
SMS558	P	71	56	84	551	431	657	767	5:47	196	0:47	2,354	20:52	1	0:04				

Figure 81. REPORT-16 DFHSM DASD VOLUME SUMMARY

The report contains the following data:

- The DASD volume serial number.
- The type of volume: P represents a primary volume; M represents a migration volume (it might be a Level-2 volume if you do not use tape for ML2 volumes).
- The next three columns present information concerning the percentage of use during the reporting period. Average, minimum and maximum values are reported. These values can assist you in determining what threshold values should be used for the volume.
- The next three columns report fragmentation index values. These values will assist you in determining the appropriate fragmentation index factors to apply to the Optimizer's defragmentation levels.
- The next two columns present migration statistics: the number of datasets migrated from the volume during the reporting period, and the elapsed time to do the migrations.
- Recall statistics are presented in the next two columns: the number of datasets recalled to the volume, and the elapsed time for the recalls.
- Backup statistics are presented next: the number of backups that occurred on the volume for the reporting period, and the elapsed time for the backups.
- Recover statistics are presented: the number of datasets recovered, and the elapsed time for the recoveries.
- The final four columns contain entries if you are using the volume dump feature of DFHSM for the volume. The entries are: the number of times the volume was dumped during the reporting period; the elapsed time for the dump operations; and the date and time of the last dump operation.

Report-17 PRIMARY DATASET ACTIVITY REPORT

The Primary Dataset Activity Report list the datasets that are thrashing. By specifying a Data Set movement index, only datasets that exceed that value will be included on the report. The index is calculated as:

$$DMIndex = \text{total migrations} + \text{total recalls} / 30$$

Note: Total Migrations and Total Recalls are calculated from thirty days preceding the Report Ending Date.

The minimum retention date for the HSM Optimizer Report Database should be two months, but the recommended retention date is three months, so that the dataset movement index will include enough data to be of value. The report is sorted in descending order by dataset movement index.

HSM OPTIMIZER 5.6		PRIMARY DATASET ACTIVITY REPORT										PAGE 43			
REPORT: 17 FORMAT: 06		02/10/02 - 02/12/02										REPORT TIME: 12:14		DATE: 2/13/02	
DATASET NAME	SIZE	PER DAY	-- MIGRATION --			--- RECALL ---			--- BACKUP ---			-- RECOVERY --			
			PAST 7	PAST 30	PREV 30	PAST 7	PAST 30	PREV 30	PAST 7	PAST 30	PREV 30	PAST 7	PAST 30	PREV 30	
ATP3.LB.BABPA.FIL.ELIG.MASTER.L17	110M	0.700	0	12	4	0	10	4	0	0	1	0	0	0	
CICSEM.SPDPAW.SOURCE	532K	0.533	0	8	0	0	8	0	1	5	0	0	0	0	
ATP3.LB.D0400.FIL.TOOTH	119M	0.433	4	7	0	3	6	0	0	1	0	0	0	0	
ATP3.LB.BABPA.FIL.CLM1	94.2M	0.433	1	7	2	1	6	2	0	0	1	0	0	0	
ATP3.LB.BABPA.FIL.CLM2	100M	0.400	0	6	1	0	6	0	0	0	1	0	0	0	
ATP3.LB.BABPA.FIL.ACUM.XTRACT.L19	207M	0.400	0	6	4	0	6	2	0	0	1	0	0	0	
ATP3.LB.BABPA.FIL.CLM4	101M	0.400	1	6	1	1	6	0	0	0	1	0	0	0	
ATP3.LB.BABPA.FIL.PELIG1.SEQ.L20	289M	0.367	1	5	3	2	6	2	1	3	1	0	0	0	
GSA2.ZZ.M5002.BIL.BILLS01	255M	0.333	0	5	9	0	5	7	1	3	1	0	1	1	
GSA3.OP.SMFD.M.BKP.SMF.G0001V00	21.4M	0.333	0	5	2	0	5	2	0	0	0	0	0	0	
ATP3.LB.BABPA.FIL.ER.HISTORY.L18	399M	0.300	1	5	3	1	4	3	0	2	1	0	0	0	
GSA4.LB.V9999.FIL.LB0BVAC	76.5M	0.267	0	4	2	0	4	0	0	3	8	0	0	0	
GSA4.LB.B9310.FIL.LB0BHST	392M	0.267	0	5	4	0	4	0	1	5	4	0	0	0	
GSA4.CY.B4113.FIL.ADJBILL	2.19M	0.233	0	4	0	0	3	0	0	1	1	0	0	0	
GSA3.OP.SMFD.M.BKP.SMF.G0002V00	22.6M	0.233	0	3	2	0	4	2	0	0	0	0	0	0	
GSA2.ZZ.M5024.FIL.BILLS.G0036V00	836K	0.200	0	3	0	1	3	0	0	0	1	0	0	0	
GSA4.LB.V9150.FIL.LB0BCHK	1.77M	0.200	1	3	0	1	3	0	0	5	2	0	0	0	
GSA2.FH.R0102.FIL.FEE	130M	0.200	0	3	0	1	3	0	1	1	2	0	0	0	
ATP3.LB.BABPA.FIL.VAC.CHECK.HISTY.L02	7.56M	0.200	0	4	0	0	3	0	0	0	1	0	0	0	
ATP3.LB.BABPA.FIL.MEMB.MSTR.L15	22.7M	0.167	1	2	1	1	3	1	0	0	1	0	0	0	
GSA5.LB.A2092.FIL.LB1APEN	102M	0.167	2	4	4	2	2	0	1	3	8	0	0	0	
GSA4.LB.B9215.FIL.ACTGERN	14.7M	0.167	0	4	0	0	2	0	0	3	0	0	0	0	
GSA2.ZZ.R0996.FIL.IC9PROC	1.14M	0.167	0	1	0	1	4	0	0	0	1	0	0	0	
GSA2.ZZ.M5024.FIL.BILLS.G0033V00	928K	0.167	0	2	0	1	3	0	0	1	0	0	0	0	
GSA2.ZZ.M5024.FIL.BILLS.G0034V00	836K	0.167	0	2	0	1	3	0	0	1	0	0	0	0	
GSA2.ZZ.M5024.FIL.BILLS.G0035V00	836K	0.167	0	2	0	1	3	0	0	1	0	0	0	0	
GSA4.AI.B080B.FIL.GENACTG.G0056V00	7.06M	0.133	1	2	0	1	2	0	0	1	0	0	0	0	
GSA4.LB.B9107.FIL.XREFILL	2.90M	0.133	1	2	0	2	2	0	1	1	0	0	0	0	
GSA5.AN.P2001.FIL.FED1099.G0016V00	3.42M	0.133	0	1	0	1	3	0	0	1	0	0	0	0	
GSA7.FN.K1010.BKP.FNEMSTB.G0023V00	4.92M	0.133	0	2	0	0	2	0	0	1	0	0	0	0	
GSA5.ZZ.P0403.FIL.MTDCHG.G0607V00	3.90M	0.133	0	2	0	0	2	0	0	1	0	0	0	0	

Figure 82. REPORT-17 PRIMARY DATASET ACTIVITY REPORT

The following data is presented:

- Dataset Name
- Size
- Movements Per Day
- Migration
 - Past 7 Days
 - Past 30 Days
 - Previous 30 Days
- Recall
 - Past 7 Days

- Past 30 Days
- Previous 30 Days
- Backup
 - Past 7 Days
 - Past 30 Days
 - Previous 30 Days
- Recovery
 - Past 7 Days
 - Past 30 Days
 - Previous 30 Days.

Report-18 DFHSM ERROR DETAIL REPORT

The DFHSM Error Detail Report lists all the datasets during the reporting period that failed DFHSM processing for one reason or another. The datasets are listed by DFHSM error and reason code.

The type of errors which require investigation include unsupported dataset errors: the dataset may have been created and never opened leaving an unknown DSORG, catalog locate errors (probably a dataset that has been uncataloged but not deleted), or any other error which you do not believe should occur. It is probably worth your time to investigate any such error the first time you produce these reports.

```
HSM OPTIMIZER 5.6                                DFHSM ERROR DETAIL REPORT                                PAGE 58
REPORT: 18 FORMAT: 05                            02/10/02 - 02/12/02                                REPORT TIME: 12:14 DATE: 2/13/02
FUNCTION: DAILY BACKUP                          RETURN CODE: 19                                REASON CODE: 00
ARC1319I DATASET IN USE BY ANOTHER USER OR JOB, BACKUP REJECTED

DATASET NAME          FROM          TO          USER ID      DATE      TIME
GSA1.OP.ZDISP.FIL.DISPAUDT.G0708V00          SMS505          **HSM***    02/12/02    2:15:49
GSA5.XI.P5035.FIL.XIICHKF                    SMS505          **HSM***    02/12/02    2:08:06
GSA9.ZZ.CICSX.FIL.DFHMPA                     SMS503          **HSM***    02/12/02    2:15:03
SPLFY.TRACE                                   SMS513          **HSM***    02/12/02    1:25:59
SYSX.VCSS.PROD.CKPT                           SYS001          **HSM***    02/10/02    21:30:10
SYSX.VCSS.TEST.CKPT                          SYS002          **HSM***    02/10/02    21:30:15
TOTAL ERRORS: 6
TOTAL DATASETS: 6
```

Figure 83. REPORT-18 DFHSM ERROR DETAIL REPORT

The report contains the following information:

- Heading Information
 - DFHSM Function
 - Function Return Code
 - Function Reason Code
 - DFHSM Error Message
- Dataset Name
- From Volume
- To volume
- User ID
- Date
- Time

Report-19 DFHSM ERROR SUMMARY REPORT

The DFHSM Error Summary Report lists the total number of errors and the number of datasets that DFHSM could not process for one reason or another. The report is summarized by DFHSM error and reason code.

The types of errors which require investigation include unsupported dataset errors: the dataset may have been created and never opened leaving an unknown DSORG, catalog locate errors (probably a dataset that has been uncataloged but not deleted), or any other error which you do not believe should occur. It is probably worth your time to investigate any such error the first time you produce these reports.

HSM OPTIMIZER 5.6		DFHSM ERROR SUMMARY REPORT				PAGE 73
REPORT: 19 FORMAT: 07		02/10/02 - 02/12/02				REPORT TIME: 12:14 DATE: 2/13/02
FUNCTION	RETURN CODE	REASON CODE	ERROR COUNT	DATASET COUNT	MESSAGE	
MIGRATE FROM PRIMARY TO ML1	19	01	15	1	ARC1219I DATASET IN USE BY ANOTHER USER OR JOB, MIGRATION REJECTED	
TOTAL			15	1		
MIGRATE FROM PRIMARY TO ML2	06	00	35	3	ARC1206I DUPLICATE DATA SET NAME IN DFHSM DATA BASE	
	19	05	11	8	ARC1219I DATASET IN USE BY ANOTHER USER OR JOB, MIGRATION REJECTED	
	19	08	1	1	ARC1219I DATASET IN USE BY ANOTHER USER OR JOB, MIGRATION REJECTED	
	58	08	46	5	ARC1258I MIGRATION FAILED FOR DATA SET	
	68	910	1	1	NO MESSAGE FOR THIS CONDITION	
TOTAL			94	18		
RECALL FROM ML2 TO PRIMARY	02	00	3	2	ARC1102I DATA SET IS NOT MIGRATED/BACKED UP	
TOTAL			3	2		
DELETE MIGRATED DATASET	02	00	12	3	ARC1202I CATALOG LOCATE ERROR DURING MIGRATION	
TOTAL			12	3		
DAILY BACKUP	17	00	1	1	ARC1317I I/O ERROR READING PDS DIRECTORY DURING BACKUP	
	19	00	6	6	ARC1319I DATASET IN USE BY ANOTHER USER OR JOB, BACKUP REJECTED	
	19	12	2	2	ARC1319I DATASET IN USE BY ANOTHER USER OR JOB, BACKUP REJECTED	
	68	799	1	1	NO MESSAGE FOR THIS CONDITION	
	68	910	2	2	NO MESSAGE FOR THIS CONDITION	
	70	13	22	22	ARC1370I AN ERROR OCCURRED WHILE DFHSM WAS PROCESSING AN SMS MANAGED DATA SET	
TOTAL	00	00	1	1	NO MESSAGE FOR THIS CONDITION	
TOTAL			35	35		
RECYCLE BACKUP VOLUME	16	00	1	1	NO MESSAGE FOR THIS CONDITION	
	31	00	1	1	NO MESSAGE FOR THIS CONDITION	
	69	00	2	2	NO MESSAGE FOR THIS CONDITION	
	00	00	2	2	NO MESSAGE FOR THIS CONDITION	
TOTAL			6	6		
RECYCLE MIGRATION VOLUME	31	00	2	2	NO MESSAGE FOR THIS CONDITION	
	69	00	1	1	NO MESSAGE FOR THIS CONDITION	
	00	00	2	2	NO MESSAGE FOR THIS CONDITION	
TOTAL			5	5		
VOLUME DUMP	08	00	1	1	NO MESSAGE FOR THIS CONDITION	
	16	00	2	1	NO MESSAGE FOR THIS CONDITION	
TOTAL			3	2		

Figure 84. REPORT-19 DFHSM ERROR SUMMARY REPORT

The report contains the following information:

- The DFHSM Function being performed.
- The Return Code
- The Reason Code
- An Error Count
- Number of Datasets having the error
- The DFHSM Error Message

Report-20 ACTIVITY SUMMARY

The Activity Summary report shows the summary activity for DFHSM processing for the last 24 hours **and** for the report period selected by the Beginning Date for Reports and the Ending Date for Reports.

HSM OPTIMIZER 5.6		ACTIVITY SUMMARY				REPORT TIME: 16:10 DATE: 3/18/02			
REPORT: 20 FORMAT: 09		02/01/02 - 03/31/02							
		LAST 24		DATA HOURS		REPORT PERIOD			
		03/15/02 19:29	03/16/02 19:29			02/01/02 00:00	03/31/02 23:59		
		TOTAL	ERROR	ERROR	ELAPSED	TOTAL	ERROR	ERROR	ELAPSED
		COUNT	COUNT	PERCENT	TIME	COUNT	COUNT	PERCENT	TIME
MIGRATE									
PRIMARY - ML1	3	0	0	0:00:18	1,395	117	8	2:38:29	
PRIMARY - ML2	36	1	3	0:42:48	15,558	1,424	9	106:14:56	
ML1 - ML2	0	0	0	0:00:00	895	0	0	6:38:41	
TOTAL	39	1	3	0:43:06	17,848	1,541	9	115:32:06	
RECALL									
ML1 - PRIMARY	0	0	0	0:00:00	199	8	4	1:06:12	
ML2 - PRIMARY	3	0	0	0:07:59	1,579	41	3	93:14:38	
TOTAL	3	0	0	0:07:59	1,778	49	3	94:20:50	
BACKUP									
DAILY	1,071	49	5	10:00:40	44,617	1,068	2	686:52:28	
SPILL	0	0	0	0:00:00	0	0	0	0:00:00	
TOTAL	1,071	49	5	10:00:40	44,617	1,068	2	686:52:28	
DELETE									
PRIMARY	0	0	0	0:00:00	0	0	0	0:00:00	
MIGRATED	275	0	0	2:02:12	15,198	3,275	22	21:50:41	
TOTAL	275	0	0	2:02:12	15,198	3,275	22	21:50:41	
RECYCLE									
MIGRATE VOLUME	0	0	0	0:00:00	8,355	8	0	37:24:19	
BACKUP VOLUME	0	0	0	0:00:00	9,981	23	0	34:03:31	
TOTAL	0	0	0	0:00:00	18,336	31	0	71:27:49	
RECOVER	0	0	0	0:00:00	25	8	32	0:59:08	
DUMP	0	0	0	0:00:00	68	11	16	21:00:03	
RESTORE	0	0	0	0:00:00	0	0	0	0:00:00	

Figure 85. REPORT-20 ACTIVITY SUMMARY

The report contains the following data:

- DFHSM Function
- Last 24 House
 - Total Count
 - Error Count
 - Error Percent
 - Elapsed Time
- Reporting Period
 - Total Count
 - Error Count
 - Error Percent
 - Elapsed Time

Report-21 MIGRATED DATASET SUMMARY

This report lists all migration activity by days aged. It shows summary information for all datasets migrated to ML1 storage, and datasets migrated to ML2 storage.

HSM OPTIMIZER 5.6				MIGRATED DATASET SUMMARY			REPORT TIME: 9:02 DATE: 2/14/02	
REPORT: 21 FORMAT: 10				02/11/02 - 02/13/02			PAGE 2	
---- MIGRATION LEVEL 1 ----				---- MIGRATION LEVEL 2 ----				
DAYS	DATASETS	AVERAGE SIZE	TOTAL SIZE	DATASETS	AVERAGE SIZE	TOTAL SIZE		
1	2	3.32M	6.63M	758	11.4M	8.48G		
2	0	0.00K	0.00K	497	6.95M	3.37G		
3	0	0.00K	0.00K	379	3.57M	1.32G		
4	0	0.00K	0.00K	139	5.43M	754M		
5	0	0.00K	0.00K	90	22.2M	1.96G		
6	0	0.00K	0.00K	223	8.20M	1.79G		
7	0	0.00K	0.00K	137	10.7M	1.43G		
8	0	0.00K	0.00K	231	12.4M	2.81G		
9	0	0.00K	0.00K	202	13.3M	2.63G		
10	0	0.00K	0.00K	112	4.51M	504M		
15	6	2.72M	16.3M	3,203	3.29M	10.2G		
20	0	0.00K	0.00K	1,614	4.84M	7.64G		
25	0	0.00K	0.00K	689	6.46M	4.34G		
30	0	0.00K	0.00K	872	7.82M	6.66G		
40	0	0.00K	0.00K	1,029	9.60M	9.65G		
50	0	0.00K	0.00K	893	12.9M	11.2G		
60	0	0.00K	0.00K	1,172	6.29M	7.20G		
70	0	0.00K	0.00K	790	7.12M	5.49G		
80	0	0.00K	0.00K	742	10.2M	7.40G		
90	0	0.00K	0.00K	481	6.31M	2.96G		
100	0	0.00K	0.00K	679	8.77M	5.82G		
125	0	0.00K	0.00K	1,586	7.56M	11.7G		
150	0	0.00K	0.00K	1,896	6.81M	12.6G		
175	0	0.00K	0.00K	1,255	8.68M	10.6G		
200	0	0.00K	0.00K	1,714	6.13M	10.2G		
250	0	0.00K	0.00K	2,768	7.70M	20.8G		
300	0	0.00K	0.00K	2,612	6.42M	16.3G		
350	0	0.00K	0.00K	2,367	7.20M	16.6G		
400	0	0.00K	0.00K	3,039	6.01M	17.8G		
450	0	0.00K	0.00K	2,030	6.06M	12.0G		
500	0	0.00K	0.00K	2,709	6.32M	16.7G		
600	0	0.00K	0.00K	3,658	4.64M	16.5G		
700	0	0.00K	0.00K	4,806	5.52M	25.9G		
800	3	6.53M	19.5M	4,527	4.11M	18.1G		
900	0	0.00K	0.00K	4,238	4.34M	17.9G		
1000	0	0.00K	0.00K	5,391	4.62M	24.3G		
1250	0	0.00K	0.00K	9,512	3.62M	33.6G		
1500	0	0.00K	0.00K	8,025	2.96M	23.1G		
1750	0	0.00K	0.00K	6,722	2.43M	15.9G		
2000	0	0.00K	0.00K	4,025	1.93M	7.57G		
OVER	0	0.00K	0.00K	4,882	3.11M	14.8G		
TOTAL	11	3.86M	42.5M	92,694	4.94M	447G		

Figure 86. REPORT-21 MIGRATED DATASET SUMMARY

The report contains:

- Age in Days
- Migration Level 1 Information
 - Number of Datasets
 - Average Dataset Size
 - Total Size of Datasets Migrated
- Migration Level 2 Information
 - Number of Datasets
 - Average Dataset Size
 - Total Size of Datasets Migrated

Report-22 DATASET BACKUP SUMMARY

This report presents a summary, by dataset age, of DFHSM backup activity for the reporting period. Since you may specify that multiple versions of a backed up dataset be retained, summaries are presented for versions 1 through 4, and for retained versions of 5 or greater.

If you have many datasets that have been retained for more than a year or two, you might want to investigate how many of these datasets are still valid. Deleting a dataset does not automatically delete a DFHSM backup copy of the dataset.

HSM OPTIMIZER 5.6		DATASET BACKUP SUMMARY										PAGE 3
REPORT: 22 FORMAT: 11		02/11/02 - 02/13/02										REPORT TIME: 9:02 DATE: 2/14/02
DAYS	TOTAL		VER 1		VER 2		VER 3		VER 4		VER 5+	
	DATASETS	SIZE	DATASETS	SIZE	DATASETS	SIZE	DATASETS	SIZE	DATASETS	SIZE	DATASETS	SIZE
1	1,636	18.3G	1,454	14.7G	182	3.59G	0	0.00K	0	0.00K	0	0.00K
2	1,168	9.81G	933	5.85G	101	1.45G	134	2.51G	0	0.00K	0	0.00K
3	0	0.00K	0	0.00K	0	0.00K	0	0.00K	0	0.00K	0	0.00K
4	8	970M	8	970M	0	0.00K	0	0.00K	0	0.00K	0	0.00K
5	1,743	10.5G	1,391	7.38G	150	441M	91	1.37G	111	1.42G	0	0.00K
6	1,519	8.32G	1,157	4.84G	114	485M	52	278M	96	1.66G	100	1.08G
7	1,240	7.09G	966	4.59G	65	971M	76	140M	39	174M	94	1.24G
8	750	7.51G	558	4.88G	57	155M	49	257M	20	202M	66	2.03G
9	2,040	7.62G	1,649	4.22G	211	2.08G	42	50.7M	92	34.4M	46	1.23G
10	0	0.00K	0	0.00K	0	0.00K	0	0.00K	0	0.00K	0	0.00K
15	4,982	30.2G	4,275	20.5G	194	4.77G	299	3.13G	70	363M	144	1.49G
20	2,746	16.0G	2,358	9.88G	146	1.09G	113	2.23G	78	1.80G	51	1.06G
25	5,890	25.0G	3,156	10.3G	651	4.22G	640	3.04G	823	4.89G	620	2.56G
30	5,206	26.3G	4,441	16.0G	167	2.53G	133	2.59G	144	2.02G	321	3.17G
40	5,900	33.0G	5,032	18.6G	377	2.90G	155	2.71G	114	2.77G	222	6.02G
50	7,392	26.7G	5,955	20.3G	1,226	4.52G	78	1.07G	58	390M	75	364M
60	5,081	18.9G	4,278	14.8G	636	3.23G	74	596M	64	138M	29	180M
70	6,181	23.5G	5,372	16.4G	230	1.15G	390	3.18G	105	1.40G	84	1.43G
80	6,713	23.4G	5,186	16.6G	138	966M	1,179	4.31G	98	811M	112	819M
90	4,353	13.2G	3,756	10.5G	31	260M	488	1.56G	51	307M	27	579M
100	5,776	18.1G	5,278	15.4G	82	260M	107	961M	248	1.18G	61	422M
125	13,611	48.9G	11,527	35.8G	178	2.44G	104	855M	1,627	6.83G	175	2.99G
150	15,363	46.7G	13,242	36.9G	178	1.19G	101	1.53G	117	1.34G	1,725	5.75G
175	12,660	35.1G	12,185	31.3G	179	2.46G	80	194M	58	452M	158	714M
200	12,754	35.9G	12,363	29.7G	174	1.94G	87	1.41G	62	927M	68	1.95G
250	25,284	74.9G	24,504	64.8G	319	4.60G	221	2.90G	122	1.43G	118	1.15G
700	50,807	90.4G	50,464	87.9G	275	2.10G	33	201M	6	23.1M	29	267M
800	45,449	71.9G	45,156	71.0G	180	651M	61	86.1M	8	4.61M	44	115M
900	9,234	38.0G	9,168	37.3G	54	534M	3	168M	2	496K	7	5.56M
1000	7,318	32.6G	7,251	32.5G	46	33.6M	6	8.51M	5	8.14M	10	12.8M
1250	13,543	49.8G	13,447	49.2G	54	544M	12	18.9M	5	583K	25	61.7M
1500	8,612	27.6G	8,490	24.9G	40	536M	16	28.2M	18	31.7M	48	2.12G
1750	7,883	18.6G	7,452	18.0G	44	82.7M	13	8.83M	16	1.16M	358	587M
2000	5,496	12.0G	5,460	11.9G	17	164M	2	1.18M	3	2.23M	14	12.0M
OVER												
TOTAL	489,375	1.30T	461,410	1.11T	9,853	71.5G	6,211	44.2G	5,258	37.4G	6,643	47.2G

Figure 87. REPORT-22 DATASET BACKUP SUMMARY

The report contains the following data:

- Dataset Age in Days
- Total
 - Datasets
 - Size
- Backup Version 1 through Version 4
 - Datasets
 - Size
- Backup Versions 5 and above
 - Datasets
 - Size

Report-23 PRIMARY VOLUMES

This report presents a list of all DFHSM primary volumes. The list is presented in serial number sequence.

HSM OPTIMIZER 5.6				PRIMARY VOLUMES										REPORT TIME: 9:02		DATE: 2/14/02		PAGE 19				
REPORT: 23 FORMAT: 12				02/11/02 - 02/13/02																		
VOLSER	DEVICE	MGT	AGE	THRSHLD	LOW	HI	SMS	RCL	AUTO	PROCESS	DATE	TIME	CLASS	ORGANIZATION	COUNT	ALLOC	USED	PCT	ABLE	PCT	FREE	
SYS001	3390	MIG	0	0	100		NO	YES		MIGRATE	00/00/00	0:00		DSORG=PS	7	36.7M	36.7M	100	0.00K	0		
										BACKUP	02/10/02	21:28		DSORG=PSU	2	14.0M	14.0M	100	0.00K	0		
										DUMP	02/03/02	11:08	OFFSITE	DSORG=PO	3	14.4M	7.90M	55	5.49M	38		
										DUMP	02/03/02	11:08	ONSITE	DSORG=VS	7	17.4M	17.4M	100	0.00K	0		
										TOTAL					19	82.7M	76.1M	92	5.49M	7	732M	
SYS002	3390	MIG	0	0	100		NO	YES		MIGRATE	00/00/00	0:00		DSORG=PS	4	17.0M	17.0M	100	0.00K	0		
										BACKUP	02/10/02	21:30		DSORG=PSU	1	1.01M	1.01M	100	0.00K	0		
										DUMP	02/10/02	11:03	OFFSITE	TOTAL	5	18.0M	18.0M	100	0.00K	0	790M	
										DUMP	02/10/02	11:03	ONSITE									
SYS003	3390	MIG	0	0	100		NO	YES		MIGRATE	00/00/00	0:00		DSORG=PS	4	35.2M	35.2M	100	0.00K	0		
										BACKUP	02/10/02	21:30		DSORG=PSU	1	12.6M	12.6M	100	0.00K	0		
										DUMP	02/10/02	11:04	OFFSITE	DSORG=DA	1	861K	861K	100	0.00K	0		
										DUMP	02/10/02	11:04	ONSITE	TOTAL	6	48.6M	48.6M	100	0.00K	0	760M	
TMM000	3390	MIG	0	1	1	YES	NO			MIGRATE	07/10/97	4:45		TOTAL	0	0.00K	0.00K	0	0.00K	0	0.00K	
										BACKUP	07/10/97	0:40										
										DUMP	00/00/00	00:00										
TMM001	3390	MIG	0	1	1	YES	NO			MIGRATE	07/10/97	4:45		TOTAL	0	0.00K	0.00K	0	0.00K	0	0.00K	
										BACKUP	07/10/97	0:40										
										DUMP	00/00/00	00:00										
TMM002	3390	MIG	0	1	1	YES	NO			MIGRATE	07/10/97	4:45		TOTAL	0	0.00K	0.00K	0	0.00K	0	0.00K	
										BACKUP	07/10/97	0:41										
										DUMP	00/00/00	00:00										
TMM003	3390	MIG	0	1	1	YES	NO			MIGRATE	07/10/97	4:45		TOTAL	0	0.00K	0.00K	0	0.00K	0	0.00K	
										BACKUP	07/10/97	0:41										
										DUMP	00/00/00	00:00										
TMM004	3390	MIG	0	1	1	YES	NO			MIGRATE	07/10/97	4:45		TOTAL	0	0.00K	0.00K	0	0.00K	0	0.00K	
										BACKUP	07/10/97	0:41										
										DUMP	00/00/00	00:00										
TMM005	3390	MIG	0	1	1	YES	NO			MIGRATE	07/10/97	4:45		TOTAL	0	0.00K	0.00K	0	0.00K	0	0.00K	
										BACKUP	07/10/97	0:41										
										DUMP	00/00/00	00:00										
TOTAL														DSORG=PS	6669	25.2G	20.9G	83	1.21G	5		
														DSORG=PSU	6	31.0M	31.0M	100	0.00K	0		
														DSORG=PO	4927	44.6G	31.1G	70	6.98G	16		
														DSORG=DA	8	40.5M	40.5M	100	0.00K	0		
														DSORG=VS	3205	44.7G	44.7G	100	0.00K	0		
														TOTAL	14815	114G	96.9G	85	8.19G	7	56.0G	

Figure 88. REPORT-23 PRIMARY VOLUMES

The data presented is:

- The DASD volume serial number.
- The DASD device type.
- The management technique used by DFHSM on the volume.
- The age in days that DFHSM uses to determine migration eligibility for datasets on the volume.
- The low and high thresholds used by DFHSM to determine when to do migration on the volume, and how many datasets to remove from the volume. These values are expressed as percentages of total data capacity of the volume.
- A list of each process done on the volume, followed by the date and time the process was last completed within the reporting period. For volume dumps, there is an indication if the dump process resulted in an onsite or offsite dump.
- The organization column lists the various dataset organizations processed by DFHSM. If the organization is ???, these datasets can not be processed by DFHSM.
- The number of datasets of each organization on the volume.
- The specified allocation size for each category of dataset organization on the volume. This is followed by the amount of the allocation actually used, the percentage actually used, the amount of storage that could be released and the percentage releasable.
- The total free storage on the volume.

If a volume contains DSORGs indicated as ???, you should investigate the volume for datasets that have been allocated but never opened.

You might also consider using the DFHSM compress option for PDS datasets, if such datasets indicate a high percentage of free space. Many PDS datasets are allocated with a large primary allocation so that they will not run out of room. If you use the DFHSM compress option, you can use a primary allocation that will hold the normal contents of the dataset, and specify a secondary allocation to handle expansion. During DFHSM migration volume processing, these datasets will be migrated, then recalled with a new allocation contain the contents within a primary allocation. This will free any unused space within the dataset. The secondary allocation will still handle expansion (to keep from fragmenting the file, consider using a secondary allocation at least as large as the primary allocation).

If you use the compress option, be sure that you set the number of extents appropriately. MVS systems consider 5 extents to be a primary allocation. Therefore, set the number of extents to at least 6.

Report-24 PRIMARY VOLUME DETAIL

This report presents a list of all DFHSM primary volumes. The list is presented in volume serial number sequence.

HSM OPTIMIZER 5.6		PRIMARY VOLUME DETAIL										PAGE 313			
REPORT: 24 FORMAT: 13		02/11/02 - 02/13/02										REPORT TIME: 9:02 DATE: 2/14/02			
VOLSER	DATASET NAME	CREATE	EXPIRE	REF DATE	TYPE	ALLOC	USED	RLSE	XT	ORG	RCFM	LRECL	BLKSZ	SMS	SC
SMS585	GSA5.AI.L0000.DBS.AILLPTH.DATA	02/14/02	02/22/12	02/14/02	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.AI.L0000.DBS.AILLPTH.INDEX	02/14/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.CM.P0000.DBS.CMLPGTR.DATA	02/13/02	02/21/12	02/13/02	CYL	5.05M	5.05M	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.CM.P0000.DBS.CMLPGTR.INDEX	02/13/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.IC.A0000.DBS.IC1ANDX.DATA	02/09/02	02/17/12	02/13/02	TRK	344K	344K	0.00K	5	VS	U		0	4096	Y PR
SMS585	GSA5.IC.A0000.DBS.IC1ANDX.INDEX	02/09/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.IC.P0000.DBS.IC1PPEN.DATA	02/09/02	02/17/12	02/14/02	TRK	1.01M	1.01M	0.00K	2	VS	U		0	4096	Y PR
SMS585	GSA5.IC.P0000.DBS.IC1PPEN.INDEX	02/09/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.OU.A0000.DBS.OU1ANDX.DATA	02/09/02	02/17/12	02/14/02	TRK	287K	287K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.OU.A0000.DBS.OU1ANDX.INDEX	02/09/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.PF.P0000.DBS.PF1PNME.DATA	02/14/02	02/22/12	02/14/02	TRK	114K	114K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.PF.P0000.DBS.PF1PNME.INDEX	02/14/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.PJ.P0000.DBS.PJ1PATR.DATA	02/13/02	02/21/12	02/13/02	CYL	6.73M	6.73M	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.PJ.P0000.DBS.PJ1PATR.INDEX	02/13/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.XL.P0000.DBS.XL1PNDX.INDEX	02/14/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.ZZ.P0000.DBS.PENPTY.PDATA	02/13/02	02/21/12	02/13/02	TRK	172K	172K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA5.ZZ.P0000.DBS.PENPTY.PINDEX	02/13/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA7.OM.K0000.DBS.OMEEAIX.DATA	02/05/02	02/13/12	02/14/02	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA7.OM.K0000.DBS.OMEEAIX.INDEX	02/05/02	00/00/00	00/00/00	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA7.PI.K0000.DBS.PIEEMST.DATA	01/25/02	02/02/12	02/14/02	CYL	225M	225M	0.00K	7	VS	U		0	4096	Y PR
SMS585	GSA7.PI.K0000.DBS.PIEEMST.INDEX	01/25/02	00/00/00	00/00/00	TRK	344K	344K	0.00K	3	VS	U		0	4096	Y PR
SMS585	GSA7.PP.K0000.DBS.PPEEMST.DATA	02/13/02	02/21/12	02/14/02	CYL	62.2M	62.2M	0.00K	18	VS	U		0	4096	Y PR
SMS585	GSA7.PP.K0000.DBS.PPEEMST.INDEX	02/13/02	00/00/00	00/00/00	TRK	114K	114K	0.00K	2	VS	U		0	4096	Y PR
SMS585	SYS1.VTOCIX.SMS585	07/16/01	00/00/00	00/00/00	TRK	2.47M	2.47M	0.00K	1	PS	F	2048	2048	Y	
SMS585	SYS1.VVDS.VSMS585	12/13/01	00/00/00	00/00/00	TRK	574K	574K	0.00K	1	VS			0	4096	Y PR

Figure 89. REPORT-24 PRIMARY VOLUME DETAIL

The data presented is:

- The volume serial number.
- The dataset name.
- The creation, expiration, and last referenced date of the dataset.
- The type of physical allocation on the device.
- The number of bytes allocated, and the number of bytes actually used.
- The number of bytes that could be released.
- The number of extents used by the file.
- The organization, record format, logical record size, and block size of the dataset.
- Whether or not DFSMS is used to manage the dataset.
- The security on the dataset. Note that all VSAM files will indicate a security of PR. Any non VSAM files with a security indicate that OS password protection applies to the file. This might indicate an error if your installation uses an external security manager.

Possible values:

RF RACF discrete profile

PR OS password to read

PW OS password to write

Report-25 PRIMARY VOLUME DATE REFERENCE DETAIL

This report presents a list of all datasets on primary volumes in reference date order. The date starts with the oldest reference date to most current. It presents the same data as the Primary Volume Detail report.

If this report indicates a fair number of large datasets on primary datasets with fairly old reference dates, there might be a problem with your ARCCMDxx specifications. Datasets not frequently referenced should not be occupying primary volume space. Such space could probably be put to better use by your installation.

The report format will be the same as the Primary Volume Detail Report.

HSM OPTIMIZER 5.6		PRIMARY VOLUME DATE REFERENCE DETAIL										PAGE 273			
REPORT: 25 FORMAT: 13		02/11/02 - 02/13/02										REPORT TIME: 9:39 DATE: 2/14/02			
VOLSER	DATASET NAME	CREATE	EXPIRE	REF DATE	TYPE	ALLOC	USED	RLSE	XT	ORG	RCFM	LRECL	BLKSZ	SMS	SC
SMS585	GSA4.PI.B0000.DBS.PI0BNRL.DATA	01/20/02	01/28/12	02/14/02	CYL	4.20M	4.20M	0.00K	2	VS	U		0	4096	Y PR
SMS585	GSA4.PL.B0000.DBS.PLOBILL.DATA	01/29/02	02/06/12	02/14/02	TRK	8.63M	8.63M	0.00K	18	VS	U		0	4096	Y PR
SMS585	GSA4.PU.B0000.DBS.PU0BNRL.DATA	01/20/02	01/28/12	02/14/02	TRK	918K	918K	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA4.SE.B0000.DBS.SEOBHST.DATA	01/29/02	02/06/12	02/14/02	CYL	63.0M	63.0M	0.00K	1	VS	U		0	4096	Y PR
SMS585	GSA4.SP.B0000.DBS.SPOBERM.DATA	02/03/02	02/11/12	02/14/02	CYL	861K	861K	0.00K	1	VS	U		0	4096	Y PR
SMS900	CATALOG.MASTER	09/07/95	00/00/00	02/14/02	CYL	2.52M	2.52M	0.00K	1	VS	U		0	4096	Y PR
SMS900	CATALOG.SYSTEMS	09/01/95	09/09/05	02/14/02	CYL	11.7M	11.7M	0.00K	14	VS	U		0	4096	Y PR
SMS900	CATALOG.TEST	09/01/95	09/09/05	02/14/02	CYL	6.73M	6.73M	0.00K	4	VS	U		0	4096	Y PR
SMS900	SYSX.ATPA.ISPMLIB	11/25/97	00/00/00	02/14/02	CYL	861K	172K	0.00K	1	PO	FB		80	6160	Y
SMS900	SYSX.ATPA.ISPSLIB	11/25/97	00/00/00	02/14/02	CYL	861K	114K	0.00K	1	PO	FB		80	6160	Y
SMS900	SYSX.ATPA.PLILINK	06/05/97	00/00/00	02/14/02	TRK	1.07M	1.07M	0.00K	1	PO	U		0	32760	Y
SMS900	SYSX.NETVIEW.CNM02.DSILIST	06/08/00	00/00/00	02/14/02	CYL	861K	0.00K	0.00K	1	PO	FB		80	6160	Y
SMS900	SYSX.NETVIEW.CNM02.DSIPRF	06/08/00	00/00/00	02/14/02	CYL	861K	0.00K	0.00K	1	PO	FB		80	3920	Y
SMS900	SYSX.NETVIEW.CNM02.SEZLNLU	06/08/00	00/00/00	02/14/02	CYL	861K	0.00K	0.00K	1	PO	FB		80	3920	Y
SMS900	SYSX.OSEM.VER55.TEST.PARMLIB	11/16/00	00/00/00	02/14/02	BLK	2.07M	0.00K	0.00K	2	PO	FB		80	32720	Y
SMS900	SYSX.OSEM.VER56.ISPCLIB	01/31/02	00/00/00	02/14/02	CYL	10.0M	0.00K	0.00K	3	PO	FB		80	23440	Y
SMS900	SYSX.OSEM.VER56.ISPPLIB	01/31/02	00/00/00	02/14/02	CYL	4.20M	0.00K	0.00K	1	PO	FB		80	23440	Y
SMS900	SYSX.OSEM.VER56.TEST.IPL.REPORT	01/31/02	00/00/00	02/14/02	BLK	516K	516K	0.00K	9	PS	VBA		125	8192	Y
SMS900	SYSX.OSEM.VER56.TEST.PARMLIB	01/31/02	00/00/00	02/14/02	BLK	459K	0.00K	0.00K	1	PO	FB		80	32720	Y
SMS900	SYS1.SMARTSMS.LOADLIB	07/22/99	00/00/00	02/14/02	TRK	4.20M	4.09M	114K	5	PO	U		0	32760	Y
SMS901	CATALOG.PROD	09/01/95	00/00/00	02/14/02	CYL	62.2M	62.2M	0.00K	27	VS	U		0	4096	Y PR
SMS901	SYSX.OPER.JCL	08/28/98	00/00/00	02/14/02	CYL	29.4M	24.7M	4.20M	1	PO	FB		80	6160	Y
SYS000	SMS.ATPA.ACDS.DATA	12/14/92	12/31/99	02/14/02	TRK	1.01M	1.01M	0.00K	1	VS	U		0	4096	N PR
SYS000	SMS.ATPA.COMMDS.DATA	01/08/92	12/31/99	02/14/02	TRK	57.4K	57.4K	0.00K	1	VS	U		0	4096	N PR
SYS000	SMS.ATPA.SCDS.DATA	01/08/92	12/31/99	02/14/02	TRK	1.01M	1.01M	0.00K	1	VS	U		0	4096	N PR
SYS000	SYS1.ATPA.PROCLIB	09/08/95	00/00/00	02/14/02	CYL	6.73M	6.39M	0.00K	1	PO	FB		80	23440	N
SYS000	SYS1.ATPA.PROD.PROCLIB	09/07/95	00/00/00	02/14/02	CYL	2.52M	114K	1.68M	1	PO	FB		80	27920	N
SYS000	SYS1.ATPA.TEST.PROCLIB	09/07/95	00/00/00	02/14/02	CYL	2.52M	114K	1.68M	1	PO	FB		80	27920	N
SYS000	SYS1.BROADCAST	09/08/95	00/00/00	02/14/02	CYL	4.20M	4.20M	0.00K	1	DA	F		129	129	N
SYS000	SYS1.JESPARMS	08/13/87	00/00/00	02/14/02	CYL	2.52M	1.46M	861K	1	PO	FB		80	3120	N
SYS000	SYS1.PARMLIB	09/08/95	00/00/00	02/14/02	CYL	1.68M	1.68M	0.00K	1	PO	FB		80	27920	N
SYS000	SYS1.PROD.HASPINDX	02/12/96	00/00/00	02/14/02	CYL	861K	861K	0.00K	1	PS	F		4096	4096	N
SYS000	SYS1.PROD.LOGREC	09/08/95	00/00/00	02/14/02	CYL	1.68M	1.68M	0.00K	1	PSU	U		0	1944	N
SYS000	SYS1.TEST.HASPINDX	02/12/96	00/00/00	02/14/02	CYL	861K	861K	0.00K	1	PS	F		4096	4096	N
SYS000	SYS1.UADS	09/08/95	00/00/00	02/14/02	CYL	861K	57.4K	0.00K	1	PO	FB		172	1720	N
SYS001	SYSX.VCSS.PROD.JSA	09/28/95	00/00/00	02/14/02	BLK	746K	746K	0.00K	1	PS	U		0	6200	N
SYS001	SYSX.VCSS.TEST.JSA	09/29/95	00/00/00	02/14/02	BLK	746K	746K	0.00K	1	PS	U		0	6200	N
SYS001	SYS1.RACF	09/21/95	00/00/00	02/14/02	CYL	12.6M	12.6M	0.00K	1	PSU	F		4096	4096	N
SYS001	SYS1.V23.PLILINK	12/13/93	00/00/00	02/14/02	CYL	5.89M	5.55M	0.00K	1	PO	U		0	32760	N

Figure 90. REPORT-25 PRIMARY VOLUME DATE REFERENCE DETAIL

The data presented is:

- The volume serial number.
- The dataset name.
- The creation, expiration, and last referenced date of the dataset.
- The type of physical allocation on the device.
- The number of bytes allocated, and the number of bytes actually used.
- The number of bytes that could be released.
- The number of extents used by the file.
- The organization, record format, logical record size, and block size of the dataset.
- Whether or not DFSMS is used to manage the dataset.

- The security on the dataset. Note that all VSAM files will indicate a security of PR. Any non VSAM files with a security indicate that OS password protection applies to the file. This might indicate an error if your installation uses an external security manager.

Possible values:

RF RACF discrete profile

PR OS password to read

PW OS password to write

Report-26 MIGRATED DATASET DETAIL (MCDS Sorted by DSN)

This report presents a list of all datasets migrated in dataset name order. The information presented is contained in the DFHSM Migration Control Data Set.

HSM OPTIMIZER 5.6		MIGRATED DATASET DETAIL - DSN SEQUENCE						REPORT TIME: 9:39 DATE: 2/14/02			PAGE 466
REPORT: 26 FORMAT: 14		02/11/02 - 02/13/02									
----- DATASET NAME -----		PRIM	MIGRATION		LVL	CREATE	EXPIRE	DS	SMS CLASSES	DATA	
VOLUME	DATE	TIME	DATE	DATE	DATE	DATE	DATE	MGMT	STOR		
GSA7.PP.K1010.BKP.PPEEMSTA.G0100V00	SMS504	02/11/02	15:05:13	2	02/07/02	00/00/00	43.9M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1010.BKP.PPEEMSTB.G0100V00	SMS502	01/05/02	20:11:15	2	01/03/02	00/00/00	43.8M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1010.BKP.PPEEMSTB.G0101V00	SMS572	02/13/02	14:21:00	2	02/05/02	00/00/00	45.0M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1010.BKP.PPEEMSTB.G0102V00	SMS505	02/13/02	13:08:39	2	02/07/02	00/00/00	45.0M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K155T.FIL.ZZKFINDH	SMS503	01/15/02	16:12:14	2	01/03/02	00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K155T.FIL.ZZKFINDL	SMS572	01/31/02	6:05:18	2	01/03/02	00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1550.BKP.PPEEMST.G0192V00	SMS566	01/15/02	20:17:32	2	01/03/02	00/00/00	44.3M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1550.BKP.PPEEMST.G0193V00	SMS503	01/05/02	19:11:03	2	01/03/02	00/00/00	44.3M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1550.BKP.PPEEMST.G0194V00	SMS506	01/12/02	5:00:45	2	01/11/02	00/00/00	44.5M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1550.BKP.PPEEMST.G0195V00	SMS518	01/14/02	19:08:24	2	01/11/02	00/00/00	44.5M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1550.BKP.PPEEMST.G0196V00	SMS508	02/14/02	4:13:36	2	02/13/02	00/00/00	43.9M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1570.BKP.PPEEMST.G0038V00	SMS566	01/15/02	20:17:05	2	01/07/02	00/00/00	44.5M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1570.FIL.PPEEMST.G0036V00	SMS558	01/30/02	17:11:43	2	07/05/01	00/00/00	0.84K	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1570.FIL.PPEEMST.G0039V00	SMS566	02/01/02	5:14:16	2	08/22/01	00/00/00	0.84K	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1570.FIL.PPEEMST.G0040V00	SMS563	01/30/02	19:18:56	2	10/29/01	00/00/00	0.84K	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K1570.FIL.PPEEMST.G0042V00	SMS504	01/28/02	19:34:42	2	11/07/01	00/00/00	0.84K	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K8520.FIL.MTDMAINT.G0455V00	SMS508	02/08/02	0:13:50	2	01/29/02	00/00/00	110K	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K8520.FIL.MTDMAINT.G0457V00	SMS508	02/11/02	16:08:16	2	01/31/02	00/00/00	110K	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K9915.BKP.PPEEMST	SMS507	02/14/02	3:16:11	2	02/13/02	00/00/00	44.1M	STD10YR	STANDARD	COMPSEQ	
GSA7.PP.K9999.BKP.PPNOTES	SMS558	01/30/02	17:18:40	2	12/07/01	00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K0758.FIL.BANKFAX	SMS508	02/08/02	0:15:28	2	01/30/02	00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K0900.BKP.SDEEMST.G0007V00	SMS558	01/30/02	4:36:39	2	01/02/02	00/00/00	1.23M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K0900.BKP.SDEEMST.G0008V00	SMS506	01/19/02	5:02:55	2	01/02/02	00/00/00	1.23M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K0900.BKP.SDEEMST.G0009V00	SMS518	01/19/02	22:16:19	2	01/16/02	00/00/00	1.23M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K1000.BKP.SDPAYRL.G0007V00	SMS506	01/02/02	23:10:33	2	01/02/02	00/00/00	1.18M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K1000.BKP.SDPAYRL.G0008V00	SMS505	02/05/02	5:05:51	2	01/16/02	00/00/00	1.18M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K1010.BKP.SDANNUAL.G0010V00	SMS505	01/21/02	5:00:27	2	01/02/02	00/00/00	1.23M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K1010.BKP.SDANNUAL.G0011V00	SMS501	01/28/02	4:54:48	2	01/16/02	00/00/00	1.23M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K1010.BKP.SDEEMSTA.G0009V00	SMS507	01/14/02	5:12:30	2	01/02/02	00/00/00	1.28M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K1010.BKP.SDEEMSTA.G0010V00	SMS518	01/19/02	22:16:10	2	01/16/02	00/00/00	1.28M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K1010.BKP.SDEEMSTB.G0010V00	SMS563	01/29/02	23:07:26	2	01/02/02	00/00/00	1.23M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K1010.BKP.SDEEMSTB.G0011V00	SMS558	02/09/02	23:01:22	2	01/16/02	00/00/00	1.23M	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K2010.FIL.BKP1099.G0001V00	SMS506	02/05/02	18:05:50	2	01/30/02	00/00/00	55.1K	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K2010.FIL.FED1099.G0001V00	SMS508	02/08/02	0:17:09	2	01/30/02	00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA7.SD.K8520.FIL.MTDMAINT.G0461V00	SMS518	02/12/02	21:08:58	2	02/02/02	00/00/00	0.84K	STD10YR	STANDARD	COMPSEQ	

Figure 91. REPORT-26 MIGRATED DATASET DETAIL (MCDS Sorted by DSN)

The dataset presented is:

- Dataset Name
- Primary Volume
 - Disk volume where the dataset resided before migration.
- Migration Date
- Migration Time
- Migration Level
- Creation Date
- Expiration Date
- Dataset Size
- SMS Management Class
- SMS Storage Class
- SMS Data Class

Report-27 BACKED UP DATASET DETAIL (BCDS Sorted by DSN With XREF)

This report presents a list of datasets which have been backed up in dataset name order with a cross-reference showing the current location of the dataset.

HSM OPTIMIZER 5.6		DATASET BACKUP DETAIL - DSN SEQUENCE										PAGE 186
REPORT: 27 FORMAT: 15		02/11/02 - 02/13/02										2/14/02
----- DATASET NAME -----		PRIM	CUR	-----	BACKUP	-----	CREATE	EXPIRE	DS	-----	SMS CLASSES	-----
		VOLUME	LOC	DATE	TIME	DATE	DATE	DATE	SIZE	MGMT	STOR	DATA
SYS1R.SMPTLOGA		SMS522	D	02/08/02	2:33:21	10/20/00	00/00/00	1.19M	SMP		STANDARD	
SYS1R.SORTLIB		SMS524	D	01/18/02	2:08:10	10/20/00	00/00/00	0.63K	SMP		STANDARD	
SYS1R.SORTLIB		SMS522	D	01/18/02	2:08:51	10/20/00	00/00/00	223K	SMP		STANDARD	
SYS1R.SORTLPA		SMS520	D	02/06/02	3:02:03	10/20/00	00/00/00	789K	SMP		STANDARD	
SYS1R.SVCLIB		SMS522	D	01/18/02	2:10:10	10/20/00	00/00/00	8.18K	SMP		STANDARD	
SYS1R.SWITCH.LINKLIB		SMS525	D	01/09/02	2:28:49	08/24/01	00/00/00	330K	SMP		STANDARD	
SYS1R.SWITCH.SOURCE		SMS525	D	01/26/02	2:42:11	08/24/01	00/00/00	334K	SMP		STANDARD	
SYS1R.SWITCH.SOURCE		SMS524	D	01/09/02	2:28:23	08/24/01	00/00/00	527K	SMP		STANDARD	
SYS1R.SWITCH.SOURCE		SMS524	D	01/26/02	2:36:33	08/24/01	00/00/00	533K	SMP		STANDARD	
SYS1R.TCPPARMS		SMS523	D	01/18/02	2:20:52	10/20/00	00/00/00	173K	SMP		STANDARD	
SYS1R.TMON.INSTLIB		SMS528	D	02/08/02	3:24:22	12/07/00	00/00/00	902K	SMP		STANDARD	
SYS1R.TMON.LMKLOAD		SMS525	D	02/08/02	2:51:16	12/14/00	00/00/00	3.00M	SMP		STANDARD	
SYS1R.TMON.LMKXSAMP		SMS527	D	02/08/02	2:59:59	12/14/00	00/00/00	3.61M	SMP		STANDARD	
SYS1R.TMON.TCEINST		SMS523	D	02/08/02	2:35:28	12/14/00	00/00/00	13.1K	SMP		STANDARD	
SYS1R.TMON.TCELOAD		SMS522	D	02/09/02	2:38:50	12/14/00	00/00/00	4.37M	SMP		STANDARD	
SYS1R.TMON.TCESAMP		SMS520	D	02/09/02	2:35:47	12/14/00	00/00/00	2.26M	SMP		STANDARD	
SYS1R.TMON.USEREXIT.LOAD		SMS524	D	02/08/02	2:32:10	12/18/00	00/00/00	3.89K	SMP		STANDARD	
SYS1R.VPS.LINKLIB		SMS521	D	01/12/02	2:06:18	11/13/00	00/00/00	3.74M	SMP		STANDARD	PDS
SYS1R.VTAMLIB		SMS524	D	02/08/02	2:35:52	10/20/00	00/00/00	9.63M	SMP		STANDARD	
SYS1R.VTAMLST		SMS529	D	01/19/02	2:59:37	10/20/00	00/00/00	4.45K	SMP		STANDARD	
SYS1S.SHASLINK		SMS529	D	02/09/02	2:43:44	11/01/01	00/00/00	1.78M	SMP		STANDARD	
SYS1S.SHASMAC		SMS525	D	01/12/02	2:08:59	08/23/01	00/00/00	20.6M	SMP		STANDARD	PDSE
USFTUN1.FTP4.CO.B9102.FIL.RDY.ELIG		SMS558	D	02/14/02	2:58:17	02/13/02	00/00/00	13.1K	TSO		STANDARD	COMPSEQ
USFTUN1.FTP4.CO.B9102.FIL.RDY.MELIG		SMS558	X	01/12/02	1:52:14		00/00/00	13.1K	TSO		STANDARD	COMPSEQ
USFTUN1.FTP4.GE.B0620.FIL.RDY.HIPAA		SMS506	X	01/09/02	1:26:56		00/00/00	13.1K	TSO		STANDARD	COMPSEQ
USFTUN1.FTP4.GE.B9102.FIL.RDY.ELIG		SMS566	X	01/09/02	2:15:44		00/00/00	13.1K	TSO		STANDARD	COMPSEQ
USFTUN1.FTP4.GE.B9202.FIL.RDY.MBRS		SMS559	X	01/09/02	2:11:37		00/00/00	13.1K	TSO		STANDARD	COMPSEQ
USFTUN1.GSA5.OT.P0308.FIL.OT1PHLD		SMS506	X	02/05/02	1:37:31		00/00/00	13.1K	TSO		STANDARD	COMPSEQ
USFTUN1.GSA5.OT.P0308.FIL.OT1PHLD		SMS508	X	01/01/02	1:57:23		00/00/00	1.14M	TSO		STANDARD	COMPSEQ
USFTUN1.GSA5.OT.P0308.FIL.OT1PHLD		SMS559	X	01/09/02	2:11:28		00/00/00	1.14M	TSO		STANDARD	COMPSEQ
USFTUN1.GSA5.OT.P0308.FIL.OT1PHLD		SMS566	M	02/05/02	2:53:01	02/02/02	00/00/00	1.14M	TSO		STANDARD	COMPSEQ
TOTAL DATASETS:		38,587		TOTAL SIZE:	216G							

Figure 92. REPORT-27 BACKED UP DATASET DETAIL (BCDS Sorted by DSN With XREF)

The data presented is:

- Dataset Name
- Primary Volume

Disk volume where the dataset resided before it was either backed up or migrated.

- Current Location

This is the cross-reference information. This information is collected by reading the catalog for each dataset. The codes have the following meanings:

compact,tsize=3.

- D** Dataset resides on disk.
- M** Dataset has been migrated.
- X** Dataset has been deleted.

- Backup Date
- Backup Time
- Creation Date
- Expiration Date
- Dataset Size
- SMS Management Class

- SMS Storage Class
- SMS Data Class

Report-28 MIGRATED DATASET DETAIL (MCDS Sorted by Date)

This report presents a list of all datasets which have been migrated. The information presented is from the Migration Control Data Set sorted by date migrated.

HSM OPTIMIZER 5.6 REPORT: 28 FORMAT: 14		MIGRATED DATASET DETAIL - DATE SEQUENCE 02/11/02 - 02/13/02						REPORT TIME: 9:39	DATE: 2/14/02	PAGE 383
DATASET NAME	PRIM	DATE	TIME	LVL	CREATE DATE	EXPIRE DATE	DS	SMS CLASSES	DATA	
GSA4.OI.B1033.FIL.PBHELIG	SMS566	02/14/02	5:26:39	2	01/31/02	00/00/00	438K	STD10YR	STANDARD COMPSEQ	
GSA5.PH.P5030.BKP.PHLPTR.G0335V00	SMS563	02/14/02	5:27:49	2	02/01/02	00/00/00	40.5M	STD10YR	STANDARD COMPSEQ	
SPJRT.VER55.EXPR.QUERY	SMS572	02/14/02	5:28:06	2	01/31/02	00/00/00	242K	TSO	STANDARD COMPSEQ	
GSA4.XI.B4120.FIL.AFP.LABELS	SMS572	02/14/02	5:28:09	2	01/31/02	00/00/00	34.9K	STD10YR	STANDARD COMPSEQ	
GSA4.UA.B4165.FIL.UAIBERM	SMS572	02/14/02	5:28:12	2	01/31/02	00/00/00	55.5K	STD10YR	STANDARD COMPSEQ	
GSA4.PH.B4175.FIL.PH0BERM.G0017V00	SMS572	02/14/02	5:28:16	2	01/31/02	00/00/00	548K	STD10YR	STANDARD COMPSEQ	
GSA4.AI.B0801.FIL.ACTGRPT	SMS572	02/14/02	5:28:19	2	01/30/02	00/00/00	493K	STD10YR	STANDARD COMPSEQ	
GSA4.LC.B0801.FIL.ACTGRPT	SMS572	02/14/02	5:28:23	2	01/31/02	00/00/00	384K	STD10YR	STANDARD COMPSEQ	
GSA4.SY.B1015.FIL.AFP.LABELS	SMS572	02/14/02	5:28:26	2	01/31/02	00/00/00	38.4K	STD10YR	STANDARD COMPSEQ	
SPHGR.OSEM.VER55.GEN2.LSPPLIB	SMS572	02/14/02	5:28:31	2	08/06/01	00/00/00	3.28M	TSO	STANDARD PDSE	
GSA5.CK.P5035.BKP.CK1PPEN.G0109V00	SMS572	02/14/02	5:28:34	2	01/31/02	00/00/00	329K	STD10YR	STANDARD COMPSEQ	
GSA4.WI.B080B.FIL.GENACTG.G0053V00	SMS572	02/14/02	5:28:38	2	01/31/02	00/00/00	712K	STD10YR	STANDARD COMPSEQ	
SPHGR.OSEM.VER56.QATESTS	SMS572	02/14/02	5:28:43	2	10/01/01	00/00/00	1.45M	TSO	STANDARD PDSE	
GSA4.CD.B0810.FIL.L101YTD.G0089V00	SMS572	02/14/02	5:28:46	2	01/31/02	00/00/00	0.84K	STD10YR	STANDARD COMPSEQ	
GSA4.PT.B4125.FIL.UNPBILL	SMS572	02/14/02	5:28:49	2	01/31/02	00/00/00	329K	STD10YR	STANDARD COMPSEQ	
GSA5.CD.A5130.FIL.CDIADET	SMS572	02/14/02	5:28:55	2	02/02/02	00/00/00	5.19M	STD10YR	STANDARD COMPSEQ	
GSA5.CY.P0101.FIL.CYPNOTE.G0032V00	SMS572	02/14/02	5:28:58	2	02/02/02	00/00/00	428K	STD10YR	STANDARD COMPSEQ	
GSA2.ZZ.D8509.BKP.VCHRN.G2703V00	SMS572	02/14/02	5:29:02	2	02/02/02	00/00/00	931K	STD10YR	STANDARD COMPSEQ	
SPKAS.OSEM.VER55.MANUAL.G0002V00	SMS572	02/14/02	5:29:12	2	01/18/01	00/00/00	2.49M	TSO	STANDARD PDS	
GSA5.CT.Q0700.FIL.MSTBK	SMS572	02/14/02	5:29:15	2	02/02/02	00/00/00	438K	STD10YR	STANDARD COMPSEQ	
GSA3.Z0.I1010.FIL.SELJRN.L.G2179V00	SMS572	02/14/02	5:29:19	2	02/02/02	00/00/00	1.23M	STD10YR	STANDARD COMPSEQ	
GSA5.CK.P5030.BKP.CK1PPTR.G0604V00	SMS572	02/14/02	5:29:22	2	02/02/02	00/00/00	1.34M	STD10YR	STANDARD COMPSEQ	
GSA4.BE.B9120.BKP.BE0BMBR.G0051V00	SMS572	02/14/02	5:29:26	2	02/02/02	00/00/00	2.26M	STD10YR	STANDARD COMPSEQ	
GSA4.BS.B9120.BKP.BS0BMBR.G0052V00	SMS572	02/14/02	5:29:38	2	02/02/02	00/00/00	12.6M	STD10YR	STANDARD COMPSEQ	
GSA4.TY.B9120.BKP.TY0BMBR.G0051V00	SMS572	02/14/02	5:29:42	2	02/02/02	00/00/00	2.67M	STD10YR	STANDARD COMPSEQ	
GSA2.ZZ.C1002.FIL.MEDTRANS.G3382V00	SMS572	02/14/02	5:29:47	2	02/02/02	00/00/00	3.42M	STD10YR	STANDARD COMPSEQ	
GSA2.AI.M7090.FIL.B0EHM.FLAT	SMS572	02/14/02	5:29:50	2	02/03/02	00/00/00	1.00M	STD10YR	STANDARD COMPSEQ	
GSA2.ZZ.M3509.FIL.LOGCHK.G3394V00	SMS572	02/14/02	5:29:54	2	02/02/02	00/00/00	3.16M	STD10YR	STANDARD COMPSEQ	
GSA2.NB.M7090.FIL.B0EHM.G0079V00	SMS572	02/14/02	5:29:57	2	02/03/02	00/00/00	43.5K	STD10YR	STANDARD COMPSEQ	
GSA2.ZZ.C3502.FIL.PORTLAND.G1054V00	SMS572	02/14/02	5:29:59	2	02/03/02	00/00/00	301K	STD10YR	STANDARD COMPSEQ	
GSA2.BS.M7090.FIL.B0EHM.G0077V00	SMS572	02/14/02	5:30:04	2	02/03/02	00/00/00	1.00M	STD10YR	STANDARD COMPSEQ	
GSA2.CI.M7090.FIL.B0EHM.G0077V00	SMS572	02/14/02	5:30:06	2	02/03/02	00/00/00	256K	STD10YR	STANDARD COMPSEQ	
MIGRATION LEVEL 1:	TOTAL DATASETS:	8	TOTAL SIZE:	22.9M						
MIGRATION LEVEL 2:	TOTAL DATASETS:	10,608	TOTAL SIZE:	69.0G						

Figure 93. REPORT-28 MIGRATED DATASET DETAIL (MCDS Sorted by Date)

The data presented is:

- Dataset Name
- Primary Volume
Volume where dataset resided before migration.
- Migration Date
- Migration Time
- Migration Level
- Creation Date
- Expiration Date
- Dataset Size
- SMS Management Class
- SMS Storage Class
- SMS Data Class

Report-29 BACKED UP DATASET DETAIL (BCDS Sorted by Date With XREF)

This report presents a list of all datasets backed up in backup date order. The information presented is from the Backup Control Data Set.

HSM OPTIMIZER 5.6		DATASET BACKUP DETAIL - DATE				SEQUENCE	REPORT TIME: 9:39	DATE: 2/14/02	PAGE 98				
REPORT: 29 FORMAT: 15		02/11/02 - 02/13/02											
----- DATASET NAME -----		PRIM	CUR	BACKUP	DATE	TIME	CREATE DATE	EXPIRE DATE	DS	MGMT	SMS CLASSES	STOR	DATA
GSA4.OI.B0305.FIL.MTDCHG.G2677V00	SMS558	X			02/14/02	3:10:28		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA4.XF.B0305.FIL.MTDCHG.G2542V00	SMS558	X			02/14/02	3:10:30		00/00/00	165K	STD10YR	STANDARD	COMPSEQ	
GSA4.AW.B0403.FIL.MTDCHG.G4069V00	SMS558	X			02/14/02	3:10:33		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA4.BE.B0403.FIL.MTDCHG.G1397V00	SMS558	X			02/14/02	3:10:34		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA4.GE.B0403.FIL.MTDCHG.G0873V00	SMS558	X			02/14/02	3:10:36		00/00/00	876K	STD10YR	STANDARD	COMPSEQ	
GSA4.BS.B0410.FIL.MTDCHG.G1245V00	SMS558	X			02/14/02	3:10:38		00/00/00	274K	STD10YR	STANDARD	COMPSEQ	
GSA4.CY.B0410.FIL.MTDCHG.G1280V00	SMS558	X			02/14/02	3:10:40		00/00/00	110K	STD10YR	STANDARD	COMPSEQ	
GSA4.PT.B0410.FIL.MTDCHG.G1206V00	SMS558	X			02/14/02	3:10:41		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA4.SE.B0410.FIL.MTDCHG.G1250V00	SMS558	X			02/14/02	3:10:43		00/00/00	110K	STD10YR	STANDARD	COMPSEQ	
GSA4.WI.B0410.FIL.MTDCHG.G1262V00	SMS558	X			02/14/02	3:10:44		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA4.ZZ.CICST.DBS.DFHGCD	SMS558	D			02/14/02	3:10:46	10/03/01	00/00/00	2.12M	SMP	STANDARD	VSAM	
GSA5.AI.P5035.BKP.A11PPTR.G0163V00	SMS518	M			02/14/02	3:11:31	02/13/02	00/00/00	122M	STD10YR	STANDARD	COMPSEQ	
GSA2.ZZ.D8509.FIL.JCHECK.TOPC	SMS508	X			02/14/02	3:11:47		00/00/00	1.87M	STD10YR	STANDARD	COMPSEQ	
GSA2.ZZ.M3509.FIL.LOGCHK.G3402V00	SMS508	X			02/14/02	3:11:49		00/00/00	7.59M	STD10YR	STANDARD	COMPSEQ	
GSA2.ZZ.M0406.FIL.FRERECON.G0208V00	SMS508	X			02/14/02	3:11:55		00/00/00	13.1K	STD10YR	STANDARD	COMPSEQ	
GSA2.ZZ.M0406.FIL.BOARECON.G2234V00	SMS508	X			02/14/02	3:11:57		00/00/00	0.84K	STD10YR	STANDARD	COMPSEQ	
GSA5.XL.P5035.FIL.XLVOID.G0151V00	SMS508	X			02/14/02	3:11:58		00/00/00	54.2K	STD10YR	STANDARD	COMPSEQ	
GSA5.KC.P5035.FIL.KCSSN	SMS508	X			02/14/02	3:12:01		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA5.PP.P5035.FIL.PPSSN	SMS508	X			02/14/02	3:12:02		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA5.PU.P5035.FIL.PUSSN	SMS508	X			02/14/02	3:12:03		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA5.TC.P5035.FIL.TCSSN	SMS508	X			02/14/02	3:12:05		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA5.UA.P5035.FIL.UASSN	SMS508	X			02/14/02	3:12:06		00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ	
GSA2.ZZ.M2296.FIL.FAX.OUT	SMS508	X			02/14/02	3:12:08		00/00/00	36.1K	STD10YR	STANDARD	COMPSEQ	
GSA4.PL.B1300.FIL.PLOMBER	SMS508	M			02/14/02	3:12:09	02/14/02	00/00/00	32.8M	STD10YR	STANDARD	COMPSEQ	
GSA1.Z0.I1199.FIL.UPSLABEL	SMS508	X			02/14/02	3:12:31		00/00/00	43.6K	STD10YR	STANDARD	COMPSEQ	
GSAE.ZZ.P0000.DBS.PENPTBL	SMS508	D			02/14/02	3:12:48	12/21/01	12/22/02	783K	TEST	STANDARD	COMPKSDS	
SPUR6.ISPF.EXPR.ISPPROF	SMS518	X			02/14/02	3:17:57		00/00/00	137K	TSO	STANDARD	PDSE	
SPKAS.OSEM.VER55.CNTL.G0002V00	SMS518	X			02/14/02	3:18:01		00/00/00	842K	TSO	STANDARD	PDS	
GSAE.LB.A0000.DBS.LB1APEN	SMS518	D			02/14/02	3:18:09	02/12/02	02/13/03	446M	TEST	STANDARD	COMPKSDS	
GSA9.ZZ.CICS2.FIL.DPHDMPB	SMS518	X			02/14/02	3:32:06		00/00/00	32.9K	SMP	STANDARD	COMPSEQ	
GSA4.ZZ.CICST.FIL.DPHDMPB	SMS518	X			02/14/02	3:32:08		00/00/00	32.9K	SMP	STANDARD	COMPSEQ	
TOTAL DATASETS:		38,587	TOTAL SIZE:		216G								

Figure 94. REPORT-29 BACKED UP DATASET DETAIL (BCDS Sorted by Date With XREF)

The data presented is:

- Dataset Name
- Primary Volume

Disk volume where the dataset resided before it was either backed up or migrated.

- Current Location

This is the cross-reference information. This information is collected by reading the catalog for each dataset. The codes have the following meanings:

compact,tsize=3.

- D** Dataset resides on disk.
- M** Dataset has been migrated.
- X** Dataset has been deleted.

- Backup Date
- Backup Time
- Creation Date
- Expiration Date
- Dataset Size
- SMS Management Class

- SMS Storage Class
- SMS Data Class

Report-30 BACKED UP DATASET DETAIL (BCDS Sorted by DSN No XREF)

This report presents a list of all datasets backed up in dataset name order. The information presented is from the Backup Control Data Set.

HSM OPTIMIZER 5.6		BCDS DETAIL - DSN SEQUENCE				REPORT TIME: 9:39		DATE: 2/14/02		PAGE 813
REPORT: 30 FORMAT: 16		02/11/02 - 02/13/02								
----- DATASET NAME -----		GEN	VOLUME	DATE	TIME	EXP	DS	SMS CLASSES	STOR	DATA
			PRIM	BACKUP		DATE	SIZE	MGMT		
SYS1R.SMPTLOGA		27	SMS522	02/08/02	2:33:21	00/00/00	1.19M	SMP	STANDARD	
SYS1R.SORTLIB		11	SMS524	01/18/02	2:08:10	00/00/00	0.63K	SMP	STANDARD	
SYS1R.SORTLIB		11	SMS522	01/18/02	2:08:51	00/00/00	223K	SMP	STANDARD	
SYS1R.SORTLPA		12	SMS520	02/06/02	3:02:03	00/00/00	789K	SMP	STANDARD	
SYS1R.SVCLIB		11	SMS522	01/18/02	2:10:10	00/00/00	8.18K	SMP	STANDARD	
SYS1R.SWITCH.LINKLIB		9	SMS525	01/09/02	2:28:49	00/00/00	330K	SMP	STANDARD	
SYS1R.SWITCH.SOURCE		10	SMS525	01/26/02	2:42:11	00/00/00	334K	SMP	STANDARD	
SYS1R.SWITCH.SOURCE		9	SMS524	01/09/02	2:28:23	00/00/00	527K	SMP	STANDARD	
SYS1R.SWITCH.SOURCE		10	SMS524	01/26/02	2:36:33	00/00/00	533K	SMP	STANDARD	
SYS1R.TCPPARMS		11	SMS523	01/18/02	2:20:52	00/00/00	173K	SMP	STANDARD	
SYS1R.TMON.INSTLIB		14	SMS528	02/08/02	3:24:22	00/00/00	902K	SMP	STANDARD	
SYS1R.TMON.LMKLOAD		11	SMS525	02/08/02	2:51:16	00/00/00	3.00M	SMP	STANDARD	
SYS1R.TMON.LMKSAMP		12	SMS527	02/08/02	2:59:59	00/00/00	3.61M	SMP	STANDARD	
SYS1R.TMON.TCEINST		11	SMS523	02/08/02	2:35:28	00/00/00	13.1K	SMP	STANDARD	
SYS1R.TMON.TCELOAD		13	SMS522	02/09/02	2:38:50	00/00/00	4.37M	SMP	STANDARD	
SYS1R.TMON.TCESAMP		13	SMS520	02/09/02	2:35:47	00/00/00	2.26M	SMP	STANDARD	
SYS1R.TMON.USEREXIT.LOAD		10	SMS524	02/08/02	2:32:10	00/00/00	3.89K	SMP	STANDARD	
SYS1R.VPS.LINKLIB		14	SMS521	01/12/02	2:06:18	00/00/00	3.74M	SMP	STANDARD	PDS
SYS1R.VTAMLIB		12	SMS524	02/08/02	2:35:52	00/00/00	9.63M	SMP	STANDARD	
SYS1R.VTAMLST		11	SMS529	01/19/02	2:59:37	00/00/00	4.45K	SMP	STANDARD	
SYS1S.SHASLINK		4	SMS529	02/09/02	2:43:44	00/00/00	1.78M	SMP	STANDARD	
SYS1S.SHASMAC		5	SMS525	01/12/02	2:08:59	00/00/00	20.6M	SMP	STANDARD	PDSE
USFTUN1.FTP4.CO.B9102.FIL.RDY.ELIG		14	SMS558	02/14/02	2:58:17	00/00/00	13.1K	TSO	STANDARD	COMPSEQ
USFTUN1.FTP4.CO.B9102.FIL.RDY.MELIG		1	SMS558	01/12/02	1:52:14	00/00/00	13.1K	TSO	STANDARD	COMPSEQ
USFTUN1.FTP4.GE.B0620.FIL.RDY.HIPAA		4	SMS506	01/09/02	1:26:56	00/00/00	13.1K	TSO	STANDARD	COMPSEQ
USFTUN1.FTP4.GE.B9102.FIL.RDY.ELIG		4	SMS566	01/09/02	2:15:44	00/00/00	13.1K	TSO	STANDARD	COMPSEQ
USFTUN1.FTP4.GE.B9202.FIL.RDY.MBRS		8	SMS559	01/09/02	2:11:37	00/00/00	13.1K	TSO	STANDARD	COMPSEQ
USFTUN1.FTP4.GE.B9202.FIL.RDY.MBRS		9	SMS506	02/05/02	1:37:31	00/00/00	13.1K	TSO	STANDARD	COMPSEQ
USFTUN1.GSA5.OT.P0308.FIL.OT1PHLD		12	SMS508	01/01/02	1:57:23	00/00/00	1.14M	TSO	STANDARD	COMPSEQ
USFTUN1.GSA5.OT.P0308.FIL.OT1PHLD		13	SMS559	01/09/02	2:11:28	00/00/00	1.14M	TSO	STANDARD	COMPSEQ
USFTUN1.GSA5.OT.P0308.FIL.OT1PHLD		14	SMS566	02/05/02	2:53:01	00/00/00	1.14M	TSO	STANDARD	COMPSEQ
TOTAL DATASETS:		38,587	TOTAL SIZE:		216G					

Figure 95. REPORT-30 BACKED UP DATASET DETAIL (BCDS Sorted by DSN No XREF)

The data presented is:

- Dataset Name
- Generation
 - Note:** This is the DFHSM generation number, not a generation data group level number.
- Primary Volume
 - Disk volume where the dataset resided before it was either backed up or migrated.
- Backup Date
- Backup Time
- Expiration Date
- Dataset Size
- SMS Management Class
- SMS Storage Class
- SMS Data Class

Report-31 BACKED UP DATASET DETAIL BY DATE

This report lists the datasets found in the BCDS in backup date sequence.

HSM OPTIMIZER 5.6		BCDS DETAIL - DATE SEQUENCE						PAGE 528			
REPORT: 31 FORMAT: 16		02/11/02 - 02/14/02						REPORT TIME: 9:39 DATE: 2/14/02			
----- DATASET NAME -----		GEN	PRIM	----- BACKUP -----		EXPIRE	DS	----- SMS CLASSES -----		DATA	
		VOLUME	DATE	TIME	DATE	SIZE	MGMT	STOR			
GSA4.OI.B0305.FIL.MTDCHG.G2677V00	1	SMS558	02/14/02	3:10:28	00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ		
GSA4.WI.B0410.FIL.MTDCHG.G1262V00	1	SMS558	02/14/02	3:10:44	00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ		
GSA4.ZZ.CICST.DBS.DFHGCD	392	SMS558	02/14/02	3:10:46	00/00/00	2.12M	SMP	STANDARD	VSAM		
GSA5.AI.P5035.BKP.A11PPTR.G0163V00	1	SMS518	02/14/02	3:11:31	00/00/00	122M	STD10YR	STANDARD	COMPSEQ		
GSA2.ZZ.D8509.FIL.JCHECK.TOPC	16655	SMS508	02/14/02	3:11:47	00/00/00	1.87M	STD10YR	STANDARD	COMPSEQ		
GSA2.ZZ.M3509.FIL.LOGCHK.G3402V00	1	SMS508	02/14/02	3:11:49	00/00/00	7.59M	STD10YR	STANDARD	COMPSEQ		
GSA5.TC.P5035.FIL.TCSSN	71	SMS508	02/14/02	3:12:05	00/00/00	55.5K	STD10YR	STANDARD	COMPSEQ		
GSA2.ZZ.M2296.FIL.FAX.OUT	216	SMS508	02/14/02	3:12:08	00/00/00	36.1K	STD10YR	STANDARD	COMPSEQ		
GSA1.Z0.I1199.FIL.UPSLABEL	16656	SMS508	02/14/02	3:12:31	00/00/00	43.6K	STD10YR	STANDARD	COMPSEQ		
GSAE.ZZ.P0000.DBS.PENPTBL	815	SMS508	02/14/02	3:12:48	12/22/02	783K	TEST	STANDARD	COMPKSDS		
SPUR6.ISPF.EXPR.ISPPROF	90	SMS518	02/14/02	3:17:57	00/00/00	137K	TSO	STANDARD	PDSE		
SPKAS.OSEM.VER55.CNTL.G0002V00	85	SMS518	02/14/02	3:18:01	00/00/00	842K	TSO	STANDARD	PDS		
GSAE.LB.A0000.DBS.LBIAPEN	21	SMS518	02/14/02	3:18:09	02/13/03	446M	TEST	STANDARD	COMPKSDS		
GSA9.ZZ.CICSZ.FIL.DFHDMPB	254	SMS518	02/14/02	3:32:06	00/00/00	32.9K	SMP	STANDARD	COMPSEQ		
GSA4.ZZ.CICST.FIL.DFHDMPB	266	SMS518	02/14/02	3:32:08	00/00/00	32.9K	SMP	STANDARD	COMPSEQ		
TOTAL DATASETS:		38,587	TOTAL SIZE:		216G						

Figure 96. REPORT-31 Backed Up Dataset Detail By Date

The data presented is:

- Dataset Name
- Generation
 - Note:** This is the DFHSM generation number, not a generation data group level number.
- Primary Volume
 - Disk volume where the dataset resided before it was either backed up or migrated.
- Backup Date
- Backup Time
- Expiration Date
- Dataset Size
- SMS Management Class
- SMS Storage Class
- SMS Data Class

HSM Optimizer Report Menu

DFHSM generates many statistics which are kept in SMF records and are not generally reported. Since tuning DFHSM can be critical to its successful operation, we have provided a series of reports which use these statistics, and will significantly reduce the tuning effort required for DFSMS, DFHSM, and the HSM Optimizer.

These reports will assist in setting and maintaining your ACS parameters in a DFSMS environment as well.

Reports are generated by selecting **4 HSM Reports** from the OS/EM Extended Functions menu. When you do so, a panel is displayed which presents you with three (3) options.

```
OS/EM ----- HSM OPTIMIZER REPORTS ----- Version 6.0
SELECTION ====>

                1  Produce HSM reports
                2  Collect SMF data for HSM Database
                3  Define/Allocate HSM OPTIMIZER Files
```

Figure 97. HSM Optimizer Reports Menu

Each of these paths is presented in the following sections:

- 1** Produce HSM Reports (see “Produce HSM Reports” on page 5-102)
- 2** Collect SMF Data (see “Collect SMF Data for HSM database” on page 5-104)
This option is used to load HSM data from a file containing the HSM SMF records into the HSM Report database. The database must already have been created by Option 3.
- 3** Define/Allocate HSM Optimizer Reports Files (see “Define/Allocate HSM Optimizer Files” on page 5-106)
This option is used to define a new HSM Optimizer Report database (either VSAM or QSAM); define the names of the HSM Migration Control Data Set (MCDS), the Backup Control Data Set (BCDS), and SMF record type being produced by DFHSM that is required for building the HSM database.

Each of these options results in a batch job being submitted which does the actual work. A panel allowing you to supply an appropriate JOB statement is presented just before the batch job is submitted.

Note: The JOBCARD information is stored in the users profile.

```

OS/EM ----- HSM OPTIMIZER REPORTS ----- Version 6.0
COMMAND ==>

                Submit Batch Job

    Verify JOB Card...

==> //OS$EMR  JOB OSEM, 'OPTIMIZER RPTS', NOTIFY=OSEMUSR,
==> //          CLASS=S, MSGCLASS=X
==> // *
==> // *
==> // *

    Verify SYSOUT Specification...

//SYSPRINT DD SYSOUT= *

Press PF3 (END) to submit job, or enter CANCEL to exit.

```

Figure 98. HSM Optimizer Reports - JCL

Field entry is as follows:

1. Verify JOB card

Enter or update the information for the JOB statement to be used for the batch job which will be submitted.

2. Verify SYSOUT Specification

Enter or update the SYSPRINT specification that will be used in the batch job which will be submitted.

Report 00 (which contains control card images), report processing messages, sort messages and other utility messages are directed to SYSPRINT. Reports 1 to 32 are written to dynamically allocated DD statements where the ddname is the name of the report.

Note: The print class used for reports 1 to 32 is taken from the SYSPRINT specification.

Produce HSM Reports

Once the Define/Allocate (see “Define/Allocate HSM Optimizer Files” on page 5-106) and the Collect SMF Data (see “Collect SMF Data for HSM database” on page 5-104) steps have been completed, you may request reports. Thirty-one (31) reports are produced in sixteen (16) basic formats.

- Report 0 is basically a cover report indicating which reports have been requested within a report run. It is not selectable.

Reports are requested by selecting **4, HSM Reports**, from the OS/EM Extended Functions panel. The HSM Optimizer Reports panel (see Figure 99) lets you set the beginning and ending reporting dates, the beginning and ending dates for the MCDS and BCDS reports as well as the data movement index needed for report-17.

The entries you make determine the reports that are generated.

```

OS/EM ----- HSM OPTIMIZER REPORTS ----- Version 6.0
COMMAND ==>                                         SCROLL ==> CSR

                Create Reports ==> NO      (YES/NO)

Optimizer Report Dates:  Begin: *M-1      End: *M      Use MM/DD/YY or
MCDS Report Dates:      Begin: *M-1      End: *M      *M or *M-x or
BCDS Report Dates:      Begin: *M-1      End: *M      *D or *D-x where x
                                         is 1 to 999

Dataset Movement Index for Report 17 ==> 0.100

SEL Selected   Report Description
-   -         01 Migration Detail      (Primary -> ML1)
-   -         02 Migration Delay Summary (Primary -> ML1)
-   -         03 Migration Age Summary  (Primary -> ML1)
-   -         04 Migration Detail      (ML1 -> ML2)
-   -         05 Migration Delay Summary (ML1 -> ML2)
-   -         06 Migration Age Summary  (ML1 -> ML2)
-   -         07 Migration Detail      (Primary -> ML2)
-   -         08 Migration Delay Summary (Primary -> ML2)
-   -         09 Migration Age Summary  (Primary -> ML2)
-   -         10 Recall Detail          (ML1 -> Primary)
-   -         11 Recall Delay Summary   (ML1 -> Primary)
-   -         12 Recall Age Summary     (ML1 -> Primary)
  
```

Figure 99. HSM Optimizer Reports - Select Reports

Field entry is as follows:

1. Beginning/Ending Report Dates

The Report Beginning/Ending dates can be specified as MM/DD/YY, or optionally by using HSM Optimizer Reports' Dynamic Date specification the user can allow the HSM Optimizer Reports to select the records included on the report based on the current run date and a 'DELTA' specified from the current date.

If the beginning Date for Reports is specified as '*M' and nothing is entered in the Ending Date for Reports then only records that match the current processing month will be included in the reports. Specifying '*M-1' in the Beginning Date for Reports includes all records from the month prior to the current processing date. Valid values are '*M' thru '*M-999' for both Beginning and Ending dates.

If the Beginning Date for Reports is specified as '*D-1' the reports will include all records from the Day prior to the current processing date. Valid values are '*D' thru '*D-999' for both Beginning and Ending Report Dates.

If the Report Beginning/Ending dates are specified as MM/DD/YY, the months, days, and years are coded as two digit numbers.

If neither a beginning nor ending date are specified, the report will contain only the last seven (7) days.

2. Dataset Movement Index for Report 17

By specifying a Dataset Movement Index, only datasets that exceed that value will be included in the report. See "Report-17 PRIMARY DATASET ACTIVITY REPORT" on page 5-80.

The bottom portion of the panel is scrollable. It lists the 31 available reports in numerical sequence. This information is saved in the OS/EM ISPTLIB library and so is available to anyone selecting reports.

There are two available fields in this section of the panel, **SEL** and **Selected**. The SEL field acts as a toggle, in other words, if the report has not been selected, placing an **S** in the SEL column will change the Selected field to **YES**. If the report has already been selected, placing an S in the SEL column will change the Selected field to blanks.

Note: The RPTRPT member provided in the OS/EM SAMPLIB provides sample JCL for the create HSM Optimizer Reports function and is to be used as an example to create any batch jobs that you may require.

Collect SMF Data for HSM database

The second step in report generation is to collect the appropriate SMF data. Three fields are required on the panel (see Figure 100): the HSM Database Retention Date, the HSM Report Database name and the SMF Input File Name.

```
OS/EM ----- HSM OPTIMIZER REPORTS ----- Version 6.0
COMMAND ==>

                Collect SMF Data for HSM Database

HSM Database Retention Date - *M-1

HSM Report Database => 'GSA3.OP.00000.DBS.HSM'
SMF Input File Name => 'GSA3.OP.SMFDM.BKP.SMF'

Press PF3 (END) to submit job, or enter CANCEL to exit.
```

Figure 100. HSM Optimizer Reports Collect SMF Data

Field entry is as follows:

1. Retention Report Dates

The Report Retention dates can be specified as MM/DD/YY, or optionally by using HSM Optimizer Reports' Dynamic Date specification the user can allow the HSM Optimizer Reports to retain the records included on the HSM Optimizer Reports database on the current run date and a 'DELTA' specified from the current date.

If the Retention is specified as '*M' then only records that match the current processing month will be retained in the HSM Optimizer Reports database. Specifying '*M-1' in the retention Date for HSM Optimizer Reports database will retain the current and prior months data. Valid values are '*M' thru '*M-999' for the Retention date.

If the Retention Date for is specified as '*D-1' the HSM Optimizer Reports database will retain the day prior to the current processing date. Valid values are '*D' thru '*D-999' for the retention date.

If the Report Retention date is specified as MM/DD/YY the months, days, and years are coded as two digit numbers.

Note: OS/EM recommends that the retention date be specified as at least '*M-2'. This retains the current month plus the two previous months on the HSM Optimizer Reports database. This is required for certain reports to function properly. i.e. Dataset Activity Report.

If a Retention Date is not specified, the database will contain all records.

2. HSM Report Database Name

Enter the name of the database created by "Define/Allocate HSM Optimizer Files" on page 5-106.

3. SMF Input File Name

The other required information is the name of the SMF file where your installation collects SMF data. This file must have a format produced by the IBM IFASMFDP program.

Note: The IFASMFDP member provided in the OS/EM SAMPLIB provides sample JCL for the dump SMF files function and is to be used as an example to create any batch jobs that you may require.

The end result of using this panel will be a batch job which will read the specified SMF file and populate the HSM Optimizer Reports database with the requested records. Each time you use the panel, more data is collected, up to the specified retention. For a QSAM database, the effective retention is the number of generations you specified when defining the HSM Optimizer Reports database. For a VSAM database, records are added and updated, as necessary, to keep the database within the desired retention period. This will mean that the database should be reorganized when a catalog listing shows an excessive number of CI and CA splits.

Note: The RPTCOLL member provided in the OS/EM SAMPLIB provides sample JCL for the collect SMF data function and is to be used as an example to create any batch jobs that you may require.

Define/Allocate HSM Optimizer Files

The HSM Optimizer files must be defined and allocated before any reports can be produced. The panel (see Figure 101) lets you specify these datasets.

```
OS/EM ----- HSM OPTIMIZER REPORTS ----- Version 6.0
COMMAND ==>
                Allocate/Define HSM OPTIMIZER Files
                NO - SUBMIT Job for Initialization
                V - HSM Database (V=VSAM Q=QSAM)      234 - HSM SMF Record Type
SMS505 - Volume to Place Database (Required for VSAM)
3390 - Unit Parameter for Database (3380/3390/3420/3480/3490)
                05 - Number of Generations for QSAM Database (Required for QSAM)
080000 - Number of Records for Primary Allocation (Required)
020000 - Number of Records for Secondary Allocation (Required)
                - Define HSM OPTIMIZER Datasets
Report Database Name - 'SYSX.OP.00000.DBS.HSM'
HSM MCDS Dataset Name - 'SYSX.HSM.MCDS'
HSM BCDS Dataset Name - 'SYSX.HSM.BCDS'
Model DSCB for GDG Dsn - 'SYSX.GDG'
                UPDATE
                SPLIT
                DSNs
                NO
                NO
```

Figure 101. HSM Optimizer Reports - Define/Allocate Files

Field entry is as follows:

1. Submit Job for Initialization

Enter **Y** to submit JOB for creating a VSAM cluster or defining the Generation Dataset Base definition for a QSAM file.

Enter **N** to not submit a JOB.

2. HSM Optimizer Database

Enter a **V** or **Q** to define a VSAM cluster or QSAM HSM Report Database.

The HSM Optimizer database will be a QSAM or VSAM dataset. If you choose QSAM, you must specify:

- whether the dataset will reside on DASD or tape
- the number of QSAM datasets that will be retained
- the number of records for the primary allocation and the number of records for the secondary allocation if you specify DASD for the database
- the name of a Model DSCB to be used when the Generation Base definition is created.

If you choose VSAM as the database organization, you must specify:

- a DASD volume serial number
- the number of records for the primary allocation and the number of records for the secondary allocation.

The default number of records for primary and secondary allocation should be adequate for most installations.

Note: You must also specify the names of the DFHSM MCDS and BCDS datasets used in your installation. Information used in some of these reports is gathered from these datasets.

3. HSM SMF Record Type

Enter the **DFHSM SMF** record number.

Note: Refer to DFHSM ARCCMDxx member or your DFHSM Storage Administration Reference to determine the SMF record number selected for your installation.

4. Volume

Enter the **volser** of the volume where the VSAM database is to be allocated.

5. Unit Type

Enter the **unit type** where the HSM Report Database will be allocated.

6. Number of Generations

Enter the **number of generations** required for QSAM database.

7. Primary Allocation

Enter the **primary allocation** specified in number of records.

8. Secondary Allocation

Enter the **secondary allocation** specified in number of records.

9. Report Database Name

Enter a **dataset name** for the HSM Optimizer Report Database

10. MCDS Database Name

Enter the **DFHSM Migration Control Data Set** (MCDS) dataset name.

11. BCDS Database Name

Enter the **DFHSM Backup Control Data Set** (BCDS) dataset name.

Note: If either your MCDS or BCDS datasets are split, enter **YES** in the **UPDATE SPLIT DSNs** field. This will present you with another panel to enter the dataset names.

12. Model DSCB for GDG Dataset Name

Enter the name of a **Model DSCB** if you are allocating a QSAM HSM Optimizer Report database.

Once all the fields on the panel are complete to your satisfaction, ensure the SUBMIT Job for Initialization field is set to Y. The submitted job will either define the GDG Base Definition, or define a VSAM file.

Note: Refer to DFHSM ARCCMDxx member or your DFHSM Storage Administration Reference to determine the SMF record number selected for your installation.

Note: The RPTALLOC member provided in the OS/EM SAMPLIB provides sample JCL for the define HSM Optimizer Reports files function and is to be used as an example to create any batch jobs that you may require.

ISPF File Prefix Controls

Description

The ISPF File Prefix Controls allow you to specify a specific prefix for ISPF **log**, **list**, and **temporary** dataset allocations.

```
OS/EM ----- ISPF File Prefix Controls ----- Version 6.0
COMMAND ==>

                Log Prefix   ==> BSYS

                List Prefix  ==> BSYS

                Temp Prefix   ==> &SYSNAME
```

Figure 102. ISPF File Prefix Controls

Field entry is as follows:

- **Log Prefix**
Enter the 1 to 8 character prefix to use in the LOG file allocation.
- **List Prefix**
Enter the 1 to 8 character prefix to use in LIST file allocations.
- **Temp Prefix**
Enter the 1 to 8 character prefix to use in TEMPORARY file allocations.

To disable the prefix for any of the above, simply blank out the field for the file type to be disabled.

System Symbolics may also be entered. If entered, they will be resolved prior to file allocation.

The dataset name constructed will be in the form:

```
userid.prefix.ISPF-specific-suffix
```

Where:

- **userid**
The TSO ID of the user
- **prefix**
The prefix entered via OS/EM
- **ISPF-specific-suffix**

This is controlled by ISPF based on the type of file being allocated.

If this option is enabled by executing the change online it takes effect immediately for all users currently using ISPF and may cause ISPF system errors. Because of this it is suggested that the option only be enabled during an IPL when OS/EM will process the INIT members in OSV6.

System Requirements

OS/EM provides a version of ISPEXITS to allow it to dynamically load and delete any of the ISPF Installation Wide Exits. IBM provides a default module of this name and if you already run ISPF exits you will have your own version. You must ensure that ISPEXITS is **not** in a STEPLIB in any ISPF logon procedure, otherwise ISPEXITS will be loaded from the STEPLIB and not from the OS/EM load library. Any exit (and associated data area) coded in your ISPEXITS must be defined to OS/EM via the Basic Exit Functions.

In addition, if you have never activated the ISPF Installation Wide Exits, you must enable them by either coding the option on the ISPMTAIL macro or with the ISPCCONF command. See the ISPF Planning and Customizing manual section Tailoring ISPF Defaults for more information.

JCL Controls

Description

JCL Controls allow installations to control various JCL parameters using an OS/EM table, or utilize an External Security Manager for checking whether Users have access to a particular resource.

Summary of Features

- Account Number controls allow Job Accounting Number(s) to be verified as valid and optionally resource checked, utilizing an External Security Manager to determine that a User has access to that Job Accounting Number
- Convert EZ-PROCLIB to JCLLIB
- JOBCLASS controls cause the External Security Manager to resource check a JOBCLASS for User access
- JOBNAME controls cause MVS Manager to determine if a JOBNAME has access to a JOBCLASS, and/or a certain JOBNAMEs are excluded from a JOBCLASS
- Virtual Storage controls provide up to 32 different virtual storage controls for region, hiperspace and data space based on JOBCLASS, JOBNAME and Program Name
 - Region Below the line (16 Megabyte)
 - Getmain Below the line (16 Megabyte)
 - Region Above the line (16 Megabyte)
 - Getmain Above the line (16 Megabyte)
 - Memlimit above 2G bar
 - Hiperspace Default Size
 - Hiperspace Total Size
 - Hiperspace Total Spaces
- SYSOUT parameters
- Tape Usage by JOBCLASS specifying Maximum Total Tapes and/or Maximum by type of tape (e.g. 3420, 3480, 3490, VTS and 3590)
- Other JCL Controls
- STEPLIB Controls
- Security Interface to an External Security Manager (e.g. RACF, CA-TOPSECRET, CA-ACF2) to allow access to OS/EM functions

JCL Control Menu

```
OS/EM ----- JCL CONTROLS ----- Version 6.0
COMMAND ==>

          1 Account Number Controls          (JES2)
          2 Convert EZ-Proclib(R) to JCLLIB  (JES2)
          3 Jobclass/Jobname Controls
          4 Other JCL Controls                (JES2)
          5 Steplib Controls
          6 Sysout Class/Parameters          (JES2)
          7 Tape Usage Controls
          8 Virtual Storage Controls

          9 Specify JES subsystem name used by
            above options (currently set to JES2)
```

Figure 103. JCL Controls for JES2

Each of these paths is presented in the following sections:

1. Account Number Controls (see “Account Number Controls” on page 5-112)
2. Convert EZ-Proclib(R) to JCLLIB (see “Convert EZ-Proclib(R) to JCLLIB” on page 5-115)
3. Jobclass/Jobname Controls (see “Jobclass/Jobname Controls” on page 5-116)
4. Other JCL Controls (see “Other JCL Controls” on page 5-122)
5. STEPLIB Controls (see “STEPLIB Controls” on page 5-127)
6. Sysout Class/Parameters (see “Sysout Class/Parameters” on page 5-131)
7. Tape Usage Controls (see “Tape Usage Controls” on page 5-135)
8. Virtual Storage Controls (see “Virtual Storage Controls” on page 5-136)
9. Specify JES2 Subsystem Name (see “Set JES2 Name” on page 8-1)

Account Number Controls

```
OS/EM ----- ACCOUNT NUMBER CONTROLS ----- Version 6.0
COMMAND ==>

                _ Account Field 1
                _ Account Field 2
                _ Account Field 3
                _ Account Field 4
                _ Account Field 5
                _ Account Field 6

Apply Account Number Controls to TSO Users? ==> YES   (Yes/No)
```

Figure 104. Account Number Controls

Account Number Controls allows you to control whether a job will be allowed to execute based upon the values entered in the Job accounting field of the job card or the step execute card.

OS/EM supports up to six sub-parameter Job accounting fields (ACCT1 to ACCT6). To set accounting field control attributes, enter a non-blank character next to the desired account field. The account control edit panel will be displayed (see Figure 105).

If you want the account number controls to validate TSO users at logon time, enter **YES** in the 'Apply Account Number Controls to TSO Users?' field.

```
OS/EM ----- JCL CONTROLS: ACCT1 ----- Version 6.0
Command ==>                                     Scroll ==> CSR

ACCT1 checking is active      ==> YES           (Yes/No)

ACCT1 values listed below
or defined to security       ==> CHECK         (Allow/Disallow/Check)

ACCT1 undefined to security  ==> DISALLOW     (Allow/Disallow)

Other ACCT1 values           ==> CHECK         (Allow/Disallow/Check)

ACCT1 format                 ==> CHAR         (CHAR/Numeric)

(CMD = (I)nsert (D)elite (S)elect)
CMD  ACCT1 / Description
'    SP$XXX
     SYSTEMS PROGRAMMING ACCOUNT
***** Bottom of data *****
```

Figure 105. JCL Controls: ACCT1

Field entry is as follows:

1. Account checking active
Enter **YES** to activate accounting field checking.
Enter **NO** to deactivate accounting field checking.
2. ACCT# values listed or defined to security

If you have entered values in the scrollable portion of this panel you may **allow** their use, **disallow** their use, or **security check** the values.

If all values to be checked have been defined to your external security manager, you may check the security manager to see if their use is allowed.

This field is the **controlling keyword** for this function. If you enter **allow** or **disallow**, you **must** enter items in the scrollable section of this panel, as those will be the items which are to be allowed or disallowed.

If you have specified **allow**, then the accounting field from the job being checked will be compared to the listed items. If the value is not found, then the **other values** field will determine if the value is allowed. See the **other values** field below for determining the action to be taken if the value is not found.

If you have specified **disallow**, then the accounting field from the job being checked will be compared to the listed items. If the value is listed, then the account number is disallowed, and the job will receive a JCL error. If the account number is not listed, then the **other values** field will determine if the value is allowed. See the **other values** field below for determining the action to be taken.

If you have specified **check** and you have listed items in the scrollable portion of the panel, then the accounting field will be compared to those items. If a match is found, then the external security manager is checked to determine if the user submitting the job has access to the value listed.

If this value is not defined to your security manager, then the **undefined to security** field will determine the action to be taken.

If this value is not defined in the list, then the **other values** field determines if the value is allowed.

If you enter **check** and **do not** enter any items in the scrollable portion of the panel, the accounting field is only checked against the external security manager and the **undefined to security** field will determine the action to be taken.

3. Account number undefined to security

If you have specified **check** as the controlling keyword, any values that have not been defined to the external security manager will either be allowed or disallowed based on your entry here.

This entry is ignored if the controlling keyword is allow or disallow.

4. Other Account values

This field specifies the action to be taken whenever a parameter is not found in the list of values displayed in the scrollable portion of the panel.

Specifying **allow** means that any parameter which was not found in the list of values will be allowed.

Disallow specifies that the parameter which was not found in the list will be disallowed and the job will fail with a JCL error.

Specifying **check** will cause the parameter not found in the list to be checked via the external security manager.

5. Account Number Format

Enter either CHAR or NUMERIC to control how the account number is validated. If NUMERIC is specified, than leading zeros are dropped, where as CHAR specifies that each character must match exactly.

6. CMD

To list specific data, use the scrollable portion of the panel. To insert a blank line, enter **I** in the CMD field.

To delete a line, enter a **D** in the CMD field for the line to be deleted.

To update a line, enter an **S** in the CMD field and overwrite the information to be changed.

7. ACCT#

Enter the accounting information being checked.

The command authorization is done by using classname FACILITY for RACF and CA-ACF2, and classname IBMFAC or DATASET for CA-TOPSECRET. The resource name is JCL.cmd.data, where 'cmd' is ACCT1, ..., ACCT6, and 'data' is the accounting information being checked.

Note: See Step 6 of the Installation instructions in the OS/EM Reference Manual for more information on defining external security.

8. Description

Enter any descriptive text (optional).

Convert EZ-Proclib(R) to JCLLIB

This control will cause OS/EM to convert any **EZ-Proclib(R)** statements to normal IBM **JCLLIB** statements.

```
OS/EM ----- CONVERT EZ-PROCLIB(R) TO JCLLIB STATEMENTS ----- Version 6.0  
COMMAND ==>
```

```
Convert EZ-Proclib(R) to JCLLIB? ==> YES          (Yes/No)
```

```
EZ-Proclib is a Registered Trademark of Computer Associates
```

Figure 106. Convert EZ-Proclib(R) to JCLLIB

To enable conversion, enter **YES**. To leave these statements alone, enter **NO**.

Any **//PROCLIB DD** statements, including concatenations, are commented out and replaced by **//PROCLIB JCLLIB ORDER=** statements.

Jobclass/Jobname Controls

Wherever possible, OS/EM optional functions are applied on a job class basis. This means that your installation should have a well-defined set of rules for job class usage. Any rules you develop should account for the following:

- If you run CICS (or any other transaction processing system) as a batch job, you should have separate production and test classes. Typically, the production class(es) will have a higher dispatching priority than almost anything else in the system. The test class(es) will be much lower (give thought to placing these classes at a lower priority than TSO. If these test systems hang, they can lock out your TSO users).
- If you are going to control tape usage for test jobs, you need enough classes defined to handle the various allocation rules you develop. You probably will want to tie job turnaround time to the number of tape devices the job uses. That is, a quick turnaround job such as a compile would normally not require any tape devices. A job that requires three or more tape devices could be given a long turnaround time.
- The number of production job classes should be held to a minimum. It is not the number of job classes that determines how many production jobs can run, but the number of initiators these classes are assigned to.
- However, you should have at least one class reserved for those production jobs that consume excessive resources and single-thread such jobs through this class. We would also recommend that you reserve one production class for those jobs that absolutely need to be executed when they are submitted. Such jobs would be the SMF dump job; and, if your CICS journal is on disk, the job that dumps a full disk journal to tape.

```
OS/EM ----- JOBCLASS/JOBNAME CONTROLS ----- Version 6.0
COMMAND ==>

          1  Enable/Disable Job Class Checking
          2  Enable/Disable Job Name Checking
```

Figure 107. Jobclass/Jobname Controls

1. Enable/Disable Job Class Checking (See “Job Class checking” on page 5-118)
2. Enable/Disable Job Name Checking (See “Job Name Checking” on page 5-119)

Job Class checking: This function uses your external security package (RACF, CA-ACF2 or CA-TOPSECRET) to verify users ability to use a particular jobclass either at submission time, execution time or both.

```
OS/EM ----- JOB CLASS CHECK ----- Version 6.0
COMMAND ==>

          Job Class Checking is active at:

          Submit time    ==> YES      (YES/NO)
            RACF Logging ==> NORMAL  (NONE/NORMAL)

          Execution time ==> YES      (YES/NO)
            RACF Logging ==> NONE    (NONE/NORMAL)
```

Figure 108. Job Class Check

Field entry is as follows:

1. Submit time

Entering **YES** specifies that a check be done to ensure that the user is authorized to submit a job in the jobclass used.

Entering **NO** disables this option.

2. RACF Logging

Entering **NORMAL** means that RACF will do normal logging for this check. **NONE** says no RACF logging will be requested.

3. Execution time

Entering **YES** specifies that a check is done when the job is selected for execution to be sure that the user is authorized to execute a job in the jobclass used.

Entering **NO** disables this option.

4. RACF Logging

Same as **2** above.

The command authorization is done by using classname FACILITY for RACF and CA-ACF2, and classname IBMFAC or DATASET for CA-TOPSECRET. The resource name is JOBCLASS.x where 'x' is the desired jobclass. Each jobclass must be properly defined to your security system.

Note: Jobclass resources that are not defined to the External Security system are always allowed.

Job Name Checking: This function allows you to control which jobs can execute within a given jobclass. Using job name masks, you can specify that only jobs which match a mask can execute and/or exclude jobs which match a mask.

When you select Job Name Checking Controls, you are presented a scrollable list of job classes.

```

OS/EM ----- JOB NAME CHECKING CONTROLS ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

CMD = (S)elect for update (I)nclude masks (E)xclude masks)

  CMD      Class      Controls      Include      and/      Exclude
  '         A         _____      NO           _____      NO
  '         B         _____      NO           _____      NO
  '         C         _____      NO           _____      NO
  '         D         _____      NO           _____      NO
  '         E         _____      NO           _____      NO
  '         F         _____      NO           _____      NO
  '         G         _____      NO           _____      NO
  '         H         _____      NO           _____      NO
  '         I         YES          YES          AND          YES
  '         J         YES          YES          OR           YES
  '         K         _____      NO           _____      NO
  '         L         _____      NO           _____      NO
  '         M         _____      NO           _____      NO
  '         N         _____      NO           _____      NO
  '         O         _____      NO           _____      NO
  '         P         _____      NO           _____      NO
  
```

Figure 109. Job Name Checking Controls

Field entry is as follows:

1. CMD

To activate a class, enter an **S** in the CMD field for that class, and enter **YES** in the Controls Active column.

2. Controls Active

Entering **YES** in this field will enable OS/EM's extended processing.

Entering **NO** in this field will disable OS/EM's extended processing.

This field must be completed before you will be allowed to leave this panel.

3. INCLUDE

To create a list of INCLUDE job masks, enter an **I** in the CMD field and press enter. You will be presented with a POPUP panel showing all of the masks previously entered.

Jobs matching an include mask are permitted to execute in the class specified.


4. AND/OR

Connective between include masks and exclude masks. If you specify **AND** then the job being submitted must match an include mask **and** must **not** match an exclude mask. If you specify **OR** then the job being submitted may either match an include mask **or not** match an exclude mask.

5. EXCLUDE

To create a list of EXCLUDE job masks, enter an **E** in the CMD field and press enter. You will be presented with a POPUP panel showing all of the masks previously entered.

Jobs matching an exclude mask are not permitted to execute in the specified class.



Field entry is as follows:

1. To add a mask, enter an **A** in the CMD field and overwrite the Job Name Mask field.
2. To delete a mask, enter a **D** in the CMD field.

Include / Exclude

Job Name Masks: The following table shows the allowable mask characters:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

Other JCL Controls




Figure 111. Other JCL Controls

When a selection is made, the next panel will reflect your choice and the verbiage on the panel will also reflect your choice. In Figure 112 on page 5-124, the choice was number 3 and the verbiage reflects DDNAMES. The same panel will appear for the other choices, but the verbiage will be different.

The following parameters are available:

Parm

Description

ADDRSPC

Type of address space required

When using the CHECK option the resource name to be checked is 'JCL.ADDRSPC.data' where data is the ADDRSPC to be checked. Each ADDRSPC that you want to check must be defined to your security system with appropriate access defined. Read access is required.

DATACLASS

DFSMS data class

When using the CHECK option the resource name to be checked is 'JCL.DATACLASS.class' where class is the DATACLASS to be checked. Each DATACLASS that you want to check must be defined to your security system with appropriate access defined. Read access is required.

DDNAMES

Data definition names

When using the CHECK option the resource name to be checked is 'JCL.DDNAMES.name' where name is the DDNAMES to be checked. Each DDNAMES that you want to check must be defined to your security system with appropriate access defined. Read access is required.

DPRTY

Dispatching priority

When using the CHECK option the resource name to be checked is 'JCL.DPRTY.data' where data is the DPRTY to be checked. Each DPRTY that you want to check must be defined to your security system with appropriate access defined. Read access is required.

EXPDT

Expiration Date

When using the CHECK option the resource name to be checked is 'JCL.EXPDT.date' where date is the EXPDT to be checked. Each EXPDT that you want to check must be defined to your security system with appropriate access defined. Read access is required.

Note: The EXPDT is normalized to the date format YYYY/DDD before checking.

MGMTCLASS

DFSMS management class

When using the CHECK option the resource name to be checked is 'JCL.MGMTCLASS.class' where class is the MGMTCLASS to be checked. Each MGMTCLASS that you want to check must be defined to your security system with appropriate access defined. Read access is required.

PERFORM

Performance group

When using the CHECK option the resource name to be checked is 'JCL.PERFORM.number' where number is the PERFORM to be checked. Each PERFORM that you want to check must be defined to your security system with appropriate access defined. Read access is required.

PROTECT

Request RACF protection of a dataset

When using the CHECK option the resource name to be checked is 'JCL.PROTECT.yes' where yes is the PROTECT to be checked. Each PROTECT that you want to check must be defined to your security system with appropriate access defined. Read access is required.

PRTY

Job selection priority

When using the CHECK option the resource name to be checked is 'JCL.PRTY.number' where number is the PRTY to be checked. Each PRTY that you want to check must be defined to your security system with appropriate access defined. Read access is required.

RETPD

Retention Period

When using the CHECK option the resource name to be checked is 'JCL.RETPD.number' where number is the RETPD to be checked. Each RETPD that you want to check must be defined to your security system with appropriate access defined. Read access is required.

STORCLASS

DFSMS storage class

When using the CHECK option the resource name to be checked is 'JCL.STORCLASS.class' where class is the STORCLASS to be checked. Each STORCLASS that you want to check must be defined to your security system with appropriate access defined. Read access is required.

SUBSYS

Subsystem which will process a dataset

When using the CHECK option the resource name to be checked is 'JCL.SUBSYS.name' where name is the SUBSYS to be checked. Each SUBSYS that you want to check must be defined to your security system with appropriate access defined. Read access is required.

TIME

Specify maximum step execution time

When using the CHECK option the resource name to be checked is 'JCL.TIME.time parameter' where time parameter is the TIME to be checked. Each TIME that you want to check must be defined to your security system with appropriate access defined. Read access is required.

Note: The only available time parameters are: **MAXIMUM, 1440, NOLIMIT,** and **HIGH.** The value **HIGH** is compared to the time parameter coded in JES PARMS for the executing job class. If the value coded in the JCL for a step is greater than that specified by JES2 the user needs **READ** access for **CHECK.**

UNIT

Storage device type

When using the CHECK option the resource name to be checked is 'JCL.UNIT.esoteric name' where esoteric name is the UNIT to be checked. Each UNIT that you want to check must be defined to your security system with appropriate access defined. Read access is required.

USERLIB

OUTPUT statement for AFP libraries.

When using the CHECK option the resource name to be checked is 'JCL.USERLIB.library name' where library name is the USERLIB to be checked. Each USERLIB that you want to check must be defined to your security system with appropriate access defined. Read access is required.

The following figure is an example of the screen that will appear:

```

OS/EM ----- JCL CONTROLS: DDNAME ----- Version 6.0
Command ==>                                     Scroll ==> CSR

  DDNAME checking is active      ==> YES          (Yes/No)

  DDNAME values listed below
    or defined to security      ==> ALLOW        (Allow/Disallow/Check)

  DDNAME undefined to security  ==> DISALLOW    (Allow/Disallow)

  Unlisted DDNAME values       ==> CHECK        (Allow/Disallow/Check)

(CMD = (I)nsert (D)elite (S)elect)
CMD  DDNAME / Description
'    JOBCAT
     MAKE SURE USER IS ALLOWED TO USE JOBCAT
'    STEPCAT
     MAKE SURE USER IS ALLOWED TO USE STEPCAT
***** Bottom of data *****

```

Figure 112. JCL Controls: DDNAME

In the discussion which follows, the word **parameter** is the used instead of the actual parameter name.

Field entry is as follows:

1. Parameter checking active

Enter **YES** to activate DDNAME checking.

Enter **NO** to deactivate DDNAME field checking.

2. Listed DDNAME values or defined to security

If you have entered values in the scrollable portion of this panel you may **allow** their use, **disallow** use, or **security check** the value.

If the values have instead been defined to your security system, you may **check** the external security manager to see if their use is allowed.

This field is the **controlling keyword** for this function. If you enter **allow** or **disallow**, you **must** enter items in the scrollable section of this panel, as those will be the items which are to be allowed or disallowed.

If you have specified **allow**, then the JCL parameter from the job being checked will be compared to the listed items. If the value is not found, then the **other values** field will determine if the value is allowed. See the **OTHER values** field below for determining the action to be taken if the value is not found.

If you have specified **disallow**, then the JCL parameter from the job being checked will be compared to the listed items. If the value is listed, then the parameter is disallowed, and the job will receive a JCL error. If the parameter is not listed, then the **other values** field will determine if the value is allowed. See the **OTHER values** field below for determining the action to be taken if the parameter is not found.

If you have specified **check**, and you have listed items in the scrollable portion of the panel, then the JCL parameter will be compared to those items. If a match is found, then the external security manager is checked to determine if the User submitting the job has access to the value listed.

If this value is not defined to your security system, then the **undefined to security** field will determine the action to be taken.

If this value is not defined in the list, then the **other values** field determines if the value is allowed.

If you enter **check** and do not enter any items in the scrollable portion of the panel, the JCL parameter is only checked against the external security manager and the **UNDEFINED to security** field will determine the action to be taken.

3. Parameter undefined to security

If you have specified **check** as the controlling keyword, any values which have not been defined to the external security manager will either be allowed or disallowed based on your entry here.

This entry is ignored if the controlling keyword is ALLOW or DISALLOW.

4. Unlisted DDNAME

This field specifies the action to be taken whenever a parameter is not found in the list of values displayed in the scrollable portion of the panel.

Specifying **allow** means that any parameter which was not found in the list of values will be allowed.

Disallow specifies that the parameter which was not found in the list will be disallowed and the job will fail with a JCL error.

Specifying **check** will cause the parameter not found in the list to be checked via the external security manager.

5. CMD

To list specific data, use the scrollable portion of the panel. To insert a blank line, enter **I** in the CMD field.

To delete a line, enter a **D** in the CMD field for the line to be deleted.

To update a line, enter an **S** in the CMD field and overwrite the information to be changed.

6. DDNAME

Enter the **DDNAME** to be checked.

The DDNAME checking above will call the External Security manager to determine if the user submitting the job is allowed to use the STEPCAT or JOBCAT DDNAME.

The class name to be checked is FACILITY for RACF and CA-ACF2, and the class name IBMFAC or DATASET for CA-TOPSECRET. The class name to be checked is specified in the OS/EM IEFSSN member of SYS1.PARMLIB during OS/EM system installation.

When using the CHECK option the resource name to be checked is 'JCL.DDNAME.data' where data is the DDNAME to be checked. Each DDNAME that you want to check must be defined to your security system with appropriate access defined. Read access is required.

STEPLIB Controls

Description: The STEPLIB option allows you to modify or replace existing STEPLIB DD statements or add a new STEPLIB DD based on job class, job name, user ID, step name or program name. You may optionally fail the job if any of the specified libraries for the STEPLIB are unavailable, or you may allow the job to continue without changing the existing STEPLIBs.

STEPLIB Controls Menu

```
OS/EM ----- STEPLIB CONTROLS ----- Version 6.0
SELECTION ==>>

                1 System Level Controls
                2 Selection Lists
```

Figure 113. STEPLIB Controls Menu

This menu contains entries to update system level control information and the selection lists. Both entries must be selected to initially setup STEPLIB Controls.

System Level Controls

```
OS/EM ----- STEPLIB SYSTEM CONTROLS ----- Version 6.0
Command ==>>                               Scroll ==>> CSR

    Steplibs Active      ==>> YES      (Yes/No)

    Wait Options:
      Dataset            ==>> YES      (Yes/No)
      Volume             ==>> NO       (Yes/No)
      Unit               ==>> NO       (Yes/No)

    Allow HSM Recalls?  ==>> NO       (Yes/No)
```

Figure 114. System Level Controls Panel

Use this panel to enter non-specific information about STEPLIB Controls. The information on this panel is required before any controls dealing with specific STEPLIBs becomes effective.

Field entry is as follows:

1. STEPLIBs Active

Enter **YES** to turn on STEPLIBs, or **NO** to disable STEPLIBs on the current system.

2. Wait Options:

The following Wait Options refer to the datasets specified as STEPLIB entities.

- Dataset

Enter **YES** to allow the system to put the job into a wait state until the dataset is available. Enter **NO** to disable the wait. If **NO** is entered, the STEPLIB will not be processed and the **FAIL JOB** option specified on the selection lists panel will take effect.

- Volume

Enter **YES** to allow the system to put the job into a wait state until the volume is available. Enter **NO** to disable the wait. If **NO** is entered, the STEPLIB will not be processed and the **FAIL JOB** option specified on the selection lists panel will take effect.


- Unit

Enter **YES** to allow the system to put the job into a wait state until the unit is available. Enter **NO** to disable the wait. If **NO** is entered, the STEPLIB will not be processed and the **FAIL JOB** option specified on the selection lists panel will take effect.

3. Allow HSM Recalls

Enter **YES** to allow the DFHSM recall to be processed. Enter **NO** to disable DFHSM recalls. If you disable recalls, the STEPLIB will not be processed and the **FAIL JOB** option specified on the selection lists panel will take effect.

Selection Lists: Up to 32 different sets of libraries and the selection criteria needed for each to be selected may be specified on this panel. You also state by selection group whether the job will fail (via a jcl error) if a specified library is unavailable, or if the job will continue without the STEPLIB being modified, replaced or added.



Field entry is as follows:

1. Active

To activate a selection group, use the tab key to place the cursor in the **Active** column and enter a **Y**.

2. Placement

Tab to the **Placement** field and enter where you want the dynamic STEPLIB libraries placed. Valid entries are:

- REPLACE

Completely replace any existing STEPLIB DDs already in the JCL.

- BEFORE

Add the dynamic libraries before any libraries specified in the JCL.

- AFTER

Add the dynamic libraries after any libraries specified in the JCL.

3. Fail Job

Tab to the **Fail Job** field and enter either **YES** or **NO**. This value determines whether the job will fail with a JCL error if any of the dynamic STEPLIB libraries are unable to be allocated. If it is acceptable that the job execute without the dynamic libraries enter **NO** here.

4. Description

You may also enter an optional description line to describe what these dynamic libraries are for.

There are 2 line commands available. Use **S** to modify the selection lists or **D** to delete the selection lists.

The **Select** line command allows you to specify the dynamic library names, enter the selection criteria based on job class, job name, user ID, step name or program name. Masks are acceptable for all but job class and the steplib dataset name.

```

OS/EM ----- SELECTOR ENTRY - 02 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enter Selector Types, either Include or Exclude
Jobclass ==> INCLUDE   Jobname ==> INCLUDE   Pgmname ==> INCLUDE
Stepname ==> INCLUDE   UserID ==> INCLUDE

Line Cmds: (D)delete line, (I)nsert line
Selector
Type      Selector Names/Mask List          VOLUME
_ JOBNAME  BKBUILD BKINDEX                    _____
_ JOBCLASS B:D                               _____
_ STEPLIB  'EOY.SEOYLOAD'                      SMS003
_ USERID  SP- HE-                             _____
_ STEPNAME BULLD INDEK                        _____
_ PGMNAME  IKJEFT01                           _____
***** Bottom of data *****

```

Figure 116. Selector Entry Panel

This panel allows you to specify the dataset names to be used for the **STEPLIB** as well as the selector types used to match this selector group to the job being checked.

Each **selector type** may be either an **INCLUDE** or **EXCLUDE** list. Types marked as **include** lists have to match the attributes of the job being checked. Types marked as **exclude** lists may **not** match the jobs attributes.

If you fail to specify either include or exclude, the list will be forced to an **include** type list.

In the scrollable portion of the panel, you enter the **selector types** and the names or masks for that type. With the exception of the **STEPLIB** type, you may enter as many names/masks that will fit on the line. If you have more entries than will fit on a line, simply insert a blank line and mark it to be the same **selector type** and continue entering names/masks. Selector types are **JOBCLASS, JOBNAME, PGMNAME, STEPNAME** and **USERID**.

The **JOBCLASS** entries may be listed individually or as a range. A range is entered as two classes separated by a colon (:), i.e. F:K.

The **STEPLIB** selector type is actually the dataset name of the library or libraries which will be used for the STEPLIB. A **volume** may be specified for datasets which are not cataloged (non-SMS) or to force use of a dataset on a different volume than that which is contained in the catalog. Only one dataset name may be specified per entry. If multiple dataset names are entered they will be concatenated in the order entered.

Any library entered here must currently exist. Standard TSO naming conventions are used, i.e. if **prefix** is turned on, any name entered without apostrophes will have your TSO ID added as the prefix.

Sysout Class/Parameters

```
OS/EM ----- SYSOUT PARAMETER CONTROLS ----- Version 6.0
COMMAND ==>

          1 BURST
          2 CHARS
          3 COPIES
          4 DEST
          5 FCB
          6 FLASH
          7 FORM
          8 FORMDEF
          9 MODIFY
         10 MSGCLASS
         11 OUTPRTY
         12 PAGEDEF
         13 PRMODE
         14 SYSOUT
         15 UCS
         16 WRITER
```

Figure 117. SYSOUT Parameter Controls

When a selection is made, the next panel will reflect your choice and the verbiage on the panel will also reflect your choice. In Figure 118 on page 5-133, the choice was number 14 and the verbiage reflects SYSOUT. The same panel will appear for the other choices, but the verbiage will be different.

The following parameters are available:

Parameter Description

CHARS

Character arrangement tables

When using the CHECK option the resource name to be checked is 'JCL.CHARS.character set' where character set is the CHARS to be checked. Each CHARS that you want to check must be defined to your security system with appropriate access defined. Read access is required.

BURST

Use 3800 burster-trimmer-stacker

When using the CHECK option the resource name to be checked is 'JCL.BURST.YES/NO' where YES/NO is the BURST to be checked. Each BURST that you want to check must be defined to your security system with appropriate access defined. Read access is required.

COPIES

Number of copies of hardcopy output

When using the CHECK option the resource name to be checked is 'JCL.COPIES.number' where number is the COPIES to be checked. Each COPIES that you want to check must be defined to your security system with appropriate access defined. Read access is required.

DEST

Destination for a SYSOUT dataset

When using the CHECK option the resource name to be checked is 'JCL.DEST.destination' where destination is the DEST to be checked. Each DEST that you want to check must be defined to your security system with appropriate access defined. Read access is required.

FCB Forms control buffer

When using the CHECK option the resource name to be checked is 'JCL.FCB.forms buffer' where forms buffer is the FCB to be checked. Each FCB that you want to check must be defined to your security system with appropriate access defined. Read access is required.

FLASH

Forms overlay

When using the CHECK option the resource name to be checked is 'JCL.FLASH.flash image' where flash image is the FLASH to be checked. Each FLASH that you want to check must be defined to your security system with appropriate access defined. Read access is required.

FORM

Form name

When using the CHECK option the resource name to be checked is 'JCL.FORM.form name' where form name is the FORM to be checked. Each FORM that you want to check must be defined to your security system with appropriate access defined. Read access is required.

FORMDEF

AFP form definition name

When using the CHECK option the resource name to be checked is 'JCL.FORMDEF.formdef name' where formdef name is the FORMDEF to be checked. Each FORMDEF that you want to check must be defined to your security system with appropriate access defined. Read access is required.

MODIFY

Copy modification module

When using the CHECK option the resource name to be checked is 'JCL.MODIFY.module name' where module name is the MODIFY to be checked. Each MODIFY that you want to check must be defined to your security system with appropriate access defined. Read access is required.

MSGCLASS

SYSOUT class for the job log, allocation messages and JCL image

When using the CHECK option the resource name to be checked is 'JCL.MSGCLASS.SYSOUT class' where SYSOUT class is the MSGCLASS to be checked. Each MSGCLASS that you want to check must be defined to your security system with appropriate access defined. Read access is required.

OUTPRTY

OUTPUT print priority.

When using the CHECK option the resource name to be checked is 'JCL.OPRTY.number' where number is the OUTPRTY to be checked. Each OUTPRTY that you want to check must be defined to your security system with appropriate access defined. Read access is required.

PAGEDEF

AFP page definition

When using the CHECK option the resource name to be checked is 'JCL.PAGEDEF.name' where name is the PAGEDEF to be checked. Each PAGEDEF that you want to check must be defined to your security system with appropriate access defined. Read access is required.

PRMODE

PSF process mode

When using the CHECK option the resource name to be checked is 'JCL.PRMODE.name' where name is the PRMODE to be checked. Each PRMODE that you want to check must be defined to your security system with appropriate access defined. Read access is required.

SYSOUT

Output print class for generated output

When using the CHECK option the resource name to be checked is 'JCL.SYSOUT.class' where class is the SYSOUT to be checked. Each SYSOUT that you want to check must be defined to your security system with appropriate access defined. Read access is required.

UCS Universal character set

When using the CHECK option the resource name to be checked is 'JCL.UCS.character set' where character set is the UCS to be checked. Each UCS that you want to check must be defined to your security system with appropriate access defined. Read access is required.

WRITER

External writer name

When using the CHECK option the resource name to be checked is 'JCL.WRITER.writer name' where writer name is the WRITER to be checked. Each WRITER that you want to check must be defined to your security system with appropriate access defined. Read access is required.

The following figure is an example of the screen that will appear:

```

OS/EM ----- JCL CONTROLS: SYSOUT ----- Version 6.0
Command ==>                                     Scroll ==> CSR

  SYSOUT checking is active      ==> YES          (Yes/No)

  SYSOUT values listed below
    or defined to security      ==> ALLOW        (Allow/Disallow/Check)

  SYSOUT undefined to security  ==> DISALLOW    (Allow/Disallow)

  Unlisted SYSOUT values       ==> CHECK        (Allow/Disallow/Check)

(CMD = (I)nsert (D)elete (S)elect)
CMD  SYSOUT / Description
     P
     Production Print Class
***** Bottom of data *****

```

Figure 118. JCL Controls: SYSOUT

In the discussion which follows, the word **parameter** is the used instead of the actual parameter name.

Field entry is as follows:

1. Parameter checking active

Enter **YES** to activate SYSOUT checking.

Enter **NO** to deactivate SYSOUT field checking.

2. Listed SYSOUT values or defined to security

If you have entered values in the scrollable portion of this panel you may **allow** their use, **disallow** use, or **security check** the value.

If the values have instead been defined to your security system, you may **check** the external security manager to see if their use is allowed.

This field is the **controlling keyword** for this function. If you enter **allow** or **disallow**, you **must** enter items in the scrollable section of this panel, as those will be the items which are to be allowed or disallowed.

If you have specified **allow**, then the JCL parameter from the job being checked will be compared to the listed items. If the value is not found, then the **other values** field will determine if the value

is allowed. See the **OTHER values** field below for determining the action to be taken if the value is not found.

If you have specified **disallow**, then the JCL parameter from the job being checked will be compared to the listed items. If the value is listed, then the parameter is disallowed, and the job will receive a JCL error. If the parameter is not listed, then the **other values** field will determine if the value is allowed. See the **OTHER values** field below for determining the action to be taken if the parameter is not found.

If you have specified **check**, and you have listed items in the scrollable portion of the panel, then the JCL parameter will be compared to those items. If a match is found, then the external security manager is checked to determine if the User submitting the job has access to the value listed.

If this value is not defined to your security system, then the **undefined to security** field will determine the action to be taken.

If this value is not defined in the list, then the **other values** field determines if the value is allowed.

If you enter **check** and do not enter any items in the scrollable portion of the panel, the JCL parameter is only checked against the external security manager and the **UNDEFINED to security** field will determine the action to be taken.

3. Parameter undefined to security

If you have specified **check** as the controlling keyword, any values which have not been defined to the external security manager will either be allowed or disallowed based on your entry here.

This entry is ignored if the controlling keyword is allow or disallow.

4. Other SYSOUT

This field specifies the action to be taken whenever a parameter is not found in the list of values displayed in the scrollable portion of the panel.

Specifying **allow** means that any parameter which was not found in the list of values will be allowed.

Disallow specifies that the parameter which was not found in the list will be disallowed and the job will fail with a JCL error.

Specifying **check** will cause the parameter not found in the list to be checked via the external security manager.

5. CMD

To list specific data, use the scrollable portion of the panel. To insert a blank line, enter **I** in the CMD field.

To delete a line, enter a **D** in the CMD field for the line to be deleted.

To update a line, enter an **S** in the CMD field and overwrite the information to be changed.

6. SYSOUT

Enter the **SYSOUT** to be checked.

The class name to be checked is FACILITY for RACF and CA-ACF2, and the class name IBMFAC or DATASET for CA-TOPSECRET. The class name to be checked is specified in the OS/EM IEFSSN member of SYS1.PARMLIB during OS/EM system installation.

When using the CHECK option the resource name to be checked is 'JCL.SYSOUT.class' where class is the SYSOUT to be checked. Each SYSOUT that you want to check must be defined to your security system with appropriate access defined. Read access is required.

Tape Usage Controls

Tape allocation checking occurs as each job step executes. That is, as each tape device is allocated, a count is accumulated and checked against the total limit specified for the job class. Once the total limit is exceeded, the job is cancelled unless operating in **WARN** mode.

```

OS/EM ----- TAPE USAGE CONTROLS ----- Version 6.0
Command ==>                                     Scroll ==> CSR

      Max Tape Controls active   ==> YES         (Yes/No)

      Violators warned/cancelled ==> CANCEL      (Warn/Cancel)

(CMD = (S)elect)

      CMD  Class  Active  Total  Total  Total  Total  Total  Total
      '    '    '      '    '    '    '    '    '
      '  A    YES   ___  ___  ___  ___  ___  ___  0
      '  B    YES   ___  ___  ___  ___  ___  ___  0
      '  C    YES   0    0    0    2    2    ___  3
      '  D    NO    ___  ___  ___  ___  ___  ___  ___
      '  E    NO    ___  ___  ___  ___  ___  ___  ___
      '  F    NO    ___  ___  ___  ___  ___  ___  ___
      '  G    NO    ___  ___  ___  ___  ___  ___  ___
  
```

Figure 119. Tape Usage Controls

Field entry is as follows:

1. Max Tape Controls

This field specifies that tape allocation control will be applied according to criteria established with the various CLASS parameters.

2. Violators Warned/Cancelled

This field provides you with a way of observing your tape allocation rules without actually enforcing those rules. WTO messages are produced which will indicate the action OS/EM would have taken if WARN mode were not in effect.

3. SELECT

To enable Tape Usage controls for a job class, select the class by placing an **S** in the CMD field and then overtyping the fields on that line.

4. ACTIVE

Enter **YES** in the Active column to enable a CLASS.

Enter **NO** to disable a CLASS.

5. Total Number of Tapes

Each jobclass - A through 9 - can be individually enabled. Enter the total tapes allowed for each type of tape device as well as the total allowed for the step. Each number can be between 0 and 255. The number of 3420, 3480, 3490 3490-VTS and 3590 devices combined may exceed the total number allowed, however no single entry may be greater than the value specified for **total tapes**.

Virtual Storage Controls




Figure 120. Virtual Storage Controls

Field entry is as follows:

1. Region Controls Active

Enter **YES** to enable Region Controls.

Enter **NO** to disable Region Controls.

2. Region Override Active

Enter **YES** to enable Region Override Controls

Enter **NO** to disable Region Override Controls

This parameter will allow OS/EM to increase the region size of a job if the job asks for a smaller amount than it is allowed.

3. Region Defaults Active

Enter **YES** to enable Region Defaults

Enter **NO** to disable Region Defaults.

This allows you to disable the default entries without disturbing the information already entered.

4. Region Defaults

Specify the default values used by OS/EM for storage utilization control. The values are used if none are specified for regions 1 to 32.

With the exception of Hiperspace/Dataspace values, and above the 2 Gigabyte bar, the numeric values are entered in K. Total spaces is entered as the total number of Hiperspaces/Dataspaces allowed within the region. Default size for Hiperspace is in 4K blocks. Total size of Hiperspace is in Megabytes. Refer to MVS Systems Modifications, SMF exit IEFUSI for further information regarding these parameters.

5. REGION

The first value is the amount of storage, below the 16M line, a program will be given to execute in. A negative value may be entered indicating that the amount of storage is to be calculated by subtracting this value from the size of the private area currently available below the 16M line.

The third value is the amount of storage, above the 16M line, a program will be given to execute in.

6. LIMIT

The second value is the maximum amount of storage, below the 16M line, a program will be allowed to GETMAIN. A negative value may be entered indicating that the amount of storage is to be calculated by subtracting this value from the size of the private area currently available below the 16M line.

The fourth value is the maximum amount of storage, above the 16M line, a program will be allowed to GETMAIN.

7. Hiperspace/Dataspace

The fifth value is the default size of a Hiperspace or Dataspace when it is created in units of 4K blocks.

The sixth value is the total size of storage that may be used for all user key Hiperspaces and Dataspaces in an address space, in units of 1 Megabyte increments.

The seventh value is the total number of Hiperspaces or Dataspaces allowed within an address space.

8. MEMLIMIT

The eighth value is the amount of storage a user may obtain above the 2 gigabyte bar up to a maximum of 16 exabytes. The value must be entered with the storage type specified as the last character of the amount, i.e. 16G would indicate 16 gigabytes, and 2P would indicate 2 petabytes. Use **M** for megabytes, **G** for gigabytes, **T** for terabytes and **P** for petabytes.

For space above the 2G bar, you may enter 0M to indicate that **NO** space above the bar may be used. Entering **0** without a type modifier indicates that the system default will be used.

9. VALUES

A **0** can be entered for any one of the values. This will nullify the previous value. Your installation's MVS default for the specific value being nullified will then apply.

The values specified for the region1 through 32 parameters can be confined to specified job classes, job names, or individual programs.

If there are no program/job/class matches, then the default values entered (if any) will be used.

10. Weight

Enter a number between 1 and 9 for each of the selection list types.

If a job matches more than one region control definition, these weight values will be used to determine which definition to use. In other words, if a job matches region 2 because of the job class, and matches region 3 because of the program name, and the weight value for job class is 8 while the weight for program name is 2, region 2 will be selected because its weight will be higher.

11. JOB, PGM, CLASS Options

The optional region parameters (1-32) specify storage values that will be applied to specified program names, job names, or job classes.

To enable an individual region, enter a **Y** in the Active column, and any numeric values which should be different than the default values.

To enter selection criteria enter an **S** in the command column and press the ENTER key. Another panel will be displayed where you can specify the selectors for this region definition.

```

OS/EM ----- SELECTOR ENTRY - 4 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enter Selector Types, either Include or Exclude
  Jobclass ==> INCLUDE   Jobname ==> INCLUDE   Pgmname ==> INCLUDE

Line Cmds: (D)elete line, (I)nsert line

  Selector
  Type      Selector Name/Mask List
- JOBCLASS  P:R
- JOBNAME   LCRD0102 MRPD-
- PGMNAME   IFCEREPl
***** Bottom of data *****

```

Figure 121. Selector Entry Panel

This panel allows you to enter the selection criteria for a region group. You may enter the following types of items:

- JOBCLASS** The class of the job being evaluated.
- JOBNAME** The jobname of the job being evaluated.
- PGMNAME** A program that will execute in the job being evaluated.

Each **Selector Type** may be either an **INCLUDE** group or an **EXCLUDE** group. This means that selectors marked as an include group must match the attributes of the job being evaluated. Selectors marked as an exclude group must **not** match the attributes of the job being evaluated.

Separate the names or masks with a space. You may enter as many names/masks as will fit on the line. To enter more items, simply insert another line and enter the same selector type keyword.

Multiple names/masks within a selector type are considered to be **OR** conditions. That is, if any of them are matched the condition is satisfied. Specifying multiple selector types, however, is considered to be an **AND** condition. All selector types must be satisfied in order for the region control to be assigned to the job being evaluated.

Masks: The following table shows the allowable mask characters:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

Job Controls

Description

JOB Controls provides the option for Step end statistics, JOB end statistics, TSO logoff statistics, Surrogate password processing, use of certain functions during TSO submit processing, correction of NOT CATALOGED 2 conditions, control number of concurrently running jobs by user or program, and allow SYSOUT extensions.

Summary of Features

- Correction of NOT CATALOGED 2 conditions specified by JOBCLASS including
 - Uncatalog and delete the improper dataset and catalog the new dataset
 - Uncatalog the improper dataset and catalog the new dataset
 - Cancel the JOB with a JCL error
- Surrogate Password processing provides
 - Password insertion in the JOB card for NJE processed JOBS for TSO Users
 - Password insertion in the JOB card for JOBS submitted by authorized JOBS, STCs and/or Users that may submit JOBS for other Users
- Enforce TSO submitted JOBS by JOBCLASS having jobnames starting with the USERID of the User submitting
- Add Notify parameter to TSO submitted JOBS by JOBCLASS
- Control submission of MVS Commands imbedded in JOBS by TSO Users
- Control submission of JES2 Commands imbedded in JOBS by TSO Users
- JOB end WTO in JESLOG for highest step end condition code
- STEP end WTO in JESLOG with step condition code
- Step end statistics including I/Os by DDNAME in JES Messages
- JOB end statistics in JES Messages
- Customization of step end statistics flower box including Customer Description
- WTOR option by JOBCLASS for operator cancelled JOBS
- Highlighted WTO option by JOBCLASS for abended JOBS
- Terminal display of TSO usage statistics at logoff
- Limit number of concurrently running jobs by user ID
- Limit number of specific programs concurrently running by program name
- Issue a message to submitter when job actually starts running
- Reformat the accounting field of job cards
- Allow SYSOUT lines extensions
- Ensure that the submitter of a job is defined to RACF

Job Controls Menu

The Job Controls Menu presents sixteen selections. Each option presents another selection menu, taking you down the path you have chosen.

Several options are activated for a specific JES2 subsystem. These options show the currently selected JES2 name to the right of the menu item. To specify the JES2 subsystem that the control will effect, set the name using the **Set JES2 Name and User Fields** menu item (“Set JES2 Name” on page 8-1).

```
OS/EM ----- JOB CONTROLS ----- Version 6.0
SELECTION ==>

      1 Add Notify Statement
      2 Control JES2 Commands
      3 Control Operating System Commands
      4 Dataset Name Conflict Resolution (JES2)
      5 Job Step Notify
      6 Job/Program Limits (JES2)
      7 Job Start Message (JES2)
      8 Job/Step Statistics
      9 Not Cataloged 2
     10 Reformat Jobcard Account Field
     11 Set JES2 Name and User Fields (JES2)
     12 Surrogate Passwords (JES2)
     13 Sysout Extensions (JES2)
     14 TSO Logoff Statistics
     15 Verify User Defined to RACF
     16 Verify User ID with Jobname
```

Figure 122. Job Controls

Each of these paths is presented in the following sections:

1. Add Notify Statement (see “Add Notify Statement” on page 5-141)
2. Allow JES2 Commands (see “Control JES2 Commands” on page 5-142)
3. Allow Operating System Commands (see “Control Operating System Commands” on page 5-143)
4. Dataset Name Conflict Resolution (see “Dataset Name Conflict Resolution” on page 5-144)
5. Job Step Notify (see “Job Step Notify” on page 5-145)
6. Job/Program Limits Controls (see “Job/Program Limits” on page 5-146)
7. Job Start Message (see “Job Start Message” on page 5-152)
8. Job/Step Statistics (see “Job/Step Statistics” on page 5-153)
9. Not Cataloged 2 (see “Not Cataloged 2 Correction” on page 5-156)
10. Reformat Jobcard Account Field (see “Reformat Jobcard Account Field” on page 5-158)
11. Set JES2 Name and User Fields (see “Set JES2 Name” on page 8-1)
12. Surrogate Passwords (see “Surrogate Password Control” on page 5-159)
13. Sysout Extensions (see “Sysout Extensions” on page 5-162)
14. TSO Logoff Statistics (see “TSO Logoff Statistics” on page 5-167)
15. Verify User Defined to RACF (see “Verify User Defined to RACF” on page 5-168)
16. Verify User ID with Jobname (see “Verify User ID with Jobname” on page 5-169)

Add Notify Statement

ADD NOTIFY specifies that a NOTIFY parameter is to be inserted on the job statement if it is missing. The insertion is limited to the classes specified.

```
OS/EM ----- ADD NOTIFY STATEMENT ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

      Add Notify Statement if Missing ==> NO

      Enter class or class range below to add Notify (exp:  TSO TSU A C:F)

      (CMD = (A)dd; (D)elete)
      CMD      Class
      '-----'
      ***** Bottom of data *****
```

Figure 123. Add Notify Statement

Field entry is as follows:

1. ADD NOTIFY

Enter **YES** to have OS/EM add a NOTIFY parameter to a job of it is missing, or enter **NO** to disable this option.

2. Add or Delete

To make the check universal, enter the class as **A:9**.

To enter a class, type an **A** in the CMD field and overtype the class.

To delete a previously entered class, type a **D** in the CMD field of the class to be deleted.

Control JES2 Commands

```
OS/EM ----- ALLOW JES2 COMMANDS ----- Version 6.0
COMMAND ==>

    Allow JES2 Commands ==> YES      (Yes/No)
    RACF Logging          ==> NORMAL  (None/Normal)
```

Figure 124. Control JES2 Commands

Field entry is as follows:

1. Entering **YES** specifies that a check is done to ensure that the user is authorized to submit jobs that contain JES2 commands. The user can be limited to only specified commands, all commands, or can be precluded from submitting jobs with any JES2 commands.
2. Specifying **NO** for this field disables this option.
3. Enter **NORMAL** or **NONE** to control RACF logging.

The command authorization is done by using classname **FACILITY** for RACF and **CA-ACF2**, and classname **IBMFAC** or **DATASET** for **CA-TOPSECRET**. The resource name is **JES2.\$cmd** where 'cmd' is the desired JES2 command.

Each defined command must be a single letter: with four exceptions; **\$VS**, **\$ADD**, **\$TRACE** and **\$DEL**.

If the user is not permitted to any **JES2.\$cmd** resources, the user will not be allowed to include JES2 commands in any submitted jobs. **READ** authority is required for access to the command.

Control Operating System Commands

```
OS/EM ----- ALLOW O/S COMMANDS ----- Version 6.0
COMMAND ==>

    Allow Operating System Commands ==> YES      (Yes/No)
    RACF Logging                      ==> NORMAL (None/Normal)
```

Figure 125. Control Operating System Commands

Entering **YES** specifies that a check is done to ensure that the user is authorized to submit jobs that contain operating system commands. The user can be limited to only specified commands, all commands, or can be precluded from submitting jobs with any operating system commands.

Specifying **NO** for this field disables this option.

Enter **NORMAL** or **NONE** to control RACF logging.

The command authorization is done by using classname **FACILITY** for RACF and CA-ACF2, and classname **IBMFAC** or **DATASET** for CA-TOPSECRET. The resource name is **COMMAND.cmd** where 'cmd' is the desired MVS command.

Each defined command must be in its **LONG** form; i.e., **VARY**, not **V**.

If the user is not permitted to any **MVS.command** resources, the user will not be permitted to include operating system commands in any submitted jobs. **READ** authority is required.

Dataset Name Conflict Resolution

The Dataset Name Conflict Resolution function prevents jobs from being selected for execution until all needed datasets are available. This prevents a job from taking an initiator when it is actually unable to run because datasets are already in use by another job or user. TSO **send** messages may optionally be issued to operators, the job owner and/or the owner of the dataset.

```
OS/EM --- DATASET NAME CONFLICT RESOLUTION CONTROLS - JES2 --- Version 6.0
COMMAND ==>

      DSN Conflict Resolution Active  ==> YES           (Yes/No)

      Send Message to Operator?       ==> YES           (Yes/No)
      Send Message to Job Owner?      ==> YES           (Yes/No)
      Send Message to Resource Owner? ==> YES           (Yes/No)
```

Figure 126. Dataset Name Conflict Resolution

Field entry is as follows:

1. DSN Conflict Resolution Active
Enter **yes** to activate the function or **no** to turn the function off.
2. Send Message to Operator?
Enter **yes** to have OS/EM send a message to the console listing the datasets which are unavailable.
3. Send Message to Job Owner?
Enter **yes** to have OS/EM send a message to the jobs owner notifying them that a dataset needed by their job is unavailable.
4. Send Message to Resource Owner?
Enter **yes** to have OS/EM send a message to the person who has control of the needed dataset.

Job Step Notify

The Job Step Notify panel allows you to request that OS/EM send a message at the end of each job step for non-zero return codes.

```
OS/EM ----- JOB STEP NOTIFY ----- Version 6.0
COMMAND ==>

        Produce Step End Notify ==> YES          (Yes/No)
        Minimum Return Code   ==> 7             (0 to 4096)
```

Figure 127. Job Step Notify

Field entry is as follows:

1. Produce Step End Notify

Enter **YES** to have a message sent to the user ID specified on the jobcard.

2. Minimum Return Code

If you leave the minimum return code field blank or enter zero, a message is sent for any non-zero return code. Specifying a number above zero results in a message being sent for any step with that value or higher.

Job/Program Limits

You may control the number of jobs running either by User ID or Program Name.

```
OS/EM ----- JOB/PROGRAM LIMITS CONTROLS - JES2 ----- Version 6.0
SELECTION ==>

                1  Job Limits by User
                2  Program Limits
```

Figure 128. Job/Program Limits Menu

Select the type of job limiting you want to perform.

1. Job Limits by User (see “Job Limits By User” on page 5-147)
2. Program Limits (see “Program Limits” on page 5-150)

Job Limits By User

The JOB LIMITING function enables the customer to control the number of jobs each user may have executing at a single time. This control may be for a single system, all systems in a multiple access spool environment, or specific system IDs. Additionally, the control can be limited to specific job classes, selected job names, certain user IDs and limited by time of day and day of week. Please note that all jobclasses are checked to determine the number of currently executing jobs unless limited by the SCOPE option.

```

OS/EM ----- JOB LIMITING CONTROLS ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Limiting Controls Active: YES                    (Yes/No)
RACF Resource Name:      RACF.X14
RACF logging:           NORMAL                   (Normal/None)

Limiting Scheme is:          (Yes/No/1-9) Days Class Job Job User
Liberal: NO , Conservative: NO or Weight: 4 3 1 9 Scope

S(select for update)
Limit      Max jobs      Max jobs
S Number  Active  w/other work  init idle  |---- Active Lists Types ----|
- 1       Y       1             1           |          EXC   INC   MAS
- 2       Y       3             2           |          INC   INC   LOC
- 3       N       _____
- 4       N       _____
- 5       N       _____
- 6       Y       6             6           |          INC           ID
- 7       N       _____
- 8       N       _____
- 9       N       _____
  
```

Figure 129. Job Limits

The Job Limiting Controls main entry panel has a fixed area in the top half of the panel where you enter global information about the function.

The bottom half of the panel is scrollable, and stores the information regarding the 32 limit selection groups.

Field entry is as follows:

Limiting Controls Active: ____ (Yes/No)

This field is the first field in the fixed portion of the panel. It controls whether any Job Limiting Controls are active or not. Entering NO here will turn off all Job Limiting Controls without disturbing any of the detail information previously entered.

RACF Resource Name: _____

To allow a user or group of users to bypass the Job Limiting controls enter the name of the RACF profile you have defined in the General Resource FACILITY class (for RACF and ACF-2) or the IBMFAC class (CA-Topsecret). Users to be allowed to bypass this control must have read authority to this profile.

RACF logging: _____ (Normal/None)

If you want RACF logging, enter NORMAL in this field. To turn off RACF logging, enter NONE.

Limiting Scheme is: (Yes/No/1-9) Days Class Job Job User
Liberal: ____, Conservative: ____ or Weight: _ _ _ _
Scope

When a job being submitted matches more than one selection group, the **Scheme** controls which group will be used.

If a scheme of LIBERAL is selected, the selection group which allows the most jobs to execute is used. Conversely, a CONSERVATIVE scheme will use the group which allows the least number of jobs to execute.

You may instead elect to give the different include/exclude lists additional weight by specifying a number from 1 to 9 for the list type. Weights are used when a job matches multiple selection lists. The weight of each list is calculated by adding the weight value specified for each matching include/exclude type. This means that if list 1 has a weight of 9 for user ID and a weight of 2 for the job class the total weight for list 1 would be 12 (1 for simply matching, 2 for job class and 9 for user ID = 12). The list having the highest weight would be used.

```

      Limit           Max Jobs       Max jobs
S  Number  Active  w/other work  init idle  |---- Active Lists Types ----|
_   1         Y         1           2          |  INC  EXE  INC  EXE  ID  |

```

In the above example which shows group 1, you can see that the group is active, only 1 job may execute at a time when other work is waiting to be processed; 2 jobs may execute at a time if an initiator attempts to select work, and nothing else is available to run. There are 4 active lists for the group: an include list for DAYS, an exclude list for JOB CLASSES, an include list for JOB NAMES and an exclude list for USER IDs. The scope of the group is by system IDs.

To update the number of jobs or whether a group is active, simply overwrite the fields and press enter. To update a selection group, you must place an 'S' in the select column.

Note: If using Work Load Manager (WLM) initiators, only the **Max Jobs Init Idle** limit is used as WLM initiators are normally available.

The scrollable portion of the panel contains entries for the 32 available limit selection groups.

After entering an 'S' and updating the number of jobs (if necessary), pressing the enter key will present the SELECTOR ENTRY panel.

The SELECTOR ENTRY panel allows you to specify the type of information jobs will be evaluated against.




Figure 130. Selector Entry Panel

The available selector types are:

MONDAY - SUNDAY

Allows you to specify the time of day, by day of week that JOB LIMITS controls will be active.

Enter the time as a range using a 24 hour clock. 8AM to 4PM would be entered as 0800:1600.

USERID This list may contain either user IDs which will be INCLUDED, or IDs which are to be EXCLUDED. If you specify an include type group, only those IDs, or ID masks you enter will be affected by job limits. If it is an exclude list, everyone except the entered IDs will be subject to job limits. This is the ID taken from the job card USER parameter which defaults to the ID of the submitter if not present on the job card.

JOBNAME This list contains job names or job name masks. Again this list type may be either an include or exclude list.

JOBCLASS This list contains any job classes which you may wish to have job limits limited to, or job classes which job limits will not affect.

Note: The classes specified here are only to select jobs which may have the limiting controls applied to them. They do **not** effect how jobs are counted. By default all job classes are checked for executing jobs. You may limit the classes whose jobs are counted with the SCOPE parameter explained below.

SCOPECLS This selector type controls which execution classes are to be considered when executing jobs are counted. This selector works in conjunction with the SCOPE Type setting (see below).

SYSID If SCOPE Type has been set to ID, you need to list the system IDs using this selector type.

You also specify the scope of the job limiting controls. The scope types and their function are:

MAS Multiple Access Spool. Specifying MAS will cause OS/EM to check each system in the MAS for executing jobs before allowing a job to execute.

LOCAL

Specifying LOCAL will limit the job limiting controls to only the machine where OS/EM is executing. No other system in the sysplex will be checked.

ID Enter a selector type of SYSID to specify the 4 character system ID of the LPARs in the MAS you want OS/EM to check for executing jobs.

Along with SCOPE, you may specify which classes will be used for the purpose of counting the number of active jobs a user may have running. If used, only the jobclasses specified will have their executing jobs counted. Use the selector type SCOPECLS to specify the classes to be checked.

Note: This parameter is the only way to control which jobclasses are used to count the number of executing jobs. If not specified every job executing regardless of jobclass will be counted to determine the number of jobs a user currently has executing.

For example if job class 'A' is the only class listed here, only jobs executing in class 'A' will be counted even if you are limiting jobs in another class. This means that if your are limiting jobs running in job class 'D' and the SCOPE is set for job class 'A', your users will be able to run as many jobs as the want in class 'D' as long as they keep the number of their jobs executing in class 'A' below the limit specified.

It is suggested that if you are limiting jobs that can execute in a particular job class, that you have the matching job class specified in SCOPECLS as well.

Program Limits

The Program Limits function allows you to control how many copies of a program may be run concurrently.

Note: This function must be specified for each JES2 subsystem you have executing to limit programs by LPAR. See “Set JES2 Name” on page 8-1.

```
OS/EM ----- PROGRAM LIMITS - JES2 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Program Limits Active ==> YES                      (Yes/No)

Produce MAS Limit Changed Message ==> YES         (Yes/No)

(I)nsert (D)elete

--Limits--
S Active  Program   Local  MAS  Description
_  YES    IEFBR14   10    10
_  YES    SAS        1     2    Uses lots of resources.
***** Bottom of data *****
```

Figure 131. Program Limits Entry Panel

The top portion of this panel contains two fields:

- **Program Limits Active**
Enter **YES** to enable this function or **NO** to disable it.
- **Produce MAS Limit Changed Message**
Enter **YES** to enable message OS\$2LM264 which has the format:

```
OS/EM sysname pgmname PGM LIMITS(xx xx) SET BY SYSTEM sysname JOB jobname.
```

The bottom portion of the panel contains a scrollable area listing all the programs which are being controlled.

Two line commands are available for this portion of the panel.

- I** Inserts a blank line to allow entry of program information.
- D** Deletes existing program information.

To control a program, insert a blank line then type the information required:

Active Enter **YES** to have this entry controlled. You may mark an existing entry **NO** to have OS/EM ignore the listed information, but not lose it so you may reactivate the entry at a later time.

Program The name of the program to be controlled.

Local Limit Enter the number of concurrently executing copies of the program allowed.
Leaving this field blank effectively marks the program as having no local limits.

MAS Limit Enter the number of concurrently executing copies of the program allowed within the MAS.
Leaving this field blank effectively marks the program as having no MAS limits.

Description An optional description line possibly used to explain why you are limiting this program (license restrictions; resource hog).

All programs executing on the system are counted, however only batch jobs will be blocked from execution if the number of running programs is above the limits specified above.

Note: The **MAS** value is propagated to each system within the MAS which has Program Limiting active when you execute your changes online.

Job Start Message

The Job Start Message function of OS/EM sends a message to the TSO ID of the user specified in the NOTIFY parameter of the job card.

The message is sent when the job actually starts executing.

```
OS/EM ----- SET JOB START MESSAGE ----- Version 6.0
COMMAND ==>

                Job Start Message Active ==> YES    (Yes/No)
```

Figure 132. Job Start Message

Field entry is as follows:

Enter a **YES** to activate this function.

Enter a **NO** to deactivate it.

Job/Step Statistics

Job/Step Statistics specifies that OS/EM will place job and/or step ending statistics in the job log for the job. The statistics will show the amount of storage the step used; I/O counts by step DDNAME; the elapsed time of the step; return code of the step; etc.

The statistics are controlled by job class (including TSO, TSU, and STC).

You may also specify a text string which will be used to replace the condition code field for any steps which have been flushed by the operating system.

Note: STEPENDSTATS and/or JOBENDSTATS must be enabled to allow printing of **Estimated Costs** if this option has been selected (See “Estimated Costs Controls” on page 5-193.)

```

OS/EM ----- JOB/STEP STATISTICS ----- Version 6.0
Command ==>                                     SCROLL ==> CSR

    Firm Name Printed? ==> YES
                                ==> ASSOCIATED THIRD PARTY
                                ==> ADMINISTRATORS
                                ==> MANAGEMENT INFORMATION SYSTEMS

    Flushed Step Text  ==> _____ (Default is ----)

    Extend Step End WTO Message? ==> ____ (Yes/No)

SEL = (S)elect for update)
SEL  Enabled  Message Type      Specify Classes (A:9 TSU STC)
'    YES      ABENDMSG          F   K:L  P:Q  ___  ___  ___  ___  ___
    ___  ___  ___  ___  ___  ___  ___  ___  ___  ___
'    YES      CANCELWTO        A:9  ___  ___  ___  ___  ___  ___  ___
    ___  ___  ___  ___  ___  ___  ___  ___  ___  ___
'    YES      STEPENDSTATS     A:9  ___  ___  ___  ___  ___  ___  ___
    ___  ___  ___  ___  ___  ___  ___  ___  ___  ___
'    YES      STEPENDWTO       A:9  ___  ___  ___  ___  ___  ___  ___
    ___  ___  ___  ___  ___  ___  ___  ___  ___  ___
'    YES      JOBENDSTATS      A:9  ___  ___  ___  ___  ___  ___  ___
    ___  ___  ___  ___  ___  ___  ___  ___  ___  ___
'    YES      JOBENDWTO        A:9  ___  ___  ___  ___  ___  ___  ___
    ___  ___  ___  ___  ___  ___  ___  ___  ___  ___

```

Figure 133. Job/Step Statistics

Field entry is as follows:

1. FIRM Name printed

To enable printing of your company's name in the Job/Step Statistics box, enter **YES**.

Enter **NO** to disable printing.

Three name lines are allowed. Each name line may contain up to 40 characters each. You may enter **any characters** you wish.

2. Flushed Step Text

By default, OS/EM displays 4 dash marks as the condition code for any step which the system has flushed. To have OS/EM print a text string, enter the string here. It may be up to 8 characters long.

3. Extend Step End WTO Message?

Entering **YES** here **and** selecting **STEPENDWTO** below will add the CPU time and I/O counts to the message generated at the end of each step.

Note: This field is ignored unless the STEPENDWTO option is also selected.

4. CLASS

Enter the job classes that the selected message will be active. The classes may be entered individually, or as a range (i.e. A:D would be the same as specifying A, B, C and D individually.)

5. ABEND MSG

Specifying this option if you wish job abend messages to remain on the console, requiring that the operator specifically delete the message from the console (this will ensure that the operator sees the message before it rolls off the console screen).

Enter **YES** to activate this option.

Enter **NO** to deactivate this option.

6. CANCEL WTOR

Specify this option if you wish the operator to be forced to enter the reason a job was cancelled.

Enter **YES** to activate this option.

Enter **NO** to deactivate this option.

7. STEPEND STATS

This option specifies that step end statistics be produced and placed in allocation message log.

Enter **YES** to activate this option.

Enter **NO** to deactivate this option.

8. STEPEND WTO

This option specifies that the return code from each completed job step or job end will be placed in the JES2 message log.

Enter **YES** to activate this option.

Enter **NO** to deactivate this option.

Note: If classes TSU or STC are selected the operating system may additionally issue an IEF170I message at execution time for these tasks. This message may be ignored and added to your MPF PARMLIB member or automated operations product for suppression.

9. JOBEND STATS

This option specifies that job end statistics are to be produced and placed in the allocation message log.

Enter **YES** to activate this option.

Enter **NO** to deactivate this option.

10. JOBEND WTO

This option specifies that the highest step return code for a job, Job CPU time, and elapsed Job time will be placed in the JES2 message log.

Enter **YES** to activate this option.

Enter **NO** to deactivate this option.

Note: If classes TSU or STC are selected the operating system may additionally issue an IEF170I message at execution time for these tasks. This message may be ignored and added to your MPF PARMLIB member or automated operations product for suppression.

Not Cataloged 2 Correction

With this option, OS/EM allows you to avoid receiving **Not Cataloged 2** errors. OS/EM will attempt to correct a **Not Cataloged 2** error by one of three means:

- OS/EM will delete and uncatalog the previous version of the file causing the error and redrive the catalog request.
- OS/EM will uncatalog the previous version of the file causing the error and then redrive the catalog request.
- OS/EM will fail the job receiving the error.

```
OS/EM ----- NOT CATALOGED 2 CONTROLS ----- Version 6.0
COMMAND ==>

      Not Cataloged 2 Controls Active ==> YES      (Yes/No)

      Operate in Warn Mode           ==> NO       (Yes/No)

CMD ACTIVE FUNCTION      |----- JOB CLASSES SELECTED -----|
_  YES  Delete Files      #####DEF#H#####
_  YES  Recatalog Files   #####J#K#L#N#####
_  YES  Fail Jobs         #####P#Q#R#U#####

(CMD = (S)elect for update; (C)lass set/modify)
```

Figure 134. Not Cataloged 2 Controls

Field entry is as follows:

1. Controls Active

Enter **YES** to enable OS/EM control of **Not Cataloged 2** errors.

Enter **NO** to disable controls.

2. Operate in Warn Mode

WARN mode provides you with a way of observing your **Not Cataloged 2** controls without changing the result of a jobs dataset allocation. WTO messages are produced which will indicate the action OS/EM would have taken if WARN mode were not in effect.

3. Delete Files

To have OS/EM **delete** an existing file and redrive the catalog request, place a **C** in the CMD field, enter **YES** in the ACTIVE field then press the Enter key. A popup window will open to allow you to enter the job classes that the Delete function will be monitor.

Reformat Jobcard Account Field

```
OS/EM ----- JOB CARD ACCOUNT FIELD ----- Version 6.0
COMMAND ==>

      Reformat Job card Account Field ==> NO      (Yes/No)
```

Figure 136. Reformat Jobcard Account Field

Field entry is as follows:

1. Entering **YES** specifies that account numbers of the form (XX-YY), 'XX-YY', and XX-YY are to be converted to (XX,YY). That is, remove surrounding apostrophes or replace with parentheses if none are present, and convert dashes to commas.
2. Specifying **NO** for this field disables this option.

Surrogate Password Control

Surrogate password control through OS/EM is intended to supply passwords to jobs submitted by started tasks, TSO users, or other batch jobs so that these jobs can properly access RACF protected datasets.

This panel also controls whether password information will be added to jobs sent over a JES network and whether a password of 1 to 8 question marks found on a jobcard will be replaced with the user's password.

```
OS/EM ----- SURROGATE PASSWORD CONTROL ----- Version 6.0
COMMAND ==>

Password Controls are active    ==> YES      (Yes, No)

Password Dataset Name          ==> 'SYSX.NEWPASS'
Delete or Load Password Dataset ==> LOAD    (Delete, Load)

Add password to jobs           ==> YES      (Yes, No)
Replace ???????? with password ==> NO      (Yes, No)

Allow surrogate password processing for listed:
Jobnames      ==> _____
Started Tasks ==> YES      Enter JOB, STC or TSU on Command line
TSO Users     ==> YES      to update name lists
```

Figure 137. Surrogate Password Control

Field entry is as follows:

1. Password Controls

Password controls activates the optional OS/EM password function.

Enter **YES** to enable this function.

Enter **NO** to disable this function.

2. Password Dataset Name

The OS/EM password dataset consists of one statement per user ID, with the user ID in positions 1-8 and the password in positions 10-17. The user ID is defined to RACF and the password is the RACF password for that user ID. This dataset is user maintained via ISPF EDIT and should be RACF protected to limit access to authorized users.

Use the file attributes: RECFM=FB,LRECL=80,BLKSIZE=0, to allocate the password dataset.

The default password dataset name is SYS1.RACFPASS.

Note: The User ID that is set in the password dataset has to be defined to RACF, and should have its password set up as "PASSWORD NOINTERVAL" in order to insure that the User ID password never expires.

3. Delete or Load Password

Requests that the OS/EM password dataset be deleted, loaded or reloaded.

4. Add Password to Jobs

Jobs sent over a JES network require password information be present on the jobcard. If you would like OS/EM to check for passwords and insert them if missing, enter **YES**.

5. Replace ???????? with Password

OS/EM can check for question marks on a jobcard and, if found, replace them with the user's password. This allows jobcards to be stored in an unprotected dataset, submitted for execution, and still prevent others from learning a user's password.

6. Allow Surrogate Password Processing

Entries for Jobnames, Started Tasks, and TSO Users specify that password insertion processing is to be active for jobs submitted by other jobs.

Enter **YES** to enable processing.

Enter **NO** to disable processing.

7. Command Line

An optional list of names can be specified which will limit password checking to the named job, STC, or user. If this list is omitted, all STCs jobs or users will have passwords added to the jobs they submit.

Enter **JOB**, **STC** or **TSU** on the command line to access the name lists.

Started task names, job names, and TSO user IDs may be specified with mask characters:

Job Name Masks

The following table shows the allowable mask characters:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

When a selection is made, the next panel will reflect your choice and the verbiage on the panel will also reflect your choice. In Figure 138, the choice was STC and the panel verbiage reflects STC. The same panel will appear for the other choices, JOB and TSU, but the verbiage will be different.




Figure 138. Job Name List - STC

Surrogate Password Use

The intended use of this function is to supply passwords to jobs submitted by started tasks, TSO users, or other batch jobs so that these jobs can properly access RACF protected datasets. Your installation

might, for example, have a job scheduling system installed. If you run it as a started task, and name it via this command, jobs which this scheduling system submits would be eligible to have passwords added to the JOB statement.

This can avoid some audit and operational exposures associated with every job submitted by the Scheduling System having the highest level of access that is required for one job or system like system backups which require RACF OPERATION privilege.

The password will be added if the submitted job's JOB statement has a USER=userid parameter that matches a USER ID in the OS/EM password dataset.

Typically, you would define one or more user IDs that represent your production jobs. These user IDs would have RACF access to production datasets. Jobs which your scheduling system submits would have a JOB statement that included the USER=userid parameter. The OS/EM password dataset would include statements with these user IDs and their associated RACF passwords. When such jobs are submitted, the appropriate password would be added.

You can create as many user IDs as are necessary within your installation.

The OS/EM password dataset consists of one statement per user ID, with the user ID in positions 1-8 and the password in positions 10-17. The user ID is defined to RACF and the password is the RACF password for that user ID. The dataset is user maintained and should be RACF protected to limit access to authorized users only.

It is your responsibility to keep this password dataset current and correct. OS/EM will use whatever password is indicated for the user ID. If the password is not correct for the user ID, the submitted job will fail with a password violation.

Note: To keep the password dataset maintenance to a minimum, the RACF password for each user ID you define should be specified as NEVER CHANGE.

Sysout Extensions

The Sysout Extension Control function of OS/EM allows you to give extensions to jobs that go over the line limit defined on an OUTLIM JCL parameter, or the JES2 initialization parameters ESTLNCT, ESTPAGE or ESTBYTE. The control can be by jobname, program name, job class or SYSOUT class. It may also be controlled by RACF resource.

There may be up to 32 different extension groups, and you may weight the different classes/names to help the selection of the group which will be used.

```

OS/EM ----- SYSOUT EXTENSION CONTROLS ----- Version 6.0
SELECTION ==>

          1 Control by JES2 Params      ( current subsystem: JES2      )

          2 Control by OUTLIM parameter
    
```

Figure 139. Sysout Extension Controls Menu

Select either **Control by JES2 Params** or **Control by OUTLIM parameter** to get to the entry panel.

Control by JES2 Params

```

OS/EM ----- JES2 SYSOUT EXTENSION CONTROLS ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Extension Controls Active:  YES                                     M
RACF Resource Name:        SYSOUT.EXTEN                          E
RACF logging:              NORMAL                                (Normal/None)          C S
                                                                    L S

----- Extension -----   WTO When   WTO After   J   P   A   A
Lines  Pages  Bytes  Granted   How Many  O   G   S   G
RACF:   5000   11   11000  YES      ---      B   M   S   E
Defaults: 10000 20   99999  YES      ---
S(select for update)                                     Weight: (1234)  1   2   3   4
S  Ext Active
- 1   Y  1000  33   _____  YES      3      INC  INC  INC  INC
- 2   Y  9999  _____  YES      ---      INC
- 3   N  _____  _____  _____  ---
- 4   N  _____  _____  _____  ---
- 5   N  _____  _____  _____  ---
- 6   N  _____  _____  _____  ---
- 7   N  _____  _____  _____  ---
- 8   N  _____  _____  _____  ---
- 9   N  _____  _____  _____  ---
- 10  N  _____  _____  _____  ---
- 11  N  _____  _____  _____  ---
    
```

Figure 140. JES2 Sysout Extension Controls

Field entry is as follows:

1. Extension Controls Active

Enter **YES** to enable JES2 Sysout Extensions, or **NO** to disable them.

2. RACF Resource Name

Enter the resource name that has been defined to RACF for extension control. This name must be defined in the general resource FACILITY class for RACF and CA-ACF2 or the IBMFAC class for CA-Topsecret. Users who will be granted extensions must be given READ access to this profile.

Note: This resource is only checked if there are no matches with the selection groups defined below. This includes the DEFAULT group. Therefore if you want to control Sysout Extensions via your Security Manager the DEFAULT group must be left blank.

3. RACF Logging

Enter **NORMAL** to have RACF logging, or **NONE** to turn off logging.

4. The following fields are used for RACF control, defaults and for the 32 possible selection groups.

Note: If a job does not match any selection group and there is no DEFAULT, and you have not specified a RACF resource name, the job will use the values defined in your JESPARMS member.

		---- Extension ----			WTO When	WTOR After
		Lines	Pages	Bytes	Granted	How Many
RACF:		5000_	11__	50000	YES	15
Defaults:		10000	20__	99999	YES	50
S	Ext Active					
_	1 Y	15000	30__	99999	YES	5_
_	32 N	_____	_____	_____	_____	_____

5. Extension Lines

Enter the number of lines that the job will be given each time an extension is granted.

6. Extension Pages

Enter the number of pages that the job will be given each time an extension is granted.

7. Extension Bytes

Enter the number of bytes that the job will be given each time an extension is granted.

8. WTO When Extension Granted

You may elect to have OS/EM send a message to the operator each time an extension is granted. Enter Yes or No in this field.

9. WTOR After How Many

To ensure that a job doesn't get over looked while extensions are being granted, you may elect to have OS/EM issue a WTOR to force the operator to allow the extension to be granted.

To update these fields for RACF or Defaults or one of the 32 selection groups, simply overwrite the previously entered information.

10. Weight

Each of the 32 selection groups may have selection lists attached to them. The different list types are: Job name, Program name, Job class and Sysout class. You must enter the weight that is to be given to each type of list. This weight will be used when a job matches more than one selection group. Enter 1, 2, 3 or 4 for each list type.

For job name and program name, you either specify the exact name or use a name mask.

Job classes and SYSOUT classes may be entered as individual classes or as a range, i.e. 1:4 specifies classes 1, 2, 3 and 4.

To update any of these lists, simply enter an **S** in the select column and press enter. Another panel will be presented to allow update of the selectors.

```

OS/EM ----- SELECTOR ENTRY - 1 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enter Selector Types, either Include or Exclude
      Jobclass ==> INCLUDE      Jobname  ==> INCLUDE
      Pgmname  ==> INCLUDE      Sysout   ==> INCLUDE

Line Cmds: (D)elete line, (I)nsert line

  Selector
  Type      Selector Names/Mask List
- JOBCLASS  P
- JOBNAME   TRSWJ- TRSMJ-
- PGMNAME   TRP030 TRP190
- SYSOUT    V
***** Bottom of data *****

```

Figure 141. JES2 Sysout Extension Selectors

This panel is displayed each time one of the selection groups is selected for update.

Each list type may be either an include list or an exclude list. For example if you have an include list of job classes which contains 6:9, only jobs running in class 6, 7, 8 or 9 will be selected by this extension group. If it were an exclude list, jobs in class A through 5 would be eligible.

The allowable selector types are:

JOBCLASS Enter jobclass as individual classes or a class range. A range is two classes separated by a colon (:).

JOBNAME Jobnames may be entered as individual jobnames, or you may use jobname masks.

PGMNAME Program names may be entered as individual programs or you may use program name masks.

SYSOUT Enter sysout classes as individual classes or a class range. A range is two classes separated by a colon (:).

For any of these lists, you may enter as many items as needed on a line separated with spaces. If you have more items than will fit on a single line, simply insert another line and use the same selector type.

Control by OUTLIM parameter

```

OS/EM ----- SYSOUT EXTENSION CONTROLS ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Extension Controls Active: YES
RACF Resource Name:      RACF.IEFUSO              S
RACF logging:           NORMAL                    (Normal/None)      C Y
                                                                L S

           Extension      WTO When      WTOR After      J   P   A   O
           Lines          Extension Granted  How Many      O   G   S   U
RACF:      444            YES              4              B   M   S   T
Defaults:  1000          YES
S(select for update)
S  Ext Active      Weight: (1234)  4   3   1   2
- 1   Y   5200            - Active Lists -
- 2   -   _____            EXC  EXC  INC  INC
- 3   -   _____
- 4   -   _____
- 5   -   _____
- 6   -   _____
- 7   -   _____
- 8   -   _____
- 9   -   _____
- 10  -   _____

```

Figure 142. Sysout Extension Controls

Field entry is as follows:

1. Extension Controls Active

Enter **YES** to enable Sysout Extensions, or **NO** to disable them.

2. RACF Resource Name

Enter the resource name which has been defined to RACF for extension control. This name must be defined in the general resource FACILITY class for RACF and CA-ACF2 or the IBMFAC class for CA-Topsecret. Users who will be granted extensions must be given READ access to this profile.

3. RACF Logging

Enter **NORMAL** to have RACF logging, or **NONE** to turn off logging.

4. The following fields are used for RACF control, as defaults and for the 32 possible selection groups.

	Extension	WTO When	WTOR After
	Lines	Extension Granted	How Many
RACF:	1500_	YES	15
Defaults:	1000_	NO_	15
S Ext Active			
_ 1	Y 15000	YES	5_
_ 32	N _____	_____	_____

5. Extension Lines

Enter the number of lines that the job will be given each time an extension is granted.

6. WTO When Extension Granted

You may elect to have OS/EM send a message to the operator each time an extension is granted. Enter Yes or No in this field.

7. WTOR After How Many

To ensure that a job doesn't get overlooked while extensions are being granted, you may elect to have OS/EM issue a WTOR to force the operator to allow the extension to be granted.

To update these fields for RACF or Defaults, simply overwrite the previously entered information.

8. Weight

Each of the 32 selection groups may have selection lists attached to them. The different list types are: Job name, Program name, Job class and Sysout class. You must enter the weight that is to be given to each type of list. This weight will be used when a job matches more than one selection group. Enter 1, 2, 3 or 4 for each list type.

For job name and program name, you either specify the exact name or use a name mask.

Job classes and SYSOUT classes may be entered as individual classes or as a range, i.e. 1:4 specifies classes 1, 2, 3 and 4.

To update any of these lists, simply enter an **S** in the select column and press enter. Another panel will be presented to allow update of the different lists.

```
OS/EM ----- SELECTOR ENTRY - 1 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enter Selector Types, either Include or Exclude
          Jobclass ==> INCLUDE      Jobname  ==> INCLUDE
          Pgmname  ==> INCLUDE      Sysout   ==> INCLUDE

Line Cnds: (D)delete line, (I)nsert line

  Selector
  Type      Selector Names/Mask List
- JOBCLASS  P
- JOBNAME   TRSWJ- TRSMJ-
- PGMNAME   TRP030 TRP190
- SYSOUT    V
***** Bottom of data *****
```

Figure 143. Sysout Extension Lists

This panel is displayed each time one of the selection groups is selected for update.

Each list type may be either an include list or an exclude list. For example if you have an include list of job classes which contains 6:9, only jobs running in class 6, 7, 8 or 9 will be selected by this extension group. If it were an exclude list, jobs in class A through 5 would be eligible.

The allowable selector types are:

JOBCLASS Enter jobclass as individual classes or a class range. A range is two classes separated by a colon (:).

JOBNAME Jobnames may be entered as individual jobnames, or you may use jobname masks.

PGMNAME Program names may be entered as individual programs or you may use program name masks.

SYSOUT Enter sysout classes as individual classes or a class range. A range is two classes separated by a colon (:).

For any of these lists, you may enter as many items as needed on a line separated with spaces. If you have more items than will fit on a single line, simply insert another line and use the same selector type.

TSO Logoff Statistics

TSO Logoff Statistics specifies that OS/EM will display TSO session statistics at logoff time.

```
OS/EM ----- LOGOFF STATISTICS ----- Version 6.0
Command ==>                                     Scroll ==> CSR

Provide TSO Logoff Statistics? ==> YES           (Yes/No)
Number of seconds to display? ==> 1             (1 - 99)
```

Figure 144. Logoff Statistics

Field entry is as follows:

1. Provide TSO Logoff Statistics

To enable TSO Logoff Statistics enter **YES**, to disable, enter **NO**.

2. Number of seconds to display

Enter the **number of seconds** to display the TSO Logoff Statistics. Valid entries are **1 to 99**. This field is required if you entered YES above.

Verify User Defined to RACF

```
OS/EM ----- USER/RACF CHECK ----- Version 6.0
COMMAND ==>

Verify User is defined to RACF ==> NO      (Yes/No)
```

Figure 145. Verify User Defined to RACF

Field entry is as follows:

1. Entering **YES** specifies that a check is done to ensure that the user is defined to your security system (RACF, CA-TOPSECRET, CA-ACF2).
2. Specifying **NO** for this field disables this option.

Verify User ID with Jobname

USERID/JOBNAME check specifies that the first characters of the jobname match the TSO USER ID. The check is limited to the classes specified.

```
OS/EM ----- USERID/JOBNAME CHECK ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Verify Jobname Starts With User ID ==> YES   (Yes/No/Blank)
Number of characters to compare ==>         (1 to 7 or blank)

RACF Resource name ==> IKJEFF10.RACF         (exp: IKJEFF10.RACF)
RACF Logging ==> NONE                       (None/Normal)

Enter class or class range below to limit verification (exp: A C:F)

(CMD = (A)dd; (D)elete)
CMD      Class
'        A:9
'        STC
'        TSU
***** Bottom of data *****
```

Figure 146. Verify UserID with Jobname

Field entry is as follows:

1. VERIFY JOBNAME

Enter **YES** to cause OS/EM to verify User ID to Jobnames. Enter **NO** to turn this option off.

2. Number of characters to compare

Enter the number of characters of the User ID that will be used to compare it to the jobname. If blank, the full length of the User ID will be used.

3. RACF Resource name

Enter the name of the RACF resource which has been defined to control this option. Leave blank to have control strictly by class.

This resource must be defined in the general resource FACILITY class for RACF and CA-ACF2 or IBMFAC for CA-Topsecret. Users must have READ access to this profile to allow job submission using a job name not matching their TSO ID. Only job classes specified below will be security checked.

4. RACF Logging

Enter **NORMAL** to have RACF logging, or **NONE** if logging is not required.

5. Add or Delete

To make the check universal enter the class as **A:9**.

To enter a class, type an **A** in the CMD field and overwrite the class.

To delete a previously entered class, type a **D** in the CMD field of the class to be deleted.

If a security resource name is supplied a RACHECK will be performed for any job submitted in the specified class(es).

Job Routing Controls

Description

The optional **Job Routing** function allows job routing between CPU's in a JES2 MAS based on defined resource names and their availability. Use the \$QA and \$QD commands to manage resource names on each system running OS/EM Job Routing (See "Appendix F. JES2 Commands for Job Routing" on page F-1) The routing may be controlled by JCL statements placed within the JOBLIB member, or by specifying routing control information through the OS/EM Job Routing Controls function.

Note: There may be a maximum of **127** routes per job. This is a combination of JCL statements and OS/EM automated routing.

This function may also be used to change the Workload Manager service class that would normally be assigned to a job, override the specified jobclass or priority specified on the jobcard and change the Workload Manager scheduling environment.

Note: If a valid JES2 NODE is found on a */*ROUTE XEQ nodename* card the job is routed to the specified node **before** OS/EM has access to the job. Therefore **no** OS/EM changes will be processed on the system where the job was submitted. If OS/EM job routing is active on the node where the job was routed, OS/EM changes will be effective there.

Refer to the **EXIT5** section of the **JES2** command in the **OS/EM Reference Manual** for more information on this function.

The \$HASP message numbers produced by the OS/EM implementation of the Mellon Modifications may also be changed. This feature is provided for customers who would like to see the original Mellon message numbers. Although Mellon had originally reused IBM message numbers, the OS/EM implementation tries to avoid this where possible. This feature allows you to specify the message number you want to appear for selected messages.

Note: The Job Routing Communications dataset must be on DASD shared by each JES within the MAS, and must be a unique dataset for each MAS or independent system running Job Routing. Failure to have unique datasets will result in unpredictable results/failures. Additionally the Job Routing function must be enabled on each LPAR within a MAS concurrently. Failure to do so will result in jobs not being allowed to execute on LPARs where Job Routing is active if they have been through the interpreter on a LPAR without Job Routing. Conversely, LPARs within the MAS without Job Routing active may select jobs for execution without the specified resources.

Job Routing/Classing Controls Menu

```
OS/EM ----- JOB ROUTING/CLASSING CONTROLS - JES2 ----- Version 6.0
SELECTION ==>

          1 System Level Controls
          2 JECL Defaults
          3 Message Number Substitution
          4 Resource Routing Groups

          5 Change Jobclass/Priority Groups
          6 Change Scheduling Environment Groups
          7 Change SRVCLASS Groups
          8 Change XEQ Node Groups

          9 Set JES name / currently: JES2
```

Figure 147. Job Routing/Classing Controls Menu

Each of these paths is presented in the following sections:

1. System Level Controls (see “System Level Controls” on page 5-172)
2. JECL Defaults (see “JECL Defaults” on page 5-174)
3. Message Number Substitution (see “Message Number Substitution” on page 5-176)
4. Resource Routing Groups (see “Job Routing Resource Groups” on page 5-177)
5. Change JOBCLASS Groups (see “Change Jobclass/Priority Groups” on page 5-181)
6. Change SCHEDENV Groups (see “Change Scheduling Environment Groups” on page 5-183)
7. Change SRVCLASS Groups (see “Change SRVCLASS Groups” on page 5-185)
8. Change XEQ Node Groups (see “Change XEQ Node Groups” on page 5-187)
9. Set JES name (see “Set JES2 Name” on page 8-1)

System Level Controls

This panel allows you to completely turn off the Job Routing Controls without deleting any of the control information previously entered. You also specify the name of the dataset containing your resource name information here.

```
OS/EM ----- JOB ROUTING SYSTEM LEVEL CONTROLS - JES2 ----- Version 6.0
COMMAND ==>

Resource DSN ==> 'SYSX.JOBROUTE.TEST.RESOURCE'

Job Routing Active ==> YES      (Yes/No)
(Controls job routing via JECL statements, automatic routing and
SRVCLASS/JOBCLASS changes)

Automatic Routing Active ==> YES (Yes/No)
(Controls generation of routing statements based upon specified
selection criteria, as well as SRVCLASS/JOBCLASS changes)

Default Resource ==> DEFAULT.RESOURCE.NAME_____
(Any job without a resource attached to it will receive this resource.)

Convert SCHENV JOBCARD parameter to OS/EM Route?      ==> NO (Yes/No)
(Workload Manager Scheduling Environments replaced by OS/EM
/*ROUTE card using SCHENV as ROUTE name)

Convert SYSAFF=name to SYSAFF=ANY if OS/EM Route present? ==> NO (Yes/No)
(Execution time only, original SYSAFF used for JCL conversion)
```

Figure 148. System Level Controls

Data entry is as follows:

1. Job Routing Active
2. Resource DSN

Enter the dataset name of the sequential file which will store the resource name information.

Each CPU in the sysplex must share this dataset. The dataset format must be: Physical Sequential, Record format of F and have a logical record length of 4504. The dataset requires three (3) tracks.

3. Job Routing Active

Specify either **YES** or **NO** here.

No OS/EM routing functions will be available unless this field is marked YES.

4. Automatic Routing Active

Specify either **YES** or **NO** here.

If you enter NO but enter YES for Job Routing, only routing via JECL will be active. This field controls automatic routing as well as the ability to change various routing information.

5. Default Resource

To have a resource name attached to any job which either does not have an OS/EM routing card (/*ROUTE XEQ resource) in the JCL or does not match an automatic routing group simply enter the **resource name** here.

To disable a default resource previously specified, simply blank out this field.

6. Convert SCHENV JOBCARD parameter to OS/EM Route?

Specifying **YES** will cause OS/EM to scan for the keyword SCHENV= on the JOBCARD statement and remove it. It then inserts an OS/EM Job Routing JECL statement using the scheduling environment name just removed as the resource name.

Note: If you are using OS/EM Job Routing to assign a Scheduling Environment based on some selection criteria it will still be assigned, as that processing occurs after any original SCHENV keyword has been converted to a route statement. This means that your jobs could end up having a route statement with the original scheduling environment name as the resource and a SCHENV keyword generated based on your selection criteria.

7. Convert SYSAFF=name to SYSAFF=ANY if OS/EM Route present?

Specifying **YES** will cause OS/EM to set a job's system affinity (SYSAFF) to **ANY**, if, and only if, the job has been assigned one or more OS/EM Job Route resources. The job route resources may be from either JECL control cards (/ROUTE XEQ resource) or automatically generated.

Note: You may use both SCHENVCONVERT and SYSAFFANY. The system affinity change occurs after any schedule environments have been replaced with ROUTE statements.

Additional notes:

- a. It is highly recommended that this option be activated if Resource Routing is being utilized.
- b. JES2 will continue to use the original SYSAFF specification to determine where JCL conversion takes place. Setting the SYSAFF to ANY occurs after JCL conversion and prior to queuing the job for execution.
- c. The independent mode status is not affected by this option. In other words, if the job routing condition is met, a job with SYSAFF=(CPU1,IND) would be changed to SYSAFF=(ANY,IND). In this way systems can be placed into independent mode and still participate fully in resource routing.

JECL Defaults

This option allows you to specify system wide defaults for the various JECL statements used for job routing and scheduling.

```
OS/EM ----- JOB ROUTING JECL DEFAULTS - JES2 ----- VERSION 6.0
COMMAND ==>

CNTL Default ==> SHR      (SHR/EXC)  THREAD Default ==> SHR      (SHR/EXC)

AFTER Statement Actions: (Ignore/Fail/Wait/OK/Cancel/Hold)
No Job          => IGNORE (I/F/W)    No Specific Job => FAIL   (I/F)
Multiple Jobs => OK      (I/F/OK)    Impossible Job => CANCEL (I/C/H)

BEFORE Statement Actions: (Ignore/Fail/OK)
No Job          => OK      (I/F/OK)    No Specific Job => FAIL   (I/F)
Multiple Jobs => OK      (I/F/OK)

EXCLUDE Statement Actions: (Ignore/Fail/OK)
No Job          => OK      (I/F/OK)    No Specific Job => FAIL   (I/F)
Multiple Jobs => OK      (I/F/OK)

PRED Statement Actions: (Ignore/Fail/Wait/OK/Cancel/Hold)
No Job          => IGNORE (I/F/W)    No Specific Job => FAIL   (I/F)
Multiple Jobs => OK      (I/F/OK)    Impossible Job => CANCEL (I/C/H)

WITH Statement Actions: (Ignore/Fail/Wait/OK/Cancel/Hold)
No Job          => WAIT   (I/F/W)    No Specific Job => FAIL   (I/F)
Multiple Jobs => OK      (I/F/OK)    Impossible Job => CANCEL (I/C/H)
```

Figure 149. JECL Defaults

Field entry is as follows:

- CNTL Default
- THREAD Default

The **CNTL** and **THREAD** statements work identically. Each may have its own default action. To have exclusive control of a resource or dataset specified with this statement, use the **EXC** default setting. To allow shared access as the default, enter **SHR**.

Each of the remaining JECL statements are processed in the same way. The **Impossible Job** parameter is not available for the **BEFORE** or **EXCLUDE** statements.

- No Job

This parameter allows you to specify the default action to be performed if the specified job is not in the execute queue. The available options are **ignore**, **fail** or **wait**.

- No Specific Job

This parameter allows you to specify the action to be taken if the specific job (job name with job number) is not in the execute queue. The available options are **ignore** or **fail**.

- Multiple Jobs

This parameter allows you to specify the default action to be performed if there are multiple matching job names in the system. The available options are **ignore**, **fail** or **OK**.

- Impossible Job

This parameter allows you to specify the default action to be taken if the specific job name and job number specified has already left the execution queue. i.e. the request of **AFTER**, **PRED** or **WITH** is impossible to fulfill. The available options are **ignore**, **cancel** or **hold**.

The meanings of the different options are:

- **Cancel**
Indicates that the job will be cancelled. i.e. **\$PJOBxxxx**.
- **Fail**
Indicates that the job is to be failed by passing a return code of 12 back to JES2.
- **Hold**
Indicates that the job will be placed on hold. Operator intervention will be required to release or cancel the job.
- **Ignore**
Indicates that the card is to be treated as a comment.
- **OK**
Indicates that the statement will apply to all jobs with the specified jobname.
- **Wait**
Indicates that the job should wait for the specified jobname to be read into the system.

Message Number Substitution

This option is provided for backward compatibility with the original version of the Mellon Modifications. It is primarily intended for customers who feel that having the original Mellon Message Numbers appear will avoid any confusion with previously trained staff, and allow the continued use of any automated operations package that has already been setup to expect specific message numbers.

```
OS/EM ----- MELLON MESSAGE SUBSTITUTION - JES2 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Message Substitution Active ==> YES           (Yes/No)

Line Cmds: (S)elect for update

   OS/EM   Replacement
Sel Msg number Msg number  Message Text
-   606     _____  INSUFFICIENT OPERANDS
-   610     710          _____  JOB(S) NOT FOUND
-   619     _____  _____  NO OUTPUT QUEUED
-   624     724          _____  'CMD' 'JOBNAME' MULTIPLE JOBS FOUND
-   646     _____  _____  NN PERCENT SPOOL UTILIZATION
-   668     _____  _____  NO DEVICE(S) FOUND
-   687     _____  _____  UNABLE TO OBTAIN SECURITY PRODUCT MESSAGES
```

Figure 150. Mellon Message Substitution

When this function is selected a scrollable list of the messages issued by the Mellon Modifications is displayed. The message text displayed is not available for update, it is simply to aid in the identification of the message numbers to change.

The input fields are as follows:

- **Message Substitution Active**
Enter **YES** or **NO** here. Entering **NO** allows you to turn message substitution off without having to modify each message previously defined.
- **Sel**
Enter an **S** in the Sel column for any message number to be overridden.
- **Replacement MSG number**
Tab to the **Replacement MSG number** column and enter the three digit number to be used in place of the OS/EM message number.
To revert back to the OS/EM number, simply blank out any previously entered replacement number.

Job Routing Resource Groups

This function allows you to specify up to 999 different sets of routing rules. The 999 rule sets are shared between normal resource routing, changing jobclass/priority, changing scheduling environments, changing the service class or changing the execution node.

These rules are searched sequentially and attached to the job in the order processed.

```
OS/EM ----- JOB ROUTING GROUPS - JES2 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Line Cnds: (S)elect for update; (D)elete group, (C)opy, (M)ove, (O)ver

  Routing  Group  Resource
Sel Group No  Active  Name      Resource Description
-   1         Y    EASYTREV  System B with Easytrieve_____
-   2         Y    THIS.IS.A.REALLY.LONG.RESOURCE.NAME
                                     Example of using long resource names_____
-   3         -    _____
-   4         -    _____
-   5         -    _____
-   6         -    _____
-   7         -    _____
```

Figure 151. Job Routing Resource Groups Entry Panel

There are 5 line commands available:

1. (S)elect for update

To add or change the selection criteria for a resource, you must enter an **S** in the **Sel** column, then press enter. Another window will open where you can specify the selector type (such as DDNAME, UNITNAME, RACFGROUP), and the selector names or masks. (See Figure 152 on page 5-178 for an example of this panel.) Resource names may be up to 44 characters long.

2. (D)elete Group

To clear a resource group, enter a **D** in the **Sel** column, then press enter. When you use this command and there are selection criteria attached to the resource, another panel will be displayed showing the selection criteria and warning you that they will be deleted if you continue. Press PF3 (end command) to process the deletion, or enter **CANCEL** on the command line to cancel the delete process. (See Figure 153 on page 5-180 for an example of this panel.)

3. (C)opy

Use the copy line command along with the **(O)ver** line command to copy an existing resource group over an empty group. All of the existing selection criteria is copied along with the resource group.

4. (M)ove

Use the move line command along with the **(O)ver** line command to move an existing resource group over an empty group. All of the existing selection criteria is moved along with the resource group.

```

OS/EM ----- SELECTOR ENTRY - 1 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Line Cmds: (D)elete line, (I)nsert line

Selector
Sel   Type           Selector Name/Mask List
-   ACCOUNT         '12345,-,PROD'
-   DDNAME          USRUPDI EZUT1
-   DSNNAME         SPJRT.OSEM.VER60.TEST.ISPCLIB.G0001V00
-   EXECPARM        'IMSP-'
-   JOBNAME         TRSP- DDAP- MISP-
-   PGMNAME         TRPG121 TRPH223
-   RACFGROUP       SYS1 REMUSRS PROD
-   UNITNAME        3480 3480X 3420 CARD OCR
-   USERID         SP- AEJKE TS242JT
***** Bottom of data *****

```

Figure 152. Selector Entry Panel.

This panel allows you to enter the selection criteria for a resource group. You may enter the following types of items:

- ACCOUNT** The **account number** or mask on the JOBCARD.
- DDNAME** The **DDNAME** or mask of any DD statement.
- DSNAME** A **dataset name** or mask.
- EXECPARM** A **PARM** field or mask found on an EXEC statement.
- JOBCLASS** The **class** of the job.
- JOBNAME** A **job name** or mask.
- JOBTIME** Time value from jobcard. The time parameters are entered as MMMMMM.SS, where MMMMMM may be from 0 to 357,912 minutes and SS may be from 0 to 59 seconds.

JOBTIME may also be entered as a range by separating the beginning and ending values with a colon (:), i.e. 0.10:2.0 would specify a range beginning with zero minutes and 10 seconds to two minutes and zero seconds. Leading and trailing zeros may be dropped, i.e. the above could also be entered as .10:2 for ten seconds to two minutes.
- PGMNAME** A **program name** or mask found on an EXEC statement.
- RACFGROUP** A **RACF group** or mask.
- SCHENV** The workload manager **scheduling environment**.
- SERVCLS** The workload manager **service class**.
- SRCNAME** The **user ID** or **job name** that submitted the job.
- SRCPRGM** The **program name** that submitted the job.
- SRCTYPE** The **source type**, either JOB, TSU or STC.
- UNITNAME** The **name of a unit** on a DD statement.
- USERID** The **user ID** associated with the job.

Note: If JOBCLASS or SERVCLS is used for job routing, unpredictable results will occur if the class is changed after the job has been submitted.

Separate the names or masks with a space. You may enter as many names/masks as will fit on the line. To enter more items, simply insert another line and enter the same type.

Note: The selector types ACCOUNT and EXECPARM only allow use of one item. In other words if you wanted jobs with execution parms of 'IMSP-' and 'IMSD-' to be routed to the same system, you would have to code two separate selection groups, one for each parm.

Multiple names/masks within a selector type are considered to be **OR** conditions. That is, if any of them are matched the condition is satisfied. Specifying multiple selector types, however, is considered to be an **AND** condition. All selector types must be a match in order for the **resource name** to be assigned to the job.

For example, if the following entries were used:

```

Selector
Sel  Type          Selector Name/Mask List
_   DDNAME         SYSUT2 SPECIAL
_   JOBNAME        TSYS- TDEV-

```

Then only those jobs which had jobnames beginning with TSYS **or** TDEV that **also** had a DDNAME of SPECIAL **or** a DDNAME of SYSUT2 in their JCL streams would be assigned that particular Resource Name.

On the other hand, if you only wanted TSYS jobs with a SYSUT2 DDNAME or only those TDEV jobs with a SPECIAL DDNAME to be assigned the Resource Name, you could code **two** Routing Groups and specify the same Resource Name for both.

Routing		Group	Resource	Resource Description
Sel	Group No	Active	Name	
_	1	Y	RES_TEST	TSYS jobs with DDNAME SYSUT2____
_	2	Y	RES_TEST	TDEV jobs with DDNAME SPECIAL__
_	3	-	_____	

Routing group 1 would have selector entries like:

```

Selector
Sel  Type          Selector Name/Mask List
_   DDNAME         SYSUT2_____
_   JOBNAME        TSYS-_____

```

Routing group 2 would have selector entries like:

```

Selector
Sel  Type          Selector Name/Mask List
_   DDNAME         SPECIAL_____
_   JOBNAME        TDEV-_____

```

In this way, TDEV jobs with a SYSUT2 DDNAME and TSYS jobs with a SPECIAL DDNAME would not be assigned the resource as they would in the first example.

There are two line commands available for this panel.

1. (D)elele line

Use this line command to delete an invalid or obsolete line.

2. (I)nsert line

Use this line command to insert a blank line into the display. Then enter the resource type and the names/masks for that type.

The display is sorted by selector type, so even if you insert a line at the end of the display, when next entered the panel will have been resorted.

```
OS/EM ----- SELECTION DELETION CONFIRMATION - 1 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

WARNING:  The following entries will be deleted if the Resource Group
          1      is deleted.

Press PF3 or END to delete Resource Group and all selection entries,
else, enter CANCEL to return without deleting group.

      Selection
      Type      Type Name/Mask List
DDNAME      OUTFILM
JOBNAME     MISPRDP
UNITNAME    MISTAP
***** Bottom of data *****
```

Figure 153. Delete Warning Panel.

This panel will be displayed showing the selection criteria for a resource group before the group is deleted. If you are sure you want the group deleted, simply press the PF3 key or enter the **END** command. To continue without deleting the group, enter the **CANCEL** command.

Change Jobclass/Priority Groups

This function allows you to specify up to 999 different sets of rules to allow changing the Jobclass or priority parameter. The 999 rule sets are shared between normal resource routing, changing jobclass/priority, changing scheduling environments, changing the service class or changing the execution node.

The rules are processed sequentially and attached to the job in the order processed. Because of this the last matching rule will be the one that actually sets the jobclass and/or priority.

Note: You must enable **Automatic Routing**. See “System Level Controls” on page 5-172.

```

OS/EM ----- JOBCLASS/PRIORITY CHANGE GROUPS - JES2 ---- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Line Cnds: (S)elect for update, (D)elete group, (C)opy, (M)ove, (O)ver

          Change
Sel Group  Active Class/Priority  Change Description
-   1      -      -      -      _____
-   3      -      -      -      _____
-   4      -      -      -      _____
-   5      -      -      -      _____
-   6      Y      T      9      jobname spx-_____
-   7      -      -      -      _____
-   9      Y      U      -      unitname myunit_____
-  11      Y      -      15     ddname mydd_____
-  16      -      -      -      _____
-  18      -      -      -      _____
-  19      -      -      -      _____
-  20      -      -      -      _____
-  21      -      -      -      _____
-  22      -      -      -      _____
-  23      -      -      -      _____
-  24      -      -      -      _____

```

Figure 154. Jobclass/Priority Change Groups Entry Panel

The fields and their meanings are listed below:

- (S)elect for update

To add or change the selection criteria for a resource, you must enter an **S** in the **Sel** column. Another window will open where you can specify the resource type (such as DDNAME, UNITNAME, RACFGROUP) and the resource names or masks. (See Figure 152 on page 5-178 for an example of this panel.)

If you are just changing the priority, leave the class field blank. Conversely, if you are just changing the class, leave the priority field blank.
- (D)elete group

To clear a resource group, enter a **D** in the **Sel** column. When you use this command and there are selection criteria attached to the resource, another panel will be displayed showing the selection criteria and warning you that they will be deleted if you continue. Press PF3 (end command) to process the deletion, or enter **CANCEL** on the command line to cancel the delete process. (See Figure 153 on page 5-180 for an example of this panel.)
- (C)opy

Use the copy line command along with the **(O)ver** line command to copy an existing resource group over an empty group. All of the existing selection criteria is copied along with the resource group.

- (M)ove

Use the move line command along with the **(O)ver** line command to move an existing resource group over an empty group. All of the existing selection criteria is moved along with the resource group.

- Change Description Field


To change or add a description, simply type into the field.

Change Scheduling Environment Groups

This function allows you to specify up to 999 different sets of rules to allow changing the Workload Manager SCHENV parameter. The 999 rule sets are shared between normal resource routing, changing jobclass/priority, changing scheduling environments, changing the service class or changing the execution node.

The rules are processed sequentially and attached to the job in the order processed. Because of this the last matching rule will be the one that actually sets the scheduling environment.

Note: You must enable **Automatic Routing**. See “System Level Controls” on page 5-172.



This panel is a scrollable list of the 999 groups available.

The fields and their meanings are listed below:

- (S)elect for update

To add or change the selection criteria for a resource, you must enter an **S** in the **Sel** column. Another window will open where you can specify the resource type (such as DDNAME, UNITNAME, RACFGROUP) and the resource names or masks. (See Figure 152 on page 5-178 for an example of this panel.)

- (D)elete group

To clear a resource group, enter a **D** in the **Sel** column. When you use this command and there are selection criteria attached to the resource, another panel will be displayed showing the selection criteria and warning you that they will be deleted if you continue. Press PF3 (end command) to process the deletion, or enter **CANCEL** on the command line to cancel the delete process. (See Figure 153 on page 5-180 for an example of this panel.)

- (C)opy

Use the copy line command along with the **(O)ver** line command to copy an existing resource group over an empty group. All the existing selection criteria is copied along with the resource group.

- (M)ove

Use the move line command along with the **(O)ver** line command to move an existing resource group over an empty group. All of the existing selection criteria is moved along with the resource group.

- Change Description Field


To change or add a description, simply type into the field.

Change SRVCLASS Groups

This function allows you to specify up to 999 different sets of rules to allow changing the Workload Manager SRVCLASS parameter. The 999 rule sets are shared between normal resource routing, changing the jobclass/priority, changing scheduling environments, changing the service class or changing the execution node.

The rules are processed sequentially and attached to the job in the order processed. Because of this the last matching rule will be the one that actually sets the service class.

Note: You must enable **Automatic Routing**. See “System Level Controls” on page 5-172.



This panel is a scrollable list of the 999 groups available.

The fields and their meanings are listed below:

- (S)elect for update

To add or change the selection criteria for a resource, you must enter an **S** in the **Sel** column. Another window will open where you can specify the resource type (such as DDNAME, UNITNAME, RACFGROUP) and the resource names or masks. (See Figure 152 on page 5-178 for an example of this panel.)

- (D)elete group

To clear a resource group, enter a **D** in the **Sel** column. When you use this command and there are selection criteria attached to the resource, another panel will be displayed showing the selection criteria and warning you that they will be deleted if you continue. Press PF3 (end command) to process the deletion, or enter **CANCEL** on the command line to cancel the delete process. (See Figure 153 on page 5-180 for an example of this panel.)

- (C)opy

Use the copy line command along with the **(O)ver** line command to copy an existing resource group over an empty group. All of the existing selection criteria is copied along with the resource group.

- (M)ove

Use the move line command along with the **(O)ver** line command to move an existing resource group over an empty group. All of the existing selection criteria is moved along with the resource group.

- Change Description Field


To change or add a description, simply type into the field.

Change XEQ Node Groups

This function allows you to specify up to 999 different sets of rules to allow changing the execution node parameter. The 999 rule sets are shared between normal resource routing, changing the jobclass/priority, changing scheduling environments, changing the service class or changing the execution node.

The rules are processed sequentially and attached to the job in the order processed. Because of this the last matching rule will be the one that actually sets the execution node.

Note: You must enable **Automatic Routing**. See “System Level Controls” on page 5-172.



This panel is a scrollable list of the 999 groups available.

The fields and their meanings are listed below:

- (S)elect for update

To add or change the selection criteria for a resource, you must enter an **S** in the **Sel** column. Another window will open where you can specify the resource type (such as DDNAME, UNITNAME, RACFGROUP) and the resource names or masks. (See Figure 152 on page 5-178 for an example of this panel.)

- (D)elete group

To clear a resource group, enter a **D** in the **Sel** column. When you use this command and there are selection criteria attached to the resource, another panel will be displayed showing the selection criteria and warning you that they will be deleted if you continue. Press PF3 (end command) to process the deletion, or enter **CANCEL** on the command line to cancel the delete process. (See Figure 153 on page 5-180 for an example of this panel.)

- (C)opy

Use the copy line command along with the (O)ver line command to copy an existing resource group over an empty group. All of the existing selection criteria is copied along with the resource group.

- (M)ove

Use the move line command along with the **(O)ver** line command to move an existing resource group over an empty group. All of the existing selection criteria is moved along with the resource group.

- Change Description Field

To change or add a description, simply type into the field.

Miscellaneous Controls

Description

The Miscellaneous Controls Menu provides access to the ACF2 Non-cancel Override, Catalog Account Control, Estimated Costs Controls, TSO Program Intercept and WTO functions.

Miscellaneous Controls Menu

```
OS/EM ----- MISCELLANEOUS CONTROLS ----- Version 6.0
SELECTION ==>

                1  ACF2 Noncancel Override Control
                2  Catalog Account Controls
                3  Estimated Costs Controls
                4  TSO Program Intercept Controls
                5  WTO Controls
```

Figure 158. Miscellaneous Controls Menu

Each of these functions is presented in the following sections:

1. ACF2 Non-cancel Override (see “ACF2 Non-cancel Override Control”)
2. Catalog Account Control (see “Catalog Account Control” on page 5-190)
3. Estimated Costs Controls (see “Estimated Costs Controls” on page 5-193)
4. TSO Program Intercept (see “TSO Program Intercept” on page 5-197)
5. WTO (see “WTO Controls” on page 5-198)

ACF2 Non-cancel Override Control

The ACF2 Non-cancel Override allows OS/EM to enforce controls previously setup for ACF2 users who have the non-cancel attribute.

```
OS/EM ----- ACF2 NONCANCEL OVERRIDE CONTROL ----- Version 6.0
COMMAND ==>

                ACF2 Noncancel Override Active ==> YES          (Yes/No)
```

Figure 159. ACF2 Non-cancel Override Entry Panel

Field entry is as follows:

- ACF2 Noncancel Override Active

Enter **YES** to activate this function, or **NO** to deactivate it.

Catalog Account Control

The Catalog Account Control function will place up to 32 characters of JOB or STEP accounting information into the catalog record for a new VSAM or SMS-managed non-VSAM data set. The Access Methods Services program, DCOLLECT, can then be used to produce charge-back reports for DASD utilization.

If a catalog account field is already present, e.g., it was specified on the IDCAMS DEFINE statement, it is not replaced. If both JOB and STEP accounting information is present, STEP accounting takes precedence.

You must enable SMF record type 61 in your SMFPRMxx parmlib member for this function to operate.

Refer to the IEFU83 section of the SMF command in the OS/EM Reference Manual.

The **Catalog Account** entry panel provides the means for tailoring the function to an installation's specific needs. The information to be selected from either a JOBS accounting fields or a STEPs accounting fields and placed in the 32-byte catalog account field can be controlled by up to eight subfield entries.

These subfield entries specify an account field, a starting position within the account field and the number of characters to select. This allows for selecting all or parts of up to eight different accounting fields or eight parts of a single accounting field or any combination in between. The subfields are processed from left-to-right and the information obtained from processing each is placed in the catalog account field in left-to-right order as well.

If a subfield requests an account number that is not present, or there is not enough data in the account field to satisfy the requested subfield length, provision is made to use an error character to fill in the gap. If the subfield length is zero, the subfield is skipped. If the combined subfield lengths are greater than 32 characters, only the first 32 are used.

There is a **DEFAULT** group of subfield entries and provision for up to 16 additional groups of subfield entries that are used in conjunction with selection criteria such as **JOBNAME**, **JOBCLASS**, **USERID** and **RACF GROUPNAME**. Weights can be assigned to the selection criteria so that if a match is made on more than one criterion, the one with the highest weight assigned is the subfield selection group used. If weights are not assigned or are equal, the first group (from 1 to 16) that satisfies the criteria is used. If no criteria are met, the default selection group is used.

The primary entry panel for the Catalog Account Controls function allows you to turn the function on or off; specify an error fill code to be used for a missing or short account field; specify the name of the started task(s) which handle recalling or recovering datasets which have been migrated or backup up; specify the default selection values to build the accounting code if a job does not match any of the 16 selection groups; specify an Owner ID to be used if missing from the ACEE; specify weights to be applied to the different selection criteria which may be specified.




Figure 160. Catalog Account Control Entry Panel

Field entry is as follows:

- **Catalog Account Active**
Enter **YES** to activate this function, or **NO** to deactivate it.
- **Error Code**
Specify a one byte character to be used to fill any missing or short account field.
- **Archival STC Names**
Specify the name of the started task which handles recalling or recovering datasets which have been migrated or backed up. Two names may be entered. If you are running IBM's DFSMSHSM, this name might be HSM. This is a **required** field so that OS/EM does not try to add accounting information to datasets being recalled from migration or recovered from a backup.
- **Select Defaults**
The Defaults fields builds the account number from the accounting codes of jobs not specifically selected by one of the 16 selection groups.

You may specify up to 8 accounting code fields to build the account number. Specify the accounting code field, the starting position within the field and the length to use. Also specify an Owner ID to be used in the event that the ACEE is unavailable.

Note: If an accounting code field is specified as 0, the first non-zero length accounting code field will be used.
- **Weights**
Enter the weight to be given to each type of selection criteria. Enter a value between 1 and 4. The weight is used when a JOB matches more than one selection group. The group with the highest weight value is used. If more than one group is determined to have the same weight, the first group selected will take effect.

This means that if the JOB being tested matches a selection group based on the JOBNAME, but also matches a selection group based on the RACF Group Name, then which group has the highest value assigned to it's weight value will be used.

The bottom portion of the panel is a scrollable area containing the 16 possible selection groups. Enter the account code field number, the starting position within the field and the length of the field to be moved. You may specify up to eight areas. They may be the same or different field numbers.

To delete a field entry no longer needed, you must blank out the field, start and length fields.

To the right of the panel are four indicators showing the type of selection list, Job Name, User ID, Job Class or RACF Group. An **I** means that it is an **INCLUDE** group, while an **E** means that it is an **EXCLUDE** group.

To make the list active, enter a **Y** in the **ACTIVE** column. Enter a **N** to turn the list off without having to blank out the entries.

To update the selection list types, place a **S** in the **S** column and press enter.

```

OS/EM ----- SELECTOR ENTRY - 3 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enter Selector Types, either Include or Exclude
          Jobclass ==>          Jobname  ==>
          RACFGRP  ==>          USERID  ==> INCLUDE

Line Cmds: (D)elete line, (I)nsert line

  Selector
  Type      Selector Names/Mask List
- USERID   SPHG-
***** Bottom of data *****

+-----+
| Selector Types:  JOBCLASS, JOBNAME, RACFGRP, USERID. |
+-----+

```

Figure 161. Catalog Account Lists

This selection panel allows you to specify the selector types active for this catalog account selection group, as well as specifying the list type, either **INCLUDE** or **EXCLUDE**.

To enter selector entries, use the **I** command to insert a blank line, then enter the **Selector Type** and the names or masks that will be checked. Separate the names with a space. If you have more names/masks than will fit on a line, simply insert another blank line and use the same selector type.

When entering jobclasses, you may enter a range of classes by separating the first and last class with a colon (:), i.e. A:D will cause OS/EM to check class A, B, C and D.

The four selector types available are:

- **JOBNAME**
Enter either complete job names, or job name masks. If the list type is **INCLUDE**, only these jobs will be processed by this control definition. If the list type is **EXCLUDE**, all jobs but these will be processed by this definition.
- **JOBCLASS**
Enter either individual job classes, or a range of classes by specifying the range with a colon (:) in between the beginning and ending classes. If the list type is **INCLUDE**, only these classes will be

eligible for processing by this definition. For an **EXCLUDE** list, all classes except for these will be processed.

The **jobclass** list specifies the execution classes to which OS/EM will apply catalog account controls.

Enter individual classes, or enter a class:class pair. Entering A:9 as the jobclass covers all possible classes.

Jobclass lists are built, independently, for each selection group.

- **RACFGRP**

Enter either complete RACF group names, or name masks. If the list type is **INCLUDE**, only these groups will be processed by this control definition. If the list type is **EXCLUDE**, all groups except these will be processed.

The **RACF GROUP NAMES** list specifies the RACF groups to which OS/EM will apply catalog account controls.

RACF group lists are built, independently, for each selection group.

- **USERID**

Enter either complete User IDs or ID masks. If the list type is **INCLUDE**, only these IDs will be processed by this control definition. If the list type is **EXCLUDE**, all IDs except these will be processed.

The **USERID** list specifies the User IDs to which OS/EM will apply catalog account controls.

User ID lists are built, independently, for each selection group.

Note: The following restrictions apply:

- SMS-managed datasets only.
- SMF record type 61 must be enabled in the SMFPRMxx parmlib member.
- If a catalog account field is already present, e.g., it was specified on the IDCAMS DEFINE statement, it is not replaced.
- If both JOB and STEP accounting information is present, STEP accounting takes precedence.

Estimated Costs Controls

The **Estimated Cost** function of OS/EM can be used to calculate an approximate charge for running each step of a job and an approximate total cost of running the job. The costs are presented in the **flower box** produced by requesting OS/EM's **STEP/JOB-end statistics** (see "Job/Step Statistics" on page 5-153.)

The Estimated Cost Controls panel provides the means for tailoring the computation of estimated cost to an Installation's specific needs. There are twelve selectable rate fields that can be specified as multipliers against usage measurements such as service units, CPU time, I/O activity and tape mounts. Additionally, field entries are provided for a CPU time normalization factor, a fixed cost that is added to each job's total cost, and a default minimum cost of a job that will be used if the calculated cost is lower. Up to sixteen separate sets of rates can be specified based upon System ID. A default set of rates can also be specified that will be used against work run on any LPAR for which there is no specific System ID set of rates.

Which rate or rates to specify is up to each individual installation. If an installation wishes to compute an estimated cost based upon TCB CPU time only, then only that rate field needs to be entered. A value of zero for a rate negates the use of that rate in the cost calculation. The computed values for each rate/usage measurement combination (rounded up to two decimal places) are added together to arrive at an estimated cost. If a fixed cost value is specified it will be added to the job's total cost. If a minimum cost value is specified it will be used for a job's total cost if the calculated value is lower.

```

OS/EM ----- ESTIMATED COST GROUPS ----- Version 6.0
Command ==>                                     Scroll ==> CSR

Estimated Cost Controls Active ==> YES

Set Default Values ==> NO

(S)elect for Update
Sel  Group  Active  SYSID  Description
-    1      Y      WXYZ  NON-EXISTANT SYSTEM LPAR
-    2      Y      TEST  TEST LPAR
-    3      Y      EXPR  PRODUCTION SYSTEM
-    4      N      _____
-    5      N      _____
-    6      N      _____
-    7      N      _____
-    8      N      _____
-    9      N      _____
-   10      N      _____
-   11      N      _____
-   12      N      _____
-   13      N      _____
-   14      N      _____

```

Figure 162. Estimated Cost Groups Panel

Field entry is as follows:

- **Estimated Cost Controls Active**
 Enter **YES** to activate this function, or **NO** to turn it off.
 Even if this function is turned on nothing will happen unless there is at least one non-zero field entry in either the Default selection or one of the 16 System ID selection groups, and the STEP/JOB-end statistics function is activated.
- **Set Default Values**
 Entering **YES** brings up a panel that allows a set of default rates to be entered that will be used if there is no specific set of rates for the System ID the job is running on. (See “Estimated Costs Controls” on page 5-193.)

The bottom portion of this panel contains a scrollable list of the sixteen (16) available rate groups. Each entry must specify the SMFID of the system to which the rates apply and for the rates to be active you must enter a **Y** in the **Active** column. An optional line of descriptive text may also be entered.

Below is a sample of the rates data entry panel along with a description of each field.

```

OS/EM ----- ESTIMATED COST CONTROLS - 0 ----- Version 6.0
COMMAND ==>

System ID:      DEFT

Minimum Cost:  00010 . 00          Fixed Cost:    00002 . 00

Service Unit Multipliers:
  TCB Service Units: . 3500000      I/O Service Units: . 7400000
  SRB Service Units: . 3300000      MSO Service Units: . 2900000

CPU Time Multipliers:
  TCB CPU Time:  01 . 32000         SRB CPU Time:  02 . 43000

I/O Activity Multipliers:
  DASD:  00 . 87300                TAPE:  02 . 25000
  VIO:   01 . 99000

Tape Mount Multipliers:
  Specific Tape Mounts:  03 . 59000  Non-Specific Tape Mounts:  02 . 11000

Normalization Factor:  001 . 0000  Device Connect Time:  01 . 11000

```

Figure 163. Estimated Cost Controls Panel

Field entry is as follows:

- **Minimum Cost**
A value of the form xxxxx.xx. If specified, it will be used as the cost of a job when the calculated cost is lower.
- **Fixed Cost**
A value of the form xxxxx.xx. If specified, it will be added to the value calculated for a job.
- **Service Unit Multipliers**
 - **TCB Service Units**
A rate value of the form .xxxxxxx specifying the cost of a TCB service unit. The number of TCB service units in the SMF type 30 record field, SMF30CSU, is multiplied by this rate to obtain the cost.
 - **I/O Service Units**
A value of the form .xxxxxxx specifying the cost of an I/O service unit. The number of I/O service units in the SMF type 30 record field, SMF30IO, is multiplied by this rate to obtain the cost.
 - **SRB Service Units**
A rate value of the form .xxxxxxx specifying the cost of a SRB service unit. The number of SRB service units in the SMF type 30 record field, SMF30SRB, is multiplied by this rate to obtain the cost.
 - **MSO Service Units**
A value of the form .xxxxxxx specifying the cost of an MSO service unit. The number of MSO service units in the SMF type 30 record field, SMF30MSO, is multiplied by this rate to obtain the cost.
- **CPU Time Multipliers**

- **TCB CPU Time**
A value of the form xx.xxxxx specifying the cost of a TCB CPU second. The number of TCB CPU seconds in the SMF type 30 record field, SMF30CPT, is multiplied by this rate to obtain the cost. If a normalization factor is specified, the cost calculated will be multiplied by the factor.
- **SRB CPU Time**
A value of the form xx.xxxxx specifying the cost of a SRB CPU second. The number of SRB CPU seconds in the SMF type 30 record field, SMF30CPS, is multiplied by this rate to obtain the cost. If a normalization factor is specified, the cost calculated will be multiplied by the factor.
- **I/O Activity Multipliers**
 - **DASD**
A value of the form xx.xxxxx specifying the cost of a disk I/O. The number of disk I/Os contained in the SMF type 30 record field, SMF30BLK (when the SMF30DEV field indicates DASD), is multiplied by this rate to obtain the cost.
 - **TAPE**
A value of the form xx.xxxxx specifying the cost of a tape I/O. The number of tape I/Os contained in the SMF type 30 record field, SMF30BLK (when the SMF30DEV field indicates tape), is multiplied by this rate to obtain the cost.
 - **VIO**
A value of the form xx.xxxxx specifying the cost of a virtual I/O. The number of virtual I/Os contained in the SMF30 record type field, SMF30BLK (when the SMF30DEV field indicates VIO), is multiplied by this rate to obtain the cost.
- **Tape Mount Multipliers**
 - **Specific Tape Mounts**
A value of the form xx.xxxxx specifying the cost of a specific tape mount. The number of specific tape mounts contained in the SMF type 30 record field, SMF30TPR, is multiplied by this rate to obtain the cost.
 - **Non-specific Tape Mounts**
A value of the form xx.xxxxx specifying the cost of a non-specific tape mount. The number of non-specific tape mounts contained in the SMF type 30 record field, SMF30PTM, is multiplied by this rate to obtain the cost.
- **CPU Time Normalization Factor**
A multiplier factor of the form xxx.xxxx that may be used to normalize processor speeds. When specified it is applied only to costs based on TCB and SRB CPU time usage to account for differences in processor speeds.
- **Device Connect Time**
A value of the form xx.xxxxx specifying the cost of a Device Connect Time second. The number of Device Connect Time seconds in the SMF type 30 record field, SMF30TCN, is multiplied by this rate to obtain the cost.

Restrictions/Requirements:

1. This function requires the use of SMF exit IEFACTRT and SMF record types 30.4 and 30.5. The SYS1.PARMLIB member, SMFPRMxx, should reflect this requirement.

2. The calculated estimated cost of a STEP/JOB is displayed in the STEP/JOB-end statistics produced by OS/EM. This function must be enabled.
3. Rounding to two (2) decimal places takes place at the end of **each** calculation, not at the end of cost processing.

TSO Program Intercept

This function allows you to specify the name of a program that is executed under TSO and disallow use of the program and writing up to 5 lines of explanation.

This would typically be used to force execution of certain programs only on the LPAR where they are licensed.

Space for thirty-two programs is provided.

```

OS/EM ----- TSO PROGRAM INTERCEPT ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

  Program Intercept Active:  YES                      (Yes/No)

S(select for update)
S  Number  Active  Program  Message
-   1      YES    TRSP011A  PLEASE DO NOT EXECUTE THIS PROGRAM ON THE TEST SY
-   2      YES    USRP015   PLEASE DO NOT EXECUTE THIS PROGRAM ON THE TEST SY
-   3      NO     _____
-   4      NO     _____
-   5      NO     _____
-   6      NO     _____
-   7      NO     _____
-   8      NO     _____
-   9      NO     _____
-  10      YES    DLSPUNK3  UNABLE TO EXECUTE ON THIS LPAR.
-  11      NO     _____
-  12      NO     _____
-  13      NO     _____
-  14      NO     _____
-  15      NO     _____

```

Figure 164. TSO Program Intercept Entry Panel

Field entry is as follows:

- Program Intercept Active

Enter **YES** to activate this function, or **NO** to deactivate it.

There are 32 available slots to specify a program name and the associated messages.

To activate any of the 32 slots, tab to the appropriate slot and enter **YES**. To deactivate a slot, enter **NO**.

For each slot activated, and program name and message must be entered. To enter or change a program name, simply tab to the program field and type the program name. To add or change the message, enter an **S** in the select column on and press enter. A popup window will open allowing 5 lines of text.

Note: Do not use apostrophes (') in your message text!

WTO Controls

Description: The WTO Controls function allows OS/EM to monitor user specified DD names for specific messages. When found, the message is written to the system console to allow appropriate action by either the operator or an automated operations package.

The DD name to be monitored may be limited to specific job names and/or program names. To have this function active, you must specify at a minimum a message id to search for, a DD name to search, and the program name (from the exec card) which owns the DD name.

WTO Controls Entry Panel

```
OS/EM ----- WTO CONTROLS ----- Version 6.0
Command ==>                                     Scroll ==> CSR

                WTO Controls Active ==> YES          (Yes/No)

Line Commands: (S)elector Groups, (D)elete Groups

                Active Selection Lists
SEL Num Active   Add      Route   Description   DD      Job      Message   Program
'  1   YES      YES      YES     YES          YES    YES     YES       YES
'  2   NO       _____
'  3   NO       _____
'  4   NO       _____
'  5   NO       _____
'  6   NO       _____
'  7   NO       _____
'  8   NO       _____
'  9   NO       _____
' 10   NO       _____
' 11   NO       _____
' 12   NO       _____
```

Figure 165. WTO Controls Entry Panel

The fields and their meanings for this entry panel are:

- WTO Controls Active

Enter **YES** to allow use of the WTO function. Entering no here turns the function off without disturbing any of the selection lists already completed.

There are 32 available groupings which control which messages are tracked. Besides specifying the selection criteria, for each group you may have an OS/EM message number appended to the front of your message (OS\$DC1195), and specify any routing codes or description codes to be used on the generated WTO.

- Active

To activate any of the 32 groups, tab to the Active column and enter **YES**. Enter **NO** to deactivate the group.

- Add OSEM ID

Enter **YES** in this field to have OS/EM's message number OS\$DC1195 appended to the front of your message. Enter **NO** to have your message written without any modifications.

There are 2 line commands available on this panel. These are used to enter information about **route codes** and **description codes**, or to specify information in a **selection criteria list**.

```

OS/EM ----- SELECTOR ENTRY - 1 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Line Cmds: (D)elete line, (I)nsert line

Selector                                         Message
Type      Selector Names/Mask List             Start
-----
- DDNAME                                         _____
  MSGGOUT_____
- DESCDCDE                                       _____
  9_____
- JOBNAME                                         _____
  TRPD030_____
- ROUTECDE                                       _____
  11_____
- MSGID                                           8
  UPDATE OF MASTER FAILED_____
- PGMNAME                                         _____
  TRP0321P_____
***** Bottom of data *****

+-----+
| Selection Types: DESCDCDE, DDNAME, JOBNAME, MSGID, PGMNAME or ROUTECDE. NOTE: |
| DDNAME, MSGID and PGMNAME are REQUIRED! |
+-----+

```

Figure 166. Selector Entry Panel

There are 6 selector types available, however two types (DESCDCDE and ROUTECDE) are used to store information to be passed back to MVS on the WTO macro and not used to select messages to be processed.

Three selector types are required to activate this function: DDNAME, PGMNAME and MSGID.

- **DESCDCDE**
 Enter any description codes that should be added to the WTO macro. Multiple description codes may be entered separated by spaces.
 For a list of acceptable values, see the IBM manual **MVS Routing and Descriptor Codes**.
- **DDNAME**
 Enter the DDNAME(s) that OS/EM will monitor. At least one DDNAME is required to have this function active.
- **JOBNAME**
 Enter the JOBNAME to be monitored. Multiple jobnames separated by spaces may be entered.
- **MSGID**
 Enter the MSGID that OS/EM will search for. At least one MSGID must be entered for this function to be active.
 This MSGID may actually be any constant text string that always appears in the message. A column number may be entered to specify where OS/EM will begin to scan for the text string. If the Message Start field is not entered, OS/EM begins searching at column 1. Column 1 is defined as the first position after an ASA or machine control character or 3800 font selection character. A range may also be specified as xx:yy which indicates that the message must start in columns xx through and including column yy.
Note: Only one message may be specified on a line. If multiple messages are to be monitored simply enter multiple lines all using the selector type of MSGID.

- PGMNAME.

Enter the PGMNAME(s) that OS/EM will monitor. At least one program name is required to have this function active. Multiple programs may be entered separated by spaces.

- ROUTECDE

Enter any route codes to be passed to the WTO macro. Multiple route codes may be specified separated by spaces.

For a list of acceptable values, see the IBM manual **MVS Routing and Descriptor Codes**.

QuickPool

Description

Quick Pool is a dynamic DASD pooling package for non-VSAM datasets and also enforces VSAM dataset placement as defined by the pooling rules.

Summary of Features

- Dataset Name Standards enforcement
- Warn Mode with messages written in the JES Log
- Dynamic masking for defining dataset name groups
- Dynamic masking for defining volume name groups
- DFSMS migration aid
- Optionally disallows RACF discrete profiles during dataset allocation

QuickPool Menu

```
OS/EM ----- QUICK POOL ----- Version 6.0
SELECTION ==>

          1  DASD Allocation Controls
          2  Quickpool Rules
```

Figure 167. QuickPool Menu

Each of these paths is presented in the following sections:

1. DASD Allocation Controls (see “DASD Allocation Control” on page 5-203)
2. QuickPool Rules (see “QuickPool Rules” on page 5-206)

DASD Allocation Control

The Control DASD allocation function consists of one panel (Figure 168). By specifying either a YES or NO, you control the following options:

- Whether absolute track allocation will be allowed
- Whether allocation requests for contiguous space will be honored
- Whether ALX allocation requests will be allowed
- Whether MXIG allocation requests will be allowed
- Whether single-level dataset names will be allowed (we recommend that you not allow such dataset names)
- Whether ISAM datasets will be allowed (if you have such datasets, you should convert them to VSAM and use the interface routines to access these datasets; IBM does not, generally, support this file organization)
- Whether unmovable datasets can be created
- Whether RACF automatic dataset protection is in effect; if this control is already set, you may set this option to RES, which will reset, or turn off, this option for a dataset (we recommend that this option be either NO, or RES; RACF generic profiles are the better approach to dataset protection)
- Whether RACF discrete profiles are allowed (again, we recommend that RACF generic profiles be used; therefore, set this option to NO or RES which will turn off existing discrete profiles)

```
OS/EM ----- CONTROL DASD ALLOCATION ----- Version 6.0
SELECTION ===>

  Select the DASD allocation function(s) from the following list.

  Specifying YES before a function means that that function will be
  allowed. Specifying NO before a function means that that function
  will not be allowed. RES (for RESET) is allowed for ADSP and PROT.

      YES  ENABLE  - Enable/Disable ALL DASD/QuickPool controls
      NO   WARN    - Operate DASD/QuickPool controls in WARN mode
      NO   ABSTR   - Absolute track allocation
      YES  CONTIG  - Contiguous space allocation
      NO   ALX     - ALX allocation
      NO   MXIG    - MXIG allocation
      NO   SINGLE  - Single-level dataset name allocation
      NO   ISAM    - ISAM file organization
      YES  UNMOVE  - Unmovable file allocation
      NO   ADSP    - RACF automatic dataset protection
      NO   PROT    - RACF discrete profiles
```

Figure 168. Control DASD Allocation

The DASD Allocation Control function may be used to allow or disallow various allocation parameters.

Field entry is as follows:

- WARN

Warn mode establishes the action of the QuickPool function. It is more fully explained in “WARN mode” on page 5-205.

Specifies whether DASD and QuickPool controls are enforced.

When operating in WARN mode, WTO messages are generated stating the action which would have occurred if the controls were active.

Enter **YES** to enable this option; **NO** to disable this option.

- **ABSTR**

Specifies whether ABSTR (ABSOLUTE TRACK) allocation will be allowed or disallowed.

Enter **YES** to enable this option; **NO** to disable this option.

It is extremely unlikely that you would ever want to allow this function for DASD allocation. Old third-party software might be the only reason for this function.

- **CONTIG**

Specifies whether CONTIG (contiguous space) allocation will be allowed or disallowed.

Enter **YES** to enable this option; **NO** to disable this option.

Allowing contiguous space allocation can result in failed allocations if the volume is badly fragmented.

- **ALX**

Specifies whether ALX allocation will be allowed or disallowed.

Enter **YES** to enable this option; **NO** to disable this option.

This option is presented as last entered by you.

- **MXIG**

Specifies whether MXIG allocation will be allowed or disallowed.

Enter **YES** to enable this option; **NO** to disable this option.

- **SINGLE**

Specifies whether single-level dataset names will be allowed or disallowed.

Enter **YES** to enable this option; **NO** to disable this option.

As a general rule, you should not allow single-level dataset names. Such datasets will be cataloged in the master catalog. The master catalog should contain only SYSRES volume datasets (usually SYS1 datasets) and ALIAS pointers to user catalogs.

- **ISAM**

Specifies whether ISAM dataset names will be allowed or disallowed.

Enter **YES** to enable this option; **NO** to disable this option.

As a general rule, you should not allow ISAM datasets. Most products, such as CICS, no longer directly support this access method. Use the IIP (ISAM Interface Program) and convert such files to VSAM - time is running out.

- **UNMOVE**

Specifies whether unmovable datasets will be allowed or disallowed.

Enter **YES** to enable this option; **NO** to disable this option.

Unmovable datasets are rare - most database software uses some sort of offset relative to the beginning of the dataset to find specific records. However, such files do exist. Be careful before enabling this option.

- **ADSP**

Specifies whether requests for datasets with the ADSP (Automatic Dataset Protection) attribute will be allowed or disallowed.

Enter **YES** to enable this option; **NO** to disable this option; **RES** to turn off the ADSP for datasets allocated with this attribute.

Proper dataset protection via your security system should make use of this attribute superfluous. That is, datasets should be defined as generic, even if only a single dataset exists under the dataset name.

- **PROT**

Specifies whether discrete RACF profiles will be allowed or disallowed.

Enter **YES** to enable this option; **NO** to disable this option; **RES** to delete the discrete attribute.

Proper dataset protection via your security system should make use of this attribute superfluous. That is, datasets should be defined as generic, even if only a single dataset exists under the dataset name.

WARN mode: WARN mode provides you with a way of observing your allocation rules without enforcing those rules. Each time a dataset allocation would violate a rule, the allocation proceeds and a WTO message is created. The WTO message will list the dataset that was allocated, and the dataset name group the dataset resolved to. With this information, you can determine why the allocation would have been disallowed if WARN mode had not been in effect.

WARN mode should be used before actually "turning on" the QuickPool function. Allocation rules can become complicated, and your installation probably would not want production jobs failing because a dataset could not be allocated. It is also quite likely that there are jobs that do not follow whatever allocation rules your installation currently has in place. And, since the QuickPool function really should be done without reference to specific volume serial number on DD statements, time will be required to alter all your installation's JCL.

- WARN mode would also be useful if your installation is contemplating a move to IBM's DFSMS. It is possible to create QuickPool allocation rules that closely mimic those of DFSMS which could help in developing the DFSMS required classes.
- While OS/EM currently does not support the automatic allocation of VSAM datasets, WARN mode can be used to determine if VSAM datasets are being properly placed. The actual allocation of the VSAM dataset goes through DADSM and is monitored by the OS/EM QuickPool function.

QuickPool Rules

The QuickPool function controls which datasets may, or may not, be allocated on which DASD volumes. It will also automatically place datasets on the correct volume if your jobs do not direct datasets to specific volumes (such directed allocations must still follow the rules you establish). You can create volume groups with certain performance objectives in mind and ensure that proper datasets are placed on these volumes. For example, some of your volumes may deliver better access times because of your hardware configuration. These volumes would be likely candidates for your online files where quick access can be critical. Or, you can create volume groups that will ensure that datasets with simultaneous, heavy access are properly separated. The effectiveness of the QuickPool function is determined by the volume and dataset name groups you have built.

```

OS/EM ----- QUICKPOOL FUNCTIONS ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

                Quickpool Active ==> YES      (Yes/No)
                Operate in Control mode ==> YES (Yes/No)

Note: The groups GLOBALA and GLOBALD contain the DSN groups which are always
      ALLOWED or DISALLOWED on QuickPool controlled volumes.

CMD = (A)dd pool (D)delete pool (C)hange DSN groups (S)elect enable/description)
CMD  Enable  Pool      Pool Type  Description
"    YES    GLOBALA   ALLOW     ALWAYS ALLOW ON QUICKPOOL VOLUMES__
"    NO    GLOBALD   DISALLOW  ALWAYS DISALLOW ON QUICKPOOL VOLUME
"    YES    MVS_AUX   ALLOW     MVS AUXILIARY VOLUMES (SMP/E SMF IS
"    YES    VOLG1     ALLOW
"    YES    VOLG10    ALLOW     DISPATCH ONLINE VIEWING_____
"    YES    VOLG16    ALLOW     HSM ML1 VOLUMES_____

```

Figure 169. QuickPool Functions

The QuickPool entry panel allows you to turn on or off QuickPool, specify that QuickPool will operate in Control mode, and create/update pools.

Field entry is as follows:

1. QuickPool Active

QuickPool is enabled by entering a **YES** (or **Y**), or disabled by entering a **NO** (or **N**).

2. Operate in Control mode

This option establishes the QuickPool span of control. If set to YES, the QuickPool function controls all of your installation's DASD volumes, even if they have not been explicitly defined to the QuickPool function.

Enter **NO** if the QuickPool function will control only those volumes specifically defined by the POOL list.

If you specify CONTROL, volumes not explicitly defined by the POOL list will be controlled by the allocation rules you establish with the global ALLOW and DISALLOW lists. If you do not create such lists, volumes not resolvable to Pool lists will not have any datasets, other than SYS1 datasets, allocated to them.

The bottom portion of the QuickPool Functions panel is a scrollable list of the pools defined. There are two special pool names which control **global** allocations. The first is **GLOBALA** where you may specify

datasets which are always allowed on QuickPool volumes; and second **GLOBALD** where you specify datasets which are always disallowed. These two pool names may not be deleted or renamed. If they are not to be used, simply disable them by entering **NO** in the enable column.

Field entry is as follows:

1. CMD

There are four line commands available. They are:

- (A)dd pool
- (D)elete pool
- (C)hange DSN groups
- (S)elect enable/description

2. POOL

The Pool list establishes an association between volumes and datasets. Each volume group may have 'either' an ALLOW list 'or' a DISALLOW list (these are subordinates to the global lists). If you do not define these lists, the volume group is strictly under the control of the global lists.

The ALLOW lists specifies which datasets are allowed on volumes within the group. The DISALLOW list specifies which datasets are not allowed on volumes within the group.

The type of list you are creating for the volume group, ALLOW or DISALLOW, is specified during the ADD a new group process. Once you have chosen the type of dataset name group list to be associated with the volume group, it cannot be changed. The type of list associated with the volume group is displayed as part of the volume group POOL list display.

The Volume group must have been previously defined (see "Define Volume Groups" on page 5-12)

3. POOL Type

a. ALLOW

ALLOW defines a global list of dataset name groups which apply to all your DASD volumes. Groups defined via this option are always allowed on a volume regardless of the volume's own specific ALLOW or DISALLOW lists. The current status of this option is always indicated.

As with any OS/EM list, if you specify NO, you are deleting the list; thus, NO has no meaning in an initialization member. It only has an effect when used via the OS/EM online function.

b. DISALLOW

DISALLOW defines a global list of dataset name groups. Such groups are not allowed on a volume (SYS1 datasets cannot be excluded from initial allocation via this option).

c. Global ALLOW

The global ALLOW list (which has a pool name of GLOBALA) specifies datasets which are always allowed on volumes controlled by the QuickPool function. This list takes precedence over the global DISALLOW list and any private DISALLOW lists specified for a volume group.

SYS1 datasets are always initially allowed on any volume.

To update the DSN groups in the Global ALLOW pool, enter C in the CMD field. A list of DSN groups will be displayed (see Figure 170 on page 5-208).

d. Global DISALLOW

The global DISALLOW list (which has a pool name of GLOBALD) specifies datasets which are always disallowed on volumes controlled by the QuickPool function. This list takes precedence over any private ALLOW lists specified for a volume group.

To update the DSN groups in the Global DISALLOW pool, enter **C** in the CMD field. A list of DSN groups will be displayed (see Figure 170).

4. Dataset Name Group




Figure 170. QuickPool Add/Delete "POPUP" screen

Field entry is as follows:

a. Add

To add entries, enter an **A** in the CMD field and **overtyp**e the Dataset Name Group on that line (**overtyping will not alter the old entry**).

The Dataset Name Group name must already be defined (see "Define Dataset Name Groups" on page 5-3) for the add to be successful. Duplicates will be rejected. Group names are kept in alphabetical order, and this is the search mode OS/EM uses in trying to resolve volume/dataset associations.

b. Delete

To delete entries, enter a **D** in the CMD field.

The DSN group must have been previously defined (see "Define Dataset Name Groups" on page 5-3)

If an ALLOW list is created, one of two actions will occur when a dataset is resolved to the volume group. In the case of a non-directed dataset allocation, each dataset within the listed dataset name groups will be allocated on a volume within the volume group. In the case of a directed dataset allocation, dataset allocation on a volume within the volume group will only be allowed if the dataset is resolved to one of the listed dataset name groups.

If a DISALLOW list is created, no dataset within a dataset name group will be allocated, or allowed to be allocated, on any volume within the volume group.

If a volume group is created without an ALLOW or DISALLOW list, the group will be controlled by the global ALLOW or DISALLOW lists. If you do not create global ALLOW or DISALLOW lists, such volumes will not be eligible for allocation.

Note: SYS1 datasets are always initially allowed on any volume. However, you cannot rename a dataset to SYS1 unless you have specifically allowed SYS1 datasets on the volume.

ALLOW/DISALLOW search order: OS/EM follows an explicit hierarchy when searching the ALLOW and DISALLOW lists for a dataset name match.

Dataset name lists established with the ALLOW and DISALLOW options are global and apply to all controlled and uncontrolled volumes. Any dataset name matches resolved to either of these two lists stops the search and the resulting allocation rule will be the one used. Any matches that might apply to a specific volume group will be ignored. For example, if a dataset name resolves to the global ALLOW list, and also to a specific volume group DISALLOW list, the allocation will be permitted. The reverse is also possible: a dataset allocation will not be permitted if it is in the global DISALLOW list and also in a specific volume group ALLOW list.

If no matches are found in the global ALLOW and DISALLOW lists, or you have not specified any global ALLOW or DISALLOW lists, the volume group ALLOW and DISALLOW lists are searched. The first match within any of these lists is the allocation rule used.

Further, within the global lists, ALLOW takes precedence over DISALLOW. That is, if a dataset name can be resolved to both an ALLOW list and a DISALLOW list (because of a dataset name specification), the dataset allocation will be allowed.

- Care must be taken when dealing with VSAM datasets. OS/EM currently cannot automatically supply a volume serial number for the dataset during the IDCAMS DEFINE step; but if a VSAM dataset is not allowed on the volume, the actual allocation of the VSAM dataset will be denied.

Volume Pool considerations: You might think it "normal" to place a given volume in only one group. However, consider the follow situation:

- You have created a volume group that consists of an entire string of DASD. You would like the head-of-string volume to contain a user catalog that will point to all the datasets on that particular string. Further, since the user catalog will only use a fraction of the space on the head-of-string volume, it should be eligible for dataset allocation like any other volume in the string. Finally, you would like to ensure that certain datasets are always placed on the head-of-string volume.

The QuickPool function covers this situation by allowing the volume to be defined in two, or more, volume groups. Specific datasets can be allowed to the volume, but the volume will also be part of a volume pool which is used for the more general case.

Also consider the HSM Optimizer defragmentation process. You may wish to place a volume in one group that is "defrag'd" on a weekly basis. You might also want to place the volume in a group that has "emergency" defrag criteria.

RACF Controls

Description

The RACF Controls Menu provides access to the Discrete Profiles and External Tapes functions.

RACF Controls Menu

```
OS/EM ----- RACF CONTROLS ----- Version 6.0
COMMAND ==>

          1 - Discrete Profiles Control
          2 - External Tape Control
```

Figure 171. RACF Controls Menu

Each of these functions is presented in the following sections:

1. Discrete Profiles Control (see “RACF Discrete Profiles”)
2. External Tape Control (see “External Tape Control” on page 5-211)

RACF Discrete Profiles

The RACF Discrete Profile provides the option to control who can create RACF discrete profiles. With DFSMSHsm System Managed Storage, RACF discrete profiles are incompatible with dynamic storage groups because of the restriction the discrete profile carries, a specific volume serial.

Note: You must define the classes to be controlled to your security manager. Use the general resource class 'FACILITY' for RACF and ACF-2 or 'IBMFAC' for CA-Topsecret and a resource name of DISCRETE.PROFILE.name where 'name' matches the class name your are protecting. For class DATASET the resource name or profile would be DISCRETE.PROFILE.DATASET. Read authority is required to allow creation of the discrete profile.

```

OS/EM ----- RACF DISCRETE PROFILES ----- Version 6.0
Command ==>                                     Scroll ==> CSR

          Discrete Check Active ==> YES          (Yes/No)
          Operate in Warn Mode  ==> NO          (Yes/No)
          RACF Logging           ==> NONE       (Normal/None)

(CMD = (A)dd (D)elete)
CMD  Class   Type Check
'    DATASET FAIL

***** Bottom of data *****

```

Figure 172. RACF Discrete Profiles Entry Panel

Field entry is as follows:

1. Discrete Check Active
 Enter **YES** to activate the control of discrete profile creation. Enter **NO** to deactivate this control.
2. Operate in Warn Mode
 Enter **YES** to enable warning messages to be sent to the person trying to create the discrete profile instead of failing the request.
3. RACF Logging
 Enter **NORMAL** to enable RACF standard logging, or **NONE** to disable RACF logging.

The bottom portion of the panel contains a scrollable area. There are two line commands available:

- Add
 To add entries, enter an **A** in the CMD field and **overtyp**e the **Class** and **Type Check** fields. (**overtyping will not alter the old entry**). The Class entry is for the RACF class to be protected. The Type Check field may contain either **WARN** or **FAIL**
- Delete
 To delete entries, enter a **D** in the CMD field.

External Tape Control

The External Tape function allows a user to read any tape dataset when the following criteria is met, thus bypassing the RACF PROTECTALL(FAIL) option:

- A RACF profile does not exist for the dataset.
- The user has READ level authority to the FACILITY class profile EXTERNAL.TAPE.

```
OS/EM ----- RACF EXTERNAL TAPES ----- Version 6.0
Command ==>
```

```
    Allow access to External Tapes? ==> YES      (Yes/No)
    RACF Logging                      ==> NONE    (Normal/None)
```

Figure 173. RACF External Tape Entry Panel

Field entry is as follows:

- Allow access to External Tapes?
Enter **YES** to activate this function, or **NO** to deactivate it.
- RACF Logging
Enter **NONE** to turn off RACF logging, or **NORMAL** to turn logging on.

Restrict Devices

Description

Restrict Devices provides the option of reserving devices for critical jobs that must complete without waiting for devices to become available. The device is reserved and only the Jobnames that are specified with this option will be able to use the device. Even Operator VARY device commands will not make a restricted device available.

Summary of Features

- Restricts device allocation and usage by Jobname or Jobname masks
- Restricts the console operator from making the device available with a VARY device command
- Automatic REPLY to make the device available for authorized Job or Jobname mask
- Automatically varies the device offline when the authorized Job or Jobname mask has completed

Restrict Devices

```
OS/EM ----- RESTRICT DEVICES ----- Version 6.0
Command ==>                                     Scroll ==> CSR

      Restrict Devices Active ==> YES          (Yes/No)

(CMD = (A)dd (D)elete (G)roup display)
CMD  Device Range      Groups
'    823   : _____  2
'    828   : 82F        2
'    901   : 902        2
'    905   : _____  2
'    907   : _____  2
'    909   : 90B        2

***** Bottom of data *****
```

Figure 174. Restrict Devices

Field entry is as follows:

1. Add

To add entries, enter an **A** in the CMD field and **overtyp**e the **Device Range**, both entries are required. (**Overtyping will not alter the old entry.**)

2. Delete

To delete entries, enter a **D** in the CMD field.

Specify Jobname

```
OS/EM ----- RESTRICT DEVICES ----- Version 6.0
Command ==>                                     Scroll ==> CSR

Restrict Devices Active ==> YES          (Yes/No)

(CMD = (A)dd (D)elete (G)roup display)
CMD Device Range   Groups
G   823   :   _____   2

'   828   |----- JOB NAMES/MASKS -----|
'   901   | (CMD = (A)dd (D)elete)          |
'   905   |   CMD   Jobname or Mask        |
'   907   |   -     OS-                     |
'   909   |   -     SP-                     |
'         | ***** Bottom of data ***** |
'         |-----|
***** | CMD => | *****
```

Figure 175. Restrict Device With Jobname "POPUP" Screen

Field entry is as follows:

1. Add

To add entries, enter an **A** in the CMD field and **overtyp**e the **Jobname** or **Jobname mask** (**overtyping will not alter the old entry**).

2. Delete

To delete entries, enter a **D** in the CMD field.

Jobname / Jobname Mask

Masking Characters: The following table shows the allowable mask characters:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

SVC Controls

Description

The **SVC DELETE/REPLACE** function allows you to delete an SVC so it cannot be executed, or optionally replace it with your own program.

Upon entry to this function you are presented with a scrollable list of the SVCs that have previously been entered, or a blank entry.

```
OS/EM ----- SVC DELETE/REPLACE CONTROLS ----- Version 6.0
Command ==>                                     Scroll ==> CSR

Select from the list below to view/change detail information:

(CMD = (A)dd (D)elete (S)elect for update)

CMD  SVC  Function  Member if
      |   |         |   Replace  Library
-----|---|-----|-----|-----
***** Bottom of data *****
```

Figure 176. SVC Delete/Replace Controls

The fields and their meaning are:

- **CMD**

Three line commands are available:

A - Add new entry. You can use the **A** command on any line. When you press enter, a blank data entry panel will be displayed (see Figure 177 on page 5-216) to allow you to enter the required information.

D - Delete an existing entry.

S - Select for update. When selected, a data entry panel (see Figure 177 on page 5-216) will be displayed to allow information about the SVC to be updated.

- **SVC**

The number of the SVC being deleted/overridden.

- **Function**

The function being performed, either **DELETE** or **REPLACE**.

- **Member if Replace**

The program name which will be loaded in place of the original SVC.

- **Library**

The library name the SVC replacement will be loaded from.

The data entry panel contains several required fields depending on the type of SVC being replaced.




Figure 177. SVC Delete/Reload Entry panel

The fields and their meaning are:

- **SVC Number**
If you are adding a new entry, this field is unprotected and you must enter the number of the SVC you are deleting or replacing. If you are updating an existing entry, this field is protected.
- **Delete/Replace SVC**
Enter the function you wish to perform. If it is delete, no other field should be entered.
- **Program Name for replace**
Enter the name of the program which will replace the existing SVC.
- **SVC Type**
You must specify the type of SVC you are replacing. Specify 1, 2, 3, 4 or 6.
- **Use Lock type CMS/Local**
Specify the type of lock your program needs. If the SVC type is '1', the LOCAL lock is not allowed. If the type is '6', neither type of lock is allowed. If the type is '2, 3 or 4' you MUST specify LOCAL if CMS is specified.
- **Restrict to APF programs**
If only APF authorized programs should be allowed to execute this SVC, enter YES.
- **Access in AR mode**
Enter YES if the SVC replacement should be accessed in Access Register mode.
- **May be Preempted for I/O**
Enter YES to allow the system to preempt your program to handle I/O.
- **Clear User CVT**

Enter YES to have the User CVT field cleared before the SVC is executed.

- Load from library

Enter the name of the library where the SVC replacement program resides. If this field is left blank, the standard search routines are used to locate the load module. The library name should be enclosed in single quotes (').

Tape Share Controls

Description

The Tape Share option allows you to define tape drives to OS/EM which will then control the devices by automatically issuing the VARY commands needed to put the drive offline on one system and online on the system where it is needed. No operator intervention is required.

Note: Since Tape Share controls whether a device is online or offline, we suggest that you configure all drives defined to Tape Share to be offline at IPL time.

This optional feature of OS/EM requires a started task to be running on each system sharing tape devices. A sample of the procedure to execute the started task may be found in the OS/EM SAMPLIB in member name OS\$TPSHR. The name of the started task must remain OS\$TPSHR as OS/EM will issue a start command for this name at IPL time.

Tape Share Controls Menu

```
OS/EM ----- TAPE SHARE CONTROLS ----- Version 6.0
SELECTION ==>

                1 System Level Controls
                2 Device Level Controls
```

Figure 178. Tape Share Controls Menu

This menu contains entries for both system level and device level control information. Both entries must be selected to initially setup Tape Share Controls.

System Level Controls

```

OS/EM ----- TAPE SHARE SYSTEM CONTROLS ----- Version 6.0
Command ==>                                         Scroll ==> CSR

Tape Share Active   ==> YES          (Yes/No)
  Inactivate Option ==> WAIT         (Global/Remove/Wait)

Wait Option         ==> NOHOLD       (Hold/Nohold)
IPL Offline Mode    ==> GLOBAL       (Global/Local)
IPL Online Mode     ==> LOCAL        (Global/Local)
Control DSN         ==> 'SYSX.OSEM.TAPESHR2'

Set System Priority ==> YES          (Yes/No)
  Specify System IDs in Priority Order Below

Primary Command:  (I)nsert  Note: System IDs in Priority Order
Line Commands:   (D)elete, (I)nsert
SEL  System ID   Comment/Description of System ID
'    PROD        Production System_____
'    ZULU        Y2K LPAR_____
'    TEST        Test LPAR_____
***** Bottom of data *****

```

Figure 179. System Level Controls Panel

Use this panel to enter non-specific information about Tape Share Controls. The information on this panel is required before any controls dealing with specific devices become effective.

Field entry is as follows:

1. Tape Share Active

Enter **YES** to turn on Tape Share, or **NO** to disable Tape Share on the current system.

2. Inactivate Option

Specify the action to be taken when Tape Share Controls are deactivated. Enter one of the following:

- Global

This will cause OS/EM to issue a **VARY OFFLINE,GLOBAL** command for all active devices in the tape share pool on every system which has Tape Share Control's active.

- Wait

This will cause OS/EM to wait until every device in the pool becomes free before disabling Tape Share Controls on the current system.

- Remove

This will cause OS/EM to immediately remove the devices from the pool on all systems.

3. Wait Option

Specify the action to be taken if resources are unavailable and the job is placed into a wait state. Specify one of the following:

- Hold

Retain all resources currently allocated.

- Nohold

Any resources currently allocated when the job is placed into a wait may be released and allocated to another task.

4. IPL Offline Mode

Cause the devices selected on the Device Level Controls panel to be taken offline at IPL time.

- Local

The OFFLINE command will only affect the system the command is executed on. Other systems will not be affected.

- Global

The OFFLINE command will affect all systems sharing the specified devices.

5. IPL Online Mode

Cause the devices selected on the Device Level Controls panel to be marked available at IPL time.

- Local

The ONLINE command will only affect the system the command is executed on. Other systems will not be affected.

- Global

The ONLINE command will affect all systems sharing the specified devices.

Note: Does **not** issue a **VARY** command to bring the device(s) online.

6. Control DSN

Specify the dataset name which will be used as the communications dataset. This file must be on shared DASD available to all systems sharing tape drives. Enter the dataset name using standard TSO naming conventions, i.e. if apostrophes do not enclose the dataset name, your TSO ID will be appended to the beginning of the entered name.

Note: The dataset must have the following attributes:

```
RECFM=F , LRECL=29080 , DSORG=PS
```

One track will be sufficient space.

7. Set System Priority

Enter either **YES** or **NO** depending upon your need to specify system priorities. If you specify YES here, you must also enter the system names in the scrollable portion of the panel.

If you have previously specified system names to set priorities, you do not need to remove them when changing this response to NO.

The bottom portion of this panel contains a scroll area. This is used to store the system names/IDs in priority order. Initially this list is empty and you must use the **Insert** primary command to enter the first entry.

There are two line commands available:

- Delete

Use this line command to delete an entry no longer needed.

- Insert

This will cause a popup window to open for entry of the system ID and an optional description of the system. After the fields are completed, press the enter key to have the new system added after the line where the insert line command was entered.

Device Level Controls

```

OS/EM ----- TAPE SHARE CONTROLS ----- Version 6.0
Command ==>                                     Scroll ==> CSR

Enter Device or Range to Add ==> ___ : ___
Comment for Device/Range ==> _____

Line Commands: (D)elete; (F)orce Delete; Overtyp e fields to update
Preference IPL
SEL Device  Alias  Order  Mode  Comment/Description of Device
'  0200  _____  _____  OFFLINE  Cart Drives_____
'  0201  _____  _____  OFFLINE  Cart Drives_____
'  0202  _____  _____  OFFLINE  Cart Drives_____
'  0203  _____  _____  OFFLINE  Cart Drives_____
'  0204  _____  _____  OFFLINE  Cart Drives_____
'  0205  _____  40      ONLINE   Cart Drives_____
'  0206  _____  _____  _____  Cart Drives_____
'  0207  _____  _____  _____  Cart Drives_____
'  0208  _____  _____  _____  Cart Drives_____
'  0209  _____  30      ONLINE   Cart Drives_____
'  020A  _____  _____  _____  Cart Drives_____
'  020B  _____  20      ONLINE   Cart Drives_____
'  020C  _____  10      ONLINE   Cart Drives_____

```

Figure 180. Device Level Controls Panel

Use this panel to enter information about specific tape device addresses. The system level controls must be completed for this information to be used.

Field entry is as follows:

1. Enter the address of a tape device to be placed into the tape share pool. A range of addresses may also be entered.
2. Enter a comment for the device or device range. This is an optional field, and is only used for documentation purposes.
3. Press the **enter** key to have the device or device range entered into the scrollable list in the bottom portion of the panel.

After the device addresses are in the scrollable list, you may assign **alias** entries, assign a **preference order** of use, and the **mode** the device will be placed in at IPL time. To change any of these entries, simply overtype the field to be added or changed and press the enter key.

Following is an explanation of each of these optional items.

Alias

Used if all systems do not refer to a device with the same address. In this case, a global name is assigned that all systems will use, and the machine which has a different address will use the ALIAS keyword to bind the local address to the global address.

Preference Order

The order in which the drives will be assigned. Lowest number to highest number. It is suggested that you enter numbers at least 10 apart to allow other drives to be added into the order at a later date.

IPL Mode

Enter either **ONLINE** or **OFFLINE** to specify the mode the drives will be placed in at IPL time. If specified, the global or local option entered on the systems controls menu will be used for that address.

Line Commands

Use the **Delete** command to remove devices from Tape Share's control. The Delete command will wait for the device(s) to become unallocated. Use the **Force Delete** command to remove the device from Tape Share's control immediately. Tape Share will **not** wait for the device to become unallocated.

Time Controls

Description

Time Controls provides the option of enforcing CPU time limitations, extending CPU time, JOB wait time, and TSO wait time as well as controlling by job class the insertion of a missing time parameter, overriding the time specified on the jobcard, or canceling the job if job time is greater than the JES2 time value.

Summary of Features

- Insert a missing time parameter
- Reset the jobcard's time parameter to match JES, or optionally cancel the job.
- Set CPU time limits by JOBCLASS
- Extend CPU time limits by JOBCLASS
- Extend SMF wait time by JOBCLASS (Avoid S522 for slow tape mounts and Operator replies)
- Re-issue Tape mount messages to Operator Console
- Check for Tape mount failures and send notification messages to Operator Console
- Extend SMF wait time for TSO users by USERID and/or Terminal ID mask for certain days of the week and time of day (good for session managers)

Time Controls Menu

```
OS/EM ----- TIME CONTROLS MENU ----- Version 6.0
SELECTION ==>>

                1  Job Time Controls

                TIME EXTENSIONS
                2  System Level Controls
                3  Selection Lists Processing
```

Figure 181. Time Controls Menu

Each of these paths is presented in the following sections:

1. Job Time Controls (see “Job Time Controls”)
2. System Level Controls (see “Time Extensions System Level Controls” on page 5-226)
3. Selection Lists Processing (see “Selection Lists Processing” on page 5-228)

Job Time Controls

The JOB TIME function allows you to control by job class the insertion of a missing time parameter, override the time specified on the jobcard or optionally cancel the job for incorrect time values.

You also have the option of cancelling **all** jobs coming into the system which do not have a time specified. This option takes precedence over the **Insert Missing** by job class function.

For each job class selected the following processing occurs:

- If Insert time parameter is active and the jobcard does not have the time parameter coded, the job's time limit is set to match the time specified for that class in JES2.
- If Reset MAXIMUM is active and the jobcard has TIME=MAXIMUM coded, execution time is reset to match the time specified for that class in JES2.
- If Reset NOLIMIT is active and the jobcard has TIME=NOLIMIT or TIME=1440 coded, execution time is reset to match the time specified for that class in JES2.
- If Reset if HIGH is active and the jobcard's time parameter is set higher than the time specified in JES2 for that class, the execution time is reset to match that specified in JES2.
- If Reset if LOW is active, and the jobcard's time parameter is set lower than that specified in JES2, the execution time is reset to match JES2.

```

OS/EM ----- JOB TIME CONTROLS ----- Version 6.0
COMMAND ==>

      Job Time Controls Active      ==> YES      (Yes/No)
            Cancel Option Active    ==> NO      (Yes/No)
            Time Parameter Required? ==> NO      (Yes/No)

CMD ACTIVE FUNCTION |----- JOB CLASSES SELECTED -----|
_ NO  Insert Time Parameter #####
_ NO  Reset MAXIMUM      #####
_ NO  Reset NOLIMIT     #####
_ NO  Reset if High     #####
_ YES Reset if Low       #####F#####

(CMD = (S)elect for update; (C)lass set/modify)

```

Figure 182. Job Time Controls

The fields and their meaning for this input panel are:

- **Job Time Controls Active**
This field allows you to turn off Job Time Controls without having to disable each function type individually.
- **Cancel Option Active**
When this option is selected, any job trying to increase it's allowable job time will be flushed instead of having it's job time simply reset.
- **Time Parameter Required?**
This option insures that every job coming into the system contains a time parameter, regardless of the class the job is submitted in. When this option is active, if the time parameter is missing, the job is flushed. This option takes precedence over the **Insert Missing** by class option.

The above example shows that all classes will have their job time set if the time parameter is missing on the jobcard; Classes A,B,C,D and E will reset the time if the jobcard has TIME=MAXIMUM coded; classes N, O and P will be reset if the job has TIME=NOLIMIT or TIME=1440; classes 4, 5, and 6 will have their time reset if the time parameter is greater than that specified in JES2; class X will be reset only if the job's time parameter is set lower than that specified in JES2.

The '#' symbol represents a class available for use.

Two line commands are available:

- S** Select for update; use this to change the Active indicator from YES to NO.
- C** Class set/modify; when you use this line command, a popup window will open (see Figure 183) allowing you to specify or change the classes for the selected function. On the popup window, you may specify the classes in a range, i.e. A:D will activate the function for classes A, B, C and D.




Figure 183. Job Time Controls Pop-up window.

Time Extensions System Level Controls

OS/EM provides support to extend execution time at both the job and step level. It also allows you to extend wait time for batch jobs, TSO users and/or terminals.

For both step and job CPU time, you may specify individual job classes or all classes to be given the default time extension. You can specify time extension by class which is different than the default time. You may also request OS/EM issue a WTO every time an extension is given.

To ensure that a job is not overlooked while extensions are being given, a WTOR may be issued every 1 to 99 times an extension is granted.

Wait time extensions may be granted by job class, and for TSO activity, by user ID, terminal ID and active hours by day of week.

If both job and step time has been exceeded at the same time, it is unpredictable which indicator will be presented to OS/EM first. Because of this, it is suggested that you setup extensions for both job and step CPU times.

Screen Figure 184 on page 5-227 shows where RACF information, default time information and selection weights are entered.

```

OS/EM ----- TIME EXTENSIONS SYSTEM LEVEL ----- Version 6.0
COMMAND ==>

Grant Time Extensions:  YES

Weights: (1 to 5)
Days:          1          Program:          2
Jobclass:     3          Terminal:       4
Jobname:      5

Defaults:
Time          WTO When   WTOR After
Job CPU:     60 (sec)   Granted      How Many
Step CPU:    60 (sec)   YES          1
TSO Time:    10 (min)   _____  (Time before Disconnect)
Wait Time:   15 (min)   _____

RACF:
Job CPU:     60 (sec)   YES          _____  RACF
Step CPU:    60 (sec)   YES          5          Logging RACF Resource Name
TSO Time:    10 (min)   _____  NORMAL   RACF.JOBCPU
Wait Time:   15 (min)   _____  NONE     _____
NORMAL   RACF.WAIT_____

```

Figure 184. System Level Controls

The fields and their meanings are as follows:

- Extension Controls Active
Enter **YES** or **NO** to activate or inactivate extension controls.

- Weights:
There are 5 weight classes:

1. Days
2. Jobclass
3. Jobname
4. Program
5. Terminal

Enter a number from 1 to 9 for each selection criteria type. The higher the number the more weight that is given to that selection type. In other words, if a job that is running matches multiple extension groups, the group with the highest weight will take effect.

The defaults block is where you can specify extension time that will take effect if no extension group matches a given job or userid.

- Job CPU Time
- Step CPU Time
- Wait Time

Specify the number of seconds a job and/or step should be given and the number of minutes of wait time a job/user/terminal may receive.

- WTO when Granted
To have a WTO issued each time an extension is granted, enter **YES** here.

- WTOR After How Many

To have a WTOR issued to allow the operator to either cancel a job or allow another extension, enter the number of extensions that may be granted before a WTOR is issued. Enter a number from 1 to 99.

Note: While OS/EM is waiting for an operator response the job will continue to execute. This was a design decision by IBM.

The RACF block is where you can specify extension time that will take effect for any job/user/terminal which matches an entry in the specified RACF resource. This block takes precedence over the normal defaults or an extension group.

The Time, WTO and WTOR fields are identical to the defaults block. The RACF block has two additional fields:

- RACF Logging

Enter either **NORMAL** or **NONE** to control RACF logging.

- RACF Resource Name

Enter the name of the resource you have assigned to control Time Extensions. This resource must be defined in the general resource FACILITY class for RACF and CA-ACF2 or the IBMFAC class for CA-Topsecret. Users to be given extensions must have **READ** access to this profile.

Selection Lists Processing

The Time Extension Controls panel lists the 32 available extension groups. Each group will have at least one list of job classes, job names, program names, terminal IDs, or time of day to control which extension is granted to whom.




Figure 185. Selection Lists

Extension 1 shown in Figure 185 is active. A job level time extension of 45 seconds will be granted. Each extension will have a message written to the operator. After 5 extensions, a WTOR will be issued to allow the operator to cancel the job if necessary. A step level extension of 15 seconds will also be given. Again a WTO will be issued at each extension and a WTOR will be issued after 2 extensions. Wait time will be extended by 30 minutes, and a WTO will **not** be issued when the extension is granted.

There are 5 active selection lists for Extension 1:

1. The Time of Day list contains the days and hours within that day that WAIT extensions will be granted. This list is always an include list.
2. The Class list contains the job classes which may have the execution time extended, if it is an include list, or the classes which will not have execution time extended in the case of an exclude list.
3. The Name list contains job names and/or TSO IDs. An include list will have the names of jobs which may have their execution and wait time extended or the TSO IDs which may have their wait time extended. An exclude list will contain the names of jobs and/or TSO IDs which may not be extended.
4. The PGM list contains program names. Again, an include list will contain programs which may be extended, and the exclude list contains programs which will not be extended while all other programs will be.
5. The terminal list contains terminal addresses. An include list contains the addresses of terminals which may have their wait time extended. The exclude list contains terminals which may not be extended, while all others will be.

There are two line commands available: **S** to add/update selector entries and **D** to remove all selector entries and clear the selection list of time and WTO values.

When the line command is processed, another panel Figure 186 is displayed where you may select any of the lists for update as well as change the list type between include and exclude. The Days list is always an include list.

```
OS/EM ----- SELECTOR ENTRY - 1 ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

Enter Selector Types, either Include or Exclude
      Jobclass ==>                               Jobname ==> INCLUDE
      Pgmname  ==> INCLUDE                       Terminal ==>

Line Cmds: (D)elete line, (I)nsert line

Selector
  Type      Selector Names/Mask List
- JOBNAME   PCEDI
- PGMNAME   IKJEFT01
- MONDAY    0001:2400
- TUESDAY   0001:2400
- WEDNESDAY 0001:2400
- THURSDAY  0001:2400
- FRIDAY    0001:2400
- SATURDAY  0001:2400
- SUNDAY    0001:2400
***** Bottom of data *****
```

Figure 186. Selector Entry Panel

The **selector entry** panel allows you to enter the criteria that will be used to select a job that will have its time adjusted.

There are five types of selectors:

JOBCLASS Enter the jobclasses that the job being evaluated must match if this is an include type list, or the classes which the job must not match for an exclude list.

The jobclasses may be entered individually separated by spaces or as a range where the beginning class and ending class is separated by a colon (:).

JOBNAME Enter any jobnames either as complete names or as a jobname mask. Separate the names or masks with a space. Enter as many names/masks as will fit on the line. If additional names need to be entered simply insert a blank line and enter the selector type as **JOBNAME** and continue entering names or masks.

PGMNAME Enter any program names either as complete names or as a program name mask. Separate the names or masks with a space. Enter as many names/masks as will fit on the line. If additional names need to be entered simply insert a blank line and enter the selector type as **PGMNAME** and continue entering names or masks.

TERMINAL Enter any terminal IDs as the complete ID or as a mask. Separate the IDs or masks with a space. Enter as many IDs/masks as will fit on the line. If additional IDs need to be entered simply insert a blank line and enter the selector type as **TERMINAL** and continue entering IDs and or masks.

Day of Week Use the day of week you need to specify a time range as the selector type then in the Selector Names/Mask List field enter the beginning and ending times separated by a colon (:), using the 24 hour time format. Only one time range is allowed per day.

If you want the control to be active on Monday between 8AM and 5PM enter the selector type as **MONDAY** then enter 0800:1700 in the list field.

Query OS/EM Status

The QUERY function displays the state of the OS/EM environment.

The ALL and ACTIVE options are mutually exclusive. If you select no options, ACTIVE is assumed.

The output of the QUERY command is to a dataset that will be browsed by the ISPF BROWSE function. When you have finished viewing the output, the END key will exit the browse function.

The SMF, TSO, DASD, ALLOC, RACF, JES2, JES3, HSM and ISPF options can be limited to a specific exit point by entering its name in the supplied field. If the exit does not exist, an error will be returned.

To limit the display of JES2 exit information, you may enter the name of the JES2 subsystem to be displayed in the JESNAME field. If left blank, all JES2 subsystems will be displayed.

The POOL display may be limited to Data Set Name Groups (DSN), Volume Name Groups (VOL), or QuickPool definitions (POOL).

```
OS/EM ----- OS$CNTL QUERY COMMAND ----- Version 6.0
COMMAND ==>

      _ ALL                _ ACTIVE
      _ ALLOC ( _____ )  _ DASD ( _____ )
      _ HSM  ( _____ )    _ ISPF ( _____ )
      _ JES2 ( _____ )    JESNAME ( _____ )
      _ JES3 ( _____ )    _ MISC ( _____ )
      _ POOL ( _____ )    _ RACF ( _____ )
      _ SAF  ( _____ )    _ SMF  ( _____ )
      _ TSO  ( _____ )    _ SYSTEM

      Name of file for browse dataset ==> TEMP.QUERY

      ENTER to continue
```

Figure 187. OS\$CNTL Query Command

To select a QUERY option, from specific to ALL, enter an S before the QUERY option.

When the query has completed you will be placed into BROWSE to view the results. Below is a sample of the first page of generated output for the SMF IEFACRT exit.

```
Menu Utilities Compilers Help
-----
BROWSE      HEJT2.OS$EM.QUERY                               Line 00000000 Col 001 080
Command ===>                                           Scroll ===> CSR
***** Top of Data *****
OS/EM VER: 6.0.1 TIME: 5:16:54 DATE: 9/10/2004 SYSPLEX: ADCDPL  SID: P390
SMF DATA
NOTIFY: <NONE>
IEFACTRT - EXIT IS ENABLED
VALID RETURN CODES: (DEFAULT) ANY
GOOD RETURN CODES: (DEFAULT) 0
DISABLING RETURN CODES: (DEFAULT) NONE
DEFAULT RETURN CODE: (DEFAULT) 0
OS/EM EXIT - CALLED FIRST - NOTIFY: <NONE>
EXIT (OS$ACTRT) - VERSION 6.0.1 2004-09-03 20:17:45
  ADDR: 0B02AAD8 EP: 8B02AAD8 - SOURCE: OSV6
```

Figure 188. Sample Query Output

Reload Exits

Selection Menu

Use of this screen will result in the generation of RELOAD commands for the optional OS/EM control functions, and for the various OS/EM interface modules.

You would not normally reload these modules unless you had applied maintenance to the OS/EM system. Instructions with the OS/EM maintenance tape will indicate if any of these modules have to be reloaded.

```
OS/EM ----- SELECT MODULE TYPE FOR RELOAD ----- Version 6.0
COMMAND ===>

          1 - JES2 User Modules
          2 - JES3 User Modules
          3 - MVS User Modules
          4 - OS/EM System Modules
          5 - RACF tables
```

Figure 189. Module Type Reload Selection

Each of these paths is presented in the following sections:

1. JES2 User Modules (see “JES2 Exits User Modules” on page 7-2)
2. JES3 User Modules (see “JES3 Exits User Modules” on page 7-3)
3. MVS Exits User Modules (see “MVS Exits User Modules” on page 7-4)
4. OS/EM System Modules (see “OS/EM System Modules” on page 7-5)
5. RACF Tables (see “RACF Tables” on page 7-6)

JES2 Exits User Modules

The JES2 Reload Selection panel displays all of the active JES2 exits. Scroll through this list to find the exit(s) which need to be reloaded.

The list of user exits displayed is controlled by the active JES2 subsystem. Please use **Option 6 - Set JES name** to select the active JES2 subsystem name. (See “Set JES2 Name” on page 8-1)

```
OS/EM ----- JES2 - EXIT RELOAD SELECTION ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

(S)elect for Reload

      Primary Exit:EP
Exit Point /Backup Exit:EP   Load Library
EXIT000 '  HASPXIT0 : EXIT00  _____
      '          :           _____
EXIT000 '  HASPXIT0 : EXIT01  _____
      '          :           _____
EXIT000 '  HASPXIT0 : EXIT02  _____
      '          :           _____
EXIT000 '  HASPXIT0 : EXIT03  _____
      '          :           _____
***** Bottom of data *****
```

Figure 190. JES2 Reload Selection

The scrollable list presented shows all the primary and backup user exits which have been defined using the ISPF Interface. Select any exit which needs to be reloaded by placing an **S** before the exit name. You may optionally specify or change the load library where the exit to be reloaded resides. The library name should be enclosed in single quotes (').

After pressing the enter key to register your selections, the exits are removed from the display.

If an exit has been **selected in error**, enter the **cancel command** to exit the selection list without reloading the exits.

The reload commands are generated and executed when you exit the selection list.

Note: If you need to reload an exit which has not been defined to the ISPF Interface, you will need to define it before it will be displayed in this list. This includes exits which OS/EM finds and loads at IPL time. You may wish to use the REBUILD function (see “Rebuild OS/EM Tables” on page 3-8) which will find and add all currently loaded user exits to the interface.

JES3 Exits User Modules

The JES3 Reload Selection panel displays all of the active JES3 exits. Scroll through this list to find the exit(s) which need to be reloaded.

```
OS/EM ----- JES3 RELOAD SELECTION ----- Version 6.0
COMMAND ==>>>                                     SCROLL ==>>> CSR

(S)elect for Reload

Exit Point      Primary
                /Backup   Load Library
IATUX03      1      ' J3USRX9   _____
                '
IATUX03      2      ' J3USRX10  _____
                ' J3USRY10  _____
IATUX07      1      ' J3USRM14  'USER.LINKLIB'
                '
***** Bottom of data *****
```

Figure 191. JES3 Reload Selection

When an exit is found, enter an **S** in front of the module name and press enter. You may **change** or **add** the **library name**. The library name should be enclosed in single quotes (').

Changes made here are not saved. To make any needed changes permanent, make the changes through the “Basic Exit Functions” on page 4-1.

If an exit has been **selected in error**, enter the **cancel command**.

The reload commands are generated and executed when you exit the selection list.

Note: If you need to reload an exit which has not been defined to the ISPF Interface, you will need to define it before it will be displayed in this list. This includes exits which OS/EM finds and loads at IPL time. You may wish to use the REBUILD function (see “Rebuild OS/EM Tables” on page 3-8) which will find and add all currently loaded user exits to the interface.

MVS Exits User Modules

The MVS Reload Selection panel displays all of the active MVS exits. Scroll through this list to find the exit(s) which need to be reloaded.

```

OS/EM ----- EXIT RELOAD SELECTION ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

(S)elect for Reload

Exit Point      Primary
                /Backup  Load Library
ICHRIX02   1      '  ICHRIX02  _____
                '
IEFU29     1      '  USRU29   'USER.LINKLIB'
                '
IGGPOST0   1      '  IGGPOST0  _____
                '
IGGPRE00   1      '  IGGPRE00  _____
                '
IKJEFF10   1      '  IKJEFF10  'SYS1.LINKLIB'
                '
IKJEFF53   1      '  IKJEFF53  'SYS1.OSEM.LOAD1 '
                '
IKJEFLN2   1      '  IKJEFLN2  'SYS1.OSEM.LOAD1 '
                '
***** Bottom of data *****

```

Figure 192. MVS Exit Reload Selection

When an exit is found, place an **S** in front of the module name and press ENTER. You may add or change the load library where the module to be reloaded resides. The library name should be enclosed in single quotes (').

Changes made here are not saved. To make any needed changes permanent, make the changes through the “Basic Exit Functions” on page 4-1.

If an exit has been **selected in error**, enter the **cancel command**.

The reload commands are generated and executed when you exit the selection list.

Note: If you need to reload an exit which has not been defined to the ISPF Interface, you will need to define it before it will be displayed in this list. This includes exits which OS/EM finds and loads at IPL time. You may wish to use the REBUILD function (see “Rebuild OS/EM Tables” on page 3-8) which will find and add all currently loaded user exits to the interface.

OS/EM System Modules

The System Reload Selection panel displays all of the active System exits. Scroll through this list to find the exit(s) which need to be reloaded.

```
OS/EM ----- SYSTEM RELOAD SELECTION ----- Version 6.0
COMMAND ==>                                     SCROLL ==> CSR

      Sel   Module Name  Description
      '     OS$ACTRT    Job/Step End Statistics
      '     OS$ADEXT    HSM Dataset Deletion
      '     OS$ALCCN    ALLOC Controller
      '     OS$ALLOD    Offline Device Allocation
      '     OS$ALLSW    Specific Wait Allocation
      '     OS$ASYNC    Asynchronous WTO/SEND Routine
      '     OS$BDEXT    HSM Dataset Backup
      '     OS$CDEXT    HSM Dataset Reblock
      '     OS$CMD      MVS Command Review
      '     OS$COMM     Common Storage Access
      '     OS$DADCN    DADSM Controller
      '     OS$DB401    Dynamic Allocation
      '     OS$DEL      OS/EM Module Delete
      '     OS$ECALL    Extended Call Function
      '     OS$EFF10    TSO Submit Command
      '     OS$EFLD1    LOGON Pre-prompt
```

Figure 193. System Reload Selection

When an exit is found, enter a **S** in front of the module name and press ENTER.

If an exit has been **selected in error**, enter the **cancel command** which will cancel all system reload processing. Reselect the OS/EM System Modules to respecify the correct system modules to be reloaded.

RACF Tables

The RACF Tables Reload Selection panel displays the three RACF Tables available to be reloaded.

```
OS/EM ----- RACF TABLE RELOAD SELECTION ----- Version 6.0
COMMAND ==>                                         SCROLL ==> CSR

Sel  Table Name  Replacement  Reset
      |          |  Module Name or (yes/no)  Library Name
'    ICHRRF01   _____  _____  _____
'    ICHRIN03   _____  _____  _____
'    ICHRRCDE   _____  _____  _____
***** Bottom of data *****
```

Figure 194. RACF Table Reload Selection

To cause a table to be reloaded, place an **S** in front of the module name. If you are replacing the table with another module, enter the module name in the field provided. If you just want to reset the module, leave the replacement module name blank and enter YES in the reset field.

An optional library name may also be specified. This library must be APF authorized. The library name should be enclosed in single quotes (').

Set JES2 Name

OS/EM requires the name of the JES2 subsystem it is to control. Since you may have several JES2 subsystems, use this function to specify those names.

If you plan to use the Password function of JES Exit2, you need to specify a free User PCE field to ensure that OS/EM does not overwrite data that one of your in-house exits might be using.

```
OS/EM ----- JES2 SUBSYSTEM NAMES ----- Version 6.0
Command ==>                                     Scroll ==> CSR

Primary Command: (A)dd new subsystem
Line Commands: (S)elect Active, (D)elele Subsystem

  Subsystem      Primary
Sel Name  Version  JES  Active  PCE  Install  Subsystem Description
'  JESL  SP510__ NO_          1    YES
'  JESX  OS210__ NO_          1    YES
'  JESZ  ZS102__ NO_          1    YES
'  JES2  ZS105__ YES  ACTIVE  1    YES
***** Bottom of data *****
```

Figure 195. JES2 Subsystem Names

This panel shows:

- The JES2 subsystem names which have been defined to OS/EM.
- The JES2 version of any defined JES2 subsystems.
 - OS270
 - OS280
 - OS210
 - ZS102
 - ZS104
 - ZS105
- The **primary** JES2 subsystem.
- Which subsystem name is currently active/available for data entry via the OS/EM ISPF interface.
- The PCE user field that OS/EM should use.
- The Auto Install option.
- An optional description of the subsystem.

There are two line commands available on this panel:

S Use **S** to select the active subsystem. All OS/EM entries processed through the interface which affect JES2 will be processed against this subsystem name.

D Use **D** to delete an incorrect or obsolete name.

The Version, Primary JES, PCE, AutoInstall and Subsystem Description fields may be changed by simply overtyping whatever is there. The PCE field will only accept a value of 0 or 1.

The one primary command available on this panel is **A** which is used to add a new subsystem. When entered on the command line and the enter key is pressed the following panel will be displayed.

```
OS/EM ----- ADD JES2 NAME ----- Version 6.0
COMMAND ==>

Specify your JES2 sub-system name and optionally a description of the system.
JESNAME ==>          Description ==> _____
Primary JES  ==> NO          (Yes/No)
JES version  ==>              (Required for secondary JES)
AutoInstall  ==> YES         (Yes or No)
PCE User Code ==> 1         (0 or 1)
```

Figure 196. Add JES2 Subsystem

All fields with the exception of the description field are required.

Execute Pending Changes

As you make changes to the OS/EM parameters through the ISPF interface, a record is kept of the parameters changed.

When you select Pending Changes from the OS/EM Primary Option Menu, you are presented with a scrollable list of the changes you have made. The items are presented in reverse date/time order so that the most current changes are displayed first.

This information is dropped either when you use the Pending Changes Maintenance function (see "Pending Changes Table Maintenance" on page 3-8) or the Rebuild function (see "Rebuild OS/EM Tables" on page 3-8.)

```
OS/EM ----- PENDING CHANGES ----- Version 6.0
COMMAND ==>>>                                SCROLL ==>> CSR

(CMD = (B)rowse changes (E)xecute online (S)ubmit Batch Job (R)eset   Last
CMD  EXE   Control Type/Last Updated                                Action
'    EXE   ACCOUNT NUMBER CONTROLS                                EXECUTED
      SPJRT   15:58   92/10/26
'      ADD NOTIFY STATEMENT                                CHANGED
      SPJRT   10:26   92/10/27
'      DATASET NAME GROUPS MAINTENANCE                       CHANGED
      SPJRT   11:00   92/10/29
'      ENABLE/DISABLE JOB NAME CHECKING                      SELECTED
      SPJRT   10:11   92/10/27
'      HSM: DIRECT TO LEVEL-2 CONTROL                        CHANGED
      SPJRT   10:19   92/10/27
'      JES2 EXITS                                           SELECTED
      SPJRT   10:05   92/10/27
'      JES3 EXITS                                           SELECTED
      SPJRT   09:55   92/10/29
'      INIT MVS EXITS                                       INIT
      SPJRT   10:33   92/10/27
'      SPECIFY TSO USERS AND/OR TERMINALS                   CHANGED
```

Figure 197. Execute Pending Changes - Review/Execute

Field entry is as follows:

1. **CMD**

Four line commands are available, **B** for Browse changes, **E** for Execute online, **S** to process the changes in batch and **R** for Reset.

When you enter a **B**, you are presented with detail information about the changes made (see Figure 198 on page 9-3).

Entering an **E**, marks the Control Type for execution at the end of your current Pending Changes session.

Entering an **S**, marks the Control Type for execution in batch at the end of your current Pending Changes session.

If you decide that you have marked a Control Type in error, enter **CAN** or **CANCEL** on the command line to cancel all pending executions.

Use the **R** or **RESET** line command if you need to remove the EXE flag to allow the changes to be re-executed.

2. **Control Type**

Control Type gives you the name of the function changed, i.e., if you made a change to your dataset name groups, the Control Type would be displayed as DATASET NAME GROUPS MAINTENANCE.

3. **Execute**

The EXE field will show INIT if the last action was the building of the initialization member, EXE if the last action was to execute the changes or either ONL or SUB if you have marked the item to be executed at the end of your pending changes session.

4. **Last Updated**

The Last Updated field displays the TSO ID of the person making the change, the time the change was made and the date.

5. **Last Action**

The Last Action field gives you an idea of what the last change was.

While an entry that has a non-blank XEQ node will have JCL generated with a route card:

```
/*ROUTE XEQ node
```

WARNING: OS/EM job routing has the ability to change any SYSAFF statements to SYSAFF=ALL so if using OS/EM job routing it is suggested you use the XEQ Node field and enter a valid resource name.

To select the systems where a batch job will be routed enter an **S** in the S column and press. Alternatively enter **YES** in the 'select ALL IDs' field to have JCL generated for jobs on all the systems listed.

When executing changes in batch a special member is created in the OS/EM PARMLIB with the name **SUBPEND**. This member contains OS\$CNTL commands for all of the changes selected. This PARMLIB must be available on each system selected.

Once each system is selected pressing the **END** key will present you with a job card skeleton which you must update with any information required by your shop, i.e. account number information.

```
OS/EM ----- EXECUTE PENDING CHANGES IN BATCH ----- Version 6.0
COMMAND ==>

Job Statement Information: Verify before proceeding

==> //HEJT2A JOB (ACCT),PENDINGCHGS,
==> //      MSGCLASS=X,CLASS=A,NOTIFY=&SYSUID,REGION=0M
==> /*
==> /*

Press PF3 (END) to submit job, or enter CANCEL to exit.
```

Figure 200. Pending Changes Job Card

Pressing **PF3** or the **END** key will cause all needed jobs to be submitted.

Build Initialization Member

Depending on the number of specifications you have entered, the process to Build Initialization Members may take some time; therefore, a panel is presented letting you know the process has been started (see Figure 202 on page 10-2). You will be told if the build has been successful or not.

```
OS/EM ----- BUILD INITIALIZATION MEMBERS ----- Version 6.0
SELECTION ==>

  Select the Initialization member(s) to build from the following list:

                SYSTEM WIDE CONTROLS
      _ SYSTEM - Authorization Codes/SMF Recording

                BASIC EXIT FUNCTIONS
      _ JES2 - Basic JES2 exits
      _ JES3 - Basic JES3 exits
      _ MVS  - Basic MVS exits

                EXTENDED FUNCTIONS
      _ DASD - DASD Allocation controls      _ DSN  - DSN group definitions
      _ HSM  - HSM Optimizer controls        _ JCL  - JCL controls
      _ JOB  - Job controls                  _ JOBR - Job Routing controls
      _ MISC - Miscellaneous Controls        _ POOL - Volume/Dataset associations
      _ PREF - ISPF Log/List/Temp Prefix    _ RACF - Discrete Profile controls
      _ RSTR - Restrict Devices controls    _ SVC  - SVC Delete/Replace controls
      _ TPSH - Tape Share controls          _ TIME - Time controls
      _ VOL  - Volume group definitions
```

Figure 201. Build Initialization Members

The output of the build is placed in the OS/EM PARMLIB whose name is constructed from the site variables which were defined in the OS\$START command during OS/EM installation. This dataset must be available to OS/EM during its startup process as the started task OSV6 uses it as input.

Member names are indicative of the function: for example, HSMINIT is the initialization member for DFHSM support.

```
OS/EM ----- INITIALIZATION MEMBER BUILD ----- Version 6.0  
COMMAND ==>
```

```
PLEASE WAIT. . . . .
```

```
The initialization member you requested:
```

```
TIME CONTROLS
```

```
is being generated.
```

```
Depending on the options you have chosen, this process may take some  
time.
```

```
Now processing: WAIT TIME CLASSES
```

Figure 202. Build Initialization Members - Status

Appendix A. Supported Exits

The following is a list of SMF, TSO, ISPF, JES2, JES3, RACF, Allocation and DFP exits that OS/EM currently supports. The standard support manages the loading and execution of up to three user exits, and optionally an OS/EM exit that provides the Extended support. The listed usage may not cover all the conditions the exit can handle; it is only suggestive of the common use.

Allocation Exits

IEFALLOD	Allocated/Offline Device Exit
IEFALLSW	Specific Waits Exit
IEFALLVE	Volume Enqueue Exit
IEFALLVM	Volume Mount Exit
IEFDB401	Allocation Input Validation Exit (SVC99)

Data Facility Product (DFP) Exits

IGGPREE00	DADSM Pre-processing for Allocate, Extend, Scratch, Partial Release and Rename
IGGPOST0	DADSM Post-processing for Allocate, Extend, Scratch, Partial Release and Rename

Data Facility Hierarchical Storage Manager (DFHSM) Exits

ARCADEXT	Data Set Deletion Exit
ARCBDEXT	Data Set Backup Exit
ARCBEEXT	ABARS Backup Error Exit
ARCCBEXT	Control Data Set Backup Exit
ARCCDEXT	Data Set Reblock Exit
ARCCREXT	ABARS Conflict Resolution Exit
ARCEDEXT	ABARS Expiration Date Exit
ARCINEXT	Initialization Exit
ARCMDEXT	Data Set Migration Exit
ARCMMEXT	Second-Level Migration Data Set Exit
ARCMVEXT	Space Management Volume Exit
ARCM2EXT	ABARS Migration Level 2 Data Set Exit
ARCRDEXT	Recall Exit (Not valid for SMS Managed Data Sets)
ARCRPEXT	Recall/Recover Priority Exit
ARCSAEXT	Space Management and Backup Exit
ARCSDEXT	Shutdown Exit
ARCSKEXT	ABARS Data Set Skip Exit
ARCTDEXT	Tape Data Set Exit
ARCTEEXT	Tape Ejected Exit
ARCTVEXT	Tape Volume Exit

ISPF Exits

Exit 1	ISPF initialization
Exit 2	ISPF termination
Exit 3	SELECT service start
Exit 4	SELECT service end
Exit 5	TSO command start
Exit 6	TSO command end
Exit 7	LIBDEF service
Exit 8	RESERVE
Exit 9	RELEASE
Exit 10	Logical screen start
Exit 11	Logical screen end
Exit 12	ISPF/PDF service start
Exit 13	ISPF/PDF service end
Exit 14	SWAP logical screens
Exit 15	DISPLAY service start
Exit 16	Log, list, and temporary data set allocation

Job Entry System Two (JES2) Exits

IBM supported Exit points 0-49

Exit 0	Pre-initialization
Exit 1	Print/Punch Separators
Exit 2	Job Statement Scan
Exit 3	Job Statement Accounting Field Scan
Exit 4	JCL and JES2 Control Statement Scan
Exit 5	JES2 Command Preprocessor
Exit 6	Converter/Interpreter Text Scan
Exit 7	JCT Read/Write (JES2)
Exit 8	Control Block Read/Write (User)
Exit 9	Job Output Overflow
Exit 10	\$WTO Screen
Exit 11	Spool Partitioning Allocation (\$TRACK)
Exit 12	Spool Partitioning Allocation (\$STRAK)
Exit 13	TSO/E Interactive Data Transmission Facility Screening and Notification
Exit 14	Job Queue Work Select - \$QGET
Exit 15	Output Data Set/Copy Select
Exit 16	Notify
Exit 17	BSC RJE SIGNON/SIGNOFF
Exit 18	SNA RJE SIGNON/SIGNOFF
Exit 19	Initialization Statement
Exit 20	End of Input
Exit 21	SMF Record
Exit 22	Cancel/Status
Exit 23	FSS Job Separator Page (JSPA) Processing
Exit 24	Post-initialization
Exit 25	JCT Read (FSS)
Exit 26	Termination/Resource Release
Exit 27	PCE Attach/Detach
Exit 28	Subsystem Interface (SSI) Job Termination
Exit 29	Subsystem Interface (SSI) End-of-Memory
Exit 30	Subsystem Interface (SSI) Data Set Open and RESTART
Exit 31	Subsystem Interface (SSI) Allocation
Exit 32	Subsystem Interface (SSI) Job Selection
Exit 33	Subsystem Interface (SSI) Data Set Close
Exit 34	Subsystem Interface (SSI) Data Set Unallocation

Exit 35	Subsystem Interface (SSI) End-of-Task
Exit 36	Pre-security Authorization Call
Exit 37	Post-security Authorization Call
Exit 38	TSO/E Receive Data Set Disposition
Exit 39	NJE SYSOUT Reception Data Set Disposition
Exit 40	Modifying SYSOUT Characteristics
Exit 41	Modifying Output Grouping Key Selection
Exit 42	Modifying a Notify User Message
Exit 43	Transaction Program Select/Terminate/Change
Exit 44	JES2 Converter Exit (Main Task)
Exit 45	Pre-SJF Exit Request
Exit 46	Transmitting a NJE Data Area
Exit 47	Receiving a NJE Data Area
Exit 48	Subsystem Interface (SSI) SYSOUT Data Set Unallocation
Exit 49	Job Queue Work Select

User Defined Exit points 50-255

Job Entry System Three (JES3) Exits

IBM supported Exit points

IATUX01	Reserved Name
IATUX02	Reserved Name
IATUX03	Examine of modify Converter/Interpreter Text created from JCL
IATUX04	Examine the Job Information from the JCL
IATUX05	Examine the Step Information from the JCL
IATUX06	Examine DD Statement Information from the JCL
IATUX07	Examine or Substitute Unit, Type and Volume Serial Information
IATUX08	Examine Setup Information
IATUX09	Examine Final Job Status, JST and JVT
IATUX10	Generate a Message
IATUX11	Inhibit Printing of the LOCATE Request or Response
IATUX14	Job Validation/Restart LOCATE Request or Response
IATUX15	Scan an Initialization Statement
IATUX16	Reserved Name
IATUX17	Define Set of Scheduler Elements
IATUX18	Check Input Authority Level for Consoles
IATUX19	Examine or Modify Data Temporary OSE
IATUX20	Examine or Modify Data Written on Job Header Pages
IATUX21	Create and Write Data Set Headers for Output Data Sets
IATUX22	Examine or Alter the Forms Alignment
IATUX23	Examine or Modify Data Written to Trailer Pages
IATUX24	Examine the Net-id and Devices Requested
IATUX25	Examine or Modify Volume Serial Number
IATUX26	Examine MVS Scheduler Control Blocks
IATUX27	Examine or Alter the JDAB, JCT and JMR
IATUX28	Examine the Accounting Information as Provided by the Job Statement
IATUX29	Examine the Accounting Information as Provided JCT, JDAB and JMR
IATUX30	Examine Authority Level for TSO/E Terminal Commands
IATUX31	Examine or Modify Destination or Message Text
IATUX32	Override the DYNALLDSN Initialization Statement
IATUX33	JES3 Control Statement and the JCL EXEC Statement Installation Exit
IATUX34	JCL DD Statement User Exit and the JCL EXEC Statement Installation Exit
IATUX35	Validity Check Network Commands
IATUX36	Collect Accounting Information
IATUX37	Modify the JES3 Networking Data Set Header

IATUX38	Change the SYSOUT Class for Networking Data Sets
IATUX39	Modify the Data Set Header for a SYSOUT Data Set
IATUX40	Modify Job Header
IATUX41	Determine the Disposition of Job Over JCL Limit
IATUX42	TSO/E Interactive Data Transmission Facility Screening and Notification
IATUX43	Modify Job Header Segments
IATUX44	Examine and Modify the JCL
IATUX45	Examine and Modify the Data Sent to an Output Writer FSS
IATUX46	Select Processors Eligible for Converter/Interpreter Processing
IATUX47	Reserved Name
IATUX48	Override Operator Modification of Output Data Sets
IATUX49	Override Address Selected for Converter/Interpreter Processing
IATUX50	Process User Defined BSIDMOD Codes for Converter/Interpreter
IATUX56	Authorize JES3 Commands Entered Through BDT
IATUX57	Select a Single WTO Routing Code for JES3 MGSROUTE
IATUX58	Modify Security Information Before JES3 Security Processing
IATUX59	Modify Security Information After JES3 Security Processing
IATUX60	Determine Action to take when a TSO/E User is Unable to Receive a Data Set
IATUX61	During MDS Processing, Choose Whether a Job Should be Cancelled or Sent to the Error Queue
IATUX62	Overrides the Decision to Accept a Tape or Disk Mount
IATUX66	Assigns Transmission Priority to a SNA/NJE Data Stream
IATUX67	Determines Action when Remote Data Set is Rejected by RACF
IATUX68	Modify Local NJE Job Trailers
IATUX69	Determine If a Message is to be Sent to the Jes3 Global Address Space
IATUX70	Perform Additional Message Processing
IATUX71	Modify a Tape Request Setup Message
IATUX72	Examine/Modify a Temporary OSE or an OSE Moved to Writer Queue

JES3 Exits IATUX73 - IATUX99

IATUX73 - IATUX99 are provided for future compatibility allowing for the specification of the Linkage Types:

BALR
 ARETURN
 ARETURN with RC=

Resource Access Control Facility (RACF)

ICHCCX00	RACF password
ICHCNX00	RACF password
ICHDEX01	RACF password encryption
ICHPWX01	New Password exit
ICHRCX01	RACROUTE REQUEST=AUTH Preprocessing
ICHRCX02	RACROUTE REQUEST=AUTH Postprocessing
ICHRDX01	RACROUTE REQUEST=DEFINE Preprocessing
ICHRDX02	RACROUTE REQUEST=DEFINE Postprocessing
ICHRFX01	RACROUTE REQUEST=FASTAUTH Preprocessing
ICHRFX02	RACROUTE REQUEST=FASTAUTH Postprocessing
ICHRFX03	RACROUTE REQUEST=FASTAUTH Preprocessing
ICHRFX04	RACROUTE REQUEST=FASTAUTH Postprocessing
ICHRIX01	RACROUTE REQUEST=VERIFY Preprocessing
ICHRIX02	RACROUTE REQUEST=VERIFY Postprocessing
ICHRLX01	RACROUTE REQUEST=LIST Pre/Postprocessing
ICHRLX02	RACROUTE REQUEST=LIST Selection
IRRACX01	ACEE Compression/Decompression Exit
IRRACX02	ACEE Compression/Decompression Exit
IRREVX01	RACF Common Command Exit

System Authorization Facility (SAF) Exits

ICHRTX00	MVS Router
IRRSXT00	SAF Callable Services Router

System Management Facility (SMF) Exits

IEFACTRT	SMF Job/Step Termination Exit
IEFUJI	Job Initiation Exit
IEFUJP	Job Purge Exit
IEFUJV	Job Validation Exit
IEFUSI	Step Initiation Exit
IEFUSO	SYSOUT Limit Exit
IEFUTL	Time Limit Exit
IEFU29	SMF Dump Exit
IEFU83	SMF Record Exit
IEFU84	SMF Record Exit
IEFU85	SMF Record Exit

Time Sharing Option Extended (TSO/E) Exits

ICQAMFX1	Application Manager Function Pre-initialization
ICQAMFX2	Application Manager Function Post-termination
ICQAMPX1	Application Manager Panel Pre-display
ICQAMPX2	Application Manager Panel Post-display
IEEVSNX0	OPER SEND subcommand Initialization
IEEVSNX1	OPER SEND subcommand Pre-display
IEEVSNX2	OPER SEND subcommand Pre-save
IEEVSNX3	OPER SEND subcommand Failure
IEEVSNX4	OPER SEND subcommand Termination
IKJADINI	ALTLIB Initialization
IKJADTER	ALTLIB Termination
IKJCNXAC	CONSOLE Activation
IKJCNXCD	CONPROFS Pre-display
IKJCNXCI	CONSPROF Initialization
IKJCNXCT	CONPROFS Termination
IKJCNXDE	CONSOLE Deactivation
IKJCNXPP	CONSOLE Pre-parse
IKJCNX50	CONSOLE 80% Message Capacity
IKJCNX64	CONSOLE 100% Message Capacity
IKJCT43I	EXEC Initialization
IKJCT43T	EXEC Termination
IKJCT44B	Add Installation-written CLIST Built-in Functions
IKJCT44S	Add Installation-written CLIST Statements
IKJEESXA	LISTBC Failure
IKJEESXB	LISTBC Termination
IKJEESX0	SEND Initialization
IKJEESX1	SEND Pre-display
IKJEESX2	SEND Pre-save
IKJEESX3	SEND Failure
IKJEESX4	SEND Termination
IKJEESX5	LISTBC Initialization
IKJEESX6	LISTBC Pre-display
IKJEESX7	LISTBC Pre-list
IKJEESX8	LISTBC Pre-read
IKJEESX9	LISTBC Pre-allocate
IKJEFD21	FREE Initialization
IKJEFD22	FREE Termination

IKJEFD47	ALLOCATE Command Initialization
IKJEFD49	ALLOCATE Command Termination
IKJEFF10	SUBMIT Command
IKJEFF53	OUTPUT, STATUS and CANCEL Commands
IKJEFLD1	Logon Authorized Pre-prompt
IKJEFLD2	LOGOFF
IKJEFLD3	LOGON post-prompt
IKJEFLN1	Logon Pre-display
IKJEFLN2	Logon Post-display
IKJEXG1	Tailor PUTGET and GETLINE processing
IKJEFY11	OUTDES Initialization
IKJEFY12	OUTDES Termination
IKJEFY60	PRINTDS Initialization
IKJEFY64	PRINTDS Termination
IKJEGASI	TESTAUTH Subcommand Initialization
IKJEGAST	TESTAUTH Subcommand Termination
IKJEGAUI	TESTAUTH Initialization
IKJEGAUT	TESTAUTH Termination
IKJEGCIE	TEST Subcommand Initialization
IKJEGCTE	TEST Subcommand Termination
IKJEGMIE	TEST Initialization
IKJEGMTE	TEST Termination
IKJPRMX1	PARMLIB Initialization
IKJPRMX2	PARMLIB Termination
INMCZ21R	TRANSMIT/RECEIVE NAMES Data Set Pre-allocation
INMRZ01R	RECEIVE Initialization
INMRZ02R	RECEIVE Termination
INMRZ04R	RECEIVE Notification
INMRZ05R	RECEIVE Acknowledgment Notification
INMRZ06R	RECEIVE Pre-acknowledgment Notification
INMRZ11R	RECEIVE Data Set Pre-processing
INMRZ12R	RECEIVE Data Set Post-processing
INMRZ13R	RECEIVE Data Set Encryption
INMRZ15R	RECEIVE Post-prompt
INMRZ21R	RECEIVE Log Data Set Pre-allocation
INMXZ01R	TRANSMIT Startup
INMXZ02R	TRANSMIT Termination
INMXZ03R	TRANSMIT Encryption
INMXZ21R	TRANSMIT Log Data Set Pre-allocation

IRXINTX	REXX Pre-environment Initialization
IRXITMV	REXX Post-environment Initialization
IRXITTS	REXX Post-environment Initialization
IRXTERM	REXX Environment Termination

Appendix B. General Masking

Masks are created by using qualifiers within a volume serial number, Jobname, Program name, TSO User ID, or Terminal ID.

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

Example Volume Serial Number Masks

Example	Explanation
VOL0%%	Matches any serial number that begins with VOL0 and any two numeric characters: VOL010
&% % % % %	Matches any serial number that begins with any alpha character and five numbers.

Example of Jobname Mask

Example	Explanation
SPJTH-	Matches any Jobname that begins with SPJTH
-SP-	Matches any Jobname that contains the characters SP in any position

Example of Terminal Mask

Example	Explanation
TSOGS%%%	Matches any Terminal ID that begins with TSOGS and three numbers

Example of Program Name Mask

Example	Explanation
DFHSIP	Matches the program name DFHSIP (CICS).

Appendix C. Define Dataset Name Groups

Dataset Name Groups are used to establish a list of dataset name masks and/or dataset names. This group name is then used in various OS/EM functions instead of specifying the same dataset names in every function.

Build groups as needed. A dataset name or mask may appear in more than one group since each OS/EM function will use Dataset Name Groups in a different way.

Create, change and delete groups by using this dialog. The panels presented allow maintenance of the list of Dataset Name Groups or masks that constitute a group, and add descriptions to groups for documentation purposes.

Refer to the OS/EM User's Guide for detailed information (see Dataset Name Groups).

Dataset name masks

Dataset name masks are created by using qualifiers within a dataset name. Valid qualifiers are:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The minus sign is used to unconditionally match a single node of the dataset name. Multiples are allowed.
+	The plus sign is used to unconditionally match all characters/nodes of the dataset name beyond where it is entered in the specification. A single plus sign may be specified.

Examples of dataset name masks

Example	Explanation
AA	Specifies single-level dataset AAA
AA?AA	Specifies a single-level dataset name of five characters. The first and last two characters are AA. The third character can be anything: AA5AA,AABAA, etc.
AA+	Specifies any dataset name beginning with the two characters AA: AA55.TEST
AA-	Specifies a single-level dataset name beginning with the characters AA: AA5PROD

- AA.+** Specifies a two or more level dataset name. The first node is AA: AA.PROD.COMP
- AA.-** Specifies a two level dataset name. The first node is AA: AA.CICS
- .AA** Specifies a two level dataset name. The last node is AA: PROD.AA
- SYS1.-.HRP1000** Specifies a three-level dataset name. The first node is SYS1
- Specifies any three-level dataset name. This type of specification will match every three-level dataset name within your installation.
- GSAX.-.PRM** Specifies a three-level dataset name. The first node is GSAX
- SYS?-** Specifies a two-level dataset name. The first node starts with SYS and any other character. The second node can be anything: SYS1.LINKLIB
- SYS&-** Specifies a two-level dataset name. The first node starts with SYS and any other alphabetic character. The second node can be anything: SYSX.LINKLIB
- SYS%-** Specifies a two-level dataset name. The first node starts with SYS and any other numeric character. The second node can be anything: SYS5.LINKLIB
- SYSX.-.EZT???** Specifies a three-level dataset name. The first node is SYSX. The second node can be anything. The third node begins with EZT and any three characters: SYSX.CICS.EZT030
- ??SYSUT?.+** Specifies a two or more level dataset name. The first node begins with any two characters, followed by SYSUT and any other single character.
- AA+.BB** Specifies a three or more level dataset name. The first node is AA and the last node is BB.
- AA+AA** Specifies a single-level dataset name. The first two characters are AA and the last two characters are AA. The up to four middle characters can be anything. There has to be at least one middle character - AAAA will not match.
- SYSX.PROCLIB** A fully qualified dataset name.

Appendix D. Define Volume Groups

Volume name groups are used to establish a list of DASD volumes. This group name is then used in various OS/EM functions instead of specifying the same volume serial numbers in every function.

Build groups as needed. A volume serial number may appear in more than one group since each OS/EM function will use volume serial numbers in a different way.

Create, change and delete groups by using this dialog. The panels presented allow specification of a subset of all groups to operate on, add descriptions to groups for documentation purposes, and maintain the list of volume serial numbers or masks that constitute a group.

Refer to the OS/EM User's Guide for detail information (see Volume Groups).

Volume/Jobname Masks

Volume/Jobname masks are created by using qualifiers within a volume serial number or Jobname. Valid qualifiers are:

Qualifier	Description
?	The question mark is used to unconditionally match any single character (except periods) where the question mark occurs in the specification. Multiples are allowed.
&	The ampersand is used to unconditionally match any single alpha character where the ampersand occurs in the specification. Multiples are allowed.
%	The percent sign is used to unconditionally match any single numeric character where the percent sign occurs in the specification. Multiples are allowed.
-	The dash is used to unconditionally match any preceding or succeeding character(s). Multiples are allowed.

Example Volume Serial Number Masks

Example

Explanation

VOL0%%

Matches any serial number that begins with VOL0 and any two numeric characters: VOL010

&% % % % %

Matches any serial number that begins with any alpha character and five numbers.

Example of Jobname Mask

Example

Explanation

SPJTH-

Matches any Jobname that begins with SPJTH

-SP- Matches any Jobname that contains the characters SP in any position

Appendix E. SMF Record Format

The SMF records written as an audit trail have the following format:

```
SMFRCD255 DSECT ,
SMF255LEN DS    BL2'0'    RECORD LENGTH
SMF255SEG DS    BL2'0'    SEGMENT DESCRIPTOR
SMF255FLG DC    BL1'0'    HEADER FLAG BYTE
SMF255RTY DC    BL1'0'    RECORD TYPE 0
SMF255TME DC    BL4'0'    TOD, USING FORMAT FROM TIME MACRO W/BIN. INTVL
SMF255DTE DC    PL4'0000'    DATE IN PACKED DECIMAL FORM: CCYYDDDF
SMF255SID DC    CL4' '    SYSTEM IDENTIFICATION
SMF255JOB DC    CL8' '    JOB NAME
SMF255SUB DC    X'0'    SUBTYPE
SMF255#SP DC    FL1'0'    LEADING SPACES
SMF255CMD DC    CL256' '    COMMAND TEXT
                ORG SMF255CMD
SMF255WTO DC    CL256' '    WTO TEXT
                ORG SMF255CMD
SMF255SSN DC    CL4' '    SUBSYSTEM NAME
SMF255ST3 DS    0CL45    RESOURCE ENTRIES - 1 TO MAX OF 127
SMF255RLN DC    X'0'    RESOURCE LEN - 0 INDICATES END
SMF255RES DC    CL44' '    RESOURCE NAME - VARIABLE LEN
*
```

Refer to “SMF Recording” on page 3-6 for instructions on activating this option.

See member SMFPRINT in the OS/EM SAMPLIB for a job to print these SMF records.

Appendix F. JES2 Commands for Job Routing

The following are JES2 commands which control the Job Routing function. Each command is protected by RACF and the resource and command authority needed is listed at the end of the appendix.

\$DB Display Backlog

This command displays information about jobs in the different JES queues.

\$DC Display Conflicts

This command displays jobs that are currently unable to run on any system in the MAS complex because they have a routing to a resource that is not defined on any member of the MAS. Note that the criterion here is whether the resource is defined to a member of the MAS, not whether that member is currently active.

Command Syntax:

```
$DC{ , LIST | , ALL }
```

With no operands, the response is a single line giving the number of jobs unable to run and the number of resources that those jobs require.

With the "LIST" parameter, the response is multiple lines giving the number of jobs that need each undefined resource, and the name of those resources.

With the "ALL" operand, the response lists each job that is unable to run as well as listing each resource that that job requires.

\$DP Display Printers/Punches

The \$DP command gives a simple one-line display for each printer or punch defined to JES, showing its status.

Command Syntax:

```
$DP{ , PUN }
```

Without the "PUN" operand, each printer is listed. With the "PUN" operand, each punch is listed.

\$DRESOURCE

Display Resources

The \$DRESOURCE command lists resources defined to the members of the MAS. These are the resources that are referenced by the /*ROUTE JECL statements and by the JOBNAME and PROGRAMNAME routing functions.

Command Syntax:

```
$DRESOURCE{ , ALL | , SID }
```

Note: The command may be abbreviated to \$DRE, but no shorter as it would then be interpreted as the standard JES2 \$DR command.

With no operands, the command produces a list of those resources attached to the MAS member where it was issued. With the "ALL" operand, it lists resources for all the members of the MAS. With the "SID" operand (the system ID of a specific MAS member), it lists the resources attached to that specific member.

\$LF List Forms

The \$LF command lists the work that exists in the hardcopy queue, grouped by form, prmode, dest, writer, burst and select. For each unique combination of the above, the number of sysout datasets in each class is listed.

The scope of the command may be changed by entering additional selection criteria on the command.

Command Syntax:

\$LF{ , F=xxxxxxxxx }	Select by FORM
{ , W=xxxxxxxxx }	Select by WRITER
{ , PRMODE=xxxxxxxxx }	Select by PRMODE
{ , C=xxxxx }	Select by FCB
{ , T=xxxxx }	Select by UCS
{ , J=Jnnnnn{ -nnnnn }	
, J=Snnnnn{ -nnnnn }	
, J=Tnnnnn{ -nnnnn } }	Select by JOB/STC/TSU numbers
{ , R=xxxxxxxxx{ -xxxxxxxxx } }	Select by Destination. Operand is NODE or NODE1-NODE2, RMT or RMT1-RMT2, NODE.RMT or NODE1.RMT1-NODE2.RMT2, NODE.USERID or USERID
{ , Q=x... }	Select by SYSOUT classes
{ , LIM=nnn{ -nnn } }	Select by LINE number range
{ , PLIM=nnn{ -nnn } }	Select by PAGE number range
{ , D=A , D=H }	Select ALL or HELD
{ , B=Y , B=N }	Select by BURST=YES or BURST=NO
{ , S=Y , S=N }	Select by SELECTABLE or NOT SELECTABLE
{ , JOBS }	Request that DISPLAY be broken down by individual JOBS

\$LN List JOBQUEUE by NAME

This command produces a detailed list of jobs awaiting execution by jobname, showing resources, DJC holds and such.

Command Syntax:

\$LN{ , ALL{ , IND}	Select by SYSAFF ALL
, ANY	Select by SYSAFF ANY
, SID	Select by SYSAFF to a SID
, IND}	Select by independent mode
{ , V=xxxxxxx}	Select by SPOOL VOLSER
{ , AFTER=xxxxxxxx{ (nnnnn) }	Select by AFTER specification JOBNAME and optional JOB NUMBER
{ , BEFORE=xxxxxxxx{ (nnnnn) }	Select by BEFORE specification JOBNAME and optional JOB NUMBER
{ , WITH=xxxxxxxx{ (nnnnn) }	Select by WITH specification JOBNAME and optional JOB NUMBER
{ , PRED=xxxxxxxx{ (nnnnn) }	Select by PRED specification JOBNAME and optional JOB NUMBER
{ , EXCLUDE=xxxxxxxx{ (nnnnn) }	Select by EXCLUDE specification JOBNAME and optional JOB NUMBER
{ , CNTL=xxxxxxx}	Select by CNTL resource, resource is 1-44 characters, alpha, numeric, national, underscore and period. Period cannot be first or last character
{ , RES=xxxxxxx}	Select by ROUTING resource Resource is 1-44 characters, alpha, numeric, national, underscore and period. Period cannot be first or last character
{ , ROUTE=nnn{-nnn} }	Select by execution routing NODE or NODE.RMT. No USERIDS.
{ , Q=XEQ	Select XEQ queue
, Q=CNV	Select CONVERT queue
, Q=STC	Select STCS
, Q=TSU	Select TSUS
, Q=HOLD	Select HELD jobs
, Q=READY	Select READY jobs
, Q=ACTIVE	Select ACTIVE JOBS/STCS/TSUS
, Q=DJCOWN	Select owners of DJC resources
, Q=DJCHOLD}	Select JOBS held for DJC
{ , C=x{-x} }	Select by JOBCLASS range; classes may be A-Z, 0-9, * (CNV), \$ (STC), or @ (TSU).

\$LQ List JOBQUEUE

This command produces a summary list of jobs awaiting execution.

The Command Syntax is the same as the \$LN command.

\$QA Resource ADD command.

\$QD Resource DELETE command.

These two commands allow you to ADD and DELETE resources from a MAS member.

Command Syntax:

\$QA \$QD	\$QA = ADD, \$QD = DELETE
,xxxx	Resource name (1-44 bytes)
{,SID}	SID where add/delete is to take place.
	The default is the system where the command is entered.
{,FORCE} (DELETE only)	Delete the resource even if the resource is currently in use by an active job on the targeted system.

\$Q'xxx', \$QJ

These commands add and delete **DEPENDENT JOB CONTROL (DJC)** conditions, routing resources and CNTL specifications for jobs already in the job queue.

Command Syntax:

\$Q'xxxxxxxx'	Specify JOBNAME
\$QJnnnnn{-nnnn}	Specify JOB number(s)
{,HSMRETRY}	Retry failed HRECALLs
{,RELEASE(HSM)}	Do not hold job for HRECALLs
{,HOLD(HSM)}	Hold job for HRECALLs
{,RELEASE(USERLIMIT)}	Do not hold job for user limits
{,HOLD(USERLIMIT)}	Hold job for user limits
{,RELEASE(PGMLIMIT)}	Do not hold job for program limits
{,HOLD(PGMLIMIT)}	Hold job for program limits
{,JOBROUTE=xxxxxx,NODE=nnnn}	Route specified job(s) to node if JOBROUTE resource is assigned to the job
{,RELEASE(DJC)}	Do not hold job for dependent job controls
{,NOAFTER}	Remove AFTER conditions
{,NOPRED}	Remove PRED conditions
{,NOBEFORE}	Remove BEFORE conditions
{,NOWITH}	Remove WITH conditions
{,NOEXCLUDE}	Remove EXCLUDE conditions
{,NOCNTL}	Remove all CNTL resources
{,NOROUTE}	Remove all ROUTING resources
{,ADDRES=xxxx}	Add ROUTING resource. OBSOLETE. Use ROUTE instead.
{,DELRES=xxxx}	Remove ROUTING resource. OBSOLETE. Use ROUTE instead.
{,ROUTE=({+ -}xxxx,....)}	Add or remove ROUTING resource. + (ADD) and - (DEL) are optional and default to add. 1 to 8 resources may be specified. Enclosing parens are optional if only 1 resource is specified. NOTE: A job can never have more than 8 ROUTING resources.
{,CNTL=({+ -}xxxx{-SHR -EXC},...)	Add or remove CNTL resource. + (ADD) and - (DEL) are optional and defaults to ADD. -SHR and -EXC are optional and default to -SHR. Not meaningful for delete. 1 to 8 CNTLs may be specified. Enclosing parens are optional if only 1 resource is specified. NOTE: A job can never have more than 8 CNTL resources.
{,AFTER=({+ -}xxxxx{(nnnn wait mult)},...)	Add or Remove AFTER resource.

+ (ADD) & - (DEL) are optional and default to ADD. JOBNUM, WAIT and MULT are optional. WAIT and MULT are not valid for DELETE. Up to 10 AFTER statements may be specified with the constraint that a job may never have more than 10 DJC entries of all types combined. The enclosing parentheses are optional if only one job is specified.

{, BEFORE= ({+|-}xxxx{ (nnnn|OK|MULT)}), ...)

Add or remove BEFORE resource.
+ (ADD) & - (DEL) are optional and default to ADD. JOBNUM, and MULT are optional. MULT and OK are not valid for DELETE. Up to 10 BEFORE statements may be specified with the constraint that a job may never have more than 10 DJC entries of all types combined. The enclosing parentheses are optional if only one job is specified.

{, EXCLUDE= ({+|-}xxxx{ (nnnn|OK|MULT)}), ...)

Add or remove EXCLUDE resource.
+ (ADD) & - (DEL) are optional and default to ADD. JOBNUM and MULT are optional. MULT and OK are not valid for DELETE. Up to 10 exclude statements may be specified with the constraint that a job may never have more than 10 DJC entries of all types combined. The enclosing parentheses are optional if only one job is specified.

{, PRED= ({+|-}xxxx{ (nnnn|WAIT|MULT)}), ...)

Add or remove PRED resource.
+ (ADD) & - (DEL) are optional and default to add. JOBNUM, WAIT and MULT are optional. WAIT and MULT are not valid for DELETE. Up to 10 PRED statements may be specified with the constraint that a job may never have more than 10 DJC entries of all types combined. The enclosing parentheses are optional if only one job is specified.

{, WITH= ({+|-}xxxx{ (nnnn|WAIT|mult)}), ...)

Add or remove WITH resource.
+ (ADD) & - (DEL) are optional and defaults to ADD. JOBNUM, WAIT and MULT are optional. WAIT and MULT are not valid for DELETE. Up to 10 WITH statements may be specified with the constraint that a job may never have more than 10 DJC entries of all types combined. The enclosing parentheses are optional if only one job is specified.

RACF Resources and Authority Table

Command	Resource Name	Authority
\$DB	jesx.DISPLAY.OSEM	READ
\$DC	jesx.DISPLAY.OSEM	READ
\$DP	jesx.DISPLAY.OSEM	READ
\$DRESOURCE	jesx.DISPLAY.OSEM	READ
\$LF	jesx.DISPLAY.OSEM	READ
\$LN	jesx.DISPLAY.OSEM	READ
\$LQ	jesx.DISPLAY.OSEM	READ
\$QA	jesx.ADD.OSEM	CONTROL
\$QD	jesx.DELETE.OSEM	CONTROL
\$Q'	jesx.MODIFY.OSEM	UPDATE
\$QJ	jesx.MODIFY.OSEM	UPDATE

Replace **jesx** with the name of your JES2 subsystem.

Note: All listed resources are defined to the **OPERCMDS** class.

Appendix G. JCL Statements for Job Routing

Resource Routing Control Cards

These cards provide a facility by which jobs can be routed to specific CPUs depending on the availability of a particular resource name assigned to a CPU. Resource names are user defined and specified with the \$QA command. Once defined, these resource names attached to a CPU remain in effect until they are detached via the \$QD command.

Resources specified can define physical I/O units which may be attached to only one CPU at a time, or possibly a software name which may only pertain to one particular CPU.

The format of the resource routing JCL statement is:

```
/*ROUTE XEQ resourcename
```

The card must follow the JOB statement.

Note: This card is not required if the optional routing rules defined with OS/EM in JES2 EXIT5 are used.

Following are some examples of using the ROUTE XEQ control card:

```
System #      Resources Attached
  1           DUALD, IMS
  2           3525
  3           IMS, TSO, NOINQ
//BSPROUT JOB ( , , 7552, 429), 'TEST RESOURCE', CLASS=A
/*ROUTE XEQ IMS
//S1 EXEC PGM=IEFBR14
```

This job will be scheduled to either system #1 or system #3 because of the IMS resource requested.

The \$DC command is used to display those jobs which have used the /*ROUTE XEQ resource control card and no CPUs have that resource name attached. For example, using the above list, if a job were submitted with a /*ROUTE XEQ SCANNER' control card, the job would never execute no matter how many initiators were available until a \$QA,SCANNER command was issued on a system in the complex. This would be detectable by issuing a \$DC command which would display those jobs waiting for resource names.

Other /*ROUTE control cards formats are:

```
/*ROUTE XEQ HERE
```

The resource name 'HERE' causes the job to be scheduled for execution on the CPU which read the JCL (controlling the card reader.)

Note: Do not have an initiator add the SYSAFF=* parameter to a job as this overrides OS/EM Job Routing.

*/*CNTL and /*THREAD Cards*

The **CNTL** and **THREAD** cards are processed identically.

This feature provides the ability to single-thread jobs through execution which need a device of which there is only one and must be used serially. Some examples would be the 3525, DUAL density drive and the OCR scanner.

By using the */*CNTL* card, you can define a resource name that you need exclusive control of. If any other jobs come into the system with the same control name, they will not execute simultaneously on the same or other CPUs in the complex. This provides better control over the resources that must be used serially. This does not affect jobs running without the */*CNTL* card or running in a system without shared spool.

The format for resource control is:

```
/*CNTL resourcename,EXC    or
/*CNTL resourcename,SHR    (the default is SHR)
```

Users may also protect datasets from being updated by different jobs on the same or different CPUs by using the */*CNTL* card. Each */*CNTL* card may have a 1 to 44 character control name and an EXC or SHR specification.

Jobs with the same control name will not execute simultaneously if one of the jobs has an EXC control specification. Jobs with SHR may execute simultaneously on any CPU.

Following are */*CNTL* and */*THREAD* usage examples:

```
//JOB1 JOB
/*CNTL MASTER,EXC
//JOB2 JOB
/*THREAD MASTER,SHR
```

In the above example, whichever job began execution first, would lockout the other job from beginning until it has completed.

```
//JOB1 JOB
/*CNTL MASTER,SHR
/*CNTL PINOT_NOIR,SHR
/*THREAD SYS1.LINKLIB,SHR
/*CNTL DUALDENS,SHR
/*CNTL CABERNET,SHR
//JOB2 JOB
/*CNTL MASTER
/*CNTL DUALDENS
//JOB3 JOB
/*THREAD MASTER,SHR
/*THREAD PINOT_NOIR
```

In the above example, all 3 jobs could run simultaneously as they all specify the SHR option. Up to 8 CNTL cards may be specified at one time.

After, Before, Exclude, PRED and With Control Cards

In the following syntax diagrams, the first optional parameter indicates the action to be taken if the referenced job is not in the **execute queue**, (for the */*BEFORE* card, the job must also not yet be executing). If a specific job is referenced, i.e. the job number is supplied, only the **IGNORE** and **FAIL** options are

acceptable. The **IGNORE** option indicates that the card is to be treated as a comment. The **FAIL** option indicates that the job is to be failed by passing a return code of 12 back to JES2. The **OK** option indicates that the statement will apply to all jobs with the specified jobname. The **WAIT** option indicates that the job is to wait until a job with the specified jobname is read into the system.

The second optional parameter indicates what action to take if there are multiple jobs in the system with the specified jobname. This situation can never arise if a job number is specified as there can only be one job with a given job number. The options are processed the same as the first option.

Note: There may be 10 Dependent Job Control statements per job.

The purpose of these options is to override, for an individual statement, the default options set by the OS\$CNTL command.

```

/*AFTER   XXXXXXXX{ (NNNNN) } { , IGNORE } { , IGNORE }
                                                { , FAIL  } { , FAIL  }
                                                { , WAIT  } { , OK   }
                                                { ,      }
/*BEFORE  XXXXXXXX{ (NNNNN) } { , IGNORE } { , IGNORE }
                                                { , FAIL  } { , FAIL  }
                                                { , OK   } { , OK   }
                                                { ,      }
/*EXCLUDE XXXXXXXX{ (NNNNN) } { , IGNORE } { , IGNORE }
                                                { , FAIL  } { , FAIL  }
                                                { , OK   } { , OK   }
                                                { ,      }
/*PRED    XXXXXXXX{ (NNNNN) } { , IGNORE } { , IGNORE }
                                                { , FAIL  } { , FAIL  }
                                                { , WAIT  } { , OK   }
                                                { ,      }
/*WITH    XXXXXXXX{ (NNNNN) } { , IGNORE } { , IGNORE }
                                                { , FAIL  } { , FAIL  }
                                                { , WAIT  } { , OK   }
                                                { ,      }

```

These cards provide a means to schedule jobs before, after or with another. The control card follows the jobcard or any other JES2 control cards (ROUTE - CNTL).

Following is an example of the use of these control cards:

```

/*PRIORITY      13
//BSPTEST JOB ( , 7552 , 429 ) , RUSBASAN , MSGLEVEL=( 1 , 1 ) , CLASS=A
/*ROUTE XEQ MSS
/*AFTER BSPFIRST , WAIT
//S1 EXEC PGM=IEFBR14
/*
/*PRIORITY      2
//BSPFIRST JOB ( , 7552 , 429 ) , RUSBASAN , MSGLEVEL=( 1 , 1 ) , CLASS=A
/*ROUTE XEQ CPU2
/*CNTL DUAL , EXC
//SA EXEC PGM=IEFBR14
/*

```

In the above example, job BSPTEST would not execute until job BSPFIRST has finished execution, even though BSPTEST has a higher priority.

Appendix H. \$HASP Messages for Job Routing

The following messages may be issued by the OS/EM Job Routing option:

\$HASP606 INSUFFICIENT OPERANDS

Produced by the \$LN command.

\$HASP608 OS/EM STATUS UNKNOWN

\$HASP610 JOB(S) NOT FOUND

\$HASP619 NO OUTPUT QUEUED

Produced by the \$LF command.

\$HASP624 'CMD' 'JOBNAME' MULTIPLE JOBS FOUND

Produced by a \$Qx command.

\$HASP646 nn PERCENT SPOOL UTILIZATION

Produced by the \$LN command.

\$HASP668 NO DEVICE(S) FOUND

Produced by the \$DP command.

\$HASP687 UNABLE TO OBTAIN SECURITY PRODUCT MESSAGES

\$HASP690 COMMAND REJECTED - AUTHORIZATION FAILURE

\$HASP900 TOO MANY|FEW OPERANDS

\$HASP901 INVALID OPERAND xxxxx

\$HASP905 RESOURCE IN USE. YOU MUST USE 'FORCE' TO DELETE

Produced by the \$QD command.

\$HASP907 JOBNAME xxxx IS NOT SUITABLE FOR DJC

Produced by a \$Qx command.

\$HASP908 NO MATCH FOUND FOR SPECIFIED RESOURCE

Produced by the \$QJ command.

\$HASP921 LIST FORMS (multiple texts)

Produced by the \$LF command.

\$HASP928 DEVICE UNIT STATUS F=FORM Q=X

Produced by the \$DP command.

\$HASP931 * -- JOBROUTE FAILED - ALREADY 8 ROUTES IN USE

Produced by Exit 44, Maximum of 8 routes per job.

\$HASP935 jjjj(nnn) JOBNAME SPECIFIED ON /*BEFORE STATEMENT IS INVALID. CORRECT - RESUBMIT.

\$HASP936 jjjj(nnn) JOBNAME SPECIFIED ON /*AFTER STATEMENT IS INVALID. CORRECT - RESUBMIT.

\$HASP937 jjjj(nnn) PARM SPECIFIED ON /*CNTL STATEMENT IS INVALID. CORRECT - RESUBMIT.

\$HASP938 jjjj(nnn) ONLY n xxxxx STATEMENTS ALLOWED. CORRECT - RESUBMIT.

\$HASP939 jjjj(nnn) JOBNAME SPECIFIED ON /*WITH STATEMENT IS INVALID. CORRECT - RESUBMIT.

\$HASP940 jjjj(nnn) * -- AFTER JOBNAME = xxxx --

\$HASP941 jjjj(nnn) * -- WITH JOBNAME = xxxx --

\$HASP942 jjjj(nnn) * -- RESOURCE ROUTING = xxxxx --

\$HASP943 jjjj(nnn) * -- CONTROL INFO = xxxxx --

\$HASP944 jjjj(nnn) * -- BEFORE JOBNAME = xxxx --

\$HASP945 LIST JOBQUEUE (multiple texts)

Produced by the \$LQ/\$LN commands.

\$HASP946 SID - NO RESOURCES ATTACHED

Produced by the \$DRESOURCE command.

\$HASP947 DISPLAY RESOURCE (multiple texts)

Produced by the \$DRESOURCE command.

\$HASP948 DISPLAY CONFLICT (multiple texts)

Produced by the \$DC command.

\$HASP949 DISPLAY BACKLOG (multiple texts)

Produced by the \$DB command.

\$HASP950 jobname(JOBnnnn) * -- JOBROUTE 999 xxxxxx = y --

Produced when OS/EM generates an automatic route or a change to jobclass/priority, scheduling environment, service class or xeq node. Where 999 corresponds to the routing rule used to assign route xxxxx.

\$HASP951 OS/EM VER n.n - JOBRouting ACTIVE

Shows the version of OS/EM that is active, and informs the user that the JOBRouting function is active.

Appendix I. MVS Commands for Tape Share

The following operator commands are available to control TAPESHR functions.

In the following command formats, **dev_spec** refers to the syntax allowed for ordinary MVS vary commands, e.g. 580 or 580-581 or (580,582-588), etc.

- V dev_spec,ONTPSHR
To vary a device onto TAPESHR control, that is to have TAPESHR assume control of varying the device online and offline as needed to fulfill the needs of the various systems.
- V dev_spec,OFFTPSHR
To cause TAPESHR to relinquish control of a device.
- V dev_spec,OFFLINE,LOCAL
To indicate to TAPESHR that a device is not to be used, that is brought online, on this system only. The device is still eligible for use on other systems.
- V dev_spec,ONLINE,LOCAL
To indicate to TAPESHR that a device which was previously varied offline locally may once again be used on this system. This command must be issued on the same system as the VARY OFFLINE,LOCAL command.
- V dev_spec,OFFLINE,GLOBAL
To indicate to TAPESHR that a device is not to be used by any system in the complex. This command may be issued on any system.
- V dev_spec,ONLINE,GLOBAL
To indicate to TAPESHR that a device that was previously varied offline globally may now be used again. This command may be issued on any system.
- D TAPESHR
Displays all devices defined to tapeshr and their current status (see Display Units command below for a list of status codes).

A **modify** command is available to shut down **OS\$TPSHR**.

```
F OS$TPSHR,STOP {option}
```

Where {option} is:

- WAIT
This causes TAPESHR to wait until all owned tape devices have gone offline and so may safely be used by other systems where TAPESHR is still active.
- REMOVE

The devices which do not go offline within 15 seconds will be removed from TAPESHR control and it will become the operator's responsibility to coordinate the use of those devices on the various systems. Note that if any uncontrolled device is eligible for use when a job goes into allocation recovery, TAPESHR will not participate in device selection other than to remove all TAPESHR devices from the candidate list, thus forcing the job to use an uncontrolled device.

- GLOBALOFFLINE (Default)

The devices which do not go offline within 15 seconds will be marked as globally offline to protect them from being allocated by another TAPESHR system. After the devices go offline on the system where TAPESHR is being terminated, the operator may issue a command to vary them back online globally to make them available to the other systems where TAPESHR is still active.

You may optionally use the **STOP** command (**P**).

```
P OS$TPSHR
```

The STOP command uses the GLOBALOFFLINE option.

The Display Units command has been enhanced to show the TAPESHR status of those devices controlled by TAPESHR. The additional data includes the system currently owning the device (or the word 'NONE'). There may also be additional characters appended to show additional information. These include:

- -A
Indicates the device is allocated.
- -LO
Indicates local offline.
The -LO status can be removed by issuing a vary online,local command.
- -LO(P)
Indicates the device is pending local offline.
- -GO
Indicates global offline.
The -GO status can be removed by issuing a vary online,global command.
- -GO(P)
Indicates pending global offline.
- -EO
Indicates error offline. Error offline indicates that an attempt was made to vary the device online and the system was unable to bring the device online for some (usually hardware) reason. This status can be cleared by re-issuing the vary online command once the problem has been resolved.
- -RST
Indicates restricted device.
- -PND
Indicates pending status.
- -D
Indicates device being deleted.

Index

A

- Abend Messages
- Account Numbers
 - Activating, 5-112
 - Defining, 5-112
 - Field Support, 5-112
 - List Validation, 5-113, 5-114
 - Security Checking, 5-113
- ACF2 Non-cancel Override Control, 5-189
- Add Notify Statement, 5-141
- ADDRSPC JCL Parameter
 - Controlling, 5-122
- ADDVOL Parameter in DFHSM
 - Setting for HSM Optimizer, 5-19
- Allocation Exits
 - Query Status, 6-1
- ALLOW, 5-207
 - Global ALLOW, 5-207
 - search order, 5-209
- Authorization Code
 - CODEINIT Member, 2-3
- Autoinstall Feature 4-2

B

- Backup Control, 5-21
- Basic Exit Functions
 - ABENDNOTIFY, 4-5, 4-12, 4-19
 - Activate JES2 user exit, 4-5
 - Activate JES3 user exit, 4-12
 - Activate MVS user exit, 4-19
 - Activate user exit, 4-5, 4-12, 4-19
 - Autoinstall Feature, 4-2
 - Basic Entry Panel, 4-3
 - Basic Exits Menu, 4-3
 - JES2 Exits, 4-4
 - JES3 Exits, 4-11
 - MVS Exits, 4-18
 - Default Return Code, 4-6, 4-13, 4-19
 - Define JES2 user exit module, 4-9
 - Define JES3 user exit module, 4-16
 - Define MVS user exit module, 4-23
 - Define user exit module, 4-9, 4-16, 4-23

- Definition and Use, 4-1
- Exits Supported, 4-2
 - JES2 user exit module selection list, 4-7
 - JES3 user exit module selection list, 4-14
 - Job Name Masks Definition, 4-10, 4-17, 4-24
 - MVS user exit module selection list, 4-21
 - Options JES2, 4-5
 - Options JES3, 4-12
 - Options MVS, 4-19
 - Options Specifications, 4-5, 4-12, 4-19
 - OS/EM Exit Functions, 4-1
 - Use With OS/EM Extended Functions, 4-3
 - User exit module selection list, 4-7, 4-14, 4-21
- Build Initialization Member, 10-1
- BURST JCL Parameter
 - Controlling, 5-131

C

- CA-ACF2
 - ADDRSPC, 5-122
 - BURST, 5-131
 - CHARS, 5-131
 - COPIES, 5-131
 - DATA CLASS, 5-122
 - DDNAME, 5-122
 - DEST, 5-131
 - DPRTY, 5-122
 - EXPDT, 5-123
 - FCB, 5-131
 - FLASH, 5-132
 - FORM, 5-132
 - FORMDEF, 5-132
 - JES2 Command Checking, 5-142
 - JES2 Command Resource Name, 5-142
 - Job Accounting, 5-112
 - Job Class Checking, 5-118
 - MANAGEMENT CLASS, 5-123
 - Message CLASS, 5-132
 - MODIFY, 5-132
 - MVS Command Checking, 5-143
 - MVS Command Resource Name, 5-143
 - OUTPRTY, 5-132
 - PAGEDEF, 5-132

- PERFORM, 5-123
- PRMODE, 5-132
- PROTECT, 5-123
- PRTY, 5-123
- Resource for Job Class Checking, 5-118
- RETPD, 5-123
- STORAGE CLASS, 5-123
- SUBSYS, 5-123
- SYSOUT Class, 5-132
- TIME, 5-123
- UCS, 5-133
- UNIT, 5-124
- USERLIB, 5-124
- WRITER, 5-133
- CA-TOPSECRET
 - ADDRSPC, 5-122
 - BURST, 5-131
 - CHARS, 5-131
 - COPIES, 5-131
 - DATA CLASS, 5-122
 - DDNAME, 5-122
 - DEST, 5-131
 - DPRTY, 5-122
 - EXPDT, 5-123
 - FCB, 5-131
 - FLASH, 5-132
 - FORM, 5-132
 - FORMDEF, 5-132
 - JES2 Command Checking, 5-142
 - JES2 Command Resource Name, 5-142
 - Job Accounting, 5-112
 - Job Class Checking, 5-118
 - MANAGEMENT CLASS, 5-123
 - Message CLASS, 5-132
 - MODIFY, 5-132
 - MVS Command Checking, 5-143
 - MVS Command Resource Name, 5-143
 - OUTPRTY, 5-132
 - PAGEDEF, 5-132
 - PERFORM, 5-123
 - PRMODE, 5-132
 - PROTECT, 5-123
 - PRTY, 5-123
 - Resource for Job Class Checking, 5-118
 - RETPD, 5-123
 - STORAGE CLASS, 5-123
 - SUBSYS, 5-123
 - SYSOUT Class, 5-132
 - TIME, 5-123
 - UCS, 5-133
 - UNIT, 5-124
 - USERLIB, 5-124
 - WRITER, 5-133
- Catalog Account Control, 5-190
- CHARS JCL Parameter
 - Controlling, 5-131
- Control JES2 Commands, 5-142
- Control Operating System Commands, 5-143
- COPIES JCL Parameter

- Controlling, 5-131

D

- DASD Allocation, 5-203
- DATACLASS JCL Parameter
 - Controlling, 5-122
- Dataset Name Conflict Resolution, 5-144
- Dataset Name Group
 - Change Group, 5-6
 - Creating Group Names, 5-3
 - Delete Group, 5-7
 - Disable, 5-4
 - Enable, 5-4
 - Temporarily Disable Group, 5-9
 - Use in Delete-By-Age (DBA), 5-29
 - Use in Delete-If-Backed-Up (DBU), 5-32
 - Use in Direct-To-Level-2, 5-35
 - Use in Exclude from Backup, 5-21
 - Use in ML0 to ML1 Control, 5-40
 - Use in ML1 to ML2 Control, 5-45
 - Use in Reblock Control, 5-57
 - Used For, 5-3
- Dataset Name Groups, C-1
- Dataset Name Masks
 - DSN masks Example, C-1
 - Examples, 5-10
 - Masking Characters, 5-10
 - Name Mask Table, 5-10
- Dataspace Controls
 - Masking, 5-138
- Day Controls
 - Definition and Use in DBA, 5-28
 - Use in DBU, 5-31
 - Use in Delete-By-Age, 5-28
- DDNAME JCL Parameter
 - Controlling, 5-122
- Define/Allocate HSM Files, 5-106
- Defragmentation
 - Activating, 5-23
 - Add Volume Groups, 5-26, 5-27
 - Automatic Defragmentation, 5-19
 - Deactivate, 5-23
 - Definition and Use, 5-23
 - DEFRAG Level, 5-26
 - Delete Volume Groups, 5-26, 5-27
 - ENABLE/DISABLE, 5-23
 - Index Level Example, 5-26
 - Procedure, 5-23
 - Specifying Multiple Defrag Groups, 5-26
 - Specifying Multiple Defrag Pools, 5-26
- Delete-By-Age Control
 - Activating, 5-28
 - Add DSN Groups, 5-30
 - Add/Delete DSN Groups, 5-29
 - Deactivate Day Hold, 5-28
 - Definition and Use, 5-28

- Delete DSN Groups, 5-30
- Maxsize And/Or Include, 5-28
- Maxsize, 5-29
- Options Panel, 5-28
- Specifying Day Hold, 5-28
- Specifying DSN Groups, 5-28
- Use of And/Or, 5-29
- Delete-If-Backed-Up Control
 - Activating, 5-31
 - Add DSN Group, 5-32
 - Add/Delete DSN Group, 5-32
 - And/Or Connective, 5-32
 - Day Controls, 5-31
 - Definition and Use, 5-31
 - Delete DSN Group, 5-32
 - Maxsize And/Or Include, 5-31
 - Maxsize Definition, 5-31
 - Maxsize, 5-31
 - Options Panel, 5-31
 - Specifying DSN Group, 5-32
- DEST JCL Parameter
 - Controlling, 5-131
- DFHSM SETSYS Parameters
 - ADDVOL for HSM Optimizer ADDVOL in the System, 5-19
 - DFHSM Record Type for HSM Optimizer Reports, 5-107
 - NOMIG in ARCCMDxx, 5-42
 - SETSYS for QuickPool Recall, 5-58
 - SETSYS REBLOCK Control for HSM Optimizer, 5-55
 - SETSYS RECALL Parameter for QuickPool, 5-19, 5-58
- DFP Exits
 - Query Status, 6-1
- Direct-to-Level-2
 - Add Exclude DSN Group, 5-35
 - Add Include DSN Group, 5-35
 - Definition and Use, 5-34
 - Delete Exclude DSN Group, 5-35
 - Delete Include DSN Group, 5-35
 - Exclude DSN Group, 5-35
 - Include DSN Group, 5-35
 - Minimum And/Or Exclude, 5-35
 - Minimum And/Or Include, 5-35
 - Specify Minimum Dataset Size, 5-34
- Disabling Return Code
 - JES2 Usage, 4-6
 - JES3 Usage, 4-13
 - MVS Usage, 4-19, 4-20
 - Valid Return Code, 4-6, 4-13, 4-20
- DISALLOW, 5-207
 - Global DISALLOW, 5-207
 - search order, 5-209
- DPRTY JCL Parameter
 - Controlling, 5-122

E

- Estimated Costs Controls, 5-193
- Execute Pending Changes, 9-1
 - Execute Pending Changes, 9-1
- Expiration Date JCL Parameter
 - Controlling, 5-123
- Extended OS/EM Functions, 5-1
- External Tape Control, 5-211
- EZ-Proclib(R) Control, 5-115

F

- FCB JCL Parameter
 - Controlling, 5-131
- FLASH JCL Parameter
 - Controlling, 5-132
- FORM JCL Parameter
 - Controlling, 5-132
- FORMDEF JCL Parameter
 - Controlling, 5-132

G

- Good Return Code
 - Disabling Return Code, 4-6, 4-13, 4-20
 - JES2 Usage, 4-6
 - JES3 Usage, 4-13
 - MVS Usage, 4-20

H

- Hiperspace Controls
 - Masking, 5-138
- HSM Exits
 - Query Status, 6-1
- HSM Optimizer
 - Backup Control, 5-21
 - Defragmentation, 5-23
 - Delete-By-Age, 5-28
 - Delete-If-Backed-Up, 5-31
 - Description, 5-18
 - Direct-to-Level-2, 5-34
 - Early Batch Recall, 5-36
 - Force DSORG to PS, 5-38
 - HSM Optimizer Menu, 5-19
 - Migration Control (ML0-ML1), 5-39
 - Migration Level-2 Control (ML1-ML2), 5-42
 - Prioritize Recall/Recover, 5-46
 - Quick Delete Control, 5-54
 - Reblock Control, 5-55
 - Recall/Recover, 5-58

- Summary of Features, 5-18
- HSM Optimizer Report System, 5-59
- HSM Optimizer Reports
 - ACS Parameters, 5-100
 - Activity Summary, 5-84
 - Allocate Reports Files, 5-100
 - Backed Up Dataset Detail (BCDS Date Sort No XREF), 5-99
 - Backed Up Dataset Detail (BCDS Date Sort w/XREF), 5-96
 - Backed Up Dataset Detail (BCDS DSN Sort No XREF), 5-98
 - Backed Up Dataset Detail (BCDS DSN Sort w/XREF), 5-93
 - Batch Job, 5-100
 - Build Job Card, 5-101
 - Collect SMF Data, 5-100
 - Dataset Backup Summary, 5-86
 - Dataset Movement Index Calculation, 5-80
 - Dataset Movement Index Use, 5-80
 - Dataset Thrashing, 5-80
 - Define/Allocate HSM Files, 5-106
 - Definition and Use, 5-59
 - Description, 5-59
 - DFHSM DASD Volume Summary, 5-79
 - DFHSM Error Detail Report, 5-82
 - DFHSM Error Summary Report, 5-83
 - DFHSM Primary Volumes Summary, 5-87
 - DFHSM Specify SMF Record Type, 5-107
 - DFHSM Volume Backup Statistics, 5-79
 - DFHSM Volume Fragmentation Statistics, 5-79
 - DFHSM Volume Last Backup, 5-87
 - DFHSM Volume Last Dump, 5-87
 - DFHSM Volume Last Migration, 5-87
 - DFHSM Volume Management Technique, 5-87
 - DFHSM Volume Recall Statistics, 5-79
 - DFHSM Volume Recover Statistics, 5-79
 - DFHSM Volume Thresholds, 5-87
 - DFHSM Volume Usage Statistics, 5-79
 - Dynamic Date Selection, 5-102, 5-104
 - HSM Optimizer Report Menu, 5-100
 - HSM Report Database, 5-104
 - Main Menu, 5-100
 - Migrated Dataset Detail (MCDS Date Sort), 5-95
 - Migrated Dataset Detail (MCDS DSN Sort), 5-92
 - Migrated Dataset Summary, 5-85
 - Migration (Primary - ML2), 5-72
 - Migration Age Summary (ML1 - ML2), 5-68
 - Migration Age Summary (Primary - ML1), 5-65
 - Migration Delay Summary (Primary - ML1), 5-64
 - Migration Delay Summary (ML1 - ML2), 5-67

- Migration Delay Summary (Primary - ML2), 5-71
- Migration Detail (ML1 - ML2), 5-66
- Migration Detail (Primary - ML1), 5-62
- Migration Detail (Primary - ML2), 5-70
- Optimizer Reports, 5-102
- Primary Dataset Activity Report, 5-80
- Primary Volume Date Reference Detail, 5-90
- Primary Volume Detail, 5-89
- Produce Reports, 5-100
- Producing Reports, 5-102
- Recall Age Summary (ML1 - Primary), 5-75
- Recall Age Summary (ML2 - Primary), 5-78
- Recall Delay Summary (ML1 - Primary), 5-74
- Recall Delay Summary (ML2 - Primary), 5-77
- Recall Detail (ML1 - Primary), 5-73
- Recall Detail (ML2 - Primary), 5-76
- Recommended Retention Date, 5-104
- Recoverable Space, 5-87, 5-88
- Report Number XREF, 5-61
- SAMPLIB IFASMFDP, 5-105
- SAMPLIB RPTALLOC, 5-107
- SAMPLIB RPTRPT, 5-103, 5-105
- Selecting Reports, 5-102
- SMF Data Collection, 5-104
- SMF Data Input Format, 5-104
- Specify Database Retention, 5-104
- Specify SYSPRINT Class, 5-101
- Specifying Beginning Date, 5-102
- Specifying Ending Date, 5-102
- Summary of Features, 5-59
- Tuning DFHSM, 5-100
- Tuning DFSMS, 5-100
- Unmovable Datasets, 5-87, 5-88

I

- ISPF File Prefix Controls
 - Description, 5-108, 5-170
- ISPF Interface
 - Description, 2-1
 - Entering data, 2-1
 - External Tape Control, 5-211
 - Generated commands, 2-3
 - Help Screens, 2-5
 - Interface, 2-1
 - Internal documentation, 2-2
 - JCL Controls, 5-110
 - Job Controls, 5-139
 - Miscellaneous Controls, 5-189
 - PF Key Usage, 2-2
 - Query OS/EM Status, 6-1
 - QuickPool, 5-201
 - RACF Controls, 5-210
 - RACF Discrete Profiles, 5-210

- Reload Exits, 7-1
- Restrict Devices, 5-213
- Set JES2 Name, 8-1
- Specifying options and parameters, 2-2
- Starting the ISPF Interface, 2-5
- SVC Controls, 5-215
- Tape Share Controls, 5-218
- Time Controls, 5-224
- WTO Controls, 5-198

J

JCL Controls

- Account Number Controls, 5-112
- Description, 5-110
- JCL Control Menu, 5-111
 - EZ-Proclib(R) Control, 5-115
 - Jobclass/Jobname Controls, 5-116
 - Other JCL Controls, 5-122
 - STEPLIB Controls, 5-127
 - Sysout Class/Parameters, 5-131
 - Tape Usage Controls, 5-135
 - Virtual Storage Controls, 5-136
- Summary of Features, 5-110

JES2 Commands

- Defining CA-ACF2 Resources, 5-142
- Defining CA-TOPSECRET Resources, 5-142
- Defining RACF Resources, 5-142

JES2 Exits

- Query Status, 6-1

JES2 Exits, 4-4

JES3 Exits

- Query Status, 6-1

JES3 Exits, 4-11

Job Class

Job Controls

- Description, 5-139
- Job Controls Menu, 5-140
 - Add Notify Statement, 5-141
 - Control JES2 Commands, 5-142
 - Control Operating System Commands, 5-143
 - Dataset Name Conflict Resolution, 5-144
 - Job Limits By User, 5-147
 - Job Start Message, 5-152
 - Job Step Notify, 5-145
 - Job/Program Limits, 5-146
 - Job/Step Statistics, 5-153
 - Not Cataloged 2, 5-156
 - Program Limits, 5-150
 - Reformat Jobcard, 5-158
 - Surrogate Password, 5-159
 - Sysout Extensions, 5-162
 - TSO Logoff Statistics, 5-167
 - Verify User to Jobname, 5-169

- Verify User to RACF, 5-168
- Summary of Features, 5-139
- Job Limits By User, 5-147
- Job Name Checking
 - Exclude Job Name Masks, 5-121
 - Include Job Name Masks, 5-121
 - Job Name Masks, 5-121
- Job Name Mask
 - Dataspace Control, 5-137
 - Example, B-1, D-1
 - Exclude Job Name, 5-121
 - Hiperspace Control, 5-137
 - Include Job Name, 5-121
 - JES2 Mask Definition, 4-10
 - JES3 Mask Definition, 4-17
 - Job Name Checking, 5-121
 - Masking Characters, D-1
 - MVS Mask Definition, 4-24
 - Region Size Control, 5-137
 - Restrict Device, 5-214
 - Surrogate Password Processing, 5-160
 - Volume Masks Examples, D-1
- Job Routing Commands and JECL F-1
 - \$HASP Messages for Job Routing, H-1
- JCL Statements G-1
 - AFTER card G-2
 - BEFORE card G-2
 - CNTL card G-2
 - EXCLUDE card G-2
 - PRED card G-2
 - Route Card G-1
 - THREAD card G-2
 - WITH card G-2
- JCL Statments for Job Routing, G-1
- JES2 Commands F-1
 - \$DB F-1
 - \$DC F-1
 - \$DP F-1
 - \$DRESOURCE F-1
 - \$LF F-2
 - \$LN F-2
 - \$LQ F-3
 - \$Q'xxx' F-4
 - \$QA F-3
 - \$QD F-3
 - \$QJ F-4
- JES2 Commands for Job Routing, F-1
- Job Routing Controls
 - Job Routing Controls Menu, 5-170
- Job Start Message, 5-152
- Job Step Notify, 5-145
- Job/Program Limits, 5-146
- Job/Step Statistics, 5-153
- JOBCAT
 - Checking for Access to, 5-126
- Jobclass/Jobname Controls, 5-116
 - Job Class Checking, 5-118
 - Job Name Checking, 5-119

M

- Maxsize Parameter
 - Use in Delete-By-Age (DBA), 5-29
 - Use in Delete-If-Backed-Up (DBU), 5-31
- Messages
 - Setting Message Number in TSO, 1-3
- MGMTCLASS JCL Parameter
 - Controlling, 5-123
- Migration Control (ML0 to ML1)
 - Activating, 5-39
 - Add DSN Groups, 5-41
 - ARCCMDxx, 5-39
 - Deactivating, 5-39
 - Definition and Use, 5-39
 - Delete DSN Groups, 5-41
 - Exclude DSN Groups, 5-40
 - Hold Days Definition, 5-39
 - Include DSN Groups, 5-40
 - Maxsize And/Or Include, 5-40
 - Maxsize Connective, 5-39
 - NOMIG in ARCCMDxx, 5-42
 - Specify Hold Days, 5-39
 - Specifying DSN Groups, 5-40
- Migration Control (ML1 to ML2)
 - Activating, 5-44
 - Add DSN Groups, 5-45
 - Deactivating, 5-44
 - Definition and Use, 5-42, 5-46
 - Delete DSN Groups, 5-45
 - Exclude DSN Groups, 5-45
 - Hold Days Definition, 5-44
 - Include DSN Groups, 5-45
 - Maxsize And/Or Include, 5-44
 - Maxsize Connective, 5-44
 - Specify Hold Days, 5-44
 - Specifying DSN Groups, 5-45
- Miscellaneous Controls
 - ACF2 Non-cancel Override Control, 5-189
 - Catalog Account Control, 5-190
 - Description, 5-189, 5-210
 - Estimated Costs, 5-193
 - Miscellaneous Controls Menu, 5-189
 - TSO Program Intercept, 5-197
 - WTO Controls, 5-198
- MODIFY JCL Parameter
 - Controlling, 5-132
- MSGCLASS JCL Parameter
 - Controlling, 5-132
- MVS Account Numbers
 - Activating, 5-112
 - Defining, 5-112
 - Field Support, 5-112
 - List Validation, 5-113, 5-114
 - Security Checking, 5-113
- MVS Commands
 - Defining CA-ACF2 Resources, 5-143

- Defining CA-TOPSECRET Resources, 5-143
- Defining RACF Resources, 5-142, 5-143
- MVS Exits
 - MVS Exits, 4-18

N

- Not Cataloged 2, 5-156

O

- Other JCL Controls, 5-122
- OUTPUT PRTY JCL Parameter
 - Controlling, 5-132

P

- PAGEDEF JCL Parameter
 - Controlling, 5-132
- PERFORM JCL Parameter
 - Controlling, 5-123
- PRMODE JCL Parameter
 - Controlling, 5-132
- Program Limits, 5-150
- Program Name Mask
 - Dataspace Control, 5-137, 5-138
 - Example, B-2
 - Hiperspace Control, 5-137, 5-138
 - Masking Characters, B-1
 - Region Size Control, 5-137, 5-138
- PROTECT JCL Parameter
 - Controlling, 5-123
- PRTY JCL Parameter
 - Controlling, 5-123

Q

- Query OS/EM Status
 - ALLOC Exits, 6-1
 - ALLOC Specific Exit, 6-1
 - DASD Dataset Name Group, 6-1
 - DASD Exits, 6-1
 - DASD Specific Exit, 6-1
 - DASD Specific Pool, 6-1
 - DASD Volume Name Groups, 6-1
 - Definition and Use, 6-1
 - HSM Exits, 6-1
 - HSM Specific Exit, 6-1
 - ISPF Exits, 6-1
 - JES2 Exits, 6-1

- JES2 Specific Exit, 6-1
- JES3 Exits, 6-1
- JES3 Specific Exit, 6-1
- MVS Exits, 6-1
- Output Dataset, 6-1
- RACF Exits, 6-1
- RACF Specific Exit, 6-1
- SMF Exits, 6-1
- SMF Specific Exit, 6-1
- TSO Exits, 6-1
- TSO Specific Exit, 6-1
- QuickPool
 - Activate, 5-206
 - Add DSN Groups, 5-208
 - Allow DSN Groups, 5-207, 5-208
 - ALLOW/DISALLOW search order, 5-209
 - Control all Volumes, 5-206
 - Control Specified Volumes, 5-206
 - Deactivate, 5-206
 - Define Pools with Allow DSN Groups, 5-207
 - Define Pools with Disallow DSN Groups, 5-207
 - Define Pools, 5-207
 - Definition and Use, 5-201
 - Delete DSN Groups, 5-208
 - Disallow DSN Groups, 5-207, 5-208
 - Global Allow DSN Groups, 5-207
 - Global Disallow DSN Groups, 5-207
 - Note on SYS1 Datasets, 5-209
 - Pool Considerations, 5-209
 - Query Dataset Name Group, 6-1
 - Query Specific Pool, 6-1
 - Query Status, 6-1
 - Query Volume Name Groups, 6-1
 - QuickPool Menu, 5-202
 - DASD Allocation Control, 5-203
 - Specify Rules, 5-206
 - Specify DSN Groups, 5-208
 - Specify Rules, 5-206
 - Summary of Features, 5-201
 - SYS1 Datasets, 5-209
 - Use with HSM Optimizer, 5-209
 - Volume Pool considerations, 5-209
 - Volumes in Multiple Pool Definitions, 5-209
 - WARN mode, 5-205
- DPRTY, 5-122
- EXPDT, 5-123
- FCB, 5-131
- FLASH, 5-132
- FORM, 5-132
- FORMDEF, 5-132
- JES2 Command Checking, 5-142
- JES2 Command Resource Name, 5-142
- Job Accounting, 5-112
- Job Class Checking, 5-118
- Load Surrogate Password Dataset, 5-159
- MANAGEMENT CLASS, 5-123
- Message CLASS, 5-132
- MODIFY, 5-132
- MVS Command Checking, 5-143
- MVS Command Resource Name, 5-143
- NJE Surrogate Password Processing, 5-159
- OUTPRTY, 5-132
- PAGEDEF, 5-132
- PERFORM, 5-123
- PRMODE, 5-132
- PROTECT, 5-123
- PRTY, 5-123
- Resource for Job Class Checking, 5-118
- RETPD, 5-123
- STORAGE CLASS, 5-123
- SUBSYS, 5-123
- Surrogate Password User ID, 5-159
- SYSOUT Class, 5-132
- TIME, 5-123
- UCS, 5-133
- UNIT, 5-124
- USERLIB, 5-124
- WRITER, 5-133
- RACF Controls
 - External Tape Control, 5-211
 - RACF Controls Menu, 5-210
- RACF Discrete Profiles
 - RACF Discrete Profiles, 5-210
- RACF Exits
 - Query Status, 6-1
- Reblock Control
 - Activating, 5-55
 - Add DSN Groups, 5-57
 - Deactivating, 5-55
 - Definition and Use, 5-55
 - Delete DSN Groups, 5-57
 - During Conversion to New DASD, 5-55
 - Exclude DSN Groups, 5-56
 - Minimum Dataset Size, 5-56
 - Reblocking BLKSIZE, 5-56
- Recall/Recover
 - Activating, 5-58
 - Deactivating, 5-58
 - Definition and Use, 5-58
 - Use with QuickPool, 5-58
- Reformat Jobcard, 5-158
- Region Size Controls
 - Controlling By Job Class, 5-137

R

RACF

- ADDRSPC, 5-122
- BURST, 5-131
- CHARS, 5-131
- COPIES, 5-131
- DATA CLASS, 5-122
- DDNAME, 5-122
- Delete Surrogate Password Dataset, 5-159
- DEST, 5-131

- Controlling By Job Name, 5-137
- Controlling By Program Name, 5-137
- Masking, 5-138
- Reload Exits, 7-1
 - Selection Menu, 7-1
 - JES2 Exits User Modules, 7-2
 - JES3 Exits User Modules, 7-3
 - MVS Exits User Modules, 7-4
 - RACF Tables, 7-6
 - System Modules, 7-5
- Restrict Devices
 - Description, 5-213
 - Jobname "POPUP" Screen, 5-213
 - Restrict Devices, 5-213
 - Specify Jobname Mask, 5-214
 - Specify Jobname, 5-214
 - Summary of Features, 5-213
- Retention Period JCL Parameter
 - Controlling, 5-123

S

- Set JES2 Name, 8-1
- SMF Data Collection
 - Definition and Use, 5-104
 - DFHSM Specify Record Type, 5-107
 - Input Format, 5-104
- SMF Exits
 - Query Status, 6-1
- SMF Record Format, E-1
- STEPCAT
 - Checking for Access to, 5-126
- STEPLIB Controls, 5-127
- STORCLASS JCL Parameter
 - Controlling, 5-123
- SUBSYS JCL Parameter
 - Controlling, 5-123
- Supported Exits
 - Allocation Exits, A-1
 - DFHSM Exits, A-3
 - DFP Exits, A-2
 - ISPF Exits, A-4
 - JES2 Exits, A-5
 - JES3 Exits, A-7
 - RACF Exits, A-9
 - SAF Exits, A-10
 - SMF Exits, A-11
 - TSO/E Exits, A-12
- Surrogate Password
 - Definition and Use, 5-159
 - Specifying Job Name Mask, 5-160
- SVC Controls
 - Description, 5-215

- Sysout Class/Parameters, 5-131
- Sysout Extensions, 5-162
- SYSOUT JCL Parameter
 - Controlling, 5-132
- System Codes
- System Controls/Maintenance/Installation Functions, 3-1
 - Abend Notify TSO IDs, 3-3
 - Authorization Codes, 3-2
 - Create OS/EM Tables, 3-10
 - Entering, 3-2
 - Execute Online Warning Message, 3-7
 - Expire Warning Messages, 3-2
 - Maintenance, 3-8
 - Online Warning Messages, 3-7
 - Pending Changes Table Maintenance, 3-8
 - Performance Counts and Timings, 3-6
 - Rebuild OS/EM Tables, 3-8
 - SMF Recording, 3-6
 - System Level Controls, 3-1
 - Upgrade to OS/EM 6.0, 3-11
- System Managed Storage
 - HSM Optimizer Recall, 5-58

T

- Tape Share Controls
 - Description, 5-218
 - Device Level Controls, 5-222
 - System Level Controls, 5-219
 - Tape Share Controls Menu, 5-218
- Tape Usage Controls, 5-135
- Terminal ID Mask
 - Example, B-1
 - Masking Characters, B-1
 - Volume Masks Examples, B-1
- Time Controls
 - Description, 5-224
 - Summary of Features, 5-224
 - Time Controls Menu, 5-224
- TIME JCL Parameter
 - Controlling, 5-123
- TSO Exits
 - Query Status, 6-1
- TSO Logoff Statistics, 5-167
- TSO Profile
 - OS/EM Message Number, 1-3
- TSO Program Intercept, 5-197
- TSO User ID Mask
 - Dataset Format, 5-161
 - RACF User ID Setup, 5-161
 - Surrogate Password Processing, 5-160

U

- UCS JCL Parameter
 - Controlling, 5-133
- UNIT JCL Parameter
 - Controlling, 5-124
- USERLIB JCL Parameter
 - Controlling, 5-124

V

- Valid Return Code
 - Good Return Code, 4-6, 4-13, 4-20
 - JES2 Usage, 4-6
 - JES3 Usage, 4-13
 - MVS Usage, 4-20
- Verify User to Jobname, 5-169
- Verify User to RACF, 5-168
- Virtual Storage Controls, 5-136
- Volume Groups
 - Add Group, 5-14
 - Change Group, 5-14

- Creating Group Names, 5-12
- Defining Volume Mask(s), 5-17
- Definition, 5-12
- Delete Group, 5-16
- Disable, 5-13
- Enable, 5-13
- Temporarily Disable Group, 5-16
- Use in QuickPool, 5-207
- Volume Name Masks
 - Examples, 5-17
 - Masking Characters, 5-17
 - Name Mask Table, 5-17

W

- Warn Mode
 - Use in Implementing DFSMS, 5-205
 - Use in QuickPool, 5-205
 - Why Use in QuickPool, 5-205
- WTO Controls
 - Description, 5-198
 - WTO Controls Entry Panel, 5-198

Readers's Comment Form

The success of this manual depends solely on its usefulness to you. To ensure such usefulness, we solicit your comments concerning the clarity, accuracy, completeness, and organization of this manual. Please enter your comments below and mail this form to the address on the front page of this manual. If you wish a reply, give your name, company, and mailing address. We would also appreciate an indication of your occupation and how you use this manual.

Please rate this manual on the following points:

accurate	1	2	3	4	5	inaccurate
readable	1	2	3	4	5	unreadable
well laid out	1	2	3	4	5	badly laid out
well organized	1	2	3	4	5	badly organized
easy to understand	1	2	3	4	5	incomprehensible
has enough examples	1	2	3	4	5	has too few examples

Thank you for your time and effort.