



**Program Directory for
IBM WebSphere MQ for z/OS
Value Unit Edition V8.0**

v8.0.0

Program Number 5655-VU8

HUE8000

for use with
z/OS on zNALC

Document Date: June 2014

G113-3332-00

Note

Before using this information and the product it supports, be sure to read the general information under Appendix C, "Notices" on page 27.

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 2013, 2014.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

| | |
|---|----|
| 1.0 Introduction | 1 |
| 1.1 MQ VUE Description | 1 |
| 1.2 MQ VUE FMIDs | 2 |
| 2.0 Program Materials | 3 |
| 2.1 Basic Machine-Readable Material | 3 |
| 2.2 Optional Machine-Readable Material | 3 |
| 2.3 Program Publications | 3 |
| 2.4 Program Source Materials | 4 |
| 2.5 Publications Useful During Installation | 4 |
| 3.0 Program Support | 5 |
| 3.1 Program Services | 5 |
| 3.2 Preventive Service Planning | 5 |
| 3.3 Statement of Support Procedures | 6 |
| 4.0 Program and Service Level Information | 7 |
| 4.1 Program Level Information | 7 |
| 4.2 Service Level Information | 7 |
| 5.0 Installation Requirements and Considerations | 9 |
| 5.1 Driving System Requirements | 9 |
| 5.1.1 Machine Requirements | 9 |
| 5.1.2 Programming Requirements | 9 |
| 5.2 Target System Requirements | 10 |
| 5.2.1 Machine Requirements | 10 |
| 5.2.2 Programming Requirements | 10 |
| 5.2.2.1 Installation Requisites | 10 |
| 5.2.2.2 Operational Requisites | 11 |
| 5.2.2.3 Toleration/Coexistence Requisites | 12 |
| 5.2.2.4 Incompatibility (Negative) Requisites | 12 |
| 5.2.3 DASD Storage Requirements | 12 |
| 5.3 FMIDs Deleted | 14 |
| 5.4 Special Considerations | 14 |
| 5.4.1 SMP/E Considerations | 14 |
| 6.0 Installation Instructions | 15 |
| 6.1 Installing MQ VUE | 15 |
| 6.1.1 SMP/E Considerations for Installing MQ VUE | 15 |
| 6.1.2 SMP/E Options Subentry Values | 15 |
| 6.1.3 Sample Jobs | 15 |
| 6.1.4 Prepare the Installation Environment | 17 |

| | |
|---|-----------|
| 6.1.4.1 Global zone | 17 |
| 6.1.4.2 Target and distribution zones | 17 |
| 6.1.5 Allocate SMP/E Target and Distribution Libraries | 18 |
| 6.1.6 Define DDDEF Entries | 18 |
| 6.1.7 Perform SMP/E RECEIVE | 18 |
| 6.1.8 Perform SMP/E APPLY | 18 |
| 6.1.9 Perform SMP/E ACCEPT | 20 |
| 6.2 Activating MQ VUE | 20 |
| 6.2.1 Updating the IBM WebSphere MQ JCL Procedure | 21 |
| Appendix A. Automated install JCL customization | 23 |
| Appendix B. High-level qualifiers and symbolic parameters. | 25 |
| B.1 High-level qualifiers | 25 |
| B.2 Symbolic parameters | 25 |
| Appendix C. Notices | 27 |
| C.1 Trademarks | 28 |
| Reader's Comments | 31 |

Figures

| | |
|--|----|
| 1. Basic Material: Program Tape | 3 |
| 2. Basic Material: Unlicensed | 4 |
| 3. Publications Useful During Installation | 4 |
| 4. PSP Upgrade and Subset ID | 5 |
| 5. Component IDs | 6 |
| 6. Driving System Software Requirements | 10 |
| 7. Target System Mandatory Installation Requisites | 11 |
| 8. Target System Mandatory Operational Requisites | 11 |
| 9. Total DASD Space Required by MQ VUE | 12 |
| 10. Storage Requirements for MQ VUE Target Libraries | 13 |
| 11. Storage Requirements for MQ VUE Distribution Libraries | 14 |
| 12. SMP/E Options Subentry Values | 15 |
| 13. Sample Installation Jobs | 16 |
| 14. High-level qualifiers for data set names | 25 |
| 15. Symbolic parameters | 25 |

1.0 Introduction

This Program Directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of IBM WebSphere MQ for z/OS Value Unit Edition. This publication refers to IBM WebSphere MQ for z/OS Value Unit Edition as MQ VUE.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 3 identifies the basic program materials and documentation for MQ VUE.
- 3.0, “Program Support” on page 5 describes the IBM support available for MQ VUE.
- 4.0, “Program and Service Level Information” on page 7 lists the APARs (program level) and PTFs (service level) that have been incorporated into MQ VUE.
- 5.0, “Installation Requirements and Considerations” on page 9 identifies the resources and considerations that are required for installing and using MQ VUE.
- 6.0, “Installation Instructions” on page 15 provides detailed installation instructions for MQ VUE. It also describes the procedures for activating the functions of MQ VUE, or refers to appropriate publications.

Before installing MQ VUE, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this Program Directory; then keep them for future reference. Section 3.2, “Preventive Service Planning” on page 5 tells you how to find any updates to the information and procedures in this Program Directory.

MQ VUE is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The Program Directory that is provided in softcopy format on the CBPDO tape is identical to the hardcopy format if one was included with your order. All service and HOLDDATA for MQ VUE are included on the CBPDO tape.

Do not use this Program Directory if you install MQ VUE with a SystemPac or ServerPac. When you use one of those offerings, use the jobs and documentation supplied with the offering. The offering will point you to specific sections of this Program Directory as needed.

1.1 MQ VUE Description

IBM WebSphere MQ for z/OS Value Unit Edition V8.0 provides all the function of IBM WebSphere MQ for z/OS V8.0 but is sold with a one-time-charge (OTC) price metric for support of eligible workloads that are deployed in qualified System z New Application License Charge (zNALC) logical partitions (LPARs).

The term, Eligible Workload, is defined as new workload which is qualified and approved through the zNALC qualification process and is then supported by the MQ VUE server environment.

The OTC price metric provides an alternative pricing model for buying IBM WebSphere MQ for z/OS to connect new workloads that are qualified to run on zNALC LPARs.

Support for the zNALC metric offers a reduced price for the z/OS operating system on LPARs that run a qualified application.

MQ VUE V8.0 can connect to other supported versions of IBM WebSphere MQ for z/OS (whether in zNALC or non-zNALC environments) for the purpose of workload federation and systems management.

MQ for z/OS V8 allows connections from MQ clients which run on other platforms, and this capability is available in the VUE edition.

1.2 MQ VUE FMIDs

MQ VUE consists of the following FMID:

HUE8000

2.0 Program Materials

An IBM program is identified by a program number. The program number for MQ VUE is 5655-VU8.

Basic Machine-Readable Materials are materials that are supplied under the base license and feature numbers, and are required for the use of the product.

The program announcement material describes the features supported by MQ VUE. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is physical media or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 15 for more information about how to install the program.

Figure 1. Basic Material: Program Tape

| Medium | Feature Number | Physical Volume | External Label | VOLSER |
|--------------|----------------|-----------------|--|--------|
| 3590 Tape | HUE8000 | 1 | IBM WebSphere MQ for z/OS Value Unit Edition V8.0 | MQVUE |

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for MQ VUE.

2.3 Program Publications

The following sections identify the basic publications for MQ VUE.

Figure 2 identifies the basic unlicensed publications for MQ VUE. Publications can be accessed at the IBM Publications Center website at <http://www.ibm.com/shop/publications/order/> Additionally IBM WebSphere MQ V8.0 documentation is published in IBM Knowledge Center, which can be viewed from a web browser with Internet access at http://www.ibm.com/support/knowledgecenter/SSFKSJ_8.0.0/welcome/WelcomePagev8r0.

Figure 2. Basic Material: Unlicensed

| Publication Title | Form Number | Media Format |
|--|--------------------|-------------------------|
| IBM WebSphere MQ for z/OS Value Unit Edition V8.0 License Information CD | GC34-2972 | CD-ROM |
| IBM WebSphere MQ for z/OS Value Unit Edition V8.0 Program Directory | G113-3332 | IBM Publications Center |

No optional publications are provided for MQ VUE.

2.4 Program Source Materials

No program source materials or viewable program listings are provided for MQ VUE.

2.5 Publications Useful During Installation

You might want to use the publications listed in Figure 3 during the installation of MQ VUE.

Figure 3. Publications Useful During Installation

| Publication Title | Form Number | Media Format |
|--|--------------------|---------------------|
| <i>IBM SMP/E for z/OS User's Guide</i> | SA22-7773 | Softcopy |
| <i>IBM SMP/E for z/OS Commands</i> | SA22-7771 | Softcopy |
| <i>IBM SMP/E for z/OS Reference</i> | SA22-7772 | Softcopy |
| <i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i> | GA22-7770 | Softcopy |

3.0 Program Support

This section describes the IBM support available for MQ VUE.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before you install MQ VUE, make sure that you have reviewed the current Preventive Service Planning (PSP) information. Review the PSP Bucket for General Information, Installation Documentation, and the Cross Product Dependencies sections. For the Recommended Service section, instead of reviewing the PSP Bucket, it is recommended you use the IBM.ProductInstall-RequiredService fix category in SMP/E to ensure you have all the recommended service installed. Use the **FIXCAT(IBM.ProductInstall-RequiredService)** operand on the **APPLY CHECK** command. See 6.1.8, “Perform SMP/E APPLY” on page 18 for a sample APPLY command.

If you obtained MQ VUE as part of a CBPDO, HOLDDATA is included.

If the CBPDO for MQ VUE is older than two weeks by the time you install the product materials, you can obtain the latest PSP Bucket information by going to the following website:

<http://www14.software.ibm.com/webapp/set2/psearch/search?domain=psp>

You can also use S/390 SoftwareXcel or contact the IBM Support Center to obtain the latest PSP Bucket information.

For program support, access the Software Support Website at <http://www.ibm.com/software/support/>.

PSP Buckets are identified by UPGRADEs, which specify product levels; and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for MQ VUE are included in Figure 4.

| UPGRADE | SUBSET | Description |
|---------|---------|-------------------------------|
| MQMESA | HUE8000 | IBM WebSphere MQ for z/OS VUE |

3.3 Statement of Support Procedures

Report any problems which you feel might be an error in the product materials to your IBM Support Center. You may be asked to gather and submit additional diagnostics to assist the IBM Support Center in their analysis.

Figure 5 on page 6 identifies the component IDs (COMPID) for MQ VUE.

| <i>Figure 5. Component IDs</i> | | | |
|--------------------------------|---------------|-------------------------------|-----------------------|
| FMID | COMPID | Component Name | RETAIN Release |
| HUE8000 | 5655VU800 | IBM WebSphere MQ for z/OS VUE | 000 |

4.0 Program and Service Level Information

This section identifies the program and relevant service levels of MQ VUE. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

4.1 Program Level Information

No APARs have been incorporated into MQ VUE.

4.2 Service Level Information

No PTFs against this release of MQ VUE have been incorporated into the product package.

It is highly recommended that you frequently check the MQ VUE PSP Bucket for HIPER and SPECIAL Attention PTFs against all FMIDs that you must install.

It is highly recommended that you frequently check the MQ VUE PSP Bucket for HIPER and SPECIAL attention PTFs against all FMIDs that you must install. You can also receive the latest HOLDDATA, then add the **FIXCAT(IBM.PRODUCTINSTALL-REQUIRESERVICE)** operand on your APPLY CHECK command. This will allow you to review the recommended and critical service that should be installed with your FMIDs.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating MQ VUE. The following terminology is used:

- *Driving system*: the system on which SMP/E is executed to install the program.
The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.
- *Target system*: the system on which the program is configured and run.
The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

- When you install a new level of a product that is already installed, the new level of the product will replace the old one. By installing the new level onto a separate target system, you can test the new level and keep the old one in production at the same time.
- When you install a product that shares libraries or load modules with other products, the installation can disrupt the other products. By installing the product onto a separate target system, you can assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install MQ VUE.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

Figure 6. Driving System Software Requirements

| Program Number | Product Name | Minimum VRM | Minimum Service Level will satisfy these APARs | Included in the shipped product? |
|----------------------------------|--------------|-------------|--|----------------------------------|
| Any one of the following: | | | | |
| 5694-A01 | z/OS | V01.13.00 | N/A | No |
| 5650-ZOS | z/OS | V02.1.00 | N/A | No |

Note: Installation might require migration to new z/OS releases to be service supported.

See http://www.ibm.com/systems/z/os/zos/support/zos_eos_dates.html. Installation requires use of the z/OS Program Management Binder as some MQ VUE code requires facilities not available in the linkage editor.

5.2 Target System Requirements

This section describes the environment of the target system that is required to install and use MQ VUE.

MQ VUE installs in the z/OS (Z038) SREL.

5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites: Installation requisites identify products that are required by and *must* be present on the system or products that are not required by but *should* be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product. These products are specified as PREs or REQs.

Figure 7. Target System Mandatory Installation Requisites

| Program Number | Product Name | Minimum VRM | Minimum Service Level will satisfy these APARs | Included in the shipped product? |
|----------------|--------------|--------------------|--|----------------------------------|
| 5694-A01 | z/OS | V01.13.0 or higher | N/A | No |
| 5650-ZOS | z/OS | V02.1.0 or higher | N/A | No |

Conditional installation requisites identify products that are *not* required for successful installation of this product but can resolve such things as certain warning messages at installation time. These products are specified as IF REQs.

MQ VUE has no conditional installation requisites.

5.2.2.2 Operational Requisites: Operational requisites are products that are required by and *must* be present on the system or products that are not required by but *should* be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions. These products are specified as PREs or REQs.

Figure 8. Target System Mandatory Operational Requisites

| Program Number | Product Name and Minimum VRM/Service Level |
|----------------|--|
| 5694-A01 | z/OS V01.13.0 |
| 5650-ZOS | z/OS V02.1.0 |
| 5655-W97 | IBM WebSphere MQ for z/OS V8.0.0 |

Conditional operational requisites identify products that are *not* required for this product to operate its basic functions but are required at run time for this product to operate specific functions. These products are specified as IF REQs.

Please refer to the following web page for the latest operational requisite product information for MQ VUE.
<http://publib.boulder.ibm.com/infocenter/prodguid/v1r0/clarity/index.jsp>

MQ VUE has no conditional operational requisites.

5.2.2.3 Toleration/Coexistence Requisites: Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

MQ VUE has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites: Negative requisites identify products that must *not* be installed on the same system as this product.

MQ VUE has no negative requisites.

5.2.3 DASD Storage Requirements

MQ VUE libraries can reside on all supported DASD types.

Figure 9 lists the total space that is required for each type of library.

| <i>Figure 9. Total DASD Space Required by MQ VUE</i> | | |
|--|--|--------------------------------|
| Library Type | Total Space Required in 3390 Trks | File System Description |
| Target | 50 | |
| Distribution | 50 | |

Notes:

1. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.
2. Abbreviations used for data set types are shown as follows.
 - U** Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
 - S** Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
 - E** Existing shared data set, used by this product and other products. This data set is *not* allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.5, “Allocate SMP/E Target and Distribution Libraries” on page 18.

3. Abbreviations used for the file system path type are as follows.

- N** New path, created by this product.
- X** Path created by this product, but might already exist from a previous release.
- P** Previously existing path, created by another product.

4. All target and distribution libraries listed have the following attributes:

- The default name of the data set can be changed.
- The default block size of the data set can be changed.
- The data set can be merged with another data set that has equivalent characteristics.
- The data set can be either a PDS or a PDSE.

5. All target libraries listed have the following attributes:

- These data sets can be SMS-managed, but they are not required to be SMS-managed.
- These data sets are not required to reside on the IPL volume.
- The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.

6. All target libraries that are listed and contain load modules have the following attributes:

- These data sets can be in the LPA, but they are not required to be in the LPA.
- These data sets can be in the LNKLIST.
- The SCUEAUTH library must be APF authorized.

The following figures describe the target and distribution libraries and file system paths required to install MQ VUE. The storage requirements of MQ VUE must be added to the storage required by other programs that have data in the same library or path.

Note: Use the data in these tables to determine which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

| <i>Figure 10 (Page 1 of 2). Storage Requirements for MQ VUE Target Libraries</i> | | | | | | | | |
|--|------------------------|--------------------------|----------------------------|----------------------|----------------------------|----------------------------------|-------------------------------------|------------------------------------|
| Library DDNAME | Member Type | Target Volume | T Y P E | O R G | R E C M | L R E C L | No. of 3390 Trks | No. of DIR Blks |
| SCUEAUTH | LMOD | ANY | U | PDS | U | 0 | 10 | 5 |

Figure 10 (Page 2 of 2). Storage Requirements for MQ VUE Target Libraries

| Library DDNAME | Member Type | Target Volume | T Y P E | O R G A N I Z A T I O N | R E C O R D S | L E N G T H | No. of 3390 Trks | No. of DIR Blks |
|-------------------|----------------|------------------|------------------|--|---------------------------------|----------------------------|---------------------------|--------------------------|
| SCUEINST | PROC | ANY | U | PDSE | FB | 80 | 10 | 3 |

Figure 11. Storage Requirements for MQ VUE Distribution Libraries

| Library DDNAME | T Y P E | O R G A N I Z A T I O N | R E C O R D S | L E N G T H | No. of 3390 Trks | No. of DIR Blks |
|-------------------|------------------|--|---------------------------------|----------------------------|---------------------------|--------------------------|
| ACUEMOD | U | PDSE | U | 0 | 10 | 5 |
| ACUEINST | U | PDSE | FB | 80 | 10 | 3 |

5.3 FMIDs Deleted

Installing MQ VUE might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install MQ VUE into separate SMP/E target and distribution zones.

Note: These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, see the SMP/E manuals for instructions.

5.4 Special Considerations

MQ VUE has no special considerations for the target system.

5.4.1 SMP/E Considerations

IBM recommends that you install MQ VUE into a new set of SMP/E zones, including SMPCSI, target, distribution, and zFS data sets, to allow independent maintenance of MQ VUE, z/OS, and other subsystems. This Program Directory provides sample jobs and instructions to create such an SMP/E environment.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of MQ VUE.

Please note the following points:

- If you want to install MQ VUE into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.
- You can use the SMP/E dialogs instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing MQ VUE

6.1.1 SMP/E Considerations for Installing MQ VUE

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of MQ VUE.

6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 12. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

| <i>Figure 12. SMP/E Options Subentry Values</i> | | |
|---|-----------------|---|
| Subentry | Value | Comment |
| DSSPACE | (1000,1000,800) | These are the minimum required values. |
| PEMAX | SMP/E Default | IBM recommends using the SMP/E default for PEMAX. |

6.1.3 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install MQ VUE:

If you wish to use the automated customization see Appendix A, “Automated install JCL customization” on page 23.

The sample installation jobs are sorted by name into an order in which to run them in sequence (after editing) to install MQ VUE. The exact order in which to run the jobs is not absolutely critical. Running the jobs in either the sequence they are listed in the list below or in the text of this chapter is acceptable.

| <i>Figure 13. Sample Installation Jobs</i> | | | |
|--|-------------|---|----------------|
| Job Name | Job Type | Description | RELFILE |
| CUE8ASYJ | CUSTOMIZE | Sample job to customize the sample JCL | IBM.HUE8000.F2 |
| CUE8BGZN | GLOBAL ZONE | Sample job to create an SMP/E Global Zone | IBM.HUE8000.F2 |
| CUE8CTZN | TARGET ZONE | Sample job to create an SMP/E Target Zone | IBM.HUE8000.F2 |
| CUE8DDZN | DIST ZONE | Sample job to create an SMP/E Distribution Zone | IBM.HUE8000.F2 |
| CUE8EALO | ALLOCATE | Sample job to allocate target and distribution libraries (FMID HUE8000) | IBM.HUE8000.F2 |
| CUE8FDDF | DDDEF | Sample job to define SMP/E DDDEFs (FMID HUE8000) | IBM.HUE8000.F2 |
| CUE8GREC | RECEIVE | Sample RECEIVE job | IBM.HUE8000.F2 |
| CUE8HAPL | APPLY | Sample APPLY job | IBM.HUE8000.F2 |
| CUE8IACP | ACCEPT | Sample ACCEPT job | IBM.HUE8000.F2 |

You can access the sample installation jobs by performing an SMP/E RECEIVE (refer to 6.1.7, “Perform SMP/E RECEIVE” on page 18) then copy the jobs from the RELFILES to a work data set for editing and submission. See Figure 13 to find the appropriate relfile data set.

You can also copy the sample installation jobs from the tape or product files by submitting the following job. Depending on your distribution medium, use either the //TAPEIN or the //FILEIN DD statement and comment out or delete the other statement. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//TAPEIN DD DSN=IBM.HUE8000.F2,UNIT=tunit,
// VOL=SER=volser,LABEL=(x,SL),
// DISP=(OLD,KEEP)
//FILEIN DD DSN=IBM.HUE8000.F2,UNIT=SYSALLDA,DISP=SHR,
// VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,
// SPACE=(TRK,(11,41,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
```

```
COPY INDD=xxxxIN,OUTDD=OUT
/*
```

See the following information to update the statements in the previous sample:

TAPEIN:

tunit is the unit value that matches the product tape.

volser is the volume serial that matches the product tape.

x is the tape file number that indicates the location of the data set name on the tape.

See the documentation that is provided by CBPDO for the location of IBM.HUE8000.F1 on the tape.

FILEIN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT:

jcl-library-name is the name of the output data set where the sample jobs are stored.

dasdvol is the volume serial of the DASD device where the output data set resides.

SYSIN:

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4 Prepare the Installation Environment

6.1.4.1 Global zone: If you are installing into an existing global zone, check that:

- The PEMAX option entry is set to 9999, or left to default.
- The DSSPACE options entry specifies at least 800 directory blocks.

If you are installing into a new global zone, edit and submit sample job **CUE8BGZN** to create a new SMP/E global zone for MQ VUE. Ensure that the job card is valid for your system. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages:

CUE8BGZN has a number of steps, all of which should complete with a return code of 0.

If any of the return codes is not 0, inspect the job output to determine what caused the problem and correct it, then rerun the job from the step that failed.

6.1.4.2 Target and distribution zones: If you need to create new target and distribution zones for MQ VUE, edit and submit the following sample jobs:

- **CUE8CTZN** to create a new target zone.
- **CUE8DDZN** to create a new distribution zone.

Ensure in each case that the job card is valid for your system. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages:

Both jobs consist of a number of steps, all of which should complete with a return code of 0.

If any of the return codes is not 0, inspect the job output to determine what caused the problem, correct it, and then rerun the job from the step that failed.

6.1.5 Allocate SMP/E Target and Distribution Libraries

Customize and run sample job **CUE8HAPL** to allocate the SMP/E target and distribution libraries for MQ VUE. Refer to the instructions in the sample job for more information.

Make sure the data sets are allocated on the required volumes.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.6 Define DDDEF Entries

Customize and run the sample job **CUE8FDDF** to create DDDEF entries for the SMP/E target and distribution libraries for MQ VUE. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.7 Perform SMP/E RECEIVE

If you have obtained MQ VUE as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the MQ VUE FMIDs, service, and HOLDDATA that are included on the CBPDO package. For more information, see the documentation that is included in the CBPDO.

Otherwise edit and submit sample job CUE8GREC to perform the SMP/E RECEIVE for MQ VUE. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.8 Perform SMP/E APPLY

1. Ensure that you have the latest HOLDDATA; then edit and submit sample job CUE8HAPL to perform an SMP/E APPLY CHECK for MQ VUE. Consult the instructions in the sample job for more information.

HOLDDATA introduces ERROR HOLDS against FMIDs for HIPER APARs. Before the installation, ensure that you have the latest HOLDDATA, which is available through several different portals, including <http://service.software.ibm.com/holddata/390holddata.html>. Install the FMIDs regardless of the status of unresolved HIPERs. However, do not deploy the software until the unresolved HIPERs are analyzed to determine applicability.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. The SMP/E root cause analysis identifies the cause only of *errors* and not of *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here is a sample to install FMIDs when ++HOLDS for HIPERs exist for the FMIDs that you install:

- a. To ensure that all recommended and critical service is installed with the FMIDs, if you have received the latest HOLDDATA, add the FIXCAT operand to the APPLY command as shown below.

```
APPLY S(fmid,fmid,...)
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND .
```

Some HIPER APARs might not have PTFs available yet. You have to analyze the symptom flags to determine if you want to bypass the specific ERROR HOLDS and continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixes available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

- b. To install the FMIDs without regard for the HIPERs, you can add a BYPASS(HOLDCLASS(HIPER)) operand to the APPLY command. In this way, you can install FMIDs even though HIPER ERROR HOLDS against them still exist. Only the HIPER ERROR HOLDS are bypassed. After the FMIDs are installed, run the SMP/E REPORT ERRSYSMODS command to identify missing HIPER maintenance.

```
APPLY S(fmid,fmid,...)
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER)) .
..any other parameters documented in the Program Directory
```

This method is the quicker of the two, but requires subsequent review of the REPORT ERRSYSMODS to investigate any HIPERs. If you have received the latest HOLDDATA, you can also choose to run REPORT MISSINGFIX for Fix Category IBM.ProductInstall-RequiredService to investigate missing recommended service.

If you bypass HOLDS during the installation of the FMIDs because PTFs are not yet available, you can be notified when the PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

2. After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 if this job runs correctly.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 if this job runs correctly.

6.1.9 Perform SMP/E ACCEPT

Edit and submit sample job CUE8IACP to perform an SMP/E ACCEPT CHECK for MQ VUE. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. The SMP/E root cause analysis identifies the cause of only *errors* but not *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the *SMP/E Commands* book for details.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 if this job runs correctly.

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 if this job runs correctly.

6.2 Activating MQ VUE

6.2.1 Updating the IBM WebSphere MQ JCL Procedure

After installing MQ VUE, the SCUEAUTH target library must be APF authorized and added to the started task JCL procedure for eligible queue managers running in the zNALC LPAR.

SCUEAUTH must be added to the STEPLIB DD concatenation above the existing SCSQAUTH library.

Appendix A. Automated install JCL customization

Automated install JCL customization makes tailoring each piece of JCL individually unnecessary, reducing the chances of making a mistake.

Edit **CUE8ASYJ** and follow the instructions in the job to define the values you want to use to tailor the install JCL. The figures in Appendix B, “High-level qualifiers and symbolic parameters.” on page 25 show the values you must tailor and have space for you to record your choices.

Submit **CUE8ASYJ** Expected return code 0, 1 or 4.

Appendix B. High-level qualifiers and symbolic parameters.

B.1 High-level qualifiers

Use Figure 14 to plan the high-level qualifiers for the MQ VUE data sets.

Figure 14. High-level qualifiers for data set names

| Parameter name in the sample JCL provided | Example value | Your value | Description |
|---|---------------|------------|-------------------|
| -SHLQUAL- | HLQ.SMPE | | MQ VUE SMP/E HLQ |
| -THLQUAL- | HLQ.TLIB | | MQ VUE TARGET HLQ |
| -DHLQUAL- | HLQ.DLIB | | MQ VUE DISTBN HLQ |

B.2 Symbolic parameters

Use Figure 15 to plan the symbolic parameters for the MQ VUE sample jobs.

Figure 15 (Page 1 of 2). Symbolic parameters

| Parameter name in the sample jobs | Example value | Your value | Description |
|-----------------------------------|---------------|------------|--|
| -MOUTPUT- | THQ.TCUEINST | | PDS name of modified Installation scripts. |
| -MINPUT- | DHQ.UCUEINST | | PDS name of unmodified Installation scripts. |
| -SMPVOL- | | | SMP/E VOLUME |
| -SMPUNIT- | 3390 | | SMP/E UNIT |
| -TARVOL- | . | | TARGET VOLUME |

Figure 15 (Page 2 of 2). Symbolic parameters

| Parameter name in the sample jobs | Example value | Your value | Description |
|-----------------------------------|---------------|------------|---|
| -DISVOL- | . | | DISTRIBUTION VOLUME |
| -DISKUNIT- | | | DASD unit type for target and distribution library allocation |
| -TAPEUNIT- | 3590 | | Tape unit type for SMP/E receive job. |
| -GZONECSI- | NEW | | GLOBAL ZONE CSI NAME |
| -TZNAME- | TZONE | | TARGET ZONE NAME |
| -DZNAME- | DZONE | | DISTBN ZONE NAME |
| -TAPEUNIT- | 3590 | | Tape unit type for SMP/E receive job. |

Appendix C. Notices

References in this document to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe on any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
USA

For online versions of this book, we authorize you to:

- Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.
- Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

THERE ARE NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Some jurisdictions do not allow the exclusion of implied warranties, so the above exclusion may not apply to you.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine readable documentation.

C.1 Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

Reader's Comments

Program Directory for IBM WebSphere MQ for z/OS Value Unit Edition, June 2014

We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Use one of the following methods to send us your comments:

1. Send an email to idrcf@hursley.ibm.com
2. Use the form on the Web at:
www.ibm.com/software/ad/rcf/
3. Mail the comments to the following address:

User Technologies Department (MP 095)
IBM United Kingdom Laboratories
Hursley Park,
WINCHESTER,
Hampshire
SO21 2JN,
United Kingdom

FAX Number:

- From outside the U.K., after your international access code use 44-1962-816151
- From within the U.K., use 01962 816151

Include the following information:

- Your name and address
- Your email address
- Your telephone or fax number
- The publication title and order number
- The topic and page number related to your comment
- The text of your comment

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit.

Thank you for your participation.



Printed in USA

G113-3332-00

