



**Program Directory for  
IBM DB2 Bind Manager for z/OS**

V02.04.00

Program Number 5655-E43

FMID H26D240

for Use with  
z/OS

Document Date: November 2009

GI10-8416-04

**Note !**

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 23.

A form for reader's comments appears at the back of this publication. When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 2000, 2009. All rights reserved.**

© **HLS Technologies - 1991, 2009**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>1.0 Introduction</b>	1
1.1 IBM DB2 Bind Manager Description	1
1.2 IBM DB2 Bind Manager FMID	2
<b>2.0 Program Materials</b>	3
2.1 Basic Machine-Readable Material	3
2.2 Optional Machine-Readable Material	4
2.3 Program Publications	4
2.3.1 Basic Program Publications	4
2.3.2 Optional Program Publications	5
2.4 Program Source Materials	5
2.5 Publications Useful During Installation	5
<b>3.0 Program Support</b>	6
3.1 Program Services	6
3.2 Preventive Service Planning	6
3.3 Statement of Support Procedures	7
<b>4.0 Program and Service Level Information</b>	8
4.1 Program Level Information	8
4.2 Service Level Information	9
<b>5.0 Installation Requirements and Considerations</b>	10
5.1 Driving System Requirements	10
5.1.1 Machine Requirements	10
5.1.2 Programming Requirements	10
5.2 Target System Requirements	11
5.2.1 Machine Requirements	11
5.2.2 Programming Requirements	11
5.2.2.1 Installation Requisites	11
5.2.2.2 Operational Requisites	12
5.2.2.3 Toleration/Coexistence Requisites	12
5.2.2.4 Incompatibility (Negative) Requisites	13
5.2.3 DASD Storage Requirements	13
5.3 FMIDs Deleted	15
5.4 Special Considerations	15
<b>6.0 Installation Instructions</b>	16
6.1 Installing IBM DB2 Bind Manager	16
6.1.1 SMP/E Considerations for Installing IBM DB2 Bind Manager	16
6.1.2 SMP/E Options Subentry Values	16
6.1.3 SMP/E CALLLIBS Processing	17

6.1.4	Sample Jobs	17
6.1.5	Allocate SMP/E CSI (Optional)	19
6.1.6	Initialize CSI zones (Optional)	19
6.1.7	Perform SMP/E RECEIVE	19
6.1.8	Allocate SMP/E Target and Distribution Libraries	19
6.1.9	Create DDDEF Entries	19
6.1.10	Perform SMP/E APPLY	20
6.1.11	Perform SMP/E ACCEPT	21
6.1.12	Run REPORT CROSSZONE	22
6.2	Activating IBM DB2 Bind Manager	22
<b>7.0</b>	<b>Notices</b>	<b>23</b>
7.1	Trademarks	24
	<b>Reader's Comments</b>	<b>25</b>

---

## Figures

1.	Program File Content	3
2.	Basic Material: Unlicensed Publications	4
3.	Basic Material: Other Unlicensed or Licensed Publications	4
4.	Publications Useful During Installation	5
5.	PSP Upgrade and Subset ID	6
6.	Component IDs	7
7.	Driving System Software Requirements	11
8.	Target System Mandatory Installation Requisites	11
9.	Total DASD Space Required by IBM DB2 Bind Manager	13
10.	Storage Requirements for IBM DB2 Bind Manager Target Libraries	14
11.	Storage Requirements for IBM DB2 Bind Manager Distribution Libraries	15
12.	SMP/E Options Subentry Values	16
13.	Sample Installation Jobs	17

---

## 1.0 Introduction

This program directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of IBM DB2 Bind Manager for z/OS. This publication refers to IBM DB2 Bind Manager for z/OS as IBM DB2 Bind Manager.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 3 identifies the basic and optional program materials and documentation for IBM DB2 Bind Manager.
- 3.0, “Program Support” on page 6 describes the IBM support available for IBM DB2 Bind Manager.
- 4.0, “Program and Service Level Information” on page 8 lists the APARs (program level) and PTFs (service level) that have been incorporated into IBM DB2 Bind Manager.
- 5.0, “Installation Requirements and Considerations” on page 10 identifies the resources and considerations that are required for installing and using IBM DB2 Bind Manager.
- 6.0, “Installation Instructions” on page 16 provides detailed installation instructions for IBM DB2 Bind Manager. It also describes the procedures for activating the functions of IBM DB2 Bind Manager, or refers to appropriate publications.

Before installing IBM DB2 Bind Manager, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this Program Directory then keep them for future reference. Section 3.2, “Preventive Service Planning” on page 6 tells you how to find any updates to the information and procedures in this Program Directory.

IBM DB2 Bind Manager is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The Program Directory that is provided in softcopy format on the CBPDO tape is identical to the hardcopy format that is provided with your order. All service and HOLDDATA for IBM DB2 Bind Manager are included on the CBPDO tape.

Do not use this program directory if you install IBM DB2 Bind Manager with a SystemPac or ServerPac. When you use these offerings, use the jobs and documentation supplied with the offering. This program directory can point you to specific sections of it as required.

---

### 1.1 IBM DB2 Bind Manager Description

DB2 Bind Manager for z/OS, V2.4 (5655-E43) allows your application programmers to safely bypass the DB2 bind process for code changes that do not alter existing SQL structures in an application. The product also provides a useful toolkit of functions for identifying and resolving various DBRM-related problems, including the ability to identify potential timestamp problems before they cause applications to fail.

## Key features of DB2 Bind Manager

- Determine whether a bind is required after an application has been precompiled and automatically reset the time stamp and bypass the bind in a majority of cases
- Handle consistency checking between an existing DBRMLIB and a DB2 subsystem (both interactively and in batch)
- Match and correlate time stamps between DBRMs, subsystems, and load modules
- Scan a load library for modules and CSECTS that contain static SQL
- Regenerate lost or missing DBRMs
- Browse DBRM contents in user-friendly format, including full Unicode support
- Remove "deadwood" from a subsystem catalog by freeing packages no longer in use by applications

This release of DB2 Bind Manager provides enhancements in two key functional areas:

- Bind Avoidance
  - Support for DB2 V9
  - Support for listing output to partitioned data set
  - Enhanced Coprocessor support
- DBRM Check Function
  - Support for DB2 V9
  - Improved performance, particularly in batch
  - New algorithms for DBRM to Load Module comparisons of connect tokens
  - Catalog Cleanup enhanced with finer granularity and enhanced filtering options
  - DBRM/Catalog timestamp correlation function helps spot potential -818 abends before they occur
  - User-friendly DBRM display (batch)

---

## 1.2 IBM DB2 Bind Manager FMID

IBM DB2 Bind Manager consists of the following FMID:

H26D240

---

## 2.0 Program Materials

An IBM program is identified by a program number and a feature number. The program number for IBM DB2 Bind Manager is 5655-E43 and its feature number is 5802.

Basic Machine-Readable Materials are materials that are supplied under the base license and feature numbers, and are required for the use of the product. Optional Machine-Readable Materials are orderable under separate feature numbers, and are not required for the product to function.

The program announcement material describes the features supported by IBM DB2 Bind Manager. Ask your IBM representative for this information if you have not already received a copy.

---

### 2.1 Basic Machine-Readable Material

The distribution medium for this program is magnetic tape or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 16 for more information about how to install the program.

Figure 1 describes the program file content for IBM DB2 Bind Manager. You can refer to the *CBPDO Memo To Users Extension* to see where the files reside on the tape.

#### Notes:

1. The data set attributes in this table must be used in the JCL of jobs that read the data sets. However, because the data sets are in IEBCOPY unloaded format, their actual attributes might be different.
2. If any RELFILEs are identified as PDSEs, ensure that SMPTLIB data sets are allocated as PDSEs.

*Figure 1 (Page 1 of 2). Program File Content*

<b>Name</b>	<b>O R G</b>	<b>R E C F M</b>	<b>L R E C L</b>	<b>BLK SIZE</b>
SMPMCS	SEQ	FB	80	6400
IBM.H26D240.F1	PDS	FB	80	8800
IBM.H26D240.F2	PDS	FB	80	8800
IBM.H26D240.F3	PDS	FB	80	8800
IBM.H26D240.F4	PDS	U	00	6144
IBM.H26D240.F5	PDS	FB	80	8800
IBM.H26D240.F6	PDS	FB	80	8800
IBM.H26D240.F7	PDS	FB	80	8800

Figure 1 (Page 2 of 2). Program File Content

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.H26D240.F8	PDS	FB	80	8800

## 2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for IBM DB2 Bind Manager.

## 2.3 Program Publications

The following sections identify the basic and optional publications for IBM DB2 Bind Manager.

### 2.3.1 Basic Program Publications

Figure 2 identifies the basic unlicensed program publications for IBM DB2 Bind Manager. One copy of each of these publications is included when you order the basic materials for IBM DB2 Bind Manager. For additional copies, contact your IBM representative.

Figure 2. Basic Material: Unlicensed Publications

Publication Title	Form Number
IBM DB2 Bind Manager for z/OS License Information	GC27-1271

Figure 3 identifies the basic unlicensed or licensed publications that are not available in hardcopy format, but are available through the internet or other media for IBM DB2 Bind Manager.

Figure 3. Basic Material: Other Unlicensed or Licensed Publications

Publication Title	Form Number	How Available
IBM DB2 Bind Manager for z/OS User's Guide	SC19-2751	<a href="http://www.ibm.com/software/data/db2imstools/library.html">http://www.ibm.com/software/data/db2imstools/library.html</a>

Publications are available in PDF and BookManager formats on CD-ROM and on DVD on the next release of software product libraries:

- *z/OS Software Products Collection, SK3T-4270*
- *z/OS and Software Products DVD Collection, SK3T-4271\**



\*requires a DVD drive in DVD-9 (single-sided, dual-layer) format

## 2.3.2 Optional Program Publications

No optional publications are provided for IBM DB2 Bind Manager.

---

## 2.4 Program Source Materials

No program source materials or viewable program listings are provided for IBM DB2 Bind Manager.

---

## 2.5 Publications Useful During Installation

You might want to use the publications listed in Figure 4 during the installation of IBM DB2 Bind Manager. To order copies, contact your IBM representative or visit the IBM Publications Center at <http://www.ibm.com/shop/publications/order>.

<i>Figure 4. Publications Useful During Installation</i>	
<b>Publication Title</b>	<b>Form Number</b>
<i>IBM SMP/E for z/OS User's Guide</i>	SA22-7773
<i>IBM SMP/E for z/OS Commands</i>	SA22-7771
<i>IBM SMP/E for z/OS Reference</i>	SA22-7772
<i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i>	GA22-7770

---

## 3.0 Program Support

This section describes the IBM support available for IBM DB2 Bind Manager.

---

### 3.1 Program Services

Contact your IBM representative for specific information about available program services.

---

### 3.2 Preventive Service Planning

Before you install IBM DB2 Bind Manager, make sure that you have reviewed the current Preventive Service Planning (PSP) information. The PSP Buckets maintain current lists (which have been identified since the package was created) of any recommended or required service for the installation of this package. This service includes software PSP information that contains HIPER and required PTFs against the base release.

Although SW, HW, and functional PSP Buckets might have overlap, review all that apply to this package to ensure that you identify all the known service that is required for your installation of this package.

If you obtained IBM DB2 Bind Manager as part of a CBPDO, HOLDDATA is included.

If the CBPDO for IBM DB2 Bind Manager is older than two weeks old by the time you install the product materials, you should contact the IBM Support Center or use S/390 SoftwareXcel to obtain the latest PSP Bucket information. You can also obtain the latest PSP Bucket information by going to the following Web site:

<https://techsupport.services.ibm.com/server/390.psp390>

For program support, access the Software Support Web site at <http://www-01.ibm.com/software/support/>.

PSP Buckets are identified by UPGRADEs, which specify product levels; and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for IBM DB2 Bind Manager are shown as follows:

<b>UPGRADE</b>	<b>SUBSET</b>	<b>Description</b>
5655E43	H26D240	DB2 Bind Manager

---

### 3.3 Statement of Support Procedures

Report any problems which you feel might be an error in the product materials to your IBM Support Center. You may be asked to gather and submit additional diagnostics to assist the IBM Support Center in their analysis.

Figure 6 on page 7 identifies the component IDs (COMPID) for IBM DB2 Bind Manager.

<i>Figure 6. Component IDs</i>			
<b>FMID</b>	<b>COMPID</b>	<b>Component Name</b>	<b>RETAIN Release</b>
H26D240	5655E4301	DB2 Bind Manager	240

---

## 4.0 Program and Service Level Information

This section identifies the program and relevant service levels of IBM DB2 Bind Manager. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

---

### 4.1 Program Level Information

The following APAR fixes against previous releases of IBM DB2 Bind Manager have been incorporated into this release. They are listed by FMID.

- FMID H26D230

PK07972	PK27051	PK51849
PK13076	PK28122	PK53274
PK13369	PK30108	PK54571
PK15340	PK30477	PK56186
PK16034	PK31177	PK57056
PK16457	PK31340	PK59870
PK16458	PK31797	PK61569
PK16460	PK33283	PK63618
PK16485	PK33820	PK65057
PK16980	PK33912	PK67279
PK17395	PK35581	PK68415
PK18294	PK35914	PK71530
PK18659	PK37313	PK74475
PK18971	PK38104	PK75210
PK19107	PK39988	PK77089
PK19556	PK40838	PK77941
PK19561	PK41059	PK81290
PK23528	PK41941	PK82498
PK23798	PK42391	PK83776
PK23945	PK42993	PK84544
PK24315	PK43748	PK89161
PK24863	PK45056	PK90131
PK25049	PK49608	PK90839
PK27023	PK51569	

---

## 4.2 Service Level Information

No PTFs against this release of IBM DB2 Bind Manager have been incorporated into the product tape.

It is highly recommended that you frequently check the IBM DB2 Bind Manager PSP Bucket for HIPER and SPECIAL Attention PTFs against all FMIDs that you must install.

---

## 5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating IBM DB2 Bind Manager. The following terminology is used:

- *Driving system*: the system used to install the program; where SMP/E executes.  
The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.
- *Target system*: the system on which the program is configured and runs.  
The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

- When you install a new level of a product that is already installed, the new level of the product will replace the old one. By installing the new level onto a separate target system, you can test the new level and keep the old one in production at the same time.
- When you install a product that shares libraries or load modules with other products, the installation can disrupt the other products. By installing the product onto a separate target system, you can assess these impacts without disrupting your production system.

---

### 5.1 Driving System Requirements

This section describes the environment of the driving system that is required to install IBM DB2 Bind Manager.

#### 5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

#### 5.1.2 Programming Requirements

Figure 7. Driving System Software Requirements				
Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in this product's shipment?
Any <b>one</b> of the following:				
5694-A01	z/OS	V01.09.00	N/A	No
5655-G52	z/OS.e	V01.09.00	N/A	No
5655-G44	IBM SMP/E for z/OS	V03.04.00	N/A	No

**Note:** Installation may require migration to new z/OS releases to be service supported. See [http://www-03.ibm.com/systems/z/os/zos/support/zos\\_eos\\_dates.html](http://www-03.ibm.com/systems/z/os/zos/support/zos_eos_dates.html).

## 5.2 Target System Requirements

This section describes the environment of the target system that is required to install and use IBM DB2 Bind Manager.

IBM DB2 Bind Manager installs in the DBS (P115) SREL.

### 5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

### 5.2.2 Programming Requirements

**5.2.2.1 Installation Requisites:** Installation requisites identify products that are required by and *must* be present on the system or products that are not required by but *should* be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product. These products are specified as PREs or REQs.

Figure 8 (Page 1 of 2). Target System Mandatory Installation Requisites				
Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in this product's shipment?
Any <b>one</b> of the following:				
5625-DB2	DB2 for z/OS	V08.01.00	N/A	No

Figure 8 (Page 2 of 2). Target System Mandatory Installation Requisites

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in this product's shipment?
5697-N29	DB2 Value Unit Edition for z/OS	V08.01.00	N/A	No
5635-DB2	DB2 for z/OS	V09.01.00	N/A	No
5697-P12	DB2 Value Unit Edition for z/OS	V09.01.00	N/A	No

**Note:** Installation may require migration to new z/OS releases to be service supported. See [http://www-03.ibm.com/systems/z/os/zos/support/zos\\_eos\\_dates.html](http://www-03.ibm.com/systems/z/os/zos/support/zos_eos_dates.html).

Conditional installation requisites identify products that are *not* required for successful installation of this product but can resolve such things as certain warning messages at installation time. These products are specified as IF REQs.

IBM DB2 Bind Manager has no conditional installation requisites.

**5.2.2.2 Operational Requisites:** Operational requisites are products that are required by and *must* be present on the system or products that are not required by but *should* be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions. These products are specified as PREs or REQs.

IBM DB2 Bind Manager has no mandatory operational requisites.

Conditional operational requisites identify products that are *not* required for this product to operate its basic functions but are required at run time for this product to operate specific functions. These products are specified as IF REQs.

IBM DB2 Bind Manager has no conditional operational requisites.

**5.2.2.3 Toleration/Coexistence Requisites:** Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

IBM DB2 Bind Manager has no toleration/coexistence requisites.



**5.2.2.4 Incompatibility (Negative) Requisites:** Negative requisites identify products that must *not* be installed on the same system as this product.

IBM DB2 Bind Manager has no negative requisites.

## 5.2.3 DASD Storage Requirements

IBM DB2 Bind Manager libraries can reside on all supported DASD types.

Figure 9 lists the total space that is required for each type of library.

Library Type	Total Space Required in 3390 Trks
Target	66 tracks
Distribution	59 tracks

### Notes:

1. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.
2. Abbreviations used for data set types are shown as follows.
  - U** Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
  - S** Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
  - E** Existing shared data set, used by this product and other products. This data set is *not* allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.8, "Allocate SMP/E Target and Distribution Libraries" on page 19.

3. All target and distribution libraries listed have the following attributes:
  - The default name of the data set may be changed.
  - The default block size of the data set may be changed.
  - The data set may be merged with another data set that has equivalent characteristics.
  - The data set may be either a PDS or a PDSE.
4. All target libraries listed have the following attributes:
  - These data sets can be SMS-managed, but they are not required to be SMS-managed.
  - These data sets are not required to reside on the IPL volume.
  - The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.
5. All target libraries that are listed and contain load modules have the following attributes:
  - These data sets can be in the LPA, but they are not required to be in the LPA.
  - These data sets can be in the LNKLIST.
  - These data sets are not required to be APF-authorized.

The following figures describe the target and distribution libraries required to install IBM DB2 Bind Manager. The storage requirements of IBM DB2 Bind Manager must be added to the storage required by other programs having data in the same library.

**Note:** The data in these tables should be used when determining which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

*Figure 10. Storage Requirements for IBM DB2 Bind Manager Target Libraries*

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SBNDBASE	SAMP	Any	U	PDS	FB	80	3	2
SBNDCLST	CLIST	Any	U	PDS	FB	80	2	2
SBNDDBRM	MACRO	Any	U	PDS	FB	80	6	5
SBNDLOAD	LMOD	Any	U	PDS	U	0	38	5
SBNDMENU	MSG	Any	U	PDS	FB	80	2	2
SBNDPENU	PNL	Any	U	PDS	FB	80	8	10
SBNDSAMP	SAMP	Any	U	PDS	FB	80	7	5

Figure 11. Storage Requirements for IBM DB2 Bind Manager Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
ABNDBASE	U	PDS	FB	80	3	2
ABNDCLST	U	PDS	FB	80	2	2
ABNDDBRM	U	PDS	FB	80	6	5
ABNDMENU	U	PDS	FB	80	2	2
ABNDNCAL	U	PDS	U	0	31	10
ABNDPENU	U	PDS	FB	80	8	10
ABNDSAMP	U	PDS	FB	80	7	5

### 5.3 FMIDs Deleted

Installing IBM DB2 Bind Manager might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install IBM DB2 Bind Manager into separate SMP/E target and distribution zones.

**Note:** These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, see the SMP/E manuals for instructions.

### 5.4 Special Considerations

IBM DB2 Bind Manager has no special considerations for the target system.

---

## 6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of IBM DB2 Bind Manager.

Please note the following:

- If you want to install IBM DB2 Bind Manager into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.
- You can use the SMP/E dialogs instead of the sample jobs to accomplish the SMP/E installation steps.

---

### 6.1 Installing IBM DB2 Bind Manager

#### 6.1.1 SMP/E Considerations for Installing IBM DB2 Bind Manager

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of IBM DB2 Bind Manager.

#### 6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 12. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

*Figure 12. SMP/E Options Subentry Values*

Subentry	Value	Comment
DSSPACE	(200,200,500)	3390 DASD tracks
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

### 6.1.3 SMP/E CALLLIBS Processing

IBM DB2 Bind Manager uses the CALLLIBS function that is provided in SMP/E to resolve external references during installation. When IBM DB2 Bind Manager is installed, ensure that DDDEFs exist for the following libraries:

- SCEELKED
- SDSNLOAD

**Note:** CALLLIBS uses the previous DDDEFs only to resolve the link-edit for IBM DB2 Bind Manager. These data sets are not updated during the installation of IBM DB2 Bind Manager.

### 6.1.4 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install IBM DB2 Bind Manager:

<i>Figure 13. Sample Installation Jobs</i>			
Job Name	Job Type	Description	RELFILE
BNDALA	SMP/E	Sample job to allocate and initialize a new SMP/E CSI data set <b>(Optional)</b>	IBM.H26D240.F2
BNDALB	SMP/E	Sample job to allocate SMP/E data sets <b>(Optional)</b>	IBM.H26D240.F2
BNDRECEV	RECEIVE	Sample RECEIVE job	IBM.H26D240.F2
BNDALLOC	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.H26D240.F2
BNDDDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.H26D240.F2
BNDAPPLY	APPLY	Sample APPLY job	IBM.H26D240.F2
BNDACCEP	ACCEPT	Sample ACCEPT job	IBM.H26D240.F2

You can access the sample installation jobs by performing an SMP/E RECEIVE and then copying the jobs from the relfiles to a work data set for editing and submission. See Figure 13 to find the appropriate relfile data set.

You can also copy the sample installation jobs from the tape or product files by submitting the following job. Depending on your distribution medium, use either the //TAPEIN or the //FILEIN DD statement and comment out or delete the other statement. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//*****
//* Make the //TAPEIN DD statement below active if you install*
//* from a CBPDO tape by uncommenting the DD statement below. *
//*****
```

```

/*TAPEIN DD DSN=IBM.H26D240.F2,UNIT=tunit,
/* VOL=SER=volser,LABEL=(x,SL),
/* DISP=(OLD,KEEP)
/*****
/* Make the //TAPEIN DD statement below active if you install*
/* from a product tape received outside the CBPDO process *
/* (using the optional SMP/E RECEIVE job) by uncommenting *
/* the DD statement below. *
/*****
/*TAPEIN DD DSN=IBM.H26D240.F2,UNIT=tunit,
/* VOL=SER=26D240,LABEL=(3,SL),
/* DISP=(OLD,KEEP)
/*****
/* Make the //FILEIN DD statement below active for *
/* downloaded DASD files. *
/*****
/*FILEIN DD DSN=IBM.H26D240.F2,UNIT=SYSALLDA,DISP=SHR,
/* VOL=SER=filevol
//OUT DD DSNAME=jcl-library-name,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,
// SPACE=(TRK,(20,10,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
/*

```

In the sample above, update the statements as noted below:

If using TAPEIN:

**tunit** is the unit address where the product tape is mounted

**volser** is the volume serial matching the product tape

**x** is the tape file number where the data set name is on the tape

Refer to the documentation provided by CBPDO to see where IBM.H26D240.F2 is on the tape.

If using FILEIN

**filevol** is the volume serial of the DASD device where the downloaded files reside.

OUT

**jcl-library-name** is the name of the output data set where the sample jobs will be stored

**dasdvol** is the volume serial of the DASD device where the output data set will reside

SYSIN

**xxxxIN** is either TAPEIN or FILEIN depending on your input DD statement.

## 6.1.5 Allocate SMP/E CSI (Optional)

If you are using an existing CSI, do not execute this job.

If you are allocating a new SMP/E data set for this install, edit, and submit sample job BNDALA to allocate the SMP/E data set for IBM DB2 Bind Manager. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.6 Initialize CSI zones (Optional)

Edit and submit sample job BNDALB to initialize SMP/E zones for IBM DB2 Bind Manager. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.7 Perform SMP/E RECEIVE

If you have obtained IBM DB2 Bind Manager as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the IBM DB2 Bind Manager FMIDs, service, and HOLDDATA that are included on the CBPDO tape. For more information, see the documentation that is included in the CBPDO.

You can also choose to edit and submit sample job BNDRECEV to perform the SMP/E RECEIVE for IBM DB2 Bind Manager. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.8 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job BNDALLOC to allocate the SMP/E target distribution libraries for IBM DB2 Bind Manager. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.9 Create DDDEF Entries

Edit and submit sample job BNDDDEF to create DDDEF entries for the SMP/E target and distribution libraries for IBM DB2 Bind Manager. Consult the instructions in the sample job for more information.

**Expected Return Codes and Messages:** You will receive a return code of 0 if this job runs correctly.

## 6.1.10 Perform SMP/E APPLY

1. Ensure that you have the latest HOLDDATA; then edit and submit sample job BNDAPPLY to perform an SMP/E APPLY CHECK for IBM DB2 Bind Manager. Consult the instructions in the sample job for more information.

HOLDDATA introduces ERROR HOLDS against FMIDs for HIPER APARs. Before the installation, ensure that you have the latest HOLDDATA, which is available through several different portals, including <http://service.software.ibm.com/holddata/390holddata.html>. Install the FMIDs regardless of the status of unresolved HIPERs. However, don't deploy the software until the unresolved HIPERs are analyzed to determine applicability.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. This is because the SMP/E root cause analysis identifies the cause only of *errors* and not of *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here are two methods to install FMIDs when ++HOLDS for HIPERs exist for the FMIDs that you install:

- a. To ensure that all recommended and critical service is installed with the FMIDs, if you are using SMP/E 3.5 or higher and have received the latest HOLDDATA, add the FIXCAT operand to the APPLY command as shown below. If you are using a prior release of SMP/E, add the SOURCEID(HIPER,RSU\*) operand to the APPLY command.

```
If using SMP/E V3.5 or higher:  
APPLY S(fmid,fmid,...)  
FORFMID(fmid,fmid,...)  
SOURCEID(RSU*)  
FIXCAT(IBM.ProductInstall-RequiredService)  
GROUPEXTEND .
```

```
If using SMP/E V3.4 or prior:  
APPLY S(fmid,fmid,...)  
FORFMID(fmid,fmid,...)  
SOURCEID(HIPER,RSU*)  
GROUPEXTEND .
```

Some HIPER APARs might not have PTFs available yet. You have to analyze the symptom flags to determine if you want to bypass the specific ERROR HOLDS and continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixes available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

- b. To install the FMIDs without regard for the HIPERs, you can add a BYPASS(HOLDCLASS(HIPER)) operand to the APPLY command. In this way, you can install FMIDs even though HIPER ERROR HOLDS against them still exist. Only the HIPER ERROR HOLDS are bypassed. After the FMIDs are installed, run the SMP/E REPORT ERRSYSMODS command to identify missing HIPER maintenance.



```
APPLY S(fmid,fmid,...)
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER)) .
..any other parameters documented in the program directory
```

This method is the quicker of the two, but requires subsequent review of the REPORT ERRSYSMODS to investigate any HIPERs. If you are running SMP/E V3.5 or higher and have received the latest HOLDDATA, you can also choose to run REPORT MISSINGFIX for Fix Category IBM.ProductInstall-RequiredService to investigate missing recommended service.

If you bypass HOLDS during the installation of the FMIDs because PTFs are not yet available, you can make yourself notified when the PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

2. After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

**Note:** The GROUPEXTEND operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

**Expected Return Codes and Messages from APPLY CHECK:** You will receive a return code of 0 or 4 if this job runs correctly.

You may receive the following message code which does not affect the product installation:  
GIM23903W

**Expected Return Codes and Messages from APPLY:** You will receive a return code of 0 or 4 if this job runs correctly.

You may receive the following message code which does not affect the product installation:  
GIM23903W

### 6.1.11 Perform SMP/E ACCEPT

Edit and submit sample job BNDACCEP to perform an SMP/E ACCEPT CHECK for IBM DB2 Bind Manager. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. This is because the SMP/E root cause analysis identifies the cause of only *errors* but not *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E manuals.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

**Note:** The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

**Expected Return Codes and Messages from ACCEPT CHECK:** You will receive a return code of 0 if this job runs correctly.

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

**Expected Return Codes and Messages from ACCEPT:** You will receive a return code of 0 if this job runs correctly.

## 6.1.12 Run REPORT CROSSZONE

The SMP/E REPORT CROSSZONE command identifies requisites for products that are installed in separate zones. This command also creates APPLY and ACCEPT commands in the SMPPUNCH data set. You can use the APPLY and ACCEPT commands to install those cross-zone requisites that the SMP/E REPORT CROSSZONE command identifies.

After you install IBM DB2 Bind Manager, it is recommended that you run REPORT CROSSZONE against the new or updated target and distribution zones. REPORT CROSSZONE requires a global zone with ZONEINDEX entries that describe all the target and distribution libraries to be reported on.

For more information about REPORT CROSSZONE, see the SMP/E manuals.

---

## 6.2 Activating IBM DB2 Bind Manager

The publication *IBM DB2 Bind Manager for z/OS User's Guide, SC19-2751* contains the necessary information to customize and use IBM DB2 Bind Manager.

---

## 7.0 Notices

References in this document to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not intended to state or imply that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe on any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, is the user's responsibility.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, New York 10504-1785  
USA

For online versions of this book, we authorize you to:

- Copy, modify, and print the documentation contained on the media, for use within your enterprise, provided you reproduce the copyright notice, all warning statements, and other required statements on each copy or partial copy.
- Transfer the original unaltered copy of the documentation when you transfer the related IBM product (which may be either machines you own, or programs, if the program's license terms permit a transfer). You must, at the same time, destroy all other copies of the documentation.

You are responsible for payment of any taxes, including personal property taxes, resulting from this authorization.

THERE ARE NO WARRANTIES, EXPRESS OR IMPLIED, INCLUDING THE WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

Some jurisdictions do not allow the exclusion of implied warranties, so the above exclusion may not apply to you.

Your failure to comply with the terms above terminates this authorization. Upon termination, you must destroy your machine readable documentation.

---

## 7.1 Trademarks

IBM, the IBM logo, and [ibm.com](http://ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

The following terms are trademarks of other companies as follows:

HLS                   HLS Technologies, Inc.

# Reader's Comments

## Program Directory for IBM DB2 Bind Manager for z/OS, November 2009

You may use this form to comment about this document, its organization, or subject matter with the understanding that IBM may use or distribute whatever information you supply in any way it believes appropriate without incurring any obligation to you.

For each of the topics below please indicate your satisfaction level by circling your choice from the rating scale. If a statement does not apply, please circle N.

RATING SCALE					
very satisfied	<----->	very dissatisfied	not applicable		
1	2 3 4	5	N		

	Satisfaction					
Ease of product installation	1	2	3	4	5	N
Contents of Program Directory	1	2	3	4	5	N
Installation Verification Programs	1	2	3	4	5	N
Time to install the product	1	2	3	4	5	N
Readability and organization of Program Directory tasks	1	2	3	4	5	N
Necessity of all installation tasks	1	2	3	4	5	N
Accuracy of the definition of the installation tasks	1	2	3	4	5	N
Technical level of the installation tasks	1	2	3	4	5	N
Ease of getting the system into production after installation	1	2	3	4	5	N

How did you order this product?

- CBPDO
- CustomPac
- ServerPac
- Independent
- Other

Is this the first time your organization has installed this product?

- Yes
- No

Were the people who did the installation experienced with the installation of z/OS products?

- Yes



International Business Machines Corporation  
Reader's Comments  
Department DTX/E269  
555 Bailey Avenue  
San Jose, California  
USA  
95141-9989

E-Mail: [comments@us.ibm.com](mailto:comments@us.ibm.com)



Printed in USA

G110-8416-04

