



**Program Directory for
IBM Tivoli Advanced Audit for DFSMSHsm**

2.6.0

Program Number 5698-B12

for Use with
z/OS

Document Date: October 2022

GI11-8939-05

Note

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 29.

Contents

1.0 Introduction	1
1.1 Advanced Audit for DFSMSHsm Description	2
1.2 Advanced Audit for DFSMSHsm FMIDs	2
2.0 Program Materials	3
2.1 Basic Machine-Readable Material	3
2.2 Program Publications	3
2.3 Program Source Materials	4
2.4 Publications Useful During Installation	4
3.0 Program Support	5
3.1 Program Services	5
3.2 Preventive Service Planning	5
3.3 Statement of Support Procedures	6
4.0 Program and Service Level Information	7
4.1 Program Level Information	7
4.2 Service Level Information	7
5.0 Installation Requirements and Considerations	8
5.1 Driving System Requirements	8
5.1.1 Machine Requirements	8
5.1.2 Programming Requirements	9
5.2 Target System Requirements	9
5.2.1 Machine Requirements	9
5.2.2 Programming Requirements	9
5.2.2.1 Installation Requisites	9
5.2.2.2 Operational Requisites	10
5.2.2.3 Toleration/Coexistence Requisites	11
5.2.2.4 Incompatibility (Negative) Requisites	11
5.2.3 DASD Storage Requirements	11
5.2.4 DASD Storage Requirements by FMID	15
5.3 FMIDs Deleted	17
5.4 Special Considerations	17
6.0 Installation Instructions	19
6.1 Installing Advanced Audit for DFSMSHsm	19
6.1.1 SMP/E Considerations for Installing Advanced Audit for DFSMSHsm	19
6.1.2 SMP/E Options Subentry Values	19
6.1.3 SMP/E CALLLIBS Processing	20
6.1.4 Installation Job Generator Utility	20
6.1.4.1 Introduction to the Job Generator	20

6.1.4.2	Product Selection	21
6.1.4.3	Installing into an existing CSI	21
6.1.4.4	Job Generator - Update Command	22
6.1.5	Sample Jobs	22
6.1.6	Create New SMP/E Support Files - Optional	24
6.1.7	Create New SMP/E CSI - Optional	24
6.1.8	Allocate SMP/E Target and Distribution Libraries	24
6.1.9	Create DDDEF Entries	25
6.1.10	Perform SMP/E RECEIVE	25
6.1.11	Perform SMP/E APPLY	25
6.1.12	Perform SMP/E ACCEPT	27
6.2	Activating Advanced Audit for DFSMSHsm	28
7.0	Notices	29
7.1	Trademarks	29
	Contacting IBM Software Support	30

Figures

1.	Basic Material: Unlicensed Publications	3
2.	Publications Useful During Installation	4
3.	PSP Upgrade and Subset ID	6
4.	Component IDs	6
5.	Driving System Software Requirements	9
6.	Target System Mandatory Installation Requisites	10
7.	Target System Mandatory Operational Requisites	10
8.	Target System Conditional Operational Requisites	11
9.	Total DASD Space Required by Advanced Audit for DFSMSHsm	11
10.	Storage Requirements for SMP/E Work Data Sets	13
11.	Storage Requirements for SMP/E Data Sets	13
12.	Storage Requirements for Advanced Audit for DFSMSHsm Target Libraries	14
13.	Storage Requirements for Advanced Audit for DFSMSHsm Distribution Libraries	14
14.	Storage Requirements for HAKD260 Libraries	15
15.	Storage Requirements for HKRG260 Libraries	16
16.	SMP/E Options Subentry Values	19
17.	Sample Installation Jobs for base function	22
18.	Sample Installation Jobs for base and monitoring agent functions	23

1.0 Introduction

This program directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of IBM Tivoli Advanced Audit for DFSMSHsm. This publication refers to IBM Tivoli Advanced Audit for DFSMSHsm as Advanced Audit for DFSMSHsm.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 3 identifies the basic program materials and documentation for Advanced Audit for DFSMSHsm.
- 3.0, “Program Support” on page 5 describes the IBM support available for Advanced Audit for DFSMSHsm.
- 4.0, “Program and Service Level Information” on page 7 lists the APARs (program level) and PTFs (service level) that have been incorporated into Advanced Audit for DFSMSHsm.
- 5.0, “Installation Requirements and Considerations” on page 8 identifies the resources and considerations that are required for installing and using Advanced Audit for DFSMSHsm.
- 6.0, “Installation Instructions” on page 19 provides detailed installation instructions for Advanced Audit for DFSMSHsm. It also describes the procedures for activating the functions of Advanced Audit for DFSMSHsm, or refers to appropriate publications.

Before installing Advanced Audit for DFSMSHsm, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this program directory; after which, keep the documents for your reference. Section 3.2, “Preventive Service Planning” on page 5 tells you how to find any updates to the information and procedures in this program directory.

Advanced Audit for DFSMSHsm is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The program directory that is provided in softcopy format on the CBPDO is identical to the hardcopy format if one was included with your order. All service and HOLDDATA for Advanced Audit for DFSMSHsm are included on the CBPDO.

Do not use this program directory if you install Advanced Audit for DFSMSHsm with a ServerPac. When you use one of those offerings, use the jobs and documentation supplied with the offering. The offering will point you to specific sections of this program directory as needed.

1.1 Advanced Audit for DFSMSHsm Description

Advanced Audit for DFSMSHsm can help storage administrators maintain healthy metadata environments and prevent temporary or permanent loss of data access. It provides extremely fast and accurate audits and diagnostics, as well as automated corrective actions to help resolve error conditions.

Using the Tivoli Enterprise Portal (TEP) interface, you can see Data Facility Storage Management Subsystem (DFSMS) audit health status at a glance, which can help ensure that the z/OS storage environment is operating efficiently and effectively. Automated alerts notify users when problems need attention and built-in expert advice, coupled with automated corrective actions, helps make it simple and practical to maintain the health of the critical DFSMS hierarchical storage management (HSM) environment.

Tivoli Advanced Audit for DFSMSHsm offers auditing reports.

- Errors cost report - Helps estimate resource cost wasted daily by DFSMSHsm on errors within the control data sets (CDSs).
- Migration data set audit - Reports DFSMSHsm managed data that is continuously thrashing, likely caused by human error or incorrect management definition.
- Storage management subsystem (SMS) volumes audit - Reports SMS managed volumes that are above the defined SMS threshold limit.
- Storage group audit - Reports storage groups that are above the defined SMS threshold limit.
- Migrated data sets needing backup - Reports migrated data sets not having a valid HSM backup.
- VSAM data sets needing backup - Reports VSAM data sets with backup data greater than two days past the last change date.
- Submission of audits from within the product - Audits can now be submitted from within the product under the Administration Panel.
- DFSMS ACS audit - Gathers information on DFSMS MGMTCLAS assignments and compares them against the DFSMS ACS routines to identify discrepancies.

Advanced Audit for DFSMSHsm is part of the IBM Tivoli System z storage management offering portfolio that provides a comprehensive z/OS management capability.

1.2 Advanced Audit for DFSMSHsm FMIDs

Advanced Audit for DFSMSHsm consists of the following FMIDs:

HAKD260
HKRG260

2.0 Program Materials

An IBM program is identified by a program number. The program number for Advanced Audit for DFSMSHsm is 5698-B12.

Basic Machine-Readable Materials are materials that are supplied under the base license and are required for the use of the product.

The program announcement material describes the features supported by Advanced Audit for DFSMSHsm. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is physical media or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 19 for more information about how to install the program.

You can find information about the physical media for the basic machine-readable materials for Advanced Audit for DFSMSHsm in the *CBPDO Memo To Users Extension*.

2.2 Program Publications

The following sections identify the basic publications for Advanced Audit for DFSMSHsm.

Figure 1 identifies the basic unlicensed publications for Advanced Audit for DFSMSHsm.

The unlicensed documentation for Advanced Audit for DFSMSHsm can be found in the IBM Documentation at: http://www.ibm.com/support/knowledgecenter/SS4J89_2.6.0/com.ibm.advaud.doc/welcome.html

Publication Title
<i>Advanced Audit for DFSMSHsm: User's Guide</i>
<i>Monitoring Agent Planning and Configuration Guide</i>
<i>Monitoring Agent User's Guide</i>

Prior to installing Advanced Audit for DFSMSHsm, IBM recommends you review the OMEGAMON shared documentation 6.3.0 Fix Pack 2 and above, **First time deployment guide (FTU installation and tasks)**, the Planning, Configuring, and Configuration Manager topics for general planning and configuration flow. This documentation focuses on the things you will need to know for a successful installation and configuration of this product.

The OMEGAMON shared documentation, and other IBM product documentation can be found at the IBM Documentation URL listed below:

<https://www.ibm.com/docs/en/om-shared>

The **First time deployment guide (FTU installation and configuration tasks)** documentation can be found on the IBM Documentation website at:

<https://www.ibm.com/docs/en/om-shared?topic=guide-ftu-installation-configuration-tasks>

Refer to the *Program Directory for IBM Tivoli Management Services on z/OS* (GI11-4105) for a complete documentation list and installation instructions for its product components.

2.3 Program Source Materials

No program source materials or viewable program listings are provided for Advanced Audit for DFSMSHsm.

2.4 Publications Useful During Installation

You might want to use the publications listed in Figure 2 during the installation of Advanced Audit for DFSMSHsm.

Publication Title	Form Number
<i>IBM SMP/E for z/OS User's Guide</i>	SA23-2277
<i>IBM SMP/E for z/OS Commands</i>	SA23-2275
<i>IBM SMP/E for z/OS Reference</i>	SA23-2276
<i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i>	GA32-0883

Note: These publications can be found in IBM Documentation. Use a web browser with internet access to refer to: <https://www.ibm.com/docs/en/zos/2.5.0?topic=zos-smpe>

3.0 Program Support

This section describes the IBM support available for Advanced Audit for DFSMSHsm.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before you install Advanced Audit for DFSMSHsm, make sure that you have reviewed the current Preventive Service Planning (PSP) information. Review the PSP Bucket for General Information, Installation Documentation, and the Cross Product Dependencies sections. For the Recommended Service section, instead of reviewing the PSP Bucket, it is recommended you use the IBM.PRODUCTINSTALL-REQUIREDSERVICE fix category in SMP/E to ensure you have all the recommended service installed. Use the **FIXCAT(IBM.PRODUCTINSTALL-REQUIREDSERVICE)** operand on the **APPLY CHECK** command. See 6.1.11, "Perform SMP/E APPLY" on page 25 for a sample APPLY command.

If you obtained Advanced Audit for DFSMSHsm as part of a CBPDO, HOLDDATA is included.

If the CBPDO for Advanced Audit for DFSMSHsm is older than two weeks by the time you install the product materials, you can obtain the latest PSP Bucket information by going to the following website:

<https://esupport.ibm.com/customercare/psearch/search?domain=psp>

You can also use S/390 SoftwareXcel or contact the IBM Support Center to obtain the latest PSP Bucket information.

For program support, access the Software Support Website at **<https://www.ibm.com/mysupport/>**.

PSP Buckets are identified by UPGRADEs, which specify product levels; and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for Advanced Audit for DFSMSHsm are included in Figure 3 on page 6.

This product has an installation requirement for IBM Tivoli Management Services on z/OS 6.3.0 (5698-A79), so you should review the PSP buckets for it as well. Refer to the *Program Directory for IBM Tivoli Management Services on z/OS* (GI11-4105) for those UPGRADE and SUBSET values.

<i>Figure 3. PSP Upgrade and Subset ID</i>		
UPGRADE	SUBSET	Description
AA4DFSMSHSM	HAKD260	Advanced Audit for DFSMSHsm base
	HKRG260	Advanced Audit for DFSMSHsm monitoring agent

3.3 Statement of Support Procedures

Report any problems which you feel might be an error in the product materials to your IBM Support Center. You may be asked to gather and submit additional diagnostics to assist the IBM Support Center in their analysis.

Figure 4 identifies the component IDs (COMPID) for Advanced Audit for DFSMSHsm.

<i>Figure 4. Component IDs</i>			
FMID	COMPID	Component Name	RETAIN Release
HAKD260	5698A9600	Advanced Audit for DFSMSHsm base	260
HKRG260	5698A9601	Advanced Audit for DFSMSHsm monitoring agent	260

4.0 Program and Service Level Information

This section identifies the program and relevant service levels of Advanced Audit for DFSMSHsm. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

4.1 Program Level Information

The following APAR fixes against previous releases of components included with Advanced Audit for DFSMSHsm have been incorporated into this release. They are listed by FMID.

- FMID HAKD260

PI06207 PI06209 PI06217 PI06218 PI06382 PI08494 PI12000 PI18053
PI18075 PI18084 PI18086 PI18090 PI18160 PI18204 PI18206 PI24197
PI26001 PI26002 PI26923 PI29775 PI29783 PI32030 PI32109 PI37465
PI37472 PI37476 PI43602 PM96931 PM96932

- FMID HKRG260

PI06030 PI16573 PI20924

4.2 Service Level Information

No PTFs against this release of Advanced Audit for DFSMSHsm have been incorporated into the product package.

Frequently check the Advanced Audit for DFSMSHsm PSP Bucket for HIPER and SPECIAL attention PTFs against all FMIDs that you must install. You can also receive the latest HOLDDATA, then add the **FIXCAT(IBM.PRODUCTINSTALL-REQUIRESERVICE)** operand on your **APPLY CHECK** command. This will allow you to review the recommended and critical service that should be installed with your FMIDs.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating Advanced Audit for DFSMSHsm. The following terminology is used:

- *Driving system*: the system on which SMP/E is executed to install the program.
The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.
- *Target system*: the system on which the program is configured and run.
The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

- When you install a new level of a product that is already installed, the new level of the product will replace the old one. By installing the new level onto a separate target system, you can test the new level and keep the old one in production at the same time.
- When you install a product that shares libraries or load modules with other products, the installation can disrupt the other products. By installing the product onto a separate target system, you can assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install Advanced Audit for DFSMSHsm.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

Figure 5. Driving System Software Requirements

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	2.4 or higher	N/A	No

Note: SMP/E is a requirement for Installation and is an element of z/OS.

Note: Installation might require migration to new z/OS releases to be service supported. See <https://www.ibm.com/support/lifecycle/>.

5.2 Target System Requirements

This section describes the environment of the target system required to install and use Advanced Audit for DFSMSHsm.

Advanced Audit for DFSMSHsm installs in the z/OS (Z038) SREL.

5.2.1 Machine Requirements

The target system can run in any hardware environment that supports the required software.

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites

Installation requisites identify products that are required and *must* be present on the system or products that are not required but *should* be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product. These products are specified as PREs or REQs.

Figure 6. Target System Mandatory Installation Requisites

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
5650-ZOS	z/OS	2.4 or higher	N/A	No
5698-A79	IBM Tivoli Management Services on z/OS	6.3.0	N/A	No

The installation of the Advanced Audit for DFSMSHsm monitoring agent, HKRG260 FMID, requires the Tivoli Enterprise Monitoring Server on z/OS be present or installed in the CSI. Refer to the *Program Directory for IBM Tivoli Management Services on z/OS* (GI11-4105) for a complete list of publications and installation instructions for its product components.

Note: Installation might require migration to new releases to obtain support. See <https://www.ibm.com/support/lifecycle/>

Conditional installation requisites identify products that are *not* required for successful installation of this product but can resolve such things as certain warning messages at installation time. These products are specified as IF REQs.

Advanced Audit for DFSMSHsm has no conditional installation requisites.

5.2.2.2 Operational Requisites

Operational requisites are products that are required and *must* be present on the system or products that are not required but *should* be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions.

Figure 7. Target System Mandatory Operational Requisites

Program Number	Product Name and Minimum VRM/Service Level
5650-ZOS	z/OS 2.4 or higher

Note: Installation might require migration to new releases to obtain support. See <https://www.ibm.com/support/lifecycle/>

Conditional operational requisites identify products that are *not* required for this product to operate its basic functions but are required at run time for this product to operate specific functions. These products are specified as IF REQs.

The use of the monitoring agent component with a Tivoli Enterprise Monitoring Server on z/OS requires the monitoring server be installed and operational.

<i>Figure 8. Target System Conditional Operational Requisites</i>	
Program Number	Product Name and Minimum VRM/Service Level
5698-A79	IBM Tivoli Management Services on z/OS 6.3.0 or higher

Note: Installation might require migration to new releases to obtain support. See <https://www.ibm.com/support/lifecycle/>

5.2.2.3 Toleration/Coexistence Requisites

Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

Advanced Audit for DFSMShsm has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites

Negative requisites identify products that must *not* be installed on the same system as this product.

Advanced Audit for DFSMShsm has no negative requisites.

5.2.3 DASD Storage Requirements

Advanced Audit for DFSMShsm libraries can reside on all supported DASD types.

Figure 9 lists the total space that is required for each type of library.

<i>Figure 9. Total DASD Space Required by Advanced Audit for DFSMShsm</i>	
Library Type	Total Space Required in 3390 Trks
Target	323
Distribution	322

Notes:

1. If you are installing into an existing environment that has the data sets in Figure 12 on page 14 and Figure 13 on page 14 already allocated, ensure sufficient disk space and directory blocks are available to support the requirement listed. This might require you to reallocate some data sets to avoid x37 abends.

2. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.
3. Abbreviations used for data set types are shown as follows.

- U** Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
- S** Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- E** Existing shared data set, used by this product and other products. This data set is *not* allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.8, "Allocate SMP/E Target and Distribution Libraries" on page 24.

4. All target and distribution libraries listed have the following attributes:
 - The default name of the data set can not be changed.
 - The default block size of the data set can be changed.
 - The data set can not be merged with another data set that has equivalent characteristics.
 - The data set can be either a PDS or a PDSE, with some exceptions. If the value in the "ORG" column specifies "PDS", the data set must be a PDS. If the value in "DIR Blks" column specifies "N/A", the data set must be a PDSE.
5. All target libraries listed have the following attributes:
 - These data sets can be SMS-managed, but they are not required to be SMS-managed.
 - These data sets are not required to reside on the IPL volume.
 - The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.
6. All target libraries that are listed and contain load modules have the following attributes:
 - These data sets can not be in the LPA, with some exceptions. If the data set should be placed in the LPA, see the Special Considerations section below.
 - These data sets can be in the LNKLST except for TKANMODR and TKANMODS.
 - These data sets are not required to be APF-authorized, with some exceptions. If the data set must be APF-authorized, see the Special Considerations section below.

If you are installing into an existing environment, ensure the values used for the SMP/E work data sets reflect the minimum values shown in Figure 10 on page 13. Check the corresponding DDDEF entries in all zones because use of values lower than these can result in failures in the installation process. Refer to the SMP/E manuals for instructions on updating DDDEF entries.

Figure 10. Storage Requirements for SMP/E Work Data Sets

Library DDNAME	T Y P E	O R G A N I Z A T I O N	R E C O R D S	L R E C O R D S	Prim No. of 3390 Trks	Sec No. of 3390 Trks	No. of DIR Blks
SMPWRK1	E	PDS	FB	80	150	150	220
SMPWRK2	E	PDS	FB	80	150	150	220
SMPWRK3	E	PDS	FB	80	300	600	1320
SMPWRK4	E	PDS	FB	80	150	150	220
SMPWRK6	E	PDS	FB	80	300	1500	660
SYSUT1	E	SEQ	--	--	75	75	0
SYSUT2	E	SEQ	--	--	75	75	0
SYSUT3	E	SEQ	--	--	75	75	0
SYSUT4	E	SEQ	--	--	75	75	0

If you are installing into an existing environment, ensure the current SMP/E support dataset allocations reflect the minimum values shown in Figure 11. Check the space and directory block allocation and reallocate the data sets, if necessary.

Figure 11. Storage Requirements for SMP/E Data Sets

Library DDNAME	T Y P E	O R G A N I Z A T I O N	R E C O R D S	L R E C O R D S	Prim No. of 3390 Trks	Sec No. of 3390 Trks	No. of DIR Blks
SMPLTS	E	PDSE	U	0	15	150	N/A
SMPMTS	E	PDS	FB	80	15	150	220
SMPPTS	E	PDSE	FB	80	300	1500	N/A
SMPSCDS	E	PDS	FB	80	15	150	220
SMPSTS	E	PDS	FB	80	15	150	220

Figure 12 on page 14 and Figure 13 on page 14 describe the target and distribution libraries that will be allocated by this product's install jobs or that will be required for installation. The space requirements reflect what is specified in the allocation job or the space that this product will require in existing libraries.

Additional tables are provided to show the specific space required for libraries that are used by each FMID. See 5.2.4, "DASD Storage Requirements by FMID" on page 15 for more information.

The storage requirements of Advanced Audit for DFSMSHsm must be added to the storage required by other programs having data in the same library or path.

Figure 12. Storage Requirements for Advanced Audit for DFSMSHsm Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SAKDCLST	CLIST	Any	U	PDS	FB	80	8	44
SAKDCNTL	Data	Any	U	PDS	FB	80	41	220
SAKDJCL	Data	Any	U	PDS	FB	80	16	44
SAKDLOAD	LMOD	Any	U	PDS	U	0	129	132
SAKDMSGGS	Data	Any	U	PDS	FB	80	19	44
SAKDPARM	Parm	Any	U	PDS	FB	80	3	44
SAKDPENU	Panel	Any	U	PDS	FB	80	4	44
SAKDPKGI	Data	Any	U	PDS	FB	80	14	44
TKANCUS	CLIST	Any	E	PDS	FB	80	12	8
TKANDATV	Data	Any	E	PDS	VB	6160	27	2
TKANMOD	LMOD	Any	E	PDS	U	0	8	1
TKANMODL	LMOD	Any	E	PDS	U	0	36	1
TKANPAR	Parm	Any	E	PDS	FB	80	3	1
TKANPKGI	Data	Any	E	PDS	FB	80	3	2

Figure 13 (Page 1 of 2). Storage Requirements for Advanced Audit for DFSMSHsm Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
AAKDCLST	U	PDS	FB	80	8	44
AAKDCNTL	U	PDS	FB	80	41	220
AAKDJCL	U	PDS	FB	80	16	44
AAKDLOAD	U	PDS	U	0	129	132
AAKDMSGGS	U	PDS	FB	80	19	44

Figure 13 (Page 2 of 2). Storage Requirements for Advanced Audit for DFSMSHsm Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
AAKDPARM	U	PDS	FB	80	3	44
AAKDPENU	U	PDS	FB	80	4	44
AAKDPKGI	U	PDS	FB	80	14	44
DKANCUS	E	PDS	FB	80	12	8
DKANDATV	E	PDS	VB	6160	27	2
DKANMOD	E	PDS	U	0	8	1
DKANMODL	E	PDS	U	0	35	1
DKANPAR	E	PDS	FB	80	3	1
DKANPKGI	E	PDS	FB	80	3	2

5.2.4 DASD Storage Requirements by FMID

The tables in this section can help determine the specific space required for components not already installed in an existing environment. There is a table for each FMID included with the product.

Figure 14 (Page 1 of 2). Storage Requirements for HAKD260 Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
SAKDCLST	CLIST	Any	U	PDS	FB	80	7	5
SAKDCNTL	Data	Any	U	PDS	FB	80	36	138
SAKDJCL	Data	Any	U	PDS	FB	80	14	6
SAKDLOAD	LMOD	Any	U	PDS	U	0	113	74
SAKDMSG	Data	Any	U	PDS	FB	80	17	14
SAKDPARM	Parm	Any	U	PDS	FB	80	3	2
SAKDPENU	Panel	Any	U	PDS	FB	80	4	3
SAKDPKGI	Data	Any	U	PDS	FB	80	13	2
AAKDCLST			U	PDS	FB	80	7	5
AAKDCNTL			U	PDS	FB	80	36	138
AAKDJCL			U	PDS	FB	80	14	6

Figure 14 (Page 2 of 2). Storage Requirements for HAKD260 Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
AAKDLOAD			U	PDS	U	0	113	74
AAKDMSG			U	PDS	FB	80	17	14
AAKDPARM			U	PDS	FB	80	3	2
AAKDPENU			U	PDS	FB	80	4	3
AAKDPKGI			U	PDS	FB	80	13	2

Figure 15. Storage Requirements for HKRG260 Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C F M	L R E C L	No. of 3390 Trks	No. of DIR Blks
TKANCUS	CLIST	Any	E	PDS	FB	80	12	8
TKANDATV	Data	Any	E	PDS	VB	6160	27	2
TKANMOD	LMOD	Any	E	PDS	U	0	8	1
TKANMODL	LMOD	Any	E	PDS	U	0	36	1
TKANPAR	Parm	Any	E	PDS	FB	80	3	1
TKANPKGI	Data	Any	E	PDS	FB	80	3	2
DKANCUS			E	PDS	FB	80	12	8
DKANDATV			E	PDS	VB	6160	27	2
DKANMOD			E	PDS	U	0	8	1
DKANMODL			E	PDS	U	0	36	1
DKANPAR			E	PDS	FB	80	3	1
DKANPKGI			E	PDS	FB	80	3	2

5.3 FMIDs Deleted

Installing Advanced Audit for DFSMSHsm might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install Advanced Audit for DFSMSHsm into separate SMP/E target and distribution zones.

Note: These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, use the SMP/E REJECT NOFMID DELETEFMID command. See the SMP/E Commands documentation for details.

5.4 Special Considerations

To effectively manage a suite of products with common components, you can install products into shared zones of a consolidated software inventory (CSI). Space requirements are reduced by installing products into shared CSI zones avoiding the duplication when different target zones, distribution zones, and data sets are used. Sharing a common set of zones also allows SMP/E to automatically manage IFREQ situations that exist across product components.

If you intend to share a Tivoli Enterprise Monitoring Server on z/OS with other products, use shared CSI zones so product configuration sets up the runtime environment correctly.

The installation of Advanced Audit for DFSMSHsm monitoring agent, HKRG260 FMID, requires the Tivoli Enterprise Monitoring Server on z/OS be installed in the CSI. Refer to the *Program Directory for IBM Tivoli Management Services on z/OS* (GI11-4105) for installation instructions of its product components.

Prior to installing Advanced Audit for DFSMSHsm, IBM recommends you review the OMEGAMON shared documentation 6.3.0 Fix Pack 2 and above, **First time deployment guide (FTU installation and tasks)**, the Planning, Configuring, and Configuration Manager topics for general planning and configuration flow. This documentation focuses on the things you will need to know for a successful installation and configuration of this product.

The OMEGAMON shared documentation, and other IBM product documentation can be found at the IBM Documentation URL listed below:

<https://www.ibm.com/docs/en/om-shared>

The **First time deployment guide (FTU installation and configuration tasks)** documentation can be found on the IBM Documentation website at:

<https://www.ibm.com/docs/en/om-shared?topic=guide-ftu-installation-configuration-tasks>

If you are installing into an existing CSI zone that contains the listed FMIDs, ensure the maintenance has been installed previously or it must be installed with this product package.

HKCI310 - UA80256
HKDS630 - UA75805 UA75806 UA75807
HKLV630 - UA75808 UA75809

Consider the following items when using shared CSI zones.

- You must specify the same high-level qualifier for the target and distribution libraries as the other products in the same zones for the configuration tool to work correctly.
- If you install a product into an existing CSI that contains a previous version of the same product, SMP/E deletes the previous version during the installation process. To maintain multiple product versions concurrently, they must be installed into separate CSI zones.
- If you install into an existing environment, you might need to remove data set references from the installation jobs to avoid errors because the data sets already exist.
- If you are installing into an existing environment that has the data sets already allocated, ensure sufficient space and directory blocks are available to support the requirement listed in the DASD tables. This might require you to reallocate some data sets to avoid x37 abends.

The PSP bucket will have the most current information and must be reviewed before installation.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of Advanced Audit for DFSMSHsm.

Please note the following points:

- If you want to install Advanced Audit for DFSMSHsm into its own SMP/E environment, consult the SMP/E manuals for instructions on creating and initializing the SMPCSI and the SMP/E control data sets.
- You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.

6.1 Installing Advanced Audit for DFSMSHsm

6.1.1 SMP/E Considerations for Installing Advanced Audit for DFSMSHsm

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of Advanced Audit for DFSMSHsm.

6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 16. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

<i>Figure 16. SMP/E Options Subentry Values</i>		
Subentry	Value	Comment
DSSPACE	300,1200,1200	Use 1200 directory blocks
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

6.1.3 SMP/E CALLLIBS Processing

Advanced Audit for DFSMSHsm Base component, HAKD260 FMID, uses the CALLLIBS function provided in SMP/E to resolve external references during installation. When Advanced Audit for DFSMSHsm Base is installed, ensure that DDDEFs exist for the following libraries:

- SCEELKED

Note: CALLLIBS uses the previous DDDEFs only to resolve the link-edit for Advanced Audit for DFSMSHsm. These data sets are not updated during the installation of Advanced Audit for DFSMSHsm.

6.1.4 Installation Job Generator Utility

A utility is available to generate the necessary installation jobs for this product and others that might be included in the product package deliverable. Be aware that not all products are supported at this time and maintenance might be required to get the latest updates for the Job Generator product selection table. It is recommended you use this job generation utility to create a set of jobs to install the product package when installing into an existing environment rather than using the sample jobs provided for each product.

The job generation utility is delivered in the z/OS Installation and Configuration Tool component of the Tivoli Management Services on z/OS product, which is a requisite of the monitoring agent (HKRG260) FMID. This utility is enhanced through the maintenance stream so there could be an issue if it is invoked from an environment without the latest maintenance. Ensure the latest maintenance is installed for the components of this product to get the latest updates for the Job Generator product selection table.

If you are installing for the first time into a new environment and don't have an existing environment available to invoke this utility, you must use the sample jobs for the Tivoli Management Services on z/OS product and install it first. This will install the FMID containing the job generation utility and the latest maintenance. Then you can invoke the utility from the target library TKANCUS to install other products in the package.

The job generation utility can be invoked from the SMP/E target library with the low-level qualifier of TKANCUS, launch the utility by using ISPF option 6 and entering the following command.

```
ex '&gb1_target_h1lev.TKANCUS'
```

Select "SMP/E-install z/OS products with Install Job Generator (JOBGEN)" from the z/OS Installation and Configuration Tool main menu.

You can use the online help available as a tutorial to become familiar with the utility and its processes.

6.1.4.1 Introduction to the Job Generator

The job generation utility creates a set of jobs to define a SMP/E environment (CSI and supporting data sets), allocate product libraries (target and distribution zone data sets and DDDEFS), and install the products (RECEIVE APPLY ACCEPT). You can use these jobs to create a totally new environment or to install the products into an existing CSI.

Processing Steps

- The jobs are generated from a series of ISPF interactive panels and ISPF file tailoring.
- The initial step is selection of the product mix. The set of products will determine any additions to the basic set of values needed to create the JCL.

Note: Install Job Generator (JOBGEN) output library: You can specify the Install Job Generator (JOBGEN) output library during the PARMGEN "KCIJPCFG Set up/Refresh PARMGEN work environment" configuration processing to reuse parameter values such as the jobcard and CSI values related to CALLLIBS and USS install directory override data.

Process Log

- One of the members of the generated job library is KCIJGLOG, which is the process log.
- This member shows the generating parameters and internal lists that were used to create the batch jobs.
- It also indicates which jobs were actually produced and need to be run. Note that the RECEIVE, APPLY, and ACCEPT jobs are always generated even if the selected products are already in the target CSI. In that case, the jobs install additional maintenance when available.

6.1.4.2 Product Selection

You can select one or more products from a table that will determine the set of FMIDs to install. You must select at least one product and you should always select the appropriate version of the IBM Tivoli Management Services on z/OS product (5698-A79) that is an installation requisite for this product offering. This will install the necessary FMIDs and maintenance for a new environment but also ensure any requisite maintenance will be processed when installing into an existing environment.

The selection table contains information about all of the supported products and might contain entries for products that you do not have or do not wish to install. Select only those products that are available in the package delivered and that you want to install.

6.1.4.3 Installing into an existing CSI

When the high-level qualifiers point to an existing environment, the job generation utility eliminates the jobs that allocate and initialize the CSI.

The job generation utility suppresses the creation of libraries that already exist in the target environment. Instead, the generator creates a job to determine whether sufficient space is available for any additional data to be installed into the libraries.

The member KCIJGANL is generated to report on the available space for each of the existing libraries that will have new data. However, KCIJGANL cannot check for the maintenance stream requirements.

The space analyzer function is very helpful in identifying data set space issues that might cause X37 abends during APPLY and ACCEPT processing.

6.1.4.4 Job Generator - Update Command

The job generation utility was enhanced to allow dynamic additions to the product table. The UPDATE routine is used to obtain additional data for products that are available but not yet included in the installation job generator table, KCIDJG00.

You must have the product RELFILES available on DASD in order to run this routine and all components of the product must be available. After a successful run, the output of this routine will replace the KCIDJG00 member of the work data set. If you make multiple changes to the data member be sure to save the original member as a backup.

Note: Not all products qualify for inclusion in the job generator process. Refer to the online help for more information about this facility.

6.1.5 Sample Jobs

If you choose not to use the installation job generator utility documented in the previous section, you can use the sample jobs that were created for Advanced Audit for DFSMSHsm. This will require you to research and tailor each of the jobs accordingly.

The sample jobs provided expect a CSI to exist already.

There are two sets of sample installation jobs provided as part of the product. The sample installation jobs in Figure 17 are to help you install only the base function of Advanced Audit for DFSMSHsm. To install both the base and monitoring agent functions, use the sample installation jobs in Figure 18 on page 23.

Figure 17. Sample Installation Jobs for base function

Job Name	Job Type	Description	RELFILE
AKDJ1SMA	Optional	Sample job to create new SMP/E support files	IBM.HAKD260.F9
AKDJ2SMI	Optional	Sample job to create and prime a new SMP/E CSI	IBM.HAKD260.F9
AKDJ3ALO	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.HAKD260.F9
AKDJ4DDF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.HAKD260.F9
AKDJ5REC	RECEIVE	Sample RECEIVE job	IBM.HAKD260.F9
AKDJ6APP	APPLY	Sample APPLY job	IBM.HAKD260.F9
AKDJ7ACC	ACCEPT	Sample ACCEPT job	IBM.HAKD260.F9

Figure 18. Sample Installation Jobs for base and monitoring agent functions

Job Name	Job Type	Description	RELFILE
KRGJ3ALO	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.HKRG260.F7
KRGJ4DDF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.HKRG260.F7
KRGJ5REC	RECEIVE	Sample RECEIVE job	IBM.HKRG260.F7
KRGJ6APP	APPLY	Sample APPLY job	IBM.HKRG260.F7
KRGJ7ACC	ACCEPT	Sample ACCEPT job	IBM.HKRG260.F7

The installation of the Advanced Audit for DFSMSHsm monitoring agent, HKRG260 FMID, requires the Tivoli Enterprise Monitoring Server on z/OS be installed in the CSI. Refer to the *Program Directory for IBM Tivoli Management Services on z/OS (GI11-4105)* for installation instructions of its product components.

You can access the sample installation jobs by performing an SMP/E RECEIVE (refer to 6.1.10, “Perform SMP/E RECEIVE” on page 25) then copy the jobs from the SMPTLIB data sets to a work data for editing and submission. See Figure 17 on page 22 or Figure 18 to find the appropriate relfile data set.

You can also copy the sample installation jobs from the product files by submitting the following job. If you intend to install only the base function, uncomment the appropriate statement containing IBM.HAKD260.F9 for the input dataset. If you intend to install both base and monitoring agent functions, uncomment the appropriate statement containing IBM.HKRG260.F7 for the input dataset. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1 EXEC PGM=IEBCOPY,REGION=4M
//SYSPRINT DD SYSOUT=*
//*IN DD DSN=IBM.HAKD260.F9,UNIT=SYSALLDA,DISP=SHR,
//*IN DD DSN=IBM.HKRG260.F7,UNIT=SYSALLDA,DISP=SHR,
//* VOL=SER=filevol
//OUT DD DSNAME=jc1-library-name,
// DISP=(NEW,CATLG,DELETE),
// VOL=SER=dasdvol,UNIT=SYSALLDA,
// SPACE=(TRK,(10,2,5))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
COPY INDD=xxxxIN,OUTDD=OUT
SELECT MEMBER=(AKDJ1SMA,AKDJ2SMI,AKDJ3ALO,AKDJ4DDF,AKDJ5REC)
SELECT MEMBER=(AKDJ6APP,AKDJ7ACC)
SELECT MEMBER=(KRGJ3ALO,KRGJ4DDF,KRGJ5REC,KRGJ6APP,KRGJ7ACC)
/*
```

See the following information to update the statements in the previous sample:

IN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT:

jcl-library-name is the name of the output data set where the sample jobs are stored.

dasdvol is the volume serial of the DASD device where the output data set resides.

If you chose to uncomment a statement containing IBM.HAKD260.F9 for the input dataset, keep the Select statements for members starting with AKD and delete the others.

If you chose to uncomment a statement containing IBM.HKRG260.F7 for the input dataset, keep the Select statements for members starting with KRG and delete the others.

6.1.6 Create New SMP/E Support Files - Optional

If you do not want to install into an existing environment, you can create a new environment. To allocate new SMP/E support data sets for Advanced Audit for DFSMSHsm installation, edit and submit the generated allocation job KCIJGSMA or edit and submit sample job AKDJ1SMA. Consult the instructions in the job for more information.

Expected Return Codes and Messages: 0

6.1.7 Create New SMP/E CSI - Optional

If you do not want to install into an existing environment, you can create a new environment. To allocate a new SMP/E CSI and prime it for Advanced Audit for DFSMSHsm installation, edit and submit the generated allocation job KCIJGSMI or edit and submit sample job AKDJ2SMI. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: 0

6.1.8 Allocate SMP/E Target and Distribution Libraries

Edit and submit the generated job KCIJGALO to allocate the SMP/E target and distribution libraries for Advanced Audit for DFSMSHsm.

If you are not using the generated allocation job, select the sample job AKDJ3ALO or KRGJ3ALO. Edit and submit it after making appropriate changes for your environment. Consult the instructions in the sample job for more information. Consider the following issues before submitting the job.

- If you are installing into an existing environment, you might have to remove lines for data sets that already exist.
- If you are installing into an existing environment that has the data sets already allocated, ensure sufficient space and directory blocks are available to support the requirement listed in the DASD tables. This might require you to reallocate some data sets to avoid x37 abends.

Expected Return Codes and Messages: 0

6.1.9 Create DDDEF Entries

Edit and submit the generated job KCIJGDDF to create DDDEF entries for the SMP/E target and distribution libraries for Advanced Audit for DFSMSHsm.

If you are not using the generated job, select the sample job AKDJ4DDF or KRGJ4DDF. Edit and submit it after making appropriate changes for your environment. Consult the instructions in the sample job for more information. If you are installing into an existing environment, you might have to remove lines for data sets that already exist.

Expected Return Codes and Messages: 0

6.1.10 Perform SMP/E RECEIVE

If you have obtained Advanced Audit for DFSMSHsm as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the Advanced Audit for DFSMSHsm FMIDs, service, and HOLDDATA that are included on the CBPDO package. For more information, see the documentation that is included in the CBPDO.

You can also choose to edit and submit the generated job KCIJGREC or the sample job AKDJ5REC or KRGJ5REC to perform the SMP/E RECEIVE for Advanced Audit for DFSMSHsm. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: 0

6.1.11 Perform SMP/E APPLY

Ensure that you have the latest HOLDDATA, then edit and submit the generated job KCIJGAPP to perform an SMP/E APPLY CHECK for Advanced Audit for DFSMSHsm.

If you are not using the generated job, select the sample job AKDJ6APP or KRGJ6APP to perform an SMP/E APPLY CHECK. Edit and submit it after making appropriate changes for your environment. Consult the instructions in the sample job for more information.

The latest HOLDDATA is available through several different portals, including <http://service.software.ibm.com/holddata/390holddata.html>. The latest HOLDDATA may identify HIPER and FIXCAT APARs for the FMIDs you will be installing. An APPLY CHECK will help you determine if any HIPER or FIXCAT APARs are applicable to the FMIDs you are installing. If there are any applicable HIPER or FIXCAT APARs, the APPLY CHECK will also identify fixing PTFs that will resolve the APARs, if a fixing PTF is available.

You should install the FMIDs regardless of the status of unresolved HIPER or FIXCAT APARs. However, do not deploy the software until the unresolved HIPER and FIXCAT APARs have been analyzed to determine their applicability. That is, before deploying the software either ensure fixing PTFs are applied

to resolve all HIPER or FIXCAT APARs, or ensure the problems reported by all HIPER or FIXCAT APARs are not applicable to your environment.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. The SMP/E root cause analysis identifies the cause only of *errors* and not of *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here are sample APPLY commands:

1. To ensure that all recommended and critical service is installed with the FMIDs, receive the latest HOLDDATA and use the APPLY CHECK command as follows

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND .
```

Some HIPER APARs might not have fixing PTFs available yet. You should analyze the symptom flags for the unresolved HIPER APARs to determine if the reported problem is applicable to your environment and if you should bypass the specific ERROR HOLDS in order to continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixing PTFs available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

2. To install the FMIDs without regard for unresolved HIPER APARs, you can add the BYPASS(HOLDCLASS(HIPER)) operand to the APPLY CHECK command. This will allow you to install FMIDs even though one or more unresolved HIPER APARs exist. After the FMIDs are installed, use the SMP/E REPORT ERRSYSMODS command to identify unresolved HIPER APARs and any fixing PTFs.

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER)) .
..any other parameters documented in the program directory
```

This method is quicker, but requires subsequent review of the Exception SYSMOD report produced by the REPORT ERRSYSMODS command to investigate any unresolved HIPERs. If you have received the latest HOLDDATA, you can also choose to use the REPORT MISSINGFIX command and specify Fix Category IBM.PRODUCTINSTALL-REQUIREDSERVICE to investigate missing recommended service.

If you bypass HOLDS during the installation of the FMIDs because fixing PTFs are not yet available, you can be notified when the fixing PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

Expected Return Codes and Messages from APPLY CHECK: 0

After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

If the BYPASS operand is not included in the control statement when processing a PTF with a ++HOLD statement, the job will get a return code of 12 and the following message.

```
GIM30206E command PROCESSING FAILED FOR SYSMOD sysmod.  
        HOLD REASON IDS WERE NOT RESOLVED.
```

Expected Return Codes and Messages from APPLY: 0

After installing new function, you should perform two operations:

1. Create a backup of the updated data sets, including any SMP/E data sets affected, in case something happens to the data sets during the next phase.
2. Do some testing before putting the new function into production.

After you are satisfied that an applied SYSMOD has performed reliably in your target system, you can install it in your distribution libraries using the ACCEPT process.

Another good practice is to accept most SYSMODs, particularly FMIDs, before performing another APPLY process. This provides you the ability to use the RESTORE process of SMP/E and to support the scenario where SMP/E needs to create a new load module from the distribution libraries during the APPLY process.

6.1.12 Perform SMP/E ACCEPT

Edit and submit the generated job KCIJGACC to perform an SMP/E ACCEPT CHECK for Advanced Audit for DFSMSHsm.

If you are not using the generated job, select the sample job AKDJ7ACC or KRGJ7ACC to perform an SMP/E ACCEPT CHECK. Edit and submit it after making appropriate changes for your environment. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. The SMP/E root cause analysis identifies the cause of *errors* but not *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E Commands documentation for details.

Expected Return Codes and Messages from ACCEPT CHECK: 0

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

If the BYPASS operand is not included in the control statement when processing a PTF with a ++HOLD statement, the job will get a return code of 12 and the following message.

```
GIM30206E command PROCESSING FAILED FOR SYSMOD sysmod.  
        HOLD REASON IDS WERE NOT RESOLVED.
```

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

Expected Return Codes and Messages from ACCEPT if no PTFs are being installed: 0

6.2 Activating Advanced Audit for DFSMSHsm

Prior to activating Advanced Audit for DFSMSHsm, IBM recommends you review the Quick Start Guide, **First time deployment guide (FTU installation and configuration tasks)**, as well as the Planning and Configuring topics if you have not already done so. This documentation focuses on the things you will need to know for a successful installation and configuration of this product.

Note: Install Job Generator (JOBGEN) output library: You can specify the Install Job Generator (JOBGEN) output library during the PARMGEN "KCIJPCFG Set up/Refresh PARMGEN work environment" configuration processing to reuse parameter values such as the jobcard and CSI values related to CALLLIBS and USS install directory override data.

The *Monitoring Agent Planning and Configuration Guide* documentation contains the step-by-step procedures to activate the TEP functions of Advanced Audit for DFSMSHsm.

This documentation can be found online at:

http://www.ibm.com/support/knowledgecenter/SS4J89_2.6.0/com.ibm.advaud.doc/welcome.html

7.0 Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan, Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan

7.1 Trademarks

IBM, the IBM logo, and other IBM trademark listed on the IBM Trademarks List are trademarks or registered trademarks of International Business Machines Corporation, in the United States and/or other countries. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on ibm.com/trademark.

Contacting IBM Software Support

For support for this or any IBM product, you can contact IBM Software Support in one of the following ways:

Submit a problem management record (PMR) electronically at **IBMSERV/IBMLINK**.

Submit a problem management record (PMR) electronically from the support Web site at:

<https://www.ibm.com/software/sysmgmt/products/support/>

You can also review the *IBM Software Support Handbook*, which is available on the Web site listed above. An *End of Support Matrix* is provided that tells you when products you are using are nearing the end of support date for a particular version or release.

When you contact IBM Software Support, be prepared to provide identification information for your company so that support personnel can readily assist you. Company identification information might also be needed to access various online services available on the Web site.

The support Web site offers extensive information, including a guide to support services (the *IBM Software Support Handbook*); frequently asked questions (FAQs); and documentation for all products, including Release Notes, Redbooks, and Whitepapers. The documentation for some product releases is available in both PDF and HTML formats. Translated documents are also available for some product releases.



Printed in USA

G111-8939-05

