



**Program Directory for
IBM Enterprise COBOL for z/OS**

V05.02.00

Program Number 5655-W32

FMIDs HADB520, JADB521, JADB522, JADB52H

for Use with
z/OS

Document Date: February 2015

GI11-9180-03

Note

Before using this information and the product it supports, be sure to read the general information under 7.0, "Notices" on page 29.

Contents

1.0 Introduction	1
1.1 Enterprise COBOL Description	1
1.2 Enterprise COBOL FMIDs	2
2.0 Program Materials	3
2.1 Basic Machine-Readable Material	3
2.2 Optional Machine-Readable Material	4
2.3 Program Publications	4
2.3.1 Optional Program Publications	4
2.4 Program Source Materials	5
2.5 Publications Useful During Installation	5
3.0 Program Support	6
3.1 Program Services	6
3.2 Preventive Service Planning	6
3.3 Statement of Support Procedures	7
4.0 Program and Service Level Information	8
4.1 Program Level Information	8
4.2 Service Level Information	9
5.0 Installation Requirements and Considerations	10
5.1 Driving System Requirements	10
5.1.1 Machine Requirements	10
5.1.2 Programming Requirements	10
5.2 Target System Requirements	11
5.2.1 Machine Requirements	11
5.2.2 Programming Requirements	12
5.2.2.1 Installation Requisites	12
5.2.2.2 Operational Requisites	12
5.2.2.3 Toleration/Coexistence Requisites	15
5.2.2.4 Incompatibility (Negative) Requisites	16
5.2.3 DASD Storage Requirements	16
5.3 FMIDs Deleted	18
5.4 Special Considerations	19
6.0 Installation Instructions	20
6.1 Installing Enterprise COBOL	20
6.1.1 SMP/E Considerations for Installing Enterprise COBOL	20
6.1.2 SMP/E Options Subentry Values	20
6.1.3 Sample Jobs	20
6.1.4 Set up ISPF Editor Macro (Optional)	22

6.1.5 Allocate and Initialize the SMP/E CSI (Optional)	23
6.1.6 Perform SMP/E RECEIVE	23
6.1.7 Allocate SMP/E Target and Distribution Libraries	23
6.1.8 Allocate, create and mount ZFS Files (Optional)	23
6.1.9 Allocate File System Paths	24
6.1.10 Create DDDEF Entries	25
6.1.11 Perform SMP/E APPLY	25
6.1.12 Run the Installation Verification Programs	26
6.1.13 Perform SMP/E ACCEPT	27
6.1.14 Run REPORT MISSINGFIX	27
6.2 Activating Enterprise COBOL	28
6.2.1 File System Execution	28
6.2.2 Product Customization	28
7.0 Notices	29
7.1 Trademarks	29
Reader's Comments	30

Figures

1. Program File Content	3
2. Basic Material: Unlicensed	4
3. Publications Useful During Installation	5
4. PSP Upgrade and Subset ID	6
5. Component IDs	7
6. Driving System Software Requirements	11
7. Target System Mandatory Installation Requisites	12
8. Target System Mandatory Operational Requisites	12
9. Target System Conditional Operational Requisites	13
10. Total DASD Space Required by Enterprise COBOL	16
11. Storage Requirements for Enterprise COBOL Target Libraries	17
12. Enterprise COBOL File System Paths	18
13. Storage Requirements for Enterprise COBOL Distribution Libraries	18
14. SMP/E Options Subentry Values	20
15. Sample Installation Jobs	20

1.0 Introduction

This program directory is intended for system programmers who are responsible for program installation and maintenance. It contains information about the material and procedures associated with the installation of IBM Enterprise COBOL for z/OS. This publication refers to IBM Enterprise COBOL for z/OS as Enterprise COBOL.

The Program Directory contains the following sections:

- 2.0, “Program Materials” on page 3 identifies the basic program materials and documentation for Enterprise COBOL.
- 3.0, “Program Support” on page 6 describes the IBM support available for Enterprise COBOL.
- 4.0, “Program and Service Level Information” on page 8 lists the APARs (program level) and PTFs (service level) that have been incorporated into Enterprise COBOL.
- 5.0, “Installation Requirements and Considerations” on page 10 identifies the resources and considerations that are required for installing and using Enterprise COBOL.
- 6.0, “Installation Instructions” on page 20 provides detailed installation instructions for Enterprise COBOL. It also describes the procedures for activating the functions of Enterprise COBOL, or refers to appropriate publications.

Before installing Enterprise COBOL, read the *CBPDO Memo To Users* and the *CBPDO Memo To Users Extension* that are supplied with this program in softcopy format and this program directory; then keep them for future reference. Section 3.2, “Preventive Service Planning” on page 6 tells you how to find any updates to the information and procedures in this program directory.

Enterprise COBOL is supplied in a Custom-Built Product Delivery Offering (CBPDO, 5751-CS3). The program directory that is provided in softcopy format on the CBPDO tape is identical to the hardcopy format if one was included with your order. All service and HOLDDATA for Enterprise COBOL are included on the CBPDO tape.

Do not use this program directory if you install Enterprise COBOL with a SystemPac or ServerPac. When you use one of those offerings, use the jobs and documentation supplied with the offering. The offering will point you to specific sections of this program directory as needed.

1.1 Enterprise COBOL Description

IBM Enterprise COBOL for z/OS is a leading-edge, z/OS-based compiler that helps you create and maintain mission-critical, line-of-business COBOL applications to execute on your z/OS systems. Enterprise COBOL for z/OS gives you access to CICS, DB2, IMS, and other transactional and data systems.

Over the course of multiple releases, Enterprise COBOL for z/OS offered new and enhanced functions to provide you with the tools needed to modernize and maintain applications to meet your critical business needs. The following are some of the new and improved features within Version 5.2:

- Support for the new zSphinx through the additional ARCH(11) option
- New, restored, and enhanced options for more flexibility
- New features towards ISO COBOL 2002 standards conformance
- New IBM extensions to COBOL
- Enhancements to the XML GENERATE statement
- Restored support for AMODE24
- New IBM SQL coprocessor
- Enhancements to the COBOL runtime

In addition, for COBOL applications in mobile and web solutions, the z/OS Client Web Enablement Toolkit provides JSON document parsing and generation. Install the PTF for APAR OA46575 to enable z/OS Client Web Enablement Toolkit support on z/OS V2.1.

Enterprise COBOL for z/OS, V5.2 continues the IBM commitment to the COBOL programming language on the z/OS platform through investment in new compiler technology and the delivery of new features, many of them client requested. With Enterprise COBOL for z/OS, V5.2, you gain the benefit of new investment combined with more than 40 years of IBM experience in compiler development.

1.2 Enterprise COBOL FMIDs

Enterprise COBOL consists of the following FMIDs:

HADB520
JADB521
JADB522
JADB52H

2.0 Program Materials

An IBM program is identified by a program number. The program number for Enterprise COBOL is 5655-W32.

Basic Machine-Readable Materials are materials that are supplied under the base license and are required for the use of the product.

The program announcement material describes the features supported by Enterprise COBOL. Ask your IBM representative for this information if you have not already received a copy.

2.1 Basic Machine-Readable Material

The distribution medium for this program is physical media or downloadable files. This program is in SMP/E RELFILE format and is installed by using SMP/E. See 6.0, "Installation Instructions" on page 20 for more information about how to install the program.

You can find information about the physical media for the basic machine-readable materials for Enterprise COBOL in the *CBPDO Memo To Users Extension*.

Figure 1 describes the program file content for Enterprise COBOL. You can refer to the *CBPDO Memo To Users Extension* to see where the files reside on the tape.

Notes:

1. The data set attributes in this table must be used in the JCL of jobs that read the data sets. However, because the data sets are in IEBCOPY unloaded format, their actual attributes might be different.
2. If any RELFILEs are identified as PDSEs, ensure that SMPTLIB data sets are allocated as PDSEs.

Figure 1 (Page 1 of 2). Program File Content

Name	O R G	R E C F M	L R E C L	BLK SIZE
SMPMCS	SEQ	FB	80	6400
IBM.HADB520.F1	PDS	FB	80	8800
IBM.HADB520.F2	PDSE	U	0	6144
IBM.HADB520.F3	PDS	FB	80	8800
IBM.JADB521.F1	PDSE	U	0	6144
IBM.JADB521.F2	PDS	FB	80	8800

Figure 1 (Page 2 of 2). Program File Content

Name	O R G	R E C F M	L R E C L	BLK SIZE
IBM.JADB522.F1	PDSE	U	0	6144
IBM.JADB52H.F1	PDS	VB	255	27998

2.2 Optional Machine-Readable Material

No optional machine-readable materials are provided for Enterprise COBOL.

2.3 Program Publications

The following sections identify the basic publications for Enterprise COBOL.

Figure 2 identifies the basic unlicensed publications for Enterprise COBOL. Those that are in softcopy format publications can be obtained from the IBM Publications Center website at:
<http://www.ibm.com/shop/publications/order/>

Figure 2. Basic Material: Unlicensed

Publication Title	Form Number	Media Format
IBM Enterprise COBOL for z/OS License Information	GI11-9181	http://www.ibm.com/software/sla/sladb.nsf or http://www.ibm.com/support/docview.wss?uid=swg27036733
IBM Enterprise COBOL for z/OS Customization Guide	SC14-7380	http://www.ibm.com/support/docview.wss?uid=swg27036733
IBM Enterprise COBOL for z/OS Language Reference	SC14-7381	http://www.ibm.com/support/docview.wss?uid=swg27036733
IBM Enterprise COBOL for z/OS Programming Guide	SC14-7382	http://www.ibm.com/support/docview.wss?uid=swg27036733
IBM Enterprise COBOL for z/OS Migration Guide	GC14-7383	http://www.ibm.com/support/docview.wss?uid=swg27036733

2.3.1 Optional Program Publications

No optional publications are provided for Enterprise COBOL.

2.4 Program Source Materials

No program source materials or viewable program listings are provided for Enterprise COBOL.

2.5 Publications Useful During Installation

You might want to use the publications listed in Figure 3 during the installation of Enterprise COBOL.

<i>Figure 3. Publications Useful During Installation</i>		
Publication Title	Form Number	Media Format
<i>IBM SMP/E for z/OS User's Guide</i>	SA23-2277	http://www.ibm.com/shop/publications/order/
<i>IBM SMP/E for z/OS Commands</i>	SA23-2275	http://www.ibm.com/shop/publications/order/
<i>IBM SMP/E for z/OS Reference</i>	SA23-2276	http://www.ibm.com/shop/publications/order/
<i>IBM SMP/E for z/OS Messages, Codes, and Diagnosis</i>	GA32-0883	http://www.ibm.com/shop/publications/order/

3.0 Program Support

This section describes the IBM support available for Enterprise COBOL.

3.1 Program Services

Contact your IBM representative for specific information about available program services.

3.2 Preventive Service Planning

Before you install Enterprise COBOL, make sure that you have reviewed the current Preventive Service Planning (PSP) information. Review the PSP Bucket for General Information, Installation Documentation, and the Cross Product Dependencies sections. For the Recommended Service section, instead of reviewing the PSP Bucket, it is recommended you use the IBM.ProductInstall-RequiredService fix category in SMP/E to ensure you have all the recommended service installed. Use the **FIXCAT(IBM.ProductInstall-RequiredService)** operand on the **APPLY CHECK** command. See 6.1.11, "Perform SMP/E APPLY" on page 25 for a sample APPLY command.

If you obtained Enterprise COBOL as part of a CBPDO, HOLDDATA is included.

If the CBPDO for Enterprise COBOL is older than two weeks by the time you install the product materials, you can obtain the latest PSP Bucket information by going to the following website:

<http://www14.software.ibm.com/webapp/set2/psearch/search?domain=psp>

You can also use S/390 SoftwareXcel or contact the IBM Support Center to obtain the latest PSP Bucket information.

For program support, access the Software Support Website at <http://www-01.ibm.com/software/support/>.

PSP Buckets are identified by UPGRADEs, which specify product levels; and SUBSETs, which specify the FMIDs for a product level. The UPGRADE and SUBSET values for Enterprise COBOL are included in Figure 4.

Figure 4. PSP Upgrade and Subset ID

UPGRADE	SUBSET	Description
COBOLZOS520	HADB520	Enterprise COBOL Base
	JADB521	Enterprise COBOL US English
	JADB522	Enterprise COBOL Japanese
	JADB52H	Enterprise COBOL HFS

3.3 Statement of Support Procedures

Report any problems which you feel might be an error in the product materials to your IBM Support Center. You may be asked to gather and submit additional diagnostics to assist the IBM Support Center in their analysis.

Figure 5 on page 7 identifies the component IDs (COMPID) for Enterprise COBOL.

<i>Figure 5. Component IDs</i>			
FMID	COMPID	Component Name	RETAIN Release
HADB520	5655W3200	Enterprise COBOL Base	520
JADB521	5655W3200	Enterprise COBOL US English	521
JADB522	5655W3200	Enterprise COBOL Japanese	522
JADB52H	5655W3200	Enterprise COBOL HFS	52H

4.0 Program and Service Level Information

This section identifies the program and relevant service levels of Enterprise COBOL. The program level refers to the APAR fixes that have been incorporated into the program. The service level refers to the PTFs that have been incorporated into the program.

4.1 Program Level Information

The following APAR fixes against previous releases of Enterprise COBOL have been incorporated into this release. They are listed by FMID.

- FMID HADB510

PI05656	PI20331	PI28332
PI05657	PI20376	PI28424
PI05658	PI20469	PI28657
PI06128	PI20532	PI28738
PI06899	PI20546	PI28923
PI07531	PI21182	PI28938
PI08238	PI21664	PI29284
PI11399	PI21773	PI29351
PI11805	PI21822	PI29538
PI12998	PI21860	PI30402
PI13222	PI21950	PI31403
PI13636	PI22094	PI32133
PI14476	PI22920	PI32825
PI14553	PI23024	PI32923
PI15609	PI23670	PI33207
PI16359	PI24639	PI33211
PI18183	PI25083	PI33323
PI18450	PI25119	PM92523
PI18572	PI25796	PM92585
PI19346	PI25926	PM92894
PI19522	PI26234	PM93583
PI19678	PI26646	PM95418
PI19712	PI26777	PM95906
PI19763	PI26944	PM96176
PI19815	PI27159	PM97763
PI19977	PI27541	PM97939
PI20292	PI27839	PM99261

4.2 Service Level Information

No PTFs against this release of Enterprise COBOL have been incorporated into the product package.

Frequently check the Enterprise COBOL PSP Bucket for HIPER and SPECIAL attention PTFs against all FMIDs that you must install. You can also receive the latest HOLDDATA, then add the **FIXCAT((IBM.TargetSystem-RequiredService.Enterprise-COBOL.V5R2)** operand on your APPLY CHECK command. This will allow you to review the recommended and critical service that should be installed with your FMIDs.

5.0 Installation Requirements and Considerations

The following sections identify the system requirements for installing and activating Enterprise COBOL. The following terminology is used:

- *Driving system*: the system on which SMP/E is executed to install the program.
The program might have specific operating system or product level requirements for using processes, such as binder or assembly utilities during the installation.
- *Target system*: the system on which the program is configured and run.
The program might have specific product level requirements, such as needing access to the library of another product for link-edits. These requirements, either mandatory or optional, might directly affect the element during the installation or in its basic or enhanced operation.

In many cases, you can use a system as both a driving system and a target system. However, you can make a separate IPL-able clone of the running system to use as a target system. The clone must include copies of all system libraries that SMP/E updates, copies of the SMP/E CSI data sets that describe the system libraries, and your PARMLIB and PROCLIB.

Use separate driving and target systems in the following situations:

- When you install a new level of a product that is already installed, the new level of the product will replace the old one. By installing the new level onto a separate target system, you can test the new level and keep the old one in production at the same time.
- When you install a product that shares libraries or load modules with other products, the installation can disrupt the other products. By installing the product onto a separate target system, you can assess these impacts without disrupting your production system.

5.1 Driving System Requirements

This section describes the environment of the driving system required to install Enterprise COBOL.

5.1.1 Machine Requirements

The driving system can run in any hardware environment that supports the required software.

5.1.2 Programming Requirements

Figure 6. Driving System Software Requirements

Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
Any one of the following:				
5694-A01	z/OS	V01.13.00	N/A	No
5650-ZOS	z/OS	V02.01.00	N/A	No

Note: SMP/E is a requirement for Installation and is an element of z/OS but can also be ordered as a separate product, 5655-G44, minimally V03.06.00.

Note: Installation might require migration to new z/OS releases to be service supported. See http://www-03.ibm.com/systems/z/os/zos/support/zos_eos_dates.html.

If you plan on installing the Japanese FMID JADB522 then ensure you have codepage 939 which is the Latin-based Japanese codepage that displays both upper and lower case characters correctly. Mixed case character usage is required for the sample IGYWDDEF, IGYWZFS, and IGYISMKD jobs; therefore, codepage 939 is required to run these jobs from the driving system.

Enterprise COBOL is installed into a file system, either HFS or zFS. Before installing Enterprise COBOL, you must ensure that the target system file system data sets are available for processing on the driving system. OMVS must be active on the driving system and the target system file data sets must be mounted on the driving system.

If you plan to install Enterprise COBOL in a zFS file system, this requires that zFS be active on the driving system. Information on activating and using zFS can be found in z/OS Distributed File Service zSeries File System Administration, SC24-5989.

5.2 Target System Requirements

This section describes the environment of the target system required to install and use Enterprise COBOL.

Enterprise COBOL installs in the z/OS (Z038) SREL.

5.2.1 Machine Requirements

Enterprise COBOL V05.02.00 will run on the following IBM System z servers:

- z13
- zEnterprise EC12 and zEnterprise BC12
- zEnterprise 196 or zEnterprise 114
- z10 Enterprise Class and z10 Business Class

- z9 Enterprise Class or z9 Business Class

5.2.2 Programming Requirements

5.2.2.1 Installation Requisites: Installation requisites identify products that are required and *must* be present on the system or products that are not required but *should* be present on the system for the successful installation of this product.

Mandatory installation requisites identify products that are required on the system for the successful installation of this product.

<i>Figure 7. Target System Mandatory Installation Requisites</i>				
Program Number	Product Name	Minimum VRM	Minimum Service Level will satisfy these APARs	Included in the shipped product?
Any one of the following:				
5694-A01	z/OS	V01.13.00	N/A	No
5650-ZOS	z/OS	V02.01.00	N/A	No

Note: Installation might require migration to new z/OS releases to be service supported. See http://www-03.ibm.com/systems/z/os/zos/support/zos_eos_dates.html.

Conditional installation requisites identify products that are *not* required for successful installation of this product but can resolve such things as certain warning messages at installation time.

Enterprise COBOL has no conditional installation requisites.

5.2.2.2 Operational Requisites: Operational requisites are products that are required and *must* be present on the system or products that are not required but *should* be present on the system for this product to operate all or part of its functions.

Mandatory operational requisites identify products that are required for this product to operate its basic functions.

<i>Figure 8 (Page 1 of 2). Target System Mandatory Operational Requisites</i>		
Program Number	Product Name and Minimum VRM/Service Level	Function
Any one of the following:		

<i>Figure 8 (Page 2 of 2). Target System Mandatory Operational Requisites</i>		
Program Number	Product Name and Minimum VRM/Service Level	Function
5694-A01	z/OS V01.13.00 or higher	z/OS Language Environment and Program Management, required to compile and run COBOL applications
5650-ZOS	z/OS V02.01.00 or higher	z/OS Language Environment and Program Management, required to compile and run COBOL applications

Conditional operational requisites identify products that are *not* required for this product to operate its basic functions but are required at run time for this product to operate specific functions.

<i>Figure 9 (Page 1 of 3). Target System Conditional Operational Requisites</i>		
Program Number	Product Name and Minimum VRM/Service Level	Function
5696-234	High Level Assembler for MVS and VM and VSE V01.06 or higher	Assembler source programs (for interlanguage communication)
5668-806, 5688-087	VS Fortran V02.01 or higher	Fortran source programs (for interlanguage communication)
5798-DYR	COBOL Report Writer V01.04	COBOL Report Writer source programs
5724-T07	Rational Developer for System z V09.01 or higher	An Integrated Development Environment to help develop applications for System z
5650-ZOS	z/OS V02.01 or higher with APAR OA46575	Client Web Enablement Toolkit
Any one of the following:		
5655-H31	Enterprise PL/I for z/OS V03.09 or higher	PL/I source programs (for interlanguage communication)
5655-W67	Enterprise PL/I for z/OS V04.02 or higher	PL/I source programs (for interlanguage communication)
Any one of the following:		
5694-A01	XL C/C++ feature of z/OS V01.13 or higher	XL C/C++ with Enterprise COBOL
5650-ZOS	XL C/C++ feature of z/OS V02.01 or higher	XL C/C++ with Enterprise COBOL
Any one of the following:		
5655-G53	Enterprise COBOL for z/OS V03.04 or higher	Interoperability of COBOL source programs
5655-S71	Enterprise COBOL for z/OS V04.02 or higher	Interoperability of COBOL source programs

Figure 9 (Page 2 of 3). Target System Conditional Operational Requisites

Program Number	Product Name and Minimum VRM/Service Level	Function
Any one of the following:		
5655-W70	Debug Tool for z/OS V12.01.00	Debugging capabilities
5655-Q10	Debug Tool for z/OS V13.01.00	Debugging capabilities
Any one of the following:		
5655-W69	Fault Analyzer for z/OS V12.01.00	Analyze and fix application and system failures
5655-Q11	Fault Analyzer for z/OS V13.01.00	Analyze and fix application and system failures
Any one of the following:		
5655-W68	File Manager for z/OS V12.01.00	Working with z/OS data sets, DB2 data, CICS data, or IMS data
5655-Q12	File Manager for z/OS V13.01.00	Working with z/OS data sets, DB2 data, CICS data, or IMS data
Any one of the following:		
5655-W71	Application Performance Analyzer for z/OS V12.01.00	Analyze application performance
5655-Q09	Application Performance Analyzer for z/OS V13.01.00	Analyze application performance
Any one of the following:		
5694-A01	DFSORT element of z/OS V13.01.00 or higher	COBOL applications using SORT/MERGE
5650-ZOS	DFSORT element of z/OS V02.01.00 or higher	COBOL applications using SORT/MERGE
Any one of the following:		
5655-R31	31-bit SDK for z/OS Java Technology Edition V06 (see note) with PTFs for APAR PK89762	Support for object-oriented COBOL syntax (Java interoperability)
5655-W43	31-bit SDK for z/OS Java Technology Edition V07 (see note)	Support for object-oriented COBOL syntax (Java interoperability)
5655-DGG	31-bit SDK for z/OS Java Technology Edition V08 (see note)	Support for object-oriented COBOL syntax (Java interoperability)
Any one of the following:		
5605-DB2	DB2 for z/OS V10.01.00	National decimal host variables in EXEC SQL statements and alternate DDNAME for DBRMLIB

Figure 9 (Page 3 of 3). Target System Conditional Operational Requisites

Program Number	Product Name and Minimum VRM/Service Level	Function
5697-P31	DB2 for z/OS Value Unit Edition V10.01.00	National decimal host variables in EXEC SQL statements and alternate DDNAME for DBRMLIB
5615-DB2	DB2 for z/OS V11.01.00	National decimal host variables in EXEC SQL statements and alternate DDNAME for DBRMLIB
5697-P43	DB2 for z/OS Value Unit Edition V11.01.00	National decimal host variables in EXEC SQL statements and alternate DDNAME for DBRMLIB
Any one of the following:		
5655-M15	CICS Transaction Server for z/OS V03.02.00	COBOL applications for CICS, and for integrated CICS Translator support
5655-S97	CICS Transaction Server for z/OS V04.01.00 or higher	COBOL applications for CICS, and for integrated CICS Translator support
5655-Y04	CICS Transaction Server for z/OS V05.01.00 or higher	COBOL applications for CICS, and for integrated CICS Translator support
5722-DFJ	CICS Transaction Server for z/OS Value Unit Edition V05.01.00 or higher	COBOL applications for CICS, and for integrated CICS Translator support
Any one of the following:		
5635-A03	IMS V12.01.00	COBOL applications with IMS
5655-TM1	IMS Transaction Manager Value Unit Edition V12.01.00	COBOL applications with IMS
5655-DSQ	IMS Database Value Unit Edition V12.01.00	COBOL applications with IMS
5635-A04	IMS V13.01.00	COBOL applications with IMS
5655-TM2	IMS Transaction Manager Value Unit Edition V13.01.00	COBOL applications with IMS
5655-DSM	IMS Database Value Unit Edition V13.01.00	COBOL applications with IMS

Note: COBOL requires a 31-bit Java SDK, 64-bit Java technology is not currently supported.

5.2.2.3 Toleration/Coexistence Requisites: Toleration/coexistence requisites identify products that must be present on sharing systems. These systems can be other systems in a multisystem environment (not necessarily sysplex), a shared DASD environment (such as test and production), or systems that reuse the same DASD environment at different time intervals.

Enterprise COBOL has no toleration/coexistence requisites.

5.2.2.4 Incompatibility (Negative) Requisites: Negative requisites identify products that must *not* be installed on the same system as this product.

Enterprise COBOL has no negative requisites.

5.2.3 DASD Storage Requirements

Enterprise COBOL libraries can reside on all supported DASD types.

Figure 10 lists the total space that is required for each type of library.

Library Type	Total Space Required in 3390 Trks
Target	2547
Distribution	2555
File System	30

Notes:

1. For non-RECFM U data sets, IBM recommends using system-determined block sizes for efficient DASD utilization. For RECFM U data sets, IBM recommends using a block size of 32760, which is most efficient from the performance and DASD utilization perspective.
2. Abbreviations used for data set types are shown as follows.

- U** Unique data set, allocated by this product and used by only this product. This table provides all the required information to determine the correct storage for this data set. You do not need to refer to other tables or program directories for the data set size.
- S** Shared data set, allocated by this product and used by this product and other products. To determine the correct storage needed for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.
- E** Existing shared data set, used by this product and other products. This data set is *not* allocated by this product. To determine the correct storage for this data set, add the storage size given in this table to those given in other tables (perhaps in other program directories). If the data set already exists, it must have enough free space to accommodate the storage size given in this table.

If you currently have a previous release of this product installed in these libraries, the installation of this release will delete the old release and reclaim the space that was used by the old release and any service that had been installed. You can determine whether these libraries have enough space by deleting the old release with a dummy function, compressing the libraries, and comparing the space requirements with the free space in the libraries.

For more information about the names and sizes of the required data sets, see 6.1.7, “Allocate SMP/E Target and Distribution Libraries” on page 23.

3. Abbreviations used for the file system path type are as follows.

- N** New path, created by this product.
- X** Path created by this product, but might already exist from a previous release.
- P** Previously existing path, created by another product.

4. All target and distribution libraries listed have the following attributes:

- The default name of the data set can be changed.
- The default block size of the data set can be changed.
- The data set can be merged with another data set that has equivalent characteristics.
- The data set can be either a PDS or a PDSE, except for SIGYCOMP, and AIGYMOD1, which must be PDSEs.

5. All target libraries listed have the following attributes:

- These data sets can be SMS-managed, but they are not required to be SMS-managed.
- These data sets are not required to reside on the IPL volume.
- The values in the "Member Type" column are not necessarily the actual SMP/E element types that are identified in the SMPMCS.

6. All target libraries that are listed and contain load modules have the following attributes:

- These data sets can be in the LPA, but they are not required to be in the LPA.
- These data sets can be in the LNKST.
- These data sets are not required to be APF-authorized.
- Enterprise COBOL requires that the SMPLTS data set must be a PDSE. If your existing SMPLTS is a PDS, you will need to allocate a new PDSE and copy your existing SMPLTS into it and then change the SMPLTS DDDEF entry to indicate the new PDSE data set.

The following figures describe the target and distribution libraries and file system paths required to install Enterprise COBOL. The storage requirements of Enterprise COBOL must be added to the storage required by other programs that have data in the same library or path.

Note: Use the data in these tables to determine which libraries can be merged into common data sets. In addition, since some ALIAS names may not be unique, ensure that no naming conflicts will be introduced before merging libraries.

<i>Figure 11 (Page 1 of 2). Storage Requirements for Enterprise COBOL Target Libraries</i>									
Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C O M	L R E C L	No. of 3390 Trks	No. of DIR Blks	
SIGYCOMP	LMOD	ANY	U	PDSE	U	0	2500	n/a	
SIGYMAC	MACRO	ANY	U	PDS	FB	80	10	5	

Figure 11 (Page 2 of 2). Storage Requirements for Enterprise COBOL Target Libraries

Library DDNAME	Member Type	Target Volume	T Y P E	O R G	R E C O R D S	L E N G T H	No. of 3390 Trks	No. of DIR Blks
SIGYPROC	PROC	ANY	U	PDS	FB	80	2	5
SIGYSAMP	SAMP	ANY	U	PDS	FB	80	35	10

Figure 12. Enterprise COBOL File System Paths

DDNAME	T Y P E	Path Name
SIGYHFS	N	/usr/lpp/IBM/cobol/igyv5r2/bin/IBM

Figure 13. Storage Requirements for Enterprise COBOL Distribution Libraries

Library DDNAME	T Y P E	O R G	R E C O R D S	L E N G T H	No. of 3390 Trks	No. of DIR Blks
AIGYHFS	U	PDS	VB	255	10	5
AIGYMOD1	U	PDSE	U	0	2500	n/a
AIGYSRC1	U	PDS	FB	80	45	12

5.3 FMIDs Deleted

Installing Enterprise COBOL might result in the deletion of other FMIDs. To see which FMIDs will be deleted, examine the ++VER statement in the SMPMCS of the product.

If you do not want to delete these FMIDs at this time, install Enterprise COBOL into separate SMP/E target and distribution zones.

Note: These FMIDs are not automatically deleted from the Global Zone. If you want to delete these FMIDs from the Global Zone, use the SMP/E REJECT NOFMID DELETEFMID command. See the SMP/E Commands book for details.

5.4 Special Considerations

COBOL and COBOL Developer Trial Co-existence:

The COBOL product and the COBOL Developer Trial product cannot be installed in the same CSI zone, or share the same target and distribution data set names.

PDSE Considerations:

Enterprise COBOL uses the "partitioned data set extended" or PDSE format for the SIGYCOMP target library. There are some operational differences between PDS and PDSE data sets. The PDS format may be shared by more than one z/OS system and no special precautions are necessary. However the PDSE format may only be shared by z/OS systems which are part of a sysplex or which are connected using Global Resource Serialization (are in a GRS complex). If z/OS systems share use of a PDSE data set outside of a sysplex or GRS environment, you may experience severe problems when the data set is updated. This is due to the fact that PDSE directory information is cached in storage, and when the data set is updated from one system the other system(s) have no knowledge of the update, and their cached directory information will be incorrect.

You must take care not to share the SIGYCOMP data set between z/OS systems unless they are in a sysplex or are connected in a GRS complex. If you need to share the content of the SIGYCOMP data set, a separate copy must be created for each z/OS system.

6.0 Installation Instructions

This chapter describes the installation method and the step-by-step procedures to install and to activate the functions of Enterprise COBOL.

Please note the following points:

- You can use the sample jobs that are provided to perform part or all of the installation tasks. The SMP/E jobs assume that all DDDEF entries that are required for SMP/E execution have been defined in appropriate zones.
- You can use the SMP/E dialogs instead of the sample jobs to accomplish the SMP/E installation steps.

6.1 Installing Enterprise COBOL

6.1.1 SMP/E Considerations for Installing Enterprise COBOL

Use the SMP/E RECEIVE, APPLY, and ACCEPT commands to install this release of Enterprise COBOL.

6.1.2 SMP/E Options Subentry Values

The recommended values for certain SMP/E CSI subentries are shown in Figure 14. Using values lower than the recommended values can result in failures in the installation. DSSPACE is a subentry in the GLOBAL options entry. PEMAX is a subentry of the GENERAL entry in the GLOBAL options entry. See the SMP/E manuals for instructions on updating the global zone.

<i>Figure 14. SMP/E Options Subentry Values</i>		
Subentry	Value	Comment
DSSPACE	(500,500,500)	3390 DASD tracks
PEMAX	SMP/E Default	IBM recommends using the SMP/E default for PEMAX.

6.1.3 Sample Jobs

The following sample installation jobs are provided as part of the product to help you install Enterprise COBOL:

<i>Figure 15 (Page 1 of 2). Sample Installation Jobs</i>			
Job Name	Job Type	Description	RELFILE
IGYWEDIT	MACRO	ISPF editor macro to aid users in making changes to the sample jobs (Optional)	IBM.HADB520.F3

Figure 15 (Page 2 of 2). Sample Installation Jobs

Job Name	Job Type	Description	RELFILE
IGYWSMPE	SMP/E	Sample job to define and prime a new SMP/E CSI (Optional)	IBM.HADB520.F3
IGYWRECV	RECEIVE	Sample RECEIVE job	IBM.HADB520.F3
IGYWALOC	ALLOCATE	Sample job to allocate target and distribution libraries	IBM.HADB520.F3
IGYWZFS	ALLOMZFS	Sample job to allocate, create mountpoint, & mount zFS data sets (Optional)	IBM.HADB520.F3
IGYISMKD	MKDIR	Sample job to invoke the supplied IGYMKDIR EXEC to allocate file system paths	IBM.HADB520.F3
IGYWDDEF	DDDEF	Sample job to define SMP/E DDDEFs	IBM.HADB520.F3
IGYWAPLY	APPLY	Sample APPLY job	IBM.HADB520.F3
IGYWIVP1	IVP	Sample job to verify installation has been successful	IBM.HADB520.F3
IGYWIVP2	IVP	Sample job to verify installation has been successful	IBM.HADB520.F3
IGYWACPT	ACCEPT	Sample ACCEPT job	IBM.HADB520.F3

You can access the sample installation jobs by performing an SMP/E RECEIVE (refer to 6.1.6, “Perform SMP/E RECEIVE” on page 23) then copy the jobs from the RELFILES to a work data set for editing and submission. See Figure 15 on page 20 to find the appropriate relfile data set.

You can also copy the sample installation jobs from the tape or product files by submitting the following job. Depending on your distribution medium, use either the //TAPEIN or the //FILEIN DD statement and comment out or delete the other statement. Before you submit the job, add a job card and change the lowercase parameters to uppercase values to meet the requirements of your site.

```
//STEP1 EXEC PGM=IEBCOPY
//SYSPRINT DD SYSOUT=*
//*****
//* Make the //TAPEIN DD statement below active if you install*
//* from a CBPDO tape by uncommenting the DD statement below. *
//*****
//*TAPEIN DD DSN=IBM.HADB520.F3,UNIT=tunit,
//* VOL=SER=volser,LABEL=(x,SL),
//* DISP=(OLD,KEEP)
//*****
//* Make the //TAPEIN DD statement below active if you install*
//* from a product tape received outside the CBPDO process *
//* (using the optional SMP/E RECEIVE job) by uncommenting *
//* the DD statement below. *
//*****
//*TAPEIN DD DSN=IBM.HADB520.F3,UNIT=tunit,
```

```

//*          VOL=SER=ADB520, LABEL=(4,SL),
//*          DISP=(OLD,KEEP)
/*****
/* Make the //FILEIN DD statement below active for          *
/* downloaded DASD files.                                   *
/*****
/*FILEIN   DD DSN=IBM.HADB520.F3,UNIT=SYSALLDA,DISP=SHR,
/*          VOL=SER=filevol
//OUT      DD DSNAME=jcl-library-name,
//          DISP=(NEW,CATLG,DELETE),
//          VOL=SER=dasdvol,UNIT=SYSALLDA,
//          SPACE=(TRK,(20,10,5))
//SYSUT3   DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN    DD *
            COPY INDD=xxxxIN,OUTDD=OUT
            SELECT MEMBER=(IGYISMKD,IGYWACPT,IGYWALOC,IGYWAPLY)
            SELECT MEMBER=(IGYWDDEF,IGYWEDIT,IGYWIVP1,IGYWIVP2)
            SELECT MEMBER=(IGYWRECV,IGYWSMPE,IGYWZFS)
/*

```

See the following information to update the statements in the previous sample:

TAPEIN:

- tunit** is the unit value that matches the product package.
- volser** is the volume serial that matches the product package.
- x** is the tape file number that indicates the location of the data set name on the tape.
- See the documentation that is provided by CBPDO for the location of IBM.HADB520.F3 on the tape.

FILEIN:

filevol is the volume serial of the DASD device where the downloaded files reside.

OUT:

jcl-library-name is the name of the output data set where the sample jobs are stored.

dasdvol is the volume serial of the DASD device where the output data set resides.

SYSIN:

xxxxIN is either TAPEIN or FILEIN depending on your input DD statement.

6.1.4 Set up ISPF Editor Macro (Optional)

To aid you in making changes to the SMP/E installation jobs (IGYISMKD, IGYWACPT, IGYWALOC, IGYWAPLY, IGYWDDEF, IGYWIVP1, IGYWIVP2, IGYWRECV, IGYWSMPE, and IGYWZFS), an ISPF editor macro, called IGYWEDIT, is supplied and is copied to your output data set **jcl-library-name** above. (See Figure 15 on page 20).

This macro lets you substitute proper values for all of the required variables in those jobs instead of making the changes repeatedly by hand.

Edit macro IGYWEDIT and provide the proper values, then copy it to any data set in your TSO logon procedure SYSEXEC concatenation. Consult the instructions in the macro for more information.

6.1.5 Allocate and Initialize the SMP/E CSI (Optional)

If you are using an existing CSI do not execute this job.

If you install into existing SMP/E data sets, make sure that you have enough space.

If you plan to install into an existing zone, the cluster should already have been allocated and primed. You can go on to the next step to perform a SMP/E RECEIVE.

To install into a new zone, use the IGYWSMPE sample job to allocate and prime the SMPCSI cluster. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.6 Perform SMP/E RECEIVE

If you have obtained Enterprise COBOL as part of a CBPDO, use the RCVPDO job in the CBPDO RIMLIB data set to receive the Enterprise COBOL FMIDs, service, and HOLDDATA that are included on the CBPDO package. For more information, see the documentation that is included in the CBPDO.

You can also choose to edit and submit sample job IGYWRECV to perform the SMP/E RECEIVE for Enterprise COBOL. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.7 Allocate SMP/E Target and Distribution Libraries

Edit and submit sample job IGYWALOC to allocate the SMP/E target and distribution libraries for Enterprise COBOL. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.8 Allocate, create and mount ZFS Files (Optional)

This job allocates, creates a mountpoint, and mounts zFS data sets.

If you plan to install Enterprise COBOL into a new z/OS UNIX file system, you can edit and submit the optional IGYWZFS job to perform the following tasks:

- Create the z/OS UNIX file system
- Create a mount point
- Mount the z/OS UNIX file system on the mountpoint

Consult the instructions in the sample job for more information.

The recommended z/OS UNIX file system type is zFS. The recommended mount point is */usr/lpp/IBM/cobol/igyv5r2*.

Before running the sample job to create the z/OS UNIX file system, you must ensure that OMVS is active on the driving system. zFS must be active on the driving system if you are installing Enterprise COBOL into a file system that is zFS.

If you create a new file system for this product, consider updating the BPXPRMxx PARMLIB member to mount the new file system at IPL time. This action can be helpful if an IPL occurs before the installation is completed.

```
MOUNT FILESYSTEM('#dsn')
MOUNTPOINT('/usr/lpp/IBM/cobol/igyv5r2')
MODE(RDRW) /* can be MODE(READ) */
TYPE(ZFS) PARM('AGGRGROW') /* zFS, with extents */
```

See the following information to update the statements in the previous sample:

#dsn is the name of the data set holding the z/OS UNIX file system.

/usr/lpp/IBM/cobol/igyv5r2 is the name of the mount point where the z/OS UNIX file system will be mounted.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.9 Allocate File System Paths

The target system HFS or zFS data set must be mounted on the driving system when running the sample IGYISMKD job since the job will create paths in the HFS or zFS.

Before running the sample job to create the paths in the file system, you must ensure that OMVS is active on the driving system and that the target system's HFS or zFS file system is mounted to the driving system. zFS must be active on the driving system if you are installing Enterprise COBOL into a file system that is zFS.

If you plan to install Enterprise COBOL into a new HFS or zFS file system, you must create the mountpoint and mount the new file system to the driving system for Enterprise COBOL.

The recommended mountpoint is */usr/lpp/IBM/cobol/igyv5r2*.

Edit and submit sample job IGYISMKD to allocate the HFS or zFS paths for Enterprise COBOL. Consult the instructions in the sample job for more information.

If you create a new file system for this product, consider updating the BPXPRMxx PARMLIB member to mount the new file system at IPL time. This action can be helpful if an IPL occurs before the installation is completed.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.10 Create DDDEF Entries

Edit and submit sample job IGYWDDEF to create DDDEF entries for the SMP/E target and distribution libraries for Enterprise COBOL. Consult the instructions in the sample job for more information.

Expected Return Codes and Messages: You will receive a return code of 0 if this job runs correctly.

6.1.11 Perform SMP/E APPLY

1. Ensure that you have the latest HOLDDATA; then edit and submit sample job IGYWAPLY to perform an SMP/E APPLY CHECK for Enterprise COBOL. Consult the instructions in the sample job for more information.

The latest HOLDDATA is available through several different portals, including <http://service.software.ibm.com/holddata/390holddata.html>. The latest HOLDDATA may identify HIPER and FIXCAT APARs for the FMIDs you will be installing. An APPLY CHECK will help you determine if any HIPER or FIXCAT APARs are applicable to the FMIDs you are installing. If there are any applicable HIPER or FIXCAT APARs, the APPLY CHECK will also identify fixing PTFs that will resolve the APARs, if a fixing PTF is available.

You should install the FMIDs regardless of the status of unresolved HIPER or FIXCAT APARs. However, do not deploy the software until the unresolved HIPER and FIXCAT APARs have been analyzed to determine their applicability. That is, before deploying the software either ensure fixing PTFs are applied to resolve all HIPER or FIXCAT APARs, or ensure the problems reported by all HIPER or FIXCAT APARs are not applicable to your environment.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the APPLY CHECK. The SMP/E root cause analysis identifies the cause only of *errors* and not of *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings, instead of errors).

Here are sample APPLY commands:

- a. To ensure that all recommended and critical service is installed with the FMIDs, receive the latest HOLDDATA and use the APPLY CHECK command as follows

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND .
```

Some HIPER APARs might not have fixing PTFs available yet. You should analyze the symptom flags for the unresolved HIPER APARs to determine if the reported problem is applicable to your environment and if you should bypass the specific ERROR HOLDS in order to continue the installation of the FMIDs.

This method requires more initial research, but can provide resolution for all HIPERs that have fixing PTFs available and are not in a PE chain. Unresolved PEs or HIPERs might still exist and require the use of BYPASS.

- b. To install the FMIDs without regard for unresolved HIPER APARs, you can add the BYPASS(HOLDCLASS(HIPER)) operand to the APPLY CHECK command. This will allow you to install FMIDs even though one or more unresolved HIPER APARs exist. After the FMIDs are installed, use the SMP/E REPORT ERRSYSMODS command to identify unresolved HIPER APARs and any fixing PTFs.

```
APPLY S(fmid,fmid,...) CHECK
FORFMID(fmid,fmid,...)
SOURCEID(RSU*)
FIXCAT(IBM.ProductInstall-RequiredService)
GROUPEXTEND
BYPASS(HOLDCLASS(HIPER),HOLDFIXCAT) .
..any other parameters documented in the program directory
```

This method is quicker, but requires subsequent review of the Exception SYSMOD report produced by the REPORT ERRSYSMODS command to investigate any unresolved HIPERs. If you have received the latest HOLDDATA, you can also choose to use the REPORT MISSINGFIX command and specify Fix Category IBM.ProductInstall-RequiredService to investigate missing recommended service.

If you bypass HOLDs during the installation of the FMIDs because fixing PTFs are not yet available, you can be notified when the fixing PTFs are available by using the APAR Status Tracking (AST) function of ServiceLink or the APAR Tracking function of ResourceLink.

2. After you take actions that are indicated by the APPLY CHECK, remove the CHECK operand and run the job again to perform the APPLY.

Note: The GROUPEXTEND operand indicates that SMP/E applies all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from APPLY CHECK: You will receive a return code of 0 if this job runs correctly.

Expected Return Codes and Messages from APPLY: You will receive a return code of 0 if this job runs correctly.

6.1.12 Run the Installation Verification Programs

Make sure you have applied the PTFs for the Language Environment and Program Management APARs listed in Figure 8 on page 12, then edit and submit sample jobs IGYWIVP1 and IGYWIVP2 to verify that you have installed Enterprise COBOL correctly. Consult the instructions in the sample jobs for more information.

Expected Return Codes and Messages: You will receive return codes of 0 if these jobs run correctly.

6.1.13 Perform SMP/E ACCEPT

Edit and submit sample job IGYWACPT to perform an SMP/E ACCEPT CHECK for Enterprise COBOL. Consult the instructions in the sample job for more information.

To receive the full benefit of the SMP/E Causer SYSMOD Summary Report, do *not* bypass the PRE, ID, REQ, and IFREQ on the ACCEPT CHECK. The SMP/E root cause analysis identifies the cause of *errors* but not *warnings* (SMP/E treats bypassed PRE, ID, REQ, and IFREQ conditions as warnings rather than errors).

Before you use SMP/E to load new distribution libraries, it is recommended that you set the ACCJCLIN indicator in the distribution zone. In this way, you can save the entries that are produced from JCLIN in the distribution zone whenever a SYSMOD that contains inline JCLIN is accepted. For more information about the ACCJCLIN indicator, see the description of inline JCLIN in the SMP/E Commands book for details.

After you take actions that are indicated by the ACCEPT CHECK, remove the CHECK operand and run the job again to perform the ACCEPT.

Note: The GROUPEXTEND operand indicates that SMP/E accepts all requisite SYSMODs. The requisite SYSMODS might be applicable to other functions.

Expected Return Codes and Messages from ACCEPT CHECK: You will receive a return code of 0 if this job runs correctly.

If PTFs that contain replacement modules are accepted, SMP/E ACCEPT processing will link-edit or bind the modules into the distribution libraries. During this processing, the Linkage Editor or Binder might issue messages that indicate unresolved external references, which will result in a return code of 4 during the ACCEPT phase. You can ignore these messages, because the distribution libraries are not executable and the unresolved external references do not affect the executable system libraries.

Expected Return Codes and Messages from ACCEPT: You will receive a return code of 0 if this job runs correctly.

6.1.14 Run REPORT MISSINGFIX

The SMP/E REPORT MISSINGFIX command helps you determine whether any FIXCAT APARs exist that are applicable and have not yet been installed.

After you install Enterprise COBOL, it is recommended that you run REPORT MISSINGFIX. This requires a global zone with ZONEINDEX entries that describe all the target and distribution libraries to be reported on, the SET BOUNDARY command must specify the global zone.

Here is a sample REPORT MISSINGFIX command to run against your z/OS CSI:

```
SET BDY(globalzone).  
REPORT MISSINGFIX ZONES(targetzone)  
FIXCAT(IBM.TargetSystem-RequiredService.Enterprise-COBOL.V5R2).
```

For more information about REPORT MISSINGFIX, see the SMP/E manuals.

6.2 Activating Enterprise COBOL

6.2.1 File System Execution

If you mount the file system in which you have installed Enterprise COBOL in read-only mode during execution, then you do not have to take further actions to activate Enterprise COBOL.

6.2.2 Product Customization

The publication *IBM Enterprise COBOL for z/OS Customization Guide* (SC14-7380) contains the necessary information to customize and use Enterprise COBOL.

7.0 Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

APAR numbers are provided in this document to assist in locating PTFs that may be required. Ongoing problem reporting may result in additional APARs being created. Therefore, the APAR lists in this document may not be complete. To obtain current service recommendations and to identify current product service requirements, always contact the IBM Customer Support Center or use S/390 SoftwareXcel to obtain the current "PSP Bucket".

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
USA

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan, Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan

7.1 Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml.

Reader's Comments

Program Directory for IBM Enterprise COBOL for z/OS, February 2015

We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Use one of the following methods to send us your comments:

1. Send an email to comments@us.ibm.com
2. Use the form on the Web at:

www.ibm.com/software/data/rcf

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit.

Thank you for your participation.



Printed in USA

G111-9180-03

